SIGNALS and SYSTEMS

reference sheet

by

Remco Litjens

(remco@aura.eecs.berkeley.edu)

Continuous-time Signals and Systems

General / Miscellaneous

$$1. \quad \omega_o = \frac{2\pi}{T_o} = 2\pi f_o$$

$$2. \quad f(\Leftrightarrow t) = f(t)$$

3.
$$f(\Leftrightarrow t) = \Leftrightarrow f(t)$$

4.
$$sinc z = \frac{sin \pi z}{\pi z}$$

$$5. \quad \int_{-\infty}^{\infty} \frac{\sin ax}{bx} dx = \frac{\pi}{b}$$

6.
$$e^{-t}\delta(t) = e^{-0}\delta(t) = \delta(t)$$

7.
$$\sqrt{\omega^2} = |\omega|$$

8.
$$H_{ ext{lpf}}(\omega) = 1 \Leftrightarrow H_{ ext{hpf}}(\omega)$$

9.
$$arctan(\frac{\omega}{0}) = \frac{\pi}{2} sgn(\omega)$$

angular or fundamental frequency

even function (e.g. cost)

odd function (e.g. sin t)

sinc-function

area under a sinc-function

Trigonometry

1.
$$sinx = cos(x \Leftrightarrow \frac{1}{2}\pi)$$

$$2. \quad \sin^2 x + \cos^2 x = 1$$

3.
$$cos2x = 2cos^2x \Leftrightarrow 1 = 1 \Leftrightarrow 2sin^2x$$

$$4. \quad \sin 2x = 2 \sin x \cos x$$

5.
$$cos(\alpha + \beta) = cos\alpha cos\beta \Leftrightarrow sin\alpha sin\beta$$

6.
$$sin(\alpha + \beta) = sin\alpha cos\beta + cos\alpha sin\beta$$

7.
$$2\cos\alpha\cos\beta = \cos(\alpha + \beta) + \cos(\alpha \Leftrightarrow \beta)$$

8.
$$\Leftrightarrow 2\sin\alpha\sin\beta = \cos(\alpha + \beta) \Leftrightarrow \cos(\alpha \Leftrightarrow \beta)$$

9.
$$\frac{d}{d\omega} \sin \omega = \cos \omega$$

10.
$$\frac{d}{d\omega}\cos\omega = \Leftrightarrow \sin\omega$$

11.
$$\frac{d}{d\omega} arctan(\omega) = \frac{1}{1+\omega^2}$$

Complex Numbers

1.
$$j = \sqrt{\Leftrightarrow 1}$$

$$2. \quad z = a + bj = Re[z] + jIm[z]$$

3.
$$z^* = a \Leftrightarrow bj = Re[z] \Leftrightarrow jIm[z]$$

4.
$$z = |z|e^{j \angle z}$$

5.
$$|z| = \sqrt{Re^2[z] + Im^2[z]}$$

6.
$$\angle z = arctan(\frac{Im[z]}{Re[z]})$$

7.
$$e^{jx} = cosx + jsinx$$

8. in
$$\mathbb{C}$$
: $1 = e^{j0}$, $\Leftrightarrow 1 = e^{j\pi}$, $j = e^{\frac{1}{2}j\pi}$, $\Leftrightarrow j = e^{-\frac{1}{2}j\pi}$

9.
$$e^{jn\pi} = (\Leftrightarrow 1)^n$$

10.
$$\cos \omega_o t = \frac{1}{2} (e^{j\omega_o t} + e^{-j\omega_o t})$$

11.
$$\sin \omega_o t = \frac{1}{2j} (e^{j\omega_o t} \Leftrightarrow e^{-j\omega_o t})$$

12.
$$\frac{1}{a+bi} = \frac{a-bj}{a^2+b^2}$$

13.
$$|(a+bj)\cdot(c+dj)| = |(a+bj)|\cdot|(c+dj)|$$

14.
$$z + z^* = 2Re[z]$$

15.
$$zz^* = |z|^2$$

16.
$$\frac{1}{z^*} = (\frac{1}{z})^*$$

17.
$$\angle z^* = \Leftrightarrow \angle z$$

imaginary constant

complex number (rectangular or Cartesian form)

complex conjugate of z

complex number (polar form)

magnitude of complex number z

angle or phase of complex number z

Euler's formula

basic points on unit circle in $\mathbb C$

18.
$$\angle \{(a+bj) \cdot (c+dj)\} = \angle \{a+bj\} + \angle \{c+dj\}$$

19.
$$z \Leftrightarrow z^* = 2jIm[z]$$

$$20. \quad \angle z^{-1} = \Leftrightarrow \angle z$$

21.
$$|z| = |z^*|$$

22.
$$|z^{-1}| = |z|^{-1}$$

Singularity Signals

1.
$$u(t) = \int_{-\infty}^{t} \delta(s)ds = 1 \ t \ge 0$$
, and 0 elsewhere

$$2. \quad r(t) = \int_{-\infty}^{t} u(s)ds = tu(t)$$

unit step function unit ramp function

3.
$$p(t) = \int_{-\infty}^{t} r(s)ds = \frac{1}{2}t^2u(t)$$

unit parabola function

4. $\Pi(t) = u(t + \frac{1}{2}) \Leftrightarrow u(t \Leftrightarrow \frac{1}{2}) = 1, |t| \leq \frac{1}{2}$, and 0 elsewhere

unit pulse function

5. $\Lambda(t) = r(t+1) \Leftrightarrow 2r(t) + r(t \Leftrightarrow 1)$

unit triangle function

6. $\delta(t) = \lim_{\epsilon \to 0} \frac{1}{2\epsilon} \Pi(\frac{t}{2\epsilon})$

unit impulse or delta function (a.k.a. the "spike")

7. $\dot{\delta}(t) = \frac{d}{dt}\delta(t)$

doublet

8.
$$\delta(at) = \frac{1}{|a|}\delta(t)$$
, for $a \in \mathbb{R}\setminus\{0\}$

$$9. \quad u(at) = u(t)$$

$$10. \quad r(at) = a \, r(t)$$

11.
$$\int_{-\infty}^{\infty} \delta(t)dt = 1$$

12.
$$x(t)\delta(t \Leftrightarrow a) = x(a)\delta(t \Leftrightarrow a)$$

13.
$$\int_{a}^{b} x(t)\delta(t)dt = x(0), \text{ if } a < 0 < b, \text{ and } 0, \text{ elsewhere}$$
14.
$$\int_{-\infty}^{\infty} x(s)\delta(t \Leftrightarrow s)ds = x(t)$$

14.
$$\int_{-\infty}^{\infty} x(s)\delta(t \Leftrightarrow s)ds = x(t)$$

sifting or convolution property (integral)

15. $\int_{-\infty}^{\infty} x(s)\delta^{(n)}(t \Leftrightarrow s)ds = (\Leftrightarrow 1)^n x^{(n)}(t)$

Power and Energy

1.
$$E = \lim_{\tau \to \infty} \int_{-\tau}^{\tau} |x(t)|^2 dt$$

average energy (in joules)

2. $P = \lim_{\tau \to \infty} \frac{1}{2\tau} \int_{-\tau}^{\tau} |x(t)|^2 dt$

average power (in watts)

- if $0 \le E < \infty$ then P = 0 and the signal is called a energy signal.
- if $0 < P < \infty$ then $E = \infty$ and the signal is called a power signal.
- the energy of a periodic signal is infinite and the power equals $P=\frac{1}{T_o}\int_{t_o}^{t_o+T_o}|x(t)|^2dt$, with t_o arbitrary.

Convolution

• definition:
$$h(t) \otimes x(t) = \int_{-\infty}^{\infty} h(t \Leftrightarrow \tau) x(\tau) d\tau = \int_{-\infty}^{\infty} h(\tau) x(t \Leftrightarrow \tau) d\tau$$

1.
$$x_1(t) \otimes x_2(t) = x_2(t) \otimes x_1(t)$$

commutativity property of convolution

2.
$$x_1(t) \otimes (x_2(t) \otimes x_3(t)) = (x_1(t) \otimes x_2(t)) \otimes x_3(t)$$

associativity property of convolution

3.
$$x_1(t) \otimes (x_2(t) + x_3(t)) = x_1(t) \otimes x_2(t) + x_1(t) \otimes x_3(t)$$

distributivity property of convolution

4. **trick 1:**
$$x(t \Leftrightarrow \tau) = x(t) \otimes \delta(t \Leftrightarrow \tau)$$

delay system

5. **trick 2:**
$$x(t) = x(t) \otimes \delta(t), \forall x(t)$$

- trick 3: convolving a signal x(t) with u(t) means taking the running time integral of x(t).
- trick 4: convolving a signal x(t) with $\frac{d}{dt}\delta(t)$ means taking the derivative of x(t).

8.
$$u(t) = u(t) \otimes \delta(t) = \int_{-\infty}^{t} \delta(s) ds$$

9.
$$r(t) = u(t) \otimes u(t) = \int_{-\infty}^{t} u(s)ds$$

10.
$$p(t) = u(t) \otimes r(t) = \int_{-\infty}^{t} r(s)ds$$

and conversely

8*.
$$\delta(t) = \frac{d}{dt}\delta(t) \otimes u(t) = \frac{d}{dt}u(t)$$

9*.
$$u(t) = \frac{d}{dt}\delta(t) \otimes r(t) = \frac{d}{dt}r(t)$$

10*.
$$r(t) = \frac{d}{dt}\delta(t) \otimes p(t) = \frac{d}{dt}p(t)$$

General Systems

$$1. \quad y(t) = H[x(t)]$$

2. $H[\alpha_1 x_1(t) + \alpha_2 x_2(t)] = \alpha_1 H[x_1(t)] + \alpha_2 H[x_2(t)]$

3. $H[D_{\tau}[x(t)]] = D_{\tau}[H[x(t)]]$

4. $y(t_o) = H[x(t_0)]$ depends only on x(t) for $t = t_o$

 $y(t_o) = H[x(t_0)]$ depends only on x(t) for $t \le t_o$

system $H[\cdot]$

condition for **linearity** of $H[\cdot]$

condition for **time-invariance** of $H[\cdot]$

condition for **memoryless** property of $H[\cdot]$

condition for **causality** of $H[\cdot]$

- note that H[x(t)] = x(t) + 1 is non-linear.
- memoryless systems are causal.

Linear Systems

1.
$$g(t,s) = H[\delta(t \Leftrightarrow s)]$$

2.
$$y(t) = \int_{-\infty}^{\infty} g(t,\tau)x(\tau)d\tau$$

check for causality: input $\delta(t \Leftrightarrow s)$ and check if for any s the output is zero $\forall t > s$.

H is time-invariant $\iff g(t + \Delta, s + \Delta) = g(t, s)$

if $H[\cdot]$ is linear and memoryless, then $H[\cdot]$ will be of the form $H[\cdot] = \alpha(t)x(t)$.

Linear and Time-Invariant (LTI) Systems

1.
$$H_1[\cdot], H_2[\cdot] \text{ LTI} \Leftrightarrow H_1[H_2[\cdot]] \text{ LTI}$$

2.
$$H_1[\cdot], H_2[\cdot] \text{ LTI} \Leftrightarrow (H_1 + H_2)[\cdot] \text{ LTI}$$

1.
$$h(t) = H[\delta(t)]$$

$$2. \quad y_{step} = H[u(t)]$$

3.
$$y_{ramp} = H[r(t)]$$

4.
$$y_{parabola} = H[p[(t)]]$$

4.
$$y_{parabola} = H[p[(t)]]$$

5. $H(\omega) = \int_{-\infty}^{\infty} h(t) e^{-j\omega t} dt = |H(\omega)| e^{j\angle H(\omega)}$
6. $H(s) = \int_{0}^{\infty} h(t) e^{-st} dt$

6.
$$H(s) = \int_{0^{-}}^{\infty} h(t) e^{-st} ds$$

7.
$$h(t) \text{ real} \Rightarrow H(\Leftrightarrow \omega) = H^*(\omega)$$

impulse response of $H[\cdot]$

step response of $H[\cdot]$

ramp response of $H[\cdot]$

parabola response of $H[\cdot]$

frequency response of $H[\cdot]$ (Fourier transform of h(t)

transfer function of $H[\cdot]$ (Laplace transform of h(t)

8.
$$y(t) = h(t) \otimes x(t) = \int_{-\infty}^{\infty} h(t \Leftrightarrow \tau) x(\tau) d\tau = \int_{-\infty}^{\infty} h(\tau) x(t \Leftrightarrow \tau) d\tau = h(t) \otimes x(t)$$

9.
$$H[e^{j\omega t}] = H(\omega) e^{j\omega t}$$

10.
$$Y(\omega) = X(\omega)H(\omega)$$

11.
$$Y(s) = X(s)H(s)$$

superposition or convolution integral

for periodic signals (scaling; eigenfunctions / -value)

Fourier transform of (8)

Laplace transform of (8)

12.
$$h(t) = \frac{d}{dt}\delta(t) \otimes y_{step}(t) = \frac{d}{dt}y_{step}(t)$$

13.
$$y_{step} = \frac{d}{dt}\delta(t) \otimes y_{ramp}(t) = \frac{d}{dt}y_{ramp}(t)$$

14.
$$y_{ramp} = \frac{d}{dt}\delta(t) \otimes y_{parabola}(t) = \frac{d}{dt}y_{parabola}(t)$$
 \uparrow

and conversely

 \downarrow
 $12*. y_{step} = h(t) \otimes u(t) = \int_{-\infty}^{t} h(s)ds$
 $13*. y_{ramp} = h(t) \otimes r(t) = h(t) \otimes u(t) \otimes u(t) = y_{step} \otimes u(t) = \int_{-\infty}^{t} y_{step}(s)ds$
 $14*. y_{parabola} = h(t) \otimes p(t) = h(t) \otimes r(t) \otimes u(t) = y_{ramp} \otimes u(t) = \int_{-\infty}^{t} y_{ramp}(s)ds$

Frequency, Phase and Magnitude Response

- 1. $H(\omega) = \int_{-\infty}^{\infty} h(t) e^{-j\omega t} dt$ frequency response is $\mathcal{F}[h(t)]$
- 2. from an LDE with CC: let $x(t) = e^{j\omega t}$ and $y(t) = H(\omega)e^{j\omega t}$; solve for $H(\omega)$
- 3. from an LDE with CC: let $X(\omega) = \mathcal{F}[x(t)]$ and $Y(\omega) = \underbrace{\mathcal{F}[y(t)]}_{X(\omega)}$; solve for $H(\omega) = \frac{Y(\omega)}{X(\omega)}$, using $\mathcal{F}[\dot{x}(t)] = j\omega X(\omega)$
- 4. if $H(\omega) = K \frac{1+aj\omega}{1+bj\omega}$, then $|H(\omega)| = |K| \frac{|1+aj\omega|}{|1+bj\omega|} = |K| \frac{\sqrt{1+(a\omega)^2}}{\sqrt{1+(b\omega)^2}}$
- 5. if $H(\omega) = K \frac{1 + aj\omega}{1 + bj\omega}$, then $\angle H(\omega) = \angle K + \angle (1 + aj\omega) \Leftrightarrow \angle (1 + bj\omega) = \angle K + \arctan(a\omega) \Leftrightarrow \arctan(b\omega)$

BIBO-Stability

- definition: system $H[\cdot]$ is BIBO-stable iff every bounded input results in a bounded output
- 1. system $H[\cdot]$ is BIBO-stable iff $\int_{-\infty}^{\infty} |h(t)| < \infty$
- 2. if system $H[\cdot]$ is BIBO-stable then $H(s) = \frac{N(s)}{D(s)}$ must be proper, i.e. degree $N(s) \leq \text{degree } D(s)$
- 3. if causal system $H[\cdot]$ is BIBO-stable then all the poles of H(s) must lie in the open left-half plane
- necessary conditions 2 and 3 for stability are sufficient if H(s) is rational (generally the case)
- for all stable causal systems, the frequency response exists

Distortion

- an LTI system is distortionless if the output $y(t) = H[x(t)] = Kx(t \Leftrightarrow \tau)$, a scaled and shifted replica of the input $x(t) \Leftrightarrow H(\omega) = K e^{-j\omega\tau} \Leftrightarrow |H(\omega)|$ is constant and $\Delta H(\omega) = \Leftrightarrow \omega\tau$ is linear in ω .
- an LTI system shows amplitude distortion when $|H(\omega)|$ varies with ω .
- an LTI system shows phase distortion when $\angle H(\omega)$ is non-linear in ω , and then we define $\tau_g(\omega) = \Leftrightarrow \frac{d\angle H(\omega)}{d\omega}$ as the group delay.

Minimum Phase

A system $H[\cdot]$ is said to be **minimum phase**, if all poles and zeros of H(s) lie in the open left half plane, so that $H^{-1}(s)$ is also minimum phase; hence a causal system that is minimum phase, is also causally invertible.

Feedback

Given a feedback system block diagram, we can write the equations:

- $e(t) = x(t) \pm y(t) \otimes h_2(t) \stackrel{\mathcal{L}}{\longleftrightarrow} E(s) = X(s) \pm Y(s)H_2(s)$ (error function);
- $y(t) = e(t) \otimes h_1(t) \quad \stackrel{\mathcal{L}}{\longleftrightarrow} \quad Y(s) = E(s)H_1(s);$
- combine: $y(t) = x(t) \otimes h_1(t) \pm y(t) \otimes h_2(t) \otimes h_1(t)$; $\stackrel{\mathcal{L}}{\longleftrightarrow} Y(s) = X(s)H_1(s) \pm Y(s)H_1(s)H_2(s) \Leftrightarrow \frac{Y(s)}{X(s)} = \frac{H_1(s)}{1 \mp H_1(s)H_2(s)}$
- in control problems, where we try to optimize feedback, we often use the final value theorem for Laplace transforms;

Finding the Output of LTI Systems

```
1. y(t) = x(t) \otimes h(t) straight convolution

2. y(t) = \mathcal{F}^{-1}[X(\omega)H(\omega)] using Fourier transforms

2. y(t) = \mathcal{L}^{-1}[X(s)H(s)] using Laplace transforms
```

3. if $x(t) = e^{j\omega_o t}$, then $y(t) = H(\omega_o)e^{j\omega_o t}$ using Fourier eigenfunctions

4. if $x(t) = e^{st}$, then $y(t) = H(s)e^{st}$ using Laplace eigenfunctions

5. if $x(t) = cos(\omega_o t + \phi)$ and h(t) is real, then $y(t) = |H(\omega_o)|cos(\omega_o t + \phi + \Delta H(\omega_o))$

steady-state sinusoidal response

6. if $x(t) = \sin(\omega_o t + \phi)$ and h(t) is real, then $y(t) = |H(\omega_o)|\sin(\omega_o t + \phi + \Delta H(\omega_o))$

steady-state sinusoidal response

7. if
$$x(t) = \sum_{n=-\infty}^{\infty} X_n e^{jn\omega_o t}$$
, then $y(t) = \sum_{n=-\infty}^{\infty} X_n H(n\omega_o) e^{jn\omega_o t} = \sum_{n=-\infty}^{\infty} X_n |H(n\omega_o)| e^{j(n\omega_o t + \Delta H(n\omega_o))}$ using Fourier series

• the transfer function and consequently the impulse response can be derived from any LDE by assuming zero initial conditions.

Remarks

- in LTI systems it makes no difference if we see h(t) as the input signal and x(t) as the impulse response of the LTI system (follows directly from the commutativity property of convolution).
- both h(t) and $H(\omega)$ completely characterize an LTI system.
- for an LTI system $H[\cdot]: h(t) = 0$ for $t < 0 \Leftrightarrow H[\cdot]$ is causal.
- a differentiator $(h(t) = \dot{\delta}(t))$ is causal.
- an ideal differentiator $\dot{\delta}(t)$ is a causal system.
- $H(\omega)$ real $\Leftrightarrow h(\Leftrightarrow) = h(t) \Rightarrow H[\cdot]$ is non-causal (unless $h(t) = 0 \ \forall t \neq 0$) \Longrightarrow filters are non-causal
- an LTI system converts a periodic input signal into a periodic output signal.
- if $H[\cdot]$ is LTI and memoryless, then h(t) = 0 for $t \neq 0$ and $H[\cdot]$ will be of the form $H[\cdot] = \alpha x(t)$.

Fourier Series

Definition of Fourier Series

We can decomposing any periodic power signal (with period T_o) into discrete frequencies, each a multiple of ω_o , yielding the Fourier series representation of that signal:

- $x(t) = \sum_{n=-\infty}^{\infty} X_n e^{jn\omega_o t}$ synthesis equation $X_n = \frac{1}{T_o} \int_{T_o} x(t) e^{-jn\omega_o t} dt$ analysis equation

Properties of Fourier Series (given $x(t) \stackrel{\mathcal{FS}}{\longleftrightarrow} X_n$):

- real signals: if x(t) is real, then $X_{-n} = X_n^*$
- if x(t) is real and even in t, then X_n is real and even in n• real and even signals:

$$\operatorname{Ev}[x(t)] \stackrel{\mathcal{FS}}{\longleftrightarrow} \operatorname{Re}[X(\omega)] \text{ and } \operatorname{Re}[x(t)] \stackrel{\mathcal{FS}}{\longleftrightarrow} \operatorname{Ev}[X(\omega)]$$

if x(t) is real and odd in t, then X_n is imaginary and odd in n • real and odd signals:

$$\operatorname{Od}[x(t)] \stackrel{\mathcal{FS}}{\longleftrightarrow} \operatorname{Im}[X(\omega)] \text{ and } \operatorname{Im}[x(t)] \stackrel{\mathcal{FS}}{\longleftrightarrow} \operatorname{Od}[X(\omega)]$$

- if $x(t \pm \frac{1}{2}T_o) = \Leftrightarrow x(t)$, $\forall t$ (e.g. x(t) = sint), then $X_n = 0$ for n even (in particular, $X_0 = 0$) • half-wave odd symmetry:
- $x(\Leftrightarrow t) \stackrel{\mathcal{FS}}{\longleftrightarrow} X_{-n}$ • time reversal:
- $x^*(t) \stackrel{\mathcal{FS}}{\longleftrightarrow} X_{-n}^* \text{ and } x^*(\Leftrightarrow t) \stackrel{\mathcal{FS}}{\longleftrightarrow} X_n^*$ • complex conjugate:
- $x(t \Leftrightarrow \tau) \stackrel{\mathcal{FS}}{\longleftrightarrow} e^{-jn\omega_o \tau} X_n$ • delay:
- $\dot{x}(t) \stackrel{\mathcal{FS}}{\longleftrightarrow} jn\omega_o X_n$ • differentiation:
- if $X_o = 0$ then $u(t) \otimes x(t) \overset{\mathcal{FS}}{\longleftrightarrow} \frac{X_n}{jn\omega_o}$, for $n \neq 0$ • integration:
- $\alpha x(t) + \beta y(t) \stackrel{\mathcal{FS}}{\longleftrightarrow} \alpha X_n + \beta Y_n$ • linearity:
- PARSEVAL's identity: $P = \sum_{n=-\infty}^{\infty} X_n^* X_n = \sum_{n=-\infty}^{\infty} |X_n|^2$ power at fundamental frequency of $x(t) = \sum_{n=-\infty}^{\infty} X_n e^{jn\omega_o t}$ equals $|X_{-1}|^2 + |X_1|^2$

Some Examples

- $x(t) = 1 \stackrel{\mathcal{FS}}{\longleftrightarrow} X_o = 1, X_n = 0$ otherwise • DC:
- $\cos \omega_o t = \frac{1}{2} (e^{j\omega_o t} + e^{-j\omega_o t})$ • cosine:
- $\sin \omega_o t = \frac{1}{2i} (e^{j\omega_o t} \Leftrightarrow e^{-j\omega_o t})$ • sine:
- even square wave: period T_o , $x_1(t) = 1$ for $|t| < T_1$ and $x_1(t) = 0$ elsewhere in that period:

$$x_1(t) \stackrel{\mathcal{FS}}{\longleftrightarrow} X_n = \frac{1}{n\pi} \sin n\omega_o T_1$$

- odd square wave: $x_2(t)$ is shifted $x_1(t)$
- even triangle wave: $x_3(t)$ is running time integral of $x_1(t)$

$$x_3(t) \stackrel{\mathcal{FS}}{\longleftrightarrow} X_n = \Leftrightarrow \frac{4}{n^2\pi^2}$$
, for n odd, and $X_n = 0$, for n even

• pulse train: $x_4(t)$ is same as $x_1(t)$ but shifted by τ and with added DC (this changes X_0 only):

$$x_4(t) = \sum_{k=-\infty}^{\infty} \prod_{\substack{t=-\infty \\ t_o}} \prod_{\substack{t=-\infty \\ t_o}} \frac{\mathcal{FS}}{t_o} X_n = \frac{t_o}{T_o} e^{-jn\omega_o \tau} sinc(\frac{nt_o}{T_o})$$
$$x_5(t) = \sum_{k=-\infty}^{\infty} \delta(at \Leftrightarrow kT) \xrightarrow{\mathcal{FS}} X_n = \frac{1}{|a|T}$$

• even impulse train:

Fourier Transform

Definition and Interpretation

The Fourier transform $X(\omega)$ is a decomposition of an (a)periodic signal x(t) into $e^{j\omega t}$ -type signals with ω real (x(t)) and (x(t)) uniquely define each other); we write $x(t) \stackrel{\mathcal{F}}{\longleftrightarrow} X(\omega)$:

• $x(t) = \mathcal{F}^{-1}[X(\omega)] = \frac{1}{2\pi} \int_{-\infty}^{\infty} X(\omega) e^{j\omega t} d\omega$ synthesis equation • $X(\omega) = \mathcal{F}[x(t)] = \int_{-\infty}^{\infty} x(t)e^{-j\omega t}dt$ analysis equation

The Fourier transform $X(\omega)$ exists when it's finite for all ω . Allowing δ -functions, we can accept a broader class of signals: sufficient conditions for the existence of the generalized Fourier transform of x(t) are (1) x(t) is bounded; and (2) x(t) is periodic ($E=\infty$) with finite power.

The interpretation of the Fourier transform is that $X(\omega)$ contains the frequency content of the signal x(t) for each ω . For example, consider $x(t) = 1 \stackrel{\mathcal{F}}{\longleftrightarrow} \delta(\omega) \text{ (DC only)}, x(t) = e^{j\omega_o t} \stackrel{\mathcal{F}}{\longleftrightarrow} 2\pi\delta(\omega \Leftrightarrow \omega_o) \text{ (single frequency at } \omega_o), \text{ and finally } x(t) = \cos\omega_o t \stackrel{\mathcal{F}}{\longleftrightarrow} \pi[\delta(\omega + \omega_o) + \delta(\omega \Leftrightarrow \omega_o)]$ (contains two frequencies: ω_o and $\Leftrightarrow \omega_o$). Note: if the signal x(t) is time-limited, $X(\omega)$ has infinite bandwidth.

Properties of Fourier Transforms (given $x(t) \stackrel{\mathcal{F}}{\longleftrightarrow} X(\omega)$):

- real signals: if x(t) is real, then $X(\omega) = X^*(\Leftrightarrow \omega)$
 - $\mathcal{R}e[X(\omega)] = \mathcal{R}e[X(\Leftrightarrow \omega)] \text{ and } \mathcal{I}m[X(\omega)] = \Leftrightarrow \mathcal{I}m[X(\Leftrightarrow \omega)]$
- if x(t) is real and even in t, then $X(\omega)$ is real and even in ω • real and even signals:
 - $\mathcal{E}v[x(t)] \stackrel{\mathcal{F}}{\longleftrightarrow} \mathcal{R}e[X(\omega)] \text{ and } \mathcal{R}e[x(t)] \stackrel{\mathcal{F}}{\longleftrightarrow} \mathcal{E}v[X(\omega)]$
- if x(t) is real and odd in t, then $X(\omega)$ is imaginary and odd in ω • real and odd signals:
 - $\mathcal{O}d[x(t)] \stackrel{\mathcal{F}}{\longleftrightarrow} j\mathcal{I}m[X(\omega)] \text{ and } j\mathcal{I}m[x(t)] \stackrel{\mathcal{F}}{\longleftrightarrow} \mathcal{O}d[X(\omega)]$
- $x(\Leftrightarrow t) \stackrel{\mathcal{F}}{\longleftrightarrow} X(\Leftrightarrow \omega)$ • time reversal:
- $x^*(t) \stackrel{\mathcal{F}}{\longleftrightarrow} X^*(\Leftrightarrow \omega) \text{ and } x^*(\Leftrightarrow t) \stackrel{\mathcal{F}}{\longleftrightarrow} X^*(\omega)$ • complex conjugate:
- $\alpha_1 x_1(t) + \alpha_2 x_2(t) \stackrel{\mathcal{F}}{\longleftrightarrow} \alpha_1 X_1(\omega) + \alpha_2 X_2(\omega)$ • linearity:
- $x(t \Leftrightarrow \tau) \stackrel{\mathcal{F}}{\longleftrightarrow} X(\omega)e^{-j\omega\tau}$ • delay:
- $x(at) \stackrel{\mathcal{F}}{\longleftrightarrow} \frac{1}{|a|} X(\frac{\omega}{a})$ • scale:
- $x(t) \stackrel{\mathcal{F}}{\longleftrightarrow} X(\omega) \Leftrightarrow X(t) \stackrel{\mathcal{F}}{\longleftrightarrow} 2\pi x (\Leftrightarrow \omega)$ • duality:
- $x(t)e^{j\omega_o t} \stackrel{\mathcal{F}}{\longleftrightarrow} X(\omega \Leftrightarrow \omega_o)$ • frequency translation:
- $\frac{d^n}{dt^n}x(t) \stackrel{\mathcal{F}}{\longleftrightarrow} (j\omega)^n X(\omega)$ • differentiation:
- $u(t) \otimes x(t) \stackrel{\mathcal{F}}{\longleftrightarrow} \frac{1}{j\omega} X(\omega) + \pi X(0) \delta(\omega)$ $x_1(t) \otimes x_2(t) \stackrel{\mathcal{F}}{\longleftrightarrow} X_1(\omega) \cdot X_2(\omega)$ • integration:
- convolution:
- $x_1(t) \cdot x_2(t) \stackrel{\mathcal{F}}{\longleftrightarrow} \frac{1}{2\pi} X_1(\omega) \otimes X_2(\omega)$ • multiplication:
- $t x(t) \stackrel{\mathcal{F}}{\longleftrightarrow} j \frac{d}{d\omega} X(\omega)$ • t-multiplication:
- $x(t)\cos\omega_o t \stackrel{\mathcal{F}}{\longleftrightarrow} \frac{1}{2}[X(\omega \Leftrightarrow \omega_o) + X(\omega + \omega_o)]$ • modulation:
- $E = \int_{-\infty}^{\infty} |x(t)|^2 dt = \frac{1}{2\pi} \int_{-\infty}^{\infty} |X(\omega)|^2 d\omega$ • PARSEVAL's identity:

- check results
- phase change (of $\Leftrightarrow \omega \tau$) only
- wide (narrow) in $t \Leftrightarrow$ narrow (wide) in ω
- used for modulation
- help solve LDEs
- δ -function accounts for DC in x(t)

Some Examples and Facts

- $X(0) = \int_{-\infty}^{\infty} x(t)dt$ is the **DC** level/power of signal x(t)
- $x(0) = \frac{1}{2\pi} \int_{-\infty}^{\infty} X(\omega) d\omega$ is the total power in x(t)
- $h(t) \stackrel{\mathcal{F}}{\longleftrightarrow} H(\omega)$
- $\frac{1}{\pi t} \stackrel{\mathcal{F}}{\longleftrightarrow} \Leftrightarrow j \, sgn(\omega) = e^{-j\frac{\pi}{2}sgn(\omega)}$

frequency response

Hilbert transform; FT exists, even though x(t) is unbounded

• $h_{HT} \otimes x(t)$ phase shifts x(t) only

- \bullet $H_{HT}[\cos t] = \sin t$ and $H_{HT}[\sin t] = \cos t$
- $\bullet \ H_{HT}[H_{HT}[x(t)]] = \Leftrightarrow x(t)$

- $sgn(t) \stackrel{\mathcal{F}}{\longleftrightarrow} \frac{2}{j\omega}$ $\Pi(\frac{t}{t_o}) \stackrel{\mathcal{F}}{\longleftrightarrow} t_o sinc(\frac{\omega t_o}{2\pi})$
- $sinc(\frac{t}{\alpha}) \stackrel{\mathcal{F}}{\longleftrightarrow} \alpha \Pi(\frac{\alpha \omega}{2\pi})$
- for $\alpha > 0$, $\beta e^{-\alpha t} u(t) \stackrel{\mathcal{F}}{\longleftrightarrow} \frac{\beta}{\alpha + j\omega}$ for $\alpha > 0$, $\beta e^{-\alpha |t|} \stackrel{\mathcal{F}}{\longleftrightarrow} \frac{2\alpha\beta}{\alpha^2 + \omega^2}$ $e^{-\pi t^2} \stackrel{\mathcal{F}}{\longleftrightarrow} e^{-\pi f^2} = e^{-\frac{\omega^2}{4\pi}}$

- $\sin \omega_o t \stackrel{\mathcal{F}}{\longleftrightarrow} \frac{\pi}{j} [\delta(\omega \Leftrightarrow \omega_o) \Leftrightarrow \delta(\omega + \omega_o)]$
- $\cos \omega_o t \stackrel{\mathcal{F}}{\longleftrightarrow} \pi[\delta(\omega \Leftrightarrow \omega_o) + \delta(\omega + \omega_o)]$
- $\bullet \ 0 \ \stackrel{\mathcal{F}}{\longleftrightarrow} \ 0$
- 1 $\stackrel{\mathcal{F}}{\longleftrightarrow} 2\pi\delta(\omega)$
- $\delta(t) \stackrel{\mathcal{F}}{\longleftrightarrow} 1$
- $\delta(t \Leftrightarrow t_o) \stackrel{\mathcal{F}}{\longleftrightarrow} e^{-j\omega t_o}$
- $\bullet \ \delta(t) \ \stackrel{\mathcal{F}}{\longleftrightarrow} \ j\omega$
- $u(t) \stackrel{\mathcal{F}}{\longleftrightarrow} \frac{1}{i\omega} + \pi\delta(\omega)$
- $\bullet \ \Lambda(\frac{t}{T}) = \frac{1}{T}\Pi(\frac{t}{T}) \otimes \Pi(\frac{t}{T}) \ \stackrel{\mathcal{F}}{\longleftrightarrow} \ Tsinc^2(\frac{\omega T}{2\pi})$
- $\bullet \ e^{j\omega_o t} \ \stackrel{\mathcal{F}}{\longleftrightarrow} \ 2\pi\delta(\omega \Leftrightarrow \omega_o)$
- $\sum_{n=-\infty}^{\infty} \delta(t \Leftrightarrow nT) \stackrel{\mathcal{F}}{\longleftrightarrow} \frac{2\pi}{T} \sum_{n=-\infty}^{\infty} \delta(\omega \Leftrightarrow n\omega_o)$ $\dot{\delta}(t) + \delta(t) + \frac{1}{2} sgn(t) \stackrel{\mathcal{F}}{\longleftrightarrow} j\omega + 1 + \frac{1}{j\omega}$
- the Fourier transform of a Gaussian $e^{-\frac{1}{2}(\frac{x-\mu}{\sigma})^2}$ is another Gaussian of the same form
- the Fourier transform of a Fourier Series $x(t) = \sum_{k=-\infty}^{\infty} X_k e^{jk\omega_o t} \overset{\mathcal{F}}{\longleftrightarrow} 2\pi \sum_{k=-\infty}^{\infty} X_k \delta(\omega \Leftrightarrow k\omega_o)$

Laplace Transform

Definition of Laplace Transform

The Laplace transform X(s) is a decomposition of an (a)periodic signal x(t) into signals of the type $e^{st} = e^{\sigma t}e^{j\omega t}$ with $s = \sigma + j\omega$ complex. Compared to the Fourier transform, the extra (real) exponential $e^{\sigma t}$ allows us to treat a broader class of signals. The $e^{\sigma t}$ part is used to model growth or decay, while the $e^{j\omega t}$ part models the oscillatory behavior of x(t). Again, x(t) and X(s) uniquely define each other and here we write $x(t) \stackrel{\mathcal{L}}{\longleftrightarrow} X(s)$:

```
• unilateral LT: X(s) = \mathcal{L}[x(t)] = \int_{0^-}^{\infty} x(t)e^{-st}dt = \int_{0^-}^{\infty} x(t)e^{-\sigma t}e^{-j\omega t}

(• bilateral LT: X(s) = \mathcal{L}[x(t)] = \int_{-\infty}^{\infty} x(t)e^{-st}dt = \int_{-\infty}^{\infty} x(t)e^{-\sigma t}e^{-j\omega t})
```

Note that the ULT only works for (real world) "causal" signals while the BLT permits us to consider any signal; furthermore, if x(t) = 0 for t < 0 (causal) then the ULT and the BLT are the same. Both the ULT and the BLT have regions of convergence (ROC) over which the transform exists. A ROC is the range of values of s over which the integral converges. A ROC cannot contain a pole, in fact for causal signals/systems, the ROC contains all s to the right of the rightmost pole. If x(t) is of finite duration, $ROC_x = \mathbb{C}$.

Any signal x(t) that is of exponential order, i.e. |x(t)| does not increase faster than Ae^{ct} with A and c real constants, can be transformed into X(s). Examples of signals that are not of exponential order, consider $x(t) = e^{t^2}u(t)$ and $x(t) = t^tu(t) = e^{t\ln t}u(t)$.

Properties of Unilateral Laplace Transforms (given $x(t) \stackrel{\mathcal{L}}{\longleftrightarrow} X(s)$ with ROC_x):

• linearity:	$\alpha_1 x_1(t) + \alpha_2 x_2(t) \stackrel{\mathcal{L}}{\longleftrightarrow} \alpha_1 X_1(s) + \alpha_2 X_2(s)$	at least $ROC_{x_1} \cap ROC_{x_2}$
• delay $(\tau > 0)$:	$x(t \Leftrightarrow \tau)u(t \Leftrightarrow \tau) \xrightarrow{\mathcal{L}} X(s)e^{-s\tau}$	ROC_x
• scale:	for real $a > 0$: $x(at) \stackrel{\mathcal{L}}{\longleftrightarrow} \frac{1}{a}X(\frac{s}{a})$	$\{s \mid \frac{s}{a} \in ROC_x\}$
• frequency translation:	$x(t)e^{-\alpha t} \stackrel{\mathcal{L}}{\longleftrightarrow} X(s+\alpha)$	$\{s \mid (s + \alpha) \in ROC_x\}$
ullet differentiation:	$\frac{d^n}{dt^n}x(t) \stackrel{\mathcal{L}}{\longleftrightarrow} s^nX(s) \Leftrightarrow s^{n-1}x(0^-) \Leftrightarrow \dots \Leftrightarrow sx^{(n-2)}(0^-) \Leftrightarrow x^{(n-1)}(0^-)$	at least ROC_x
• integration:	for $t > 0$: $u(t) \otimes x(t) \stackrel{\mathcal{L}}{\longleftrightarrow} \frac{1}{s} X(s) + \frac{1}{s} \int_{-\infty}^{0} x(\tau) d\tau$	at least $ROC_x \cap \{s \mid Re(s) > 0\}$
• convolution:	$x_1(t) \otimes x_2(t) \stackrel{\mathcal{L}}{\longleftrightarrow} X_1(s) \cdot X_2(s)$	at least $ROC_{x_1} \cap ROC_{x_2}$
\bullet t-multiplication:	$t \cdot x(t) \stackrel{\mathcal{L}}{\longleftrightarrow} \Leftrightarrow \frac{dX(s)}{ds}$	ROC_x
	1. Y() 1. (1) 1. 1. 1. 1. 1. 1.	

• initial value: $lim_{s\to\infty}\,sX(s)\,=\,lim_{t\to0+}\,x(t), \mbox{if this limit exists}$ • final value: $lim_{s\to0}\,sX(s)\,=\,lim_{t\to\infty}\,x(t), \mbox{if this limit exists}$

transfer function

IMPORTANT: $sin\ t\ u(t) \stackrel{\mathcal{L}}{\longleftrightarrow} \frac{1}{s^2+1}$, so $\lim_{s\to 0}\ sX(s) = 0$, but $\lim t\to \infty\ sin\ t\ u(t)$ clearly does not exist!!!

Some Examples

• $h(t) \stackrel{\mathcal{L}}{\longleftrightarrow} H(s)$

- (-)			
$\bullet \ 0 \ \stackrel{\mathcal{L}}{\longleftrightarrow} \ 0$		$ullet$ $\dot{\delta}(t) \stackrel{\mathcal{L}}{\longleftrightarrow} s$	all s
• $\delta(t) \stackrel{\mathcal{L}}{\longleftrightarrow} 1$	all s	• $\delta(t \Leftrightarrow \tau) \stackrel{\mathcal{L}}{\longleftrightarrow} e^{-s\tau}$	all s
• $u(t) \stackrel{\mathcal{L}}{\longleftrightarrow} \frac{1}{s}$	$\mathcal{R}e[s] > 0$	$\bullet \Leftrightarrow u(\Leftrightarrow t) \stackrel{\mathcal{L}}{\longleftrightarrow} \frac{1}{s}$	$\Re e[s] < 0$
• $r(t) \stackrel{\mathcal{L}}{\longleftrightarrow} \frac{1}{s^2}$	$\mathcal{R}e[s] > 0$	• $\Leftrightarrow r(\Leftrightarrow t) \stackrel{\mathcal{L}}{\longleftrightarrow} \frac{1}{s}$	$\Re e[s] < 0$
• $\frac{t^{n-1}}{(n-1)!} u(t) \stackrel{\mathcal{L}}{\longleftrightarrow} \frac{1}{s^n}$	$\mathcal{R}e[s] > 0$	$\bullet \Leftrightarrow \frac{t^{n-1}}{(n-1)!} u(\Leftrightarrow t) \xleftarrow{\mathcal{L}} \frac{1}{s^n}$	$\Re e[s] < 0$
$\bullet \ e^{-\alpha t} u(t) \stackrel{\mathcal{L}}{\longleftrightarrow} \frac{1}{s+\alpha}$	$\mathcal{R}e[s] > \Leftrightarrow \mathcal{R}e[\alpha]$	$\bullet \Leftrightarrow e^{-\alpha t} u(\Leftrightarrow t) \stackrel{\mathcal{L}}{\longleftrightarrow} \frac{1}{s+\alpha}$	$\mathcal{R}e[s] < \Leftrightarrow \mathcal{R}e[\alpha]$
• $\frac{t^{n-1}}{(n-1)!} e^{-\alpha t} u(t) \stackrel{\mathcal{L}}{\longleftrightarrow} \frac{1}{(s+\alpha)^n}$	$\mathcal{R}e[s] > \Leftrightarrow \mathcal{R}e[\alpha]$	$\bullet \Leftrightarrow \frac{t^{n-1}}{(n-1)!} e^{-\alpha t} u(\Leftrightarrow t) \stackrel{\mathcal{L}}{\longleftrightarrow} \frac{1}{(s+\alpha)^n}$	$\mathcal{R}e[s] < \Leftrightarrow \mathcal{R}e[\alpha]$
• $(\sin \omega_o t)u(t) \stackrel{\mathcal{L}}{\longleftrightarrow} \frac{\omega_o}{s^2 + \omega_o^2}$	$\mathcal{R}e[s] > 0$	• $(e^{-\alpha t} \sin \omega_o t) u(t) \stackrel{\mathcal{L}}{\longleftrightarrow} \frac{\omega_o}{(s+\alpha)^2 + \omega_o^2}$	$\mathcal{R}e[s] > \Leftrightarrow \mathcal{R}e[\alpha]$
• $(\cos \omega_o t)u(t) \stackrel{\mathcal{L}}{\longleftrightarrow} \frac{s}{s^2+\omega^2}$	$\Re e[s] > 0$	• $(e^{-\alpha t}\cos\omega_o t)u(t) \stackrel{\mathcal{L}}{\longleftrightarrow} \frac{s+\alpha}{(s+\alpha)^2+\omega^2}$	$\mathcal{R}e[s] > \Leftrightarrow \mathcal{R}e[\alpha]$

Linear Differential Equations

Solving LDE w/CC using Fourier transforms

One can solve LDE w/CC using Fourier transforms or Laplace transforms. Below we show how to do it with Laplace transform. For Fourier transforms, the procedure is identical: find $h(t) = \mathcal{F}^{-1}[H(\omega)]$ with $H(\omega) = \frac{Y(\omega)}{X(\omega)}$ and $X(\omega) = \mathcal{F}[\delta(t)] = 1$. $Y(\omega)$ follows from using the differentiation property for Fourier transforms and some algebraic manipulations.

 $\begin{array}{ll} \textbf{Example:} & \text{if } \ddot{y}(t) \Leftrightarrow \dot{y}(t) \Leftrightarrow 30y(t) = x(t), \text{ then for } x(t) = \delta(t) \text{ we find } (j\omega)^2 H(\omega) \Leftrightarrow (j\omega) H(\omega) \Leftrightarrow 30H(\omega) = 1 \\ & \iff H(\omega) = \frac{1}{(j\omega)^2 - (j\omega) - 30}, \text{ so } h(t) = \mathcal{F}^{-1} \big[\frac{1}{(j\omega+5)(j\omega-6)} \big] = \mathcal{F}^{-1} \big[\frac{1}{j\omega+5} \big] + \mathcal{F}^{-1} \big[\frac{1}{j\omega-6} \big] = \Leftrightarrow \frac{1}{11} e^{-5t} u(t) + \frac{1}{11} e^{6t} u(t). \end{array}$ Note that this system is BIBO unstable.

Solving LDE w/CC using Laplace transforms

We show how the unilateral Laplace transform can be used to solve linear differential equations with constant coefficients. In particular, the integration property of the unilateral Laplace transform is utilized. The procedures are not shown for the general case, but rather for an example.

Example: Assume we are given the following LDE w/CC that we are trying to solve:

$$\ddot{y}(t) + 2\dot{y}(t) + y(t) = 2\dot{x}(t)$$

with initial conditions $\dot{y}(0^-) = 2$, $y(0^-) = 2$ and $x(0^-) = 0$.

First, take the unilateral Laplace transform of both sides, using the differentiation property:

$$[s^{2}Y(s) \Leftrightarrow sy(0^{-}) \Leftrightarrow \dot{y}(0^{-})] + a[sY(s) \Leftrightarrow y(0^{-})] + Y(s) = c[sX(s) \Leftrightarrow x(0^{-})] \iff Y(s) = \frac{s(2 + 2X(s)) + 2 + 4}{s^{2} + 2s + 1}$$

For input signal $x(t) = cost u(t) \stackrel{\mathcal{L}}{\longleftrightarrow} \frac{s}{s^2+1}$:

$$Y(s) = \frac{2s + 6 + 2s \cdot \frac{s}{s^2 + 1}}{s^2 + 2s + 1} = \frac{2s^3 + 8s^2 + 2s + 6}{(s + 1)^2(s^2 + 1)} = \frac{1}{s + 1} + \frac{5}{(s + 1)^2} + \frac{s}{s^2 + 1} \iff y(t) = \mathcal{L}^{-1}[Y(s)] = (e^{-t} + 5te^{-t} + \cos t)u(t)$$

ZIR and ZSR

The zero-input response $y_{zir}(t)$ is y(t) when the non-zero intial conditions are assumed to contain all information about what happened in the past, and for $t \ge t_o$, there is no input to the system: x(t) = 0, for $t \ge t_o$. So $y_{zir}(t)$ is the system response to initial conditions only. In the example above, $y_{zir}(t) = (2e^{-t} + 4te^{-t})u(t)$.

The zero-state response $y_{zsr}(t)$ is y(t) when zero initial conditions are assumed and for $t \ge t_o$, the input x(t) is known. In the example, $y_{zsr}(t) = (\Leftrightarrow e^{-t} + te^{-t} + cost)u(t)$.

Note that $y(t) = y_{zir}(t) + y_{zsr}(t)$ always holds. In the example: $y_{zir}(t) + y_{zsr}(t) = (2e^{-t} + 4te^{-t})u(t) + (\Leftrightarrow e^{-t} + te^{-t} + cost)u(t) = (e^{-t} + 5te^{-t} + cost)u(t) = y(t)$.

Partial Fraction Expansions

Sorry, I never found the time to do this section: see your notes!

Discrete-time Signals and Systems

General Remarks

Since in discrete time, when observing some continuous-time signal at times t = nT, complex exponentials $e^{j\omega_1 nT}$ and $e^{j\omega_2 nT}$ with $\omega_2 = \omega_1 + \frac{2\pi}{T}$, look exactly identical, we introduce the concept of **normalized frequency**: $\Omega \equiv \omega T$ (note that we basically only rescaled the time axis). All of this implies that DISCRETE-TIME SIGNALS HAVE PERIODIC DTFTs, with period $\frac{2\pi}{L}$ in unnormalized frequency and period 2π in normalized frequency.

In discrete-time, high frequencies lie around odd multiples of π , while low frequencies lie around even multiples of π . Consequently, an ideal low-pass filter with cut-off frequency $\Omega_1 < \pi$ has impulse response $h_{lpf}[n] = \frac{\Omega_1}{\pi} sinc \frac{n\Omega_1}{\pi}$ and a pulse train as frequency response. The frequency response of a high-pass, bandpass or notch filter is simply a shifted and possibly duplicated version of the frequency response of a low-pass filter.

Singularity Signals

1. $\delta[n] = u[n] \Leftrightarrow u[n \Leftrightarrow 1] = 1, n = 0, \text{ and } 0 \text{ elsewhere}$

2. $u[n] = \sum_{k=-\infty}^{n} \delta[k] = \sum_{k=0}^{\infty} \delta[n \Leftrightarrow k] = 1 \ n \geq 0$, and 0 elsewhere 3. $x[n] = \sum_{k=-\infty}^{\infty} x[k] \delta[n]$

delta function

unit step function

sifting property (sum)

Convolution

definition: $h[n] \otimes x[n] = \sum_{k=-\infty}^{\infty} x[k] h[n \Leftrightarrow k] = \sum_{k=-\infty}^{\infty} x[n \Leftrightarrow k] h[k]$ often very easy to do!

trick 1: $x[n \Leftrightarrow n_o] = x[n] \otimes \delta[n \Leftrightarrow n_o]$

delay system

trick 2: $x[n] = x[n] \otimes \delta[n], \forall x[n]$

trick 3: $\sum_{k=-\infty}^{n} x[n] = u[n] \otimes x[n]$

convolving with u[n] means taking the running sum

example: $u[n] \otimes u[n] = \sum_{k=-\infty}^{\infty} u[k] u[n \Leftrightarrow k] = \sum_{k=0}^{n} 1 = (n+1)u[n]$

BIBO-Stability

- definition: system $H[\cdot]$ is BIBO-stable iff every bounded input results in a bounded output
- system $H[\cdot]$ is BIBO-stable iff $\sum_{k=-\infty}^{\infty} |h[k]| < \infty$
- causal system $H[\cdot]$ is BIBO-stable iff all the poles of H(z) are strictly inside the unit circle
- for all stable causal systems, the frequency response exists

Finding the Output of LTI Systems

1. $h[n] = H[\delta[n]]$

 $2. \quad y[n] = x[n] \otimes h[n]$

3. $y[n] = \mathcal{F}^{-1}[X(e^{j\Omega})H(e^{j\Omega})]$

4. $y[n] = \mathcal{L}^{-1}[X(z)H(z)]$

5. if $x[n] = e^{j\Omega_o n}$, then $y[n] = H(e^{j\Omega_o})e^{j\Omega_o n}$

unit sample response

straight convolution

using Discrete-time Fourier transforms

using Z-transforms

using Fourier eigenfunctions

6. if $x[n] = z^n$, then $y[n] = H(z)z^n$

using Z-eigenfunctions

7. if $x[n] = cos(\Omega_o n + \phi)$ and h[n] is real, then $y[n] = |H(e^{j\Omega_o})|cos(\Omega_o n + \phi + \Delta H(e^{j\Omega_o}))$

steady-state sinusoidal response

8. if $x[n] = sin(\Omega_o n + \phi)$ and h[n] is real, then $y[n] = |H(e^{j\Omega_o})|sin(\Omega_o n + \phi + \Delta H(e^{j\Omega_o}))$

steady-state sinusoidal response

• the transfer function and consequently the impulse response can be derived from any LDE by assuming zero initial conditions.

Discrete-time Fourier Transform

Definition of Discrete-time Fourier Transform:

The Discrete-time Fourier transform $X(\Omega)$ is a decomposition of an (a)periodic signal x[n] into $e^{j\Omega n}$ -type signals with Ω real (x[n] and $X(\Omega)$ uniquely define each other). $X(\Omega)$ is periodic in Ω with period 2π . We write $x[n] \stackrel{\mathcal{F}}{\longleftrightarrow} X(\Omega)$:

• $x[n] = \mathcal{F}^{-1}[X(\Omega)] = \frac{1}{2\pi} \int_{\Omega_o}^{\Omega_o + 2\pi} X(\Omega) e^{jn\Omega} d\Omega$ synthesis equation • $X(\Omega) = \mathcal{F}[x(t)] = \sum_{n=-\infty}^{\infty} x[n]e^{-jn\Omega}$ analysis equation

The discrete-time Fourier transform $X(\Omega)$ exists when it's finite for all Ω . The interpretation of the discrete-time Fourier transform is that $X(\omega)$ contains the frequency content of the signal x[n]. The **DTFT** is always periodic. Often, the DTFT of a discrete-time signal can be found more easily, by writing x[n] as a sampled continuous-time signal $x[n] = x(nT) = \sum_{n=-\infty}^{\infty} x(nT)\delta(t \Leftrightarrow nT)$, which has Fourier transform $\sum_{n=-\infty}^{\infty} x(nT)e^{-j\omega nT}; \text{ the change of variables } \omega T = \Omega \text{ gives the DTFT of } x[n]: X(\Omega) = \sum_{n=-\infty}^{\infty} x[n]e^{-jn\Omega} \text{ (EXTREMELY HELPFUL!)}.$

Properties of Discrete-time Fourier Transforms (given $x[n] \stackrel{\mathcal{F}}{\longleftrightarrow} X(\Omega)$):

- real signals: if x[n] is real, then $X(\Omega) = X^*(\Leftrightarrow\Omega)$ • check results
 - $\mathcal{R}e[X(\Omega)] = \mathcal{R}e[X(\Leftrightarrow\Omega)] \text{ and } \mathcal{I}m[X(\Omega)] = \Leftrightarrow \mathcal{I}m[X(\Leftrightarrow\Omega)]$ • check results
- if x[n] is real and even in n, then $X(\Omega)$ is real and even in Ω • real and even signals: • check results $\mathcal{E}v[x[n]] \stackrel{\mathcal{F}}{\longleftrightarrow} \mathcal{R}e[X(\Omega)] \text{ and } \mathcal{R}e[x[n]] \stackrel{\mathcal{F}}{\longleftrightarrow} \mathcal{E}v[X(\Omega)]$ • check results
- if x[n] is real and odd in n, then $X(\Omega)$ is imaginary and odd in Ω • real and odd signals: • check results
- $\mathcal{O}d[x[n]] \stackrel{\mathcal{F}}{\longleftrightarrow} j\mathcal{I}m[X(\Omega)] \text{ and } j\mathcal{I}m[x[n]] \stackrel{\mathcal{F}}{\longleftrightarrow} \mathcal{O}d[X(\Omega)]$ • check results
- $x[\Leftrightarrow n] \stackrel{\mathcal{F}}{\longleftrightarrow} X(\Leftrightarrow \Omega)$ • time reversal: $x^*[n] \stackrel{\mathcal{F}}{\longleftrightarrow} X^*(\Leftrightarrow\Omega)$ • complex conjugate:
- $\alpha_1 x_1[n] + \alpha_2 x_2[n] \stackrel{\mathcal{F}}{\longleftrightarrow} \alpha_1 X_1(\Omega) + \alpha_2 X_2(\Omega)$ • linearity:
- $x[n \Leftrightarrow n_o] \stackrel{\mathcal{F}}{\longleftrightarrow} X(\Omega)e^{-jn_o\Omega}$ • delay:
- $x[n]e^{j\Omega_o n} \stackrel{\mathcal{F}}{\longleftrightarrow} X(\Omega \Leftrightarrow \Omega_o)$ • frequency translation:
- $x[n] \Leftrightarrow x[n \Leftrightarrow 1] \stackrel{\mathcal{F}}{\longleftrightarrow} X(\Omega)(1 \Leftrightarrow e^{-j\Omega})$ • first difference:
- $u[n] \otimes x[n] \stackrel{\mathcal{F}}{\longleftrightarrow} \frac{1}{1 e^{-j\Omega}} X(\Omega) + \pi X(0) \sum_{k=-\infty}^{\infty} \delta(\Omega \Leftrightarrow 2\pi k)$ • running sum:
- convolution:
- $x_1[n] \otimes x_2[n] \xrightarrow{\mathcal{F}} X_1(\Omega) \cdot X_2(\Omega)$ $x_1[n] \cdot x_2[n] \xrightarrow{\mathcal{F}} \frac{1}{2\pi} \int_{\Omega_0}^{\Omega_0 + 2\pi} X_1(\theta) \otimes X_2(\Omega \Leftrightarrow \theta) d\theta$ • multiplication:
- n-multiplication: $n x[n] \stackrel{\mathcal{F}}{\longleftrightarrow} j \frac{d}{d\Omega} X(\Omega)$ $x_{(k)}[n] \stackrel{\mathcal{F}}{\longleftrightarrow} X(k\Omega)$ • upsampling:
- $E = \sum_{n=-\infty}^{\infty} |x[n]|^2 = \frac{1}{2\pi} \int_{\Omega_o}^{\Omega_o + 2\pi} |X(\Omega)|^2 d\Omega$ • PARSEVAL's identity:

- phase change (of $\Leftrightarrow n_o\Omega$) only
- used for modulation
- δ -functions account for DC in x[n]
- periodic convolution
- $x_{(k)}[n] = x[\frac{n}{k}]$, if n is a multiple of k and 0 otherwise

Some Examples

- $h[n] \stackrel{\mathcal{F}}{\longleftrightarrow} H(\Omega)$
- $\sin \Omega_o n \stackrel{\mathcal{F}}{\longleftrightarrow} \frac{\pi}{j} \sum_{k=-\infty}^{\infty} \left[\delta(\Omega \Leftrightarrow \Omega_o \Leftrightarrow 2\pi k) \Leftrightarrow \delta(\Omega + \Omega_o \Leftrightarrow 2\pi k) \right]$ $\cos \Omega_o n \stackrel{\mathcal{F}}{\longleftrightarrow} \pi \sum_{k=-\infty}^{\infty} \left[\delta(\Omega \Leftrightarrow \Omega_o \Leftrightarrow 2\pi k) + \delta(\Omega + \Omega_o \Leftrightarrow 2\pi k) \right]$
- $\bullet \ 0 \stackrel{\mathcal{F}}{\longleftrightarrow} \ 0$
- $\delta[n] \stackrel{\mathcal{F}}{\longleftrightarrow} 1$
- $u[n] \stackrel{\mathcal{F}}{\longleftrightarrow} \frac{1}{1 e^{j\Omega}} + \pi \sum_{k = -\infty}^{\infty} \delta(\Omega \Leftrightarrow 2\pi k)$ $\frac{\Omega_1}{\pi} sinc(\frac{\Omega_1 n}{\pi}) \stackrel{\mathcal{F}}{\longleftrightarrow} \sum_{k = -\infty}^{\infty} \Pi(\frac{\Omega 2\pi k}{2\Omega_1})$

- frequency response
- $1 \stackrel{\mathcal{F}}{\longleftrightarrow} 2\pi \sum_{k=-\infty}^{\infty} \delta(\Omega \Leftrightarrow 2\pi k)$ $\delta[n \Leftrightarrow n_o] \stackrel{\mathcal{F}}{\longleftrightarrow} e^{-jn_o\Omega}$
- $e^{j\Omega_o n} \stackrel{\mathcal{F}}{\longleftrightarrow} 2\pi \sum_{k=-in\,ftv}^{\infty} \delta(\Omega \Leftrightarrow \Omega_o \Leftrightarrow 2\pi k)$

Z-Transform or DT Laplace Transform

Definition of Z-Transform:

The **Z-transform** X(z) is a decomposition of an (a)periodic signal x(t) into signals of the type $z^{-n} = r^{-n}e^{-jn\Omega}$ with $z = re^{j\Omega}$ complex. Compared to the discrete-time Fourier transform, the extra (real) exponential r^{-n} allows us to treat a broader class of signals. The r^{-n} part is used to model growth or decay, while the $e^{-jn\omega}$ part models the oscillatory behavior of x(t). Again, x[n] and X(z) uniquely define each other and here we write $x[n] \stackrel{\mathcal{Z}}{\longleftrightarrow} X(z)$:

```
• unilateral ZT: X(z) = \mathcal{Z}[x[n]] = \sum_{k=0}^{\infty} x[n]z^{-n}

(• bilateral ZT: X(z) = \mathcal{Z}[x[n]] = \sum_{k=-\infty}^{\infty} x[n]z^{-n})
```

Note that the UZT only works for (real world) "causal" signals while the BZT permits us to consider any signal; furthermore, if x[n] = 0 for n < 0 (causal) then the UZT and the BZT are the same. Both the UZT and the BZT have regions of convergence (ROC) over which the transform exists. A ROC is the range of values of z over which the integral converges. A ROC cannot contain a pole, in fact for causal signals/ systems, the ROC contains all z on the outside of the circle that crosses the outermost pole. If x[n] is of finite duration, $ROC_x = \mathbb{C}$, except possibly for z = 0 and $z = \infty$.

Any signal x[n] that is of exponential order, i.e. |x[n]| does not increase faster than $A c^n$ with A and c real constants, can be transformed into X(z). As an example of a signal that is not of exponential order, consider for instance $x[n] = 2^{n^2}u[n]$

Properties of Unilateral Z-Transforms (given rightsided $x[n] \stackrel{\mathcal{Z}}{\longleftrightarrow} X(z)$ with ROC_x):

• linearity:	$\alpha_1 x_1[n] + \alpha_2 x_2[n] \stackrel{\mathcal{Z}}{\longleftrightarrow} \alpha_1 X_1(z) + \alpha_2 X_2(z)$	at least $ROC_{x_1} \cap ROC_{x_2}$
• time reversal:	$x[\Leftrightarrow n] \stackrel{\mathcal{Z}}{\longleftrightarrow} X(z^{-1})$	$\{z \mid z^{-1} \in ROC_x\}$
• delay $(M > 0)$:	$x[n \Leftrightarrow M] \stackrel{\mathcal{Z}}{\longleftrightarrow} z^{-M}X(z)$	ROC_x
• advance $(M > 0)$:	$x[n+M] \stackrel{\mathcal{Z}}{\longleftrightarrow} z^M \{X(z) \Leftrightarrow x[M \Leftrightarrow 1]z^{-(M-1)} \Leftrightarrow \cdots \Leftrightarrow x[0]\}$	ROC_x
• frequency translation:	$x[n]p^{-n} \stackrel{\mathcal{Z}}{\longleftrightarrow} X(pz)$	$\{z \mid pz \in ROC_x\}$
• running sum:	$u[n] \otimes x[n] = \sum_{k=-\infty}^{n} x[k] \stackrel{\mathcal{Z}}{\longleftrightarrow} \frac{1}{1-z^{-1}} X(z)$	at least $ROC_x \cap \{z \mid z > 1\}$
• convolution:	$x_1[n] \otimes x_2[n] \stackrel{\mathcal{Z}}{\longleftrightarrow} X_1(z) \cdot X_2(z)$	at least $ROC_{x_1} \cap ROC_{x_2}$
ullet n-multiplication:	$n \cdot x[n] \stackrel{\mathcal{Z}}{\longleftrightarrow} \Leftrightarrow z \frac{dX(z)}{dz}$	ROC_x
• initial value:	$\lim_{z\to\infty} X(z) = x[0]$, which always exists	
• final value:	$\lim_{z\to 1} (1 \Leftrightarrow z^{-1})X(z) = \lim_{n\to\infty} x[n]$, if this limit exists	
FOR A TWOSIDED $x[n] \stackrel{\mathcal{Z}}{\longleftrightarrow}$	X(z) (useful for INITIAL CONDITIONS in LDEs):	

 $x[n \Leftrightarrow M] \stackrel{\mathcal{Z}}{\longleftrightarrow} z^{-M}X(z) + \{x[\Leftrightarrow M] + x[\Leftrightarrow M+1]z^{-1} + \dots + x[\Leftrightarrow 1]z^{-M+1}\}$

Some Examples

• delay (M > 0):

• $h[n] \stackrel{\mathcal{Z}}{\longleftrightarrow} H(z)$	transfer function				
$\bullet \ 0 \stackrel{\mathcal{Z}}{\longleftrightarrow} \ 0$					
$ullet$ $\delta[n] \stackrel{\mathcal{Z}}{\longleftrightarrow} 1$	$\mathbf{all}\ z$	• $\delta[n \Leftrightarrow M] \stackrel{\mathcal{Z}}{\longleftrightarrow} z^{-M}$	all s except 0 (∞) if $m > 0$ $(m < 0)$		
• $u[n] \stackrel{\mathcal{Z}}{\longleftrightarrow} \frac{1}{1-z^{-1}}$	z > 1	• $u[\Leftrightarrow n \Leftrightarrow 1] \stackrel{\mathcal{Z}}{\longleftrightarrow} \frac{1}{1-z^{-1}}$	z < 1		
$\bullet \ \alpha^n u[n] \ \stackrel{\mathcal{Z}}{\longleftrightarrow} \ \frac{1}{1 - \alpha z^{-1}}$	$ z > \alpha $	• $\Leftrightarrow \alpha^n u [\Leftrightarrow n \Leftrightarrow 1] \stackrel{\mathcal{Z}}{\longleftrightarrow} \frac{1}{1-\alpha z^{-1}}$	$ z < \alpha $		
$\bullet \ n\alpha^n u[n] \stackrel{\mathcal{Z}}{\longleftrightarrow} \frac{\alpha z^{-1}}{(1-\alpha z^{-1})^2}$	$ z > \alpha $	• $\Leftrightarrow n\alpha^n u [\Leftrightarrow n \Leftrightarrow 1] \stackrel{\mathcal{Z}}{\longleftrightarrow} \frac{\alpha z^{-1}}{(1-\alpha z^{-1})^2}$	$ z < \alpha $		
• $[\cos\Omega_o n]u[n] \stackrel{\overset{\sim}{\mathcal{Z}}}{\longleftrightarrow} \frac{1 - [\cos\Omega_o]z^{-1}}{1 - [2\cos\Omega_o]z^{-1} + z^{-2}}$	z > 1	• $[sin\Omega_o n]u[n] \stackrel{\mathcal{Z}}{\longleftrightarrow} \frac{[sin\Omega_o]z^{-1}}{1-[2cos\Omega_o]z^{-1}+z^{-2}}$	z > 1		
$\bullet \ [r^n cos\Omega_o n] u[n] \ \stackrel{\mathcal{Z}}{\longleftrightarrow} \ \frac{1 - [r cos\Omega_o] z^{-1}}{1 - [2r cos\Omega_o] z^{-1} + r^2 z^{-2}}$	z > r	$\bullet \ [r^n sin\Omega_o n] u[n] \ \stackrel{\mathcal{Z}}{\longleftrightarrow} \ \frac{[r sin\Omega_o] z^{-1}}{1 - [2r cos\Omega_o] z^{-1} + r^2 z^{-2}}$	z > r		

Linear Difference Equations

Solving LDE w/CC using Z-transforms

We show how the unilateral Z-transform can be used to solve linear differential equations with constant coefficients. In particular, the delay property of the unilateral Z-transform is utilized. The procedures are not shown for the general case, but rather for an example.

Example: Assume we are given the following LDE w/CC that we are trying to solve:

$$y[n] \Leftrightarrow 2y[n \Leftrightarrow 1] = x[n] + x[n \Leftrightarrow 1]$$

with initial conditions $y[\Leftrightarrow 1] = 1$ and $x[\Leftrightarrow 1] = 0$.

First, take the unilateral Z-transform of both sides, using the delay property:

$$Y(z) \Leftrightarrow [2z^{-1}Y(z) + 2y[\Leftrightarrow 1]] = X(z) + [z^{-1}X(z) + x[\Leftrightarrow 1]] \iff$$

$$\iff Y(z) = \frac{1 + z^{-1}}{(1 \Leftrightarrow z^{-1})(1 \Leftrightarrow 2z^{-1})} + \frac{x[\Leftrightarrow 1] + 2y[\Leftrightarrow 1]}{1 \Leftrightarrow 2z^{-1}},$$

wherein inverse Z-transform of the first part equals the zero-state-response:

$$y_{zsr}[n] = \mathcal{Z}\left[\frac{1+z^{-1}}{(1 \Leftrightarrow z^{-1})(1 \Leftrightarrow 2z^{-1})}\right] = \mathcal{Z}\left[\frac{1}{(1 \Leftrightarrow z^{-1})(1 \Leftrightarrow 2z^{-1})}\right] + \mathcal{Z}\left[\frac{z^{-1}}{(1 \Leftrightarrow z^{-1})(1 \Leftrightarrow 2z^{-1})}\right] = (\delta[n] + \delta[n \Leftrightarrow 1]) \otimes \mathcal{Z}\left[\frac{1}{(1 \Leftrightarrow z^{-1})(1 \Leftrightarrow 2z^{-1})}\right] = (\delta[n] + \delta[n \Leftrightarrow 1]) \otimes \mathcal{Z}\left[\frac{1}{(1 \Leftrightarrow z^{-1})(1 \Leftrightarrow 2z^{-1})}\right] = (\delta[n] + \delta[n \Leftrightarrow 1]) \otimes \mathcal{Z}\left[\frac{1}{(1 \Leftrightarrow z^{-1})(1 \Leftrightarrow 2z^{-1})}\right] = (\delta[n] + \delta[n \Leftrightarrow 1]) \otimes \mathcal{Z}\left[\frac{1}{(1 \Leftrightarrow z^{-1})(1 \Leftrightarrow 2z^{-1})}\right] = (\delta[n] + \delta[n \Leftrightarrow 1]) \otimes \mathcal{Z}\left[\frac{1}{(1 \Leftrightarrow z^{-1})(1 \Leftrightarrow 2z^{-1})}\right] = (\delta[n] + \delta[n \Leftrightarrow 1]) \otimes \mathcal{Z}\left[\frac{1}{(1 \Leftrightarrow z^{-1})(1 \Leftrightarrow 2z^{-1})}\right] = (\delta[n] + \delta[n \Leftrightarrow 1]) \otimes \mathcal{Z}\left[\frac{1}{(1 \Leftrightarrow z^{-1})(1 \Leftrightarrow 2z^{-1})}\right] = (\delta[n] + \delta[n \Leftrightarrow 1]) \otimes \mathcal{Z}\left[\frac{1}{(1 \Leftrightarrow z^{-1})(1 \Leftrightarrow 2z^{-1})}\right] = (\delta[n] + \delta[n \Leftrightarrow 1]) \otimes \mathcal{Z}\left[\frac{1}{(1 \Leftrightarrow z^{-1})(1 \Leftrightarrow 2z^{-1})}\right] = (\delta[n] + \delta[n \Leftrightarrow 1]) \otimes \mathcal{Z}\left[\frac{1}{(1 \Leftrightarrow z^{-1})(1 \Leftrightarrow 2z^{-1})}\right] = (\delta[n] + \delta[n \Leftrightarrow 1]) \otimes \mathcal{Z}\left[\frac{1}{(1 \Leftrightarrow z^{-1})(1 \Leftrightarrow 2z^{-1})}\right] = (\delta[n] + \delta[n \Leftrightarrow 1]) \otimes \mathcal{Z}\left[\frac{1}{(1 \Leftrightarrow z^{-1})(1 \Leftrightarrow 2z^{-1})}\right] = (\delta[n] + \delta[n \Leftrightarrow 1]) \otimes \mathcal{Z}\left[\frac{1}{(1 \Leftrightarrow z^{-1})(1 \Leftrightarrow 2z^{-1})}\right] = (\delta[n] + \delta[n \Leftrightarrow 1]) \otimes \mathcal{Z}\left[\frac{1}{(1 \Leftrightarrow z^{-1})(1 \Leftrightarrow 2z^{-1})}\right] = (\delta[n] + \delta[n \Leftrightarrow 1]) \otimes (\delta[n] + \delta[n] + \delta[n \Leftrightarrow 1]) \otimes (\delta[n] + \delta[n] + \delta[n]) \otimes (\delta[n] + \delta[n] + \delta[n]) \otimes (\delta[n] + \delta[n] + \delta[n]) \otimes (\delta[n] + \delta[n]) \otimes (\delta[n]) \otimes (\delta[n] + \delta[n]) \otimes (\delta[n]) \otimes (\delta[n] + \delta[n]) \otimes (\delta[n] + \delta[n]) \otimes (\delta[n])$$

Secondly, we have the zero-input-response:

$$y_{zir}[n] = \mathcal{Z}\left[\frac{2}{(1 \Leftrightarrow 2z^{-1})}\right] = 2 \cdot 2^n u[n] = 2^{n+1} u[n].$$

The actual output y[n] is the sum of the two:

$$y[n] = y_{zir}[n] + y_{zir}[n] = \Leftrightarrow u[n] \Leftrightarrow u[n \Leftrightarrow 1] + 2^{n+1}u[n] + 2^nu[n \Leftrightarrow 1] + 2^{n+1}u[n] = \Leftrightarrow u[n] \Leftrightarrow u[n \Leftrightarrow 1] + 2^{n+2}u[n] + 2^nu[n \Leftrightarrow 1].$$

Partial Fraction Expansions

Suppose we are given $Y(z) = \frac{1}{(1-z^{-1})(1-2z^{-1})}$ (see also above) that we wish to expand into partial fractions. The procedure for doing this, is to first factor and expand into partial fractions $\frac{Y(z)}{z}$, expressed in terms of z:

$$\frac{Y(z)}{z} = \frac{z}{z} \cdot \frac{1}{(1 \Leftrightarrow z^{-1})(1 \Leftrightarrow 2z^{-1})} = \frac{z}{(z \Leftrightarrow 1)(z \Leftrightarrow 2)} = \frac{\Leftrightarrow 1}{z \Leftrightarrow 1} + \frac{2}{z \Leftrightarrow 2},$$

whereafter we multiply both sides again by z and write the partial fractions in terms of z^{-1} , so that we can use the Z-transform tables in order to find y[n]:

$$Y(z) = \frac{\Leftrightarrow 1}{1 \Leftrightarrow z^{-1}} + \frac{2}{1 \Leftrightarrow 2z^{-1}} \implies y[n] = \Leftrightarrow u[n] + 2 \cdot 2^n u[n] = \Leftrightarrow u[n] + 2^{n+1} u[n].$$

Comparison of FS and FT

Decomposing a periodic signal into discrete frequencies, each a multiple of some basic frequency ω_o , gives us the Fourier series representation of that signal. With Fourier transforms, we can decompose aperiodic signals into its component frequencies, which, however, are not multiples of some frequency, but rather range from $\omega = \Leftrightarrow \infty$ to $\omega = \infty$. For periodic signals, x(t), $\mathcal{F}[x(t)]$ and the FS representation all carry the same information.

How to get from FS to FT? If a periodic signal x(t) is written as a Fourier Series, $x(t) = \sum_{n=-\infty}^{\infty} X_n e^{jn\omega_o t}$, then its Fourier Transform is

$$X(\omega) = \mathcal{F}[x(t)] = \mathcal{F}[\sum_{n=-\infty}^{\infty} X_n e^{jn\omega_o t}] = \sum_{n=-\infty}^{\infty} X_n \mathcal{F}[e^{jn\omega_o t}] = 2\pi \sum_{n=-\infty}^{\infty} X_n \delta(\omega \Leftrightarrow n\omega_o).$$

How to get from FT to FS (if the signal is periodic)? If a periodic signal x(t) is written as a Fourier Series,

$$X_n = \frac{1}{T_o} X(\omega) \mid_{\omega = n\omega_o}.$$

THIS SECTION IS FINISHED NOR CLEAR TO MYSELF; APOLOGIES

Comparison of FT and ULT

The Laplace transform is a more general transform than the Fourier transform, meaning that it can be used for all signals that can be Fourier transformed, and more. From the definitions, the relationship between the Laplace and Fourier transform seems to follow relatively straightforwardly:

$$X(s) = \mathcal{F}[x(t) e^{-\sigma t}]$$
 and $\mathcal{F}[x(t)] = X(j\omega)$

However, we should distinguish between three cases:

Case (a): when ROC_x includes the $j\omega$ -axis then $X(s)|_{s=j\omega}=X(j\omega)=\mathcal{F}[x(t)]$ and $\mathcal{F}^{-1}[X(j\omega)]=x(t)$.

Case (b): when ROC_x is just bounded by the $j\omega$ -axis then $\mathcal{F}[x(t)]$ can sometimes be computed, but if so, then $\mathcal{F}[x(t)] \neq X(j\omega)$ and $\mathcal{F}^{-1}[X(j\omega)] \neq x(t)$. For example, $u(t) \stackrel{\mathcal{L}}{\longleftrightarrow} \frac{1}{s}$ with $ROC = \{s \mid \text{Re}[s] > 0\}$, but $u(t) \stackrel{\mathcal{F}}{\longleftrightarrow} \frac{1}{j\omega} + \pi\delta(\omega) \neq \frac{1}{j\omega} = X(j\omega)$. Furthermore, $\mathcal{F}^{-1}[\frac{1}{j\omega}] = \frac{1}{2}sgn(t)$.

Case (c): when ROC_x doesn't include the $j\omega$ -axis then $\mathcal{F}[x(t)]$ cannot be computed. Although $X(j\omega)$ may be defined, $\mathcal{F}^{-1}[X(j\omega)] \neq x(t)$. For example, $e^t u(t) \xleftarrow{\mathcal{L}} \frac{1}{s-1}$ with $ROC = \{s \mid \mathcal{R} \mid [s] > 1\}$; $\mathcal{F}[e^t u(t)]$ is undefined and $\mathcal{F}^{-1}[\frac{1}{j\omega-1}] = \Leftrightarrow e^{-t} u(\Leftrightarrow t)$.

• $\mathcal{F}^{-1}\left[\frac{1}{i\omega-\alpha}\right] = \Leftrightarrow e^{\alpha t}u(\Leftrightarrow t)$ for complex α

•
$$\mathcal{F}^{-1}[\frac{1}{1-\omega^2}] = \mathcal{F}^{-1}[\frac{1}{(j\omega+j)(j\omega-j)}] = \mathcal{F}^{-1}[\frac{\frac{j}{2}}{(j\omega+j)}] \Leftrightarrow \mathcal{F}^{-1}[\frac{\frac{j}{2}}{(j\omega-j)}] = \frac{j}{4}sgn(t)(e^{-jt} + e^{jt}) = \frac{1}{2}sgn(t)sin(t)$$

Comparison of DTFT and UZT

The Z-transform is a more general transform than the discrete-time Fourier transform, meaning that it can be used for all signals that can be Fourier transformed, and more. From the definitions, the relationship between the Laplace and Fourier transform seems to follow relatively straightforwardly:

$$X(z) = \mathcal{F}[x[n] r^{-n}]$$
 and $\mathcal{F}[x[n]] = X(e^{j\Omega})$

However, as above, we should distinguish between the cases where the ROC contains the unit circle (given by $|z| = 1 \Leftrightarrow z = e^{j\Omega}$), is just bounded by it, or does not contain it at all. These three cases lead to perfectly similar conclusion about the existence of the Fourier transform as in the continuous-time case above.

Modulation

NOTE: • modulators are generally time-variant systems;

- some modulators are linear, some non-linear;
- asynchronous demodulators can only demodulate DSB-AM-LC;
- synchronous demodulators can demodulate all linear schemes discussed;
- (with synchronous we mean that the received signal is multiplied with a copy of the carrier;)
- WB-FM is much more **noise immune** than AM, since noise mainly effects the amplitude of a signal and not so much the (instantaneous) frequency; furthermore, the amount of used bandwidth is much larger for WB-FM, leading to better noise immunity.

Motivation for Modulation

- baseband signals will not propagate, but higher frequency signals will;
- in order to simultaneously send multiple signals, one must use (distinct) carrier frequencies to prevent (limit) interference.

Assumptions and Terminology

- In H[m(t)] = x(t), $H[\cdot]$ is the modulation system, m(t) the message or modulating signal and x(t) the transmitted modulated signal;
- the message signal, $m(t) \stackrel{\mathcal{F}}{\longleftrightarrow} M(\omega)$, is bandlimited to $|\omega| \leq 2\pi B_M \ rad/s$; furthermore, we assume $|m(t)| \leq 1$, $\forall t$;
- the modulated signal, $x(t) \stackrel{\mathcal{F}}{\longleftrightarrow} X(\omega)$, is a narrowband bandpass signal, centered at ω_c and has bandwidth $2\pi B_X \ll \omega_c \, rad/s$;

Underlying Fourier Transform Properties

- $\bullet \ e^{j\omega_o t} \ \stackrel{\mathcal{F}}{\longleftrightarrow} \ 2\pi\delta(\omega \Leftrightarrow \omega_o)$
- $x(t)e^{j\omega_o t} \stackrel{\mathcal{F}}{\longleftrightarrow} X(\omega \Leftrightarrow \omega_o)$
- frequency translation

Overview of Analog Modulation Systems

Amplitude Modulation (linear): • Double-Sideband Amplitude Modulation (DSB-AM)

- Double-Sideband Amplitude Modulation with Large Carrier (DSB-AM-LC; a.k.a. broadcast AM)
- Single-Sideband Amplitude Modulation (SSB-AM)
- Quadrature Amplitude Modulation (QAM; see notes 15)

Angle Modulation (non-linear): • Narrowband Frequence Modulation (NB-FM)

- Narrowband Phase Modulation (NB-PM)
- Wideband Frequency Modulation (WB-FM)
- Wideband Phase Modulation (WB-PM)

• modulation: $H[m(t)] = x(t) = m(t)\cos\omega_c t \stackrel{\mathcal{F}}{\longleftrightarrow} X(\omega) = \frac{1}{2\pi}M(\omega) \otimes \pi[\delta(\omega + \omega_c) + \delta(\omega \Leftrightarrow \omega_c)] = \frac{1}{2}[M(\omega + \omega_c) + M(\omega \Leftrightarrow \omega_c)];$

• demodulation: $y(t) = x(t)\cos\omega_c t = m(t)\cos^2\omega_c t = \frac{1}{2}m(t) + \frac{1}{2}m(t)\cos 2\omega_c t \iff Y(\omega) = \frac{1}{2}M(\omega) + \frac{1}{4}[M(\omega + 2\omega_c) + M(\omega \Leftrightarrow 2\omega_c)];$ subsequently, an ideal LPF with $H_{lpf}(\omega) = 1(0)$, $|\omega| \leq (>)2\pi B_M$ passes $\frac{1}{2}m(t)$ only;

• remarks: • demodulator must have the cos ωct carrier in phase lock to carrier at modulator, which requires a phase locked loop;

• you can demodulate SSB-AM using imperfect carrier $cos(\omega_c t + \theta)$: received signal is $\frac{1}{2}cos(\theta) m(t)$: fine as long as $cos(\theta) \neq 0$;

• you can demodulate SSB-AM using imperfect carrier $cos([\omega_c + \Delta\omega]t)$;

• the modulated signal x(t) takes up twice the bandwidth $2\pi B_M$ of the message signal m(t): $B_X = 2B_M$;

ullet DSB-AM: power-efficient, wastes bandwidth, requires synchronized reception.

Double-Sideband Amplitude Modulation w/ Large Carrier (DSB-AM-LC)

• modulation: $H[m(t)] = x(t) = [1 + \mu m(t)] \cos \omega_c t \stackrel{\mathcal{F}}{\longleftrightarrow} X(\omega) = \pi [\delta(\omega + \omega_c) + \delta(\omega \Leftrightarrow \omega_c)] + \frac{\mu}{2} [M(\omega \Leftrightarrow \omega_c) + M(\omega + \omega_c)];$

• demodulation: (sync) $y(t) = x(t)\cos\omega_c t = [1 + \mu m(t)]\cos^2\omega_c t = \stackrel{\mathcal{F}}{\longleftrightarrow} Y(\omega) = \mu Y_{\text{DSB-AM}}(\omega) + \frac{\pi}{4}[\delta(\omega \Leftrightarrow 2\omega_c) + 2\delta(\omega) + \delta(\omega + 2\omega_c)];$

subsequently, an ideal LPF with $H_{lpf}(\omega)=1(0), \ |\omega|\leq (>)2\pi B_M$ passes $\frac{1}{4}+\frac{\mu}{2}m(t)$ only;

(async) $x(t) \Leftrightarrow \text{rectifier} \Leftrightarrow y(t) = |x(t)| \Leftrightarrow \text{LPF} \Leftrightarrow z(t) = 1 + \mu m(t) \Leftrightarrow \text{capacitor} \Leftrightarrow \mu m(t);$

• remarks: • demodulation of DSB-AM-LC can be done asynchronously, i.e. there is no need for synchronization of demodulator to modulator;

• μ is the modulation index;

• if the amplitude of $\mu m(t) = (>) 1$ we have full modulation (overmodulation \Leftrightarrow distorted recovery);

• power efficiency is poor (= $\frac{\frac{1}{2}\mu^2 P_M}{\frac{1}{2}(1+\mu^2 P_M)}$ < 50%), because of large carrier;

• the modulated signal x(t) takes up twice the bandwidth $2\pi B_M$ of the message signal m(t): $B_X = 2B_M$;

• DSB-AM-LC: power-inefficient, wastes bandwidth, does not require synchronized reception.

Single-Sideband Amplitude Modulation (SSB-AM)

Upper-Sideband Amplitude Modulation (USB-AM)

• modulation: $H[m(t)] = x_u(t) = m(t)\cos\omega_c t \Leftrightarrow \hat{m}(t)\sin\omega_c t \stackrel{\mathcal{F}}{\longleftrightarrow} X_u(\omega) = M(\omega + \omega_c)u(\Leftrightarrow\omega_c) + M(\omega \Leftrightarrow\omega_c)u(\omega \Leftrightarrow\omega_c);$

• demodulation: $y(t) = x_u(t) \cos \omega_c t = \cdots = \frac{1}{2}m(t) + \frac{1}{2}m(t) \cos 2\omega_c t \Leftrightarrow \frac{1}{2}\hat{m}(t) \sin 2\omega_c t \Leftrightarrow \text{LPF} \Leftrightarrow z(t) = \frac{1}{2}m(t);$

Lower-Sideband Amplitude Modulation (LSB-AM)

• modulation: $H[m(t)] = x_l(t) = m(t)\cos\omega_c t + \hat{m}(t)\sin\omega_c t \stackrel{\mathcal{F}}{\longleftrightarrow} X_l(\omega) = M(\omega + \omega_c)u(\omega + \omega_c) + M(\omega \Leftrightarrow \omega_c)u(\Leftrightarrow \omega + \omega_c);$

• demodulation: $y(t) = x_l(t)\cos\omega_c t = \cdots = \frac{1}{2}m(t) + \frac{1}{2}m(t)\cos 2\omega_c t + \frac{1}{2}\hat{m}(t)\sin 2\omega_c t \Leftrightarrow \text{LPF} \Leftrightarrow z(t) = \frac{1}{2}m(t);$

Remarks on SSB-AM

- Hilbert transformer is a system with $h_{HT}(t) = \frac{1}{\pi t}$ and $H_{HT}(\omega) = \Leftrightarrow j \, sgn(\omega) = e^{-j\frac{\pi}{2} \, sgn(\omega)}$ (phase shift); $\hat{x}(t) = x(t) \otimes h_{HT}$;
- power efficient: no carrier transmitted;

- bandwidth efficient: now the modulated signal x(t) takes up the same amount of bandwidth as the message signal: $B_X = B_M$.
- you can demodulate SSB-AM using imperfect carrier $cos(\omega_c t + \theta)$: received signal is $\frac{1}{2}cos(\theta) m(t)$: fine as long as $cos(\theta) \neq 0$ (see notes 15);
- you can demodulate SSB-AM using imperfect carrier $cos([\omega_c + \Delta\omega]t)$ (see notes 15);
- SSB-AM: power-efficient, no waste of bandwidth, requires synchronized reception.

Design of AM Receivers (DSB-AM-LC)

- total received signal is $x_{tot} = \sum_{n=1}^{N} [1 + \mu m_n(t)] \cos \omega_{cn} t$, the sum of N DSB-AM-LC signals; we need message signal $m_n(t)$ only;
- solution A: use a tunable BPF; however it is hard to make a (multi-stage) filter with sufficiently shapr cutoff;
- solution B: heterodyne receiver;
- solution C: superheterodyne receiver;
- SEE NOTES SEE NOTES SEE NOTES SEE NOTES

Angle Modulation (FM and PM)

- A: PM: $x(t) = A\cos[\omega_c t + \theta(t)]$, with $\theta(t) = \phi_{\Delta} m(t)$, with $|\phi_{\Delta}| \leq \pi$ the phase deviation constant;
 - $\theta(t) = \phi_{\Delta} m(t)$ is the instantaneous phase;
- B: FM: $x(t) = A \cos[\omega_c t + \theta(t)]$, with $\theta(t) = \omega_\Delta \int_{-\infty}^t m(s) ds$, with ω_Δ the frequency deviation constant;
 - $\omega(t) = \frac{d}{dt}[\omega_c t + \theta(t)] = \omega_c + \omega_{\Delta} m(t \text{ is the instantaneous frequency};$
- we speak of NARROWBAND angle modulation when $|\theta(t)| \ll 1$, hence $e^{j\theta(t)} \approx 1 + j\theta(t)$, so $x(t) \approx \cos \omega_c t \Leftrightarrow \theta(t) \sin \omega_c t$;
- note that in narrowband angle modulation a LARGE CARRIER $\cos \omega_c t$ is transmitted (inefficient!)

NARROWBAND PHASE MODULATION (NB-PM)

• modulation: $\theta = \phi_{\Delta} m(t)$, so $H[m(t)] = x(t) = \cos \omega_c t \Leftrightarrow \phi_{\Delta} m(t) \sin \omega_c t \stackrel{\mathcal{F}}{\longleftrightarrow} X(\omega) = \pi [\delta(\omega \Leftrightarrow \omega_c) + \delta(\omega + \omega_c)] + \frac{i}{2} \phi_{\Delta} [M(\omega \Leftrightarrow \omega_c) \Leftrightarrow M(\omega + \omega_c)]$ (similar to DSB-AM-LC);

NARROWBAND FREQUENCY MODULATION (NB-FM)

• modulation: $\theta = \omega_{\Delta} \int_{-\infty}^{t} m(s)ds, \text{ with } |\theta(t)| \ll 1, \text{ hence } m(t) \text{ cannot have a DC component, hence } M(\omega)|_{\omega=0} = 0;$ $H[m(t)] = x(t) = \cos \omega_{c}t \Leftrightarrow \theta(t) \sin \omega_{c}t \overset{\mathcal{F}}{\longleftrightarrow} X(\omega) = \pi[\delta(\omega \Leftrightarrow \omega_{c}) + \delta(\omega + \omega_{c})] + \frac{j}{2}[\Theta(\omega \Leftrightarrow \omega_{c}) \Leftrightarrow \Theta(\omega + \omega_{c})],$ with $\Theta(\omega) = \omega_{\Delta} \frac{M(\omega)}{j\omega}$, so $X(\omega) = \pi[\delta(\omega \Leftrightarrow \omega_{c}) + \delta(\omega + \omega_{c})] + \frac{\omega_{\Delta}}{2}[\frac{M(\omega - \omega_{c})}{\omega - \omega_{c}} \Leftrightarrow \frac{M(\omega + \omega_{c})}{\omega + \omega_{c}}];$

Examples of Systems and their Properties

			$_{ m time}$			BIBO
	system	$_{ m linear}$	invariant	causal	${f memoryless}$	\mathbf{stable}
(CT-1)	$y(t) = x(t) \otimes sin(t)u(t)$	yes	yes	yes	no	
,	$y(t) = x(t) \cdot cos(t)u(t)$	yes	no	yes	yes	
(CT-3)	$y(t) = \int_{-\infty}^{t} \sqrt{x(s)} ds$	no	yes	yes	no	
(CT-4)	y(t) = x(2t) + 1	no	no	no	no	
(CT-5)	$y(t) = x(t) \otimes e^t u(t+1)$	yes	yes	no	no	
,	$y(t) = x(\Leftrightarrow t)$	yes	no	no	no	
(CT-7)	$y(t) = \int_{-\infty}^{t-1} x(s)ds$	yes	yes	yes	no	
(CT-8)	$y(t) = \int_{-\infty}^{t} e^{-(t-s)} x^2(s) ds$	no	yes	yes	no	
(CT-9)	y(t) = x(t)	no	yes	yes	yes	
(CT-10)	$y(t) = \int_{-\infty}^{\infty} e^{- t-s } x(s) ds$	yes	yes	no	no	
(DT-1)	y[n] = 0	yes	yes	yes		yes
(DT-2)	$y[n] = \cos(n)2^{x[n]}$	no	no	yes		yes
	$y[n] + y[n \Leftrightarrow 1] = x[n]$	yes	yes	\mathbf{yes}		no
(DT-4)	$y[n] = \sum_{k=-\infty}^{n} x[k]$	yes	yes	yes		no

Electronics

1. v(t) = i(t)R

2. R_1 and R_2 in series equals $R_1 + R_2$

3. R_1 and R_2 in parallel equals $(R_1^{-1} + R_2^{-1})^{-1}$

4. $i(t) = C \frac{dv(t)}{dt}$

5. C_1 and C_2 in series equals $(C_1^{-1} + C_2^{-1})^{-1}$

6. C_1 and C_2 in parallel equals $C_1 + C_2$

7. $v(t) = L \frac{di(t)}{dt}$

8. L_1 and L_2 in series equals

9. L_1 and L_2 in parallel equals

10. KCL

11. KVL

RESISTOR

 $I \text{ same; } V = V_1 + V_2 \text{ (splits)}$

V same; $I = I_1 + I_2$ (splits)

CAPACITOR

q (charge) same; $V = qC^{-1}$


V same; q = CV

INDUCTOR

Kirchoff's Current Law (KCL)

Kirchoff's Voltage Law (KVL)

- inductors and capacitors (amount of charge) are components with memory.
- ullet resistors and opamps are memoryless components.
- a circuit with an L and a C in parallel is of order 2; a circuit with two L's or C's in parallel is of order 1.



 $Figure \ 0.1: \ Relations \ between \ System \ Descriptors.$




Figure 0.2: Relations between System Descriptors.