# libuv documentation

Release 1.14.1-dev

libuv contributors

# Contents

1	Overview	1
2	Features	3
3	Documentation	5
4	Downloads	119
5	Installation	121

			- 4
CHA	PT	FF	₹I

## Overview

libuv is a multi-platform support library with a focus on asynchronous I/O. It was primarily developed for use by Node.js, but it's also used by Luvit, Julia, pyuv, and others.

**Note:** In case you find errors in this documentation you can help by sending pull requests!

# CHAPTER 2

## **Features**

- Full-featured event loop backed by epoll, kqueue, IOCP, event ports.
- Asynchronous TCP and UDP sockets
- Asynchronous DNS resolution
- Asynchronous file and file system operations
- File system events
- ANSI escape code controlled TTY
- IPC with socket sharing, using Unix domain sockets or named pipes (Windows)
- Child processes
- Thread pool
- Signal handling
- High resolution clock
- Threading and synchronization primitives

4 Chapter 2. Features

# CHAPTER 3


## **Documentation**

## **Design overview**

libuv is cross-platform support library which was originally written for NodeJS. It's designed around the event-driven asynchronous I/O model.

The library provides much more than a simple abstraction over different I/O polling mechanisms: 'handles' and 'streams' provide a high level abstraction for sockets and other entities; cross-platform file I/O and threading functionality is also provided, amongst other things.

Here is a diagram illustrating the different parts that compose libuv and what subsystem they relate to:



## Handles and requests

libusy provides users with 2 abstractions to work with, in combination with the event loop: handles and requests.

Handles represent long-lived objects capable of performing certain operations while active. Some examples:

- A prepare handle gets its callback called once every loop iteration when active.
- A TCP server handle that gets its connection callback called every time there is a new connection.


Requests represent (typically) short-lived operations. These operations can be performed over a handle: write requests are used to write data on a handle; or standalone: getaddrinfo requests don't need a handle they run directly on the loop.

## The I/O loop

The I/O (or event) loop is the central part of libuv. It establishes the content for all I/O operations, and it's meant to be tied to a single thread. One can run multiple event loops as long as each runs in a different thread. The libuv event loop (or any other API involving the loop or handles, for that matter) is not thread-safe except where stated otherwise.

The event loop follows the rather usual single threaded asynchronous I/O approach: all (network) I/O is performed on non-blocking sockets which are polled using the best mechanism available on the given platform: epoll on Linux, kqueue on OSX and other BSDs, event ports on SunOS and IOCP on Windows. As part of a loop iteration the loop will block waiting for I/O activity on sockets which have been added to the poller and callbacks will be fired indicating socket conditions (readable, writable hangup) so handles can read, write or perform the desired I/O operation.

In order to better understand how the event loop operates, the following diagram illustrates all stages of a loop iteration:



- 1. The loop concept of 'now' is updated. The event loop caches the current time at the start of the event loop tick in order to reduce the number of time-related system calls.
- 2. If the loop is *alive* an iteration is started, otherwise the loop will exit immediately. So, when is a loop considered to be *alive*? If a loop has active and ref'd handles, active requests or closing handles it's considered to be *alive*.
- 3. Due timers are run. All active timers scheduled for a time before the loop's concept of *now* get their callbacks called.

- 4. Pending callbacks are called. All I/O callbacks are called right after polling for I/O, for the most part. There are cases, however, in which calling such a callback is deferred for the next loop iteration. If the previous iteration deferred any I/O callback it will be run at this point.
- 5. Idle handle callbacks are called. Despite the unfortunate name, idle handles are run on every loop iteration, if they are active.
- Prepare handle callbacks are called. Prepare handles get their callbacks called right before the loop will block for I/O.
- 7. Poll timeout is calculated. Before blocking for I/O the loop calculates for how long it should block. These are the rules when calculating the timeout:
  - If the loop was run with the UV\_RUN\_NOWAIT flag, the timeout is 0.
  - If the loop is going to be stopped (uv\_stop () was called), the timeout is 0.
  - If there are no active handles or requests, the timeout is 0.
  - If there are any idle handles active, the timeout is 0.
  - If there are any handles pending to be closed, the timeout is 0.
  - If none of the above cases matches, the timeout of the closest timer is taken, or if there are no active timers, infinity.
- 8. The loop blocks for I/O. At this point the loop will block for I/O for the duration calculated in the previous step. All I/O related handles that were monitoring a given file descriptor for a read or write operation get their callbacks called at this point.
- 9. Check handle callbacks are called. Check handles get their callbacks called right after the loop has blocked for I/O. Check handles are essentially the counterpart of prepare handles.
- 10. Close callbacks are called. If a handle was closed by calling uv\_close() it will get the close callback called.
- 11. Special case in case the loop was run with UV\_RUN\_ONCE, as it implies forward progress. It's possible that no I/O callbacks were fired after blocking for I/O, but some time has passed so there might be timers which are due, those timers get their callbacks called.
- 12. Iteration ends. If the loop was run with UV\_RUN\_NOWAIT or UV\_RUN\_ONCE modes the iteration ends and uv\_run() will return. If the loop was run with UV\_RUN\_DEFAULT it will continue from the start if it's still alive, otherwise it will also end.

**Important:** libuv uses a thread pool to make asynchronous file I/O operations possible, but network I/O is **always** performed in a single thread, each loop's thread.

**Note:** While the polling mechanism is different, libuv makes the execution model consistent across Unix systems and Windows.

#### File I/O

Unlike network I/O, there are no platform-specific file I/O primitives libuv could rely on, so the current approach is to run blocking file I/O operations in a thread pool.

For a thorough explanation of the cross-platform file I/O landscape, checkout this post.

libuv currently uses a global thread pool on which all loops can queue work on. 3 types of operations are currently run on this pool:

- File system operations
- DNS functions (getaddrinfo and getnameinfo)
- User specified code via uv\_queue\_work ()

**Warning:** See the *Thread pool work scheduling* section for more details, but keep in mind the thread pool size is quite limited.

## **API** documentation

## **Error handling**

In libuv errors are negative numbered constants. As a rule of thumb, whenever there is a status parameter, or an API functions returns an integer, a negative number will imply an error.

When a function which takes a callback returns an error, the callback will never be called.

**Note:** Implementation detail: on Unix error codes are the negated *errno* (or *-errno*), while on Windows they are defined by libuv to arbitrary negative numbers.

#### **Error constants**

#### UV E2BIG

argument list too long

## UV\_EACCES

permission denied

## UV\_EADDRINUSE

address already in use

#### UV EADDRNOTAVAIL

address not available

## UV\_EAFNOSUPPORT

address family not supported

## UV\_EAGAIN

resource temporarily unavailable

## UV EAI ADDRFAMILY

address family not supported

#### UV\_EAI\_AGAIN

temporary failure

## UV\_EAI\_BADFLAGS

bad ai\_flags value

## UV\_EAI\_BADHINTS

invalid value for hints

#### UV\_EAI\_CANCELED

request canceled

#### UV\_EAI\_FAIL

permanent failure

#### UV\_EAI\_FAMILY

ai\_family not supported

## UV EAI MEMORY

out of memory

## UV\_EAI\_NODATA

no address

## UV\_EAI\_NONAME

unknown node or service

## UV\_EAI\_OVERFLOW

argument buffer overflow

## UV\_EAI\_PROTOCOL

resolved protocol is unknown

#### UV EAI SERVICE

service not available for socket type

## UV\_EAI\_SOCKTYPE

socket type not supported

#### UV EALREADY

connection already in progress

#### UV EBADF

bad file descriptor

## UV\_EBUSY

resource busy or locked

## UV\_ECANCELED

operation canceled

## UV\_ECHARSET

invalid Unicode character

## UV\_ECONNABORTED

software caused connection abort

## UV ECONNREFUSED

connection refused

#### UV ECONNRESET

connection reset by peer

## UV\_EDESTADDRREQ

destination address required

## UV\_EEXIST

file already exists

### UV EFAULT

bad address in system call argument

## UV\_EFBIG

file too large

#### UV EHOSTUNREACH

host is unreachable

## UV\_EINTR

interrupted system call

## UV EINVAL

invalid argument

## UV\_EIO

i/o error

#### UV EISCONN

socket is already connected

## UV\_EISDIR

illegal operation on a directory

## UV\_ELOOP

too many symbolic links encountered

#### UV EMFILE

too many open files

## UV\_EMSGSIZE

message too long

## UV ENAMETOOLONG

name too long

#### UV ENETDOWN

network is down

## UV\_ENETUNREACH

network is unreachable

## UV\_ENFILE

file table overflow

## UV\_ENOBUFS

no buffer space available

### UV ENODEV

no such device

## UV\_ENOENT

no such file or directory

#### UV ENOMEM

not enough memory

## UV ENONET

machine is not on the network

## UV\_ENOPROTOOPT

protocol not available

### UV ENOSPC

no space left on device

## UV\_ENOSYS

function not implemented

#### UV ENOTCONN

socket is not connected

## UV\_ENOTDIR

not a directory

## UV ENOTEMPTY

directory not empty

#### UV ENOTSOCK

socket operation on non-socket

## UV\_ENOTSUP

operation not supported on socket

## UV\_EPERM

operation not permitted

## UV\_EPIPE

broken pipe

## UV EPROTO

protocol error

## UV\_EPROTONOSUPPORT

protocol not supported

## UV EPROTOTYPE

protocol wrong type for socket

#### UV ERANGE

result too large

## UV\_EROFS

read-only file system

## UV\_ESHUTDOWN

cannot send after transport endpoint shutdown

## UV\_ESPIPE

invalid seek

## UV\_ESRCH

no such process

## UV\_ETIMEDOUT

connection timed out

#### UV ETXTBSY

text file is busy

## UV\_EXDEV

cross-device link not permitted

## UV\_UNKNOWN

unknown error

#### UV EOF

end of file

## UV\_ENXIO

no such device or address

#### UV EMLINK

too many links

#### **API**

## const char\* uv\_strerror (int err)

Returns the error message for the given error code. Leaks a few bytes of memory when you call it with an unknown error code.

#### const char\* uv err name (int err)

Returns the error name for the given error code. Leaks a few bytes of memory when you call it with an unknown error code.

## int uv\_translate\_sys\_error (int sys\_errno)

Returns the libuv error code equivalent to the given platform dependent error code: POSIX error codes on Unix (the ones stored in *errno*), and Win32 error codes on Windows (those returned by *GetLastError()*) or *WSAGetLastError()*).

If sys\_errno is already a libuv error, it is simply returned.

Changed in version 1.10.0: function declared public.

## Version-checking macros and functions

Starting with version 1.0.0 libuv follows the semantic versioning scheme. This means that new APIs can be introduced throughout the lifetime of a major release. In this section you'll find all macros and functions that will allow you to write or compile code conditionally, in order to work with multiple libuv versions.

## **Macros**

## UV VERSION MAJOR

libuv version's major number.

#### UV VERSION MINOR

libuv version's minor number.

## UV\_VERSION\_PATCH

libuv version's patch number.

#### UV VERSION IS RELEASE

Set to 1 to indicate a release version of libuv, 0 for a development snapshot.

## UV\_VERSION\_SUFFIX

libuv version suffix. Certain development releases such as Release Candidates might have a suffix such as "rc".

## UV\_VERSION\_HEX

Returns the libuv version packed into a single integer. 8 bits are used for each component, with the patch number stored in the 8 least significant bits. E.g. for libuv 1.2.3 this would be 0x010203.

New in version 1.7.0.

#### **Functions**

## unsigned int uv\_version (void)

Returns UV VERSION HEX.

```
const char* uv version string (void)
```

Returns the libuv version number as a string. For non-release versions the version suffix is included.

## uv\_loop\_t — Event loop

The event loop is the central part of libuv's functionality. It takes care of polling for i/o and scheduling callbacks to be run based on different sources of events.

## **Data types**

#### uv\_loop\_t

Loop data type.

## uv\_run\_mode

Mode used to run the loop with uv\_run().

```
typedef enum {
    UV_RUN_DEFAULT = 0,
    UV_RUN_ONCE,
    UV_RUN_NOWAIT
} uv_run_mode;
```

```
void (*uv_walk_cb) (uv_handle_t* handle, void* arg)
```

Type definition for callback passed to uv\_walk().

#### **Public members**

### void\* uv loop t.data

Space for user-defined arbitrary data. libuv does not use and does not touch this field.

#### API

```
int uv_loop_init (uv_loop_t* loop)
```

Initializes the given uv loop t structure.

```
\verb|int uv_loop_configure| (uv_loop_t* loop, uv_loop_option| option, ...)
```

New in version 1.0.2.

Set additional loop options. You should normally call this before the first call to  $uv\_run$  () unless mentioned otherwise.

Returns 0 on success or a UV\_E\* error code on failure. Be prepared to handle UV\_ENOSYS; it means the loop option is not supported by the platform.

Supported options:

•UV\_LOOP\_BLOCK\_SIGNAL: Block a signal when polling for new events. The second argument to uv\_loop\_configure() is the signal number.

This operation is currently only implemented for SIGPROF signals, to suppress unnecessary wakeups when using a sampling profiler. Requesting other signals will fail with UV EINVAL.

```
int uv_loop_close (uv_loop_t* loop)
```

Releases all internal loop resources. Call this function only when the loop has finished executing and all open

handles and requests have been closed, or it will return UV\_EBUSY. After this function returns, the user can free the memory allocated for the loop.

## uv\_loop\_t\* uv\_default\_loop (void)

Returns the initialized default loop. It may return NULL in case of allocation failure.

This function is just a convenient way for having a global loop throughout an application, the default loop is in no way different than the ones initialized with  $uv\_loop\_init()$ . As such, the default loop can (and should) be closed with  $uv\_loop\_close()$  so the resources associated with it are freed.

## int uv\_run (uv\_loop\_t\* loop, uv\_run\_mode mode)

This function runs the event loop. It will act differently depending on the specified mode:

- •UV\_RUN\_DEFAULT: Runs the event loop until there are no more active and referenced handles or requests. Returns non-zero if uv\_stop() was called and there are still active handles or requests. Returns zero in all other cases.
- •UV\_RUN\_ONCE: Poll for i/o once. Note that this function blocks if there are no pending callbacks. Returns zero when done (no active handles or requests left), or non-zero if more callbacks are expected (meaning you should run the event loop again sometime in the future).
- •UV\_RUN\_NOWAIT: Poll for i/o once but don't block if there are no pending callbacks. Returns zero if done (no active handles or requests left), or non-zero if more callbacks are expected (meaning you should run the event loop again sometime in the future).

## int uv\_loop\_alive (const uv\_loop\_t\* loop)

Returns non-zero if there are active handles or request in the loop.

```
void uv_stop (uv_loop_t* loop)
```

Stop the event loop, causing uv\_run() to end as soon as possible. This will happen not sooner than the next loop iteration. If this function was called before blocking for i/o, the loop won't block for i/o on this iteration.

```
size_t uv_loop_size (void)
```

Returns the size of the *uv\_loop\_t* structure. Useful for FFI binding writers who don't want to know the structure layout.

```
int uv_backend_fd (const uv_loop_t* loop)
```

Get backend file descriptor. Only kqueue, epoll and event ports are supported.

This can be used in conjunction with  $uv\_run(loop, UV\_RUN\_NOWAIT)$  to poll in one thread and run the event loop's callbacks in another see test/test-embed.c for an example.

**Note:** Embedding a kqueue fd in another kqueue pollset doesn't work on all platforms. It's not an error to add the fd but it never generates events.

#### int uv backend timeout (const uv loop t\* loop)

Get the poll timeout. The return value is in milliseconds, or -1 for no timeout.

```
uint64_t uv_now (const uv_loop_t* loop)
```

Return the current timestamp in milliseconds. The timestamp is cached at the start of the event loop tick, see  $uv\_update\_time()$  for details and rationale.

The timestamp increases monotonically from some arbitrary point in time. Don't make assumptions about the starting point, you will only get disappointed.

**Note:** Use *uv\_hrtime()* if you need sub-millisecond granularity.

```
void uv_update_time (uv_loop_t* loop)
```

Update the event loop's concept of "now". Libuv caches the current time at the start of the event loop tick in order to reduce the number of time-related system calls.

You won't normally need to call this function unless you have callbacks that block the event loop for longer periods of time, where "longer" is somewhat subjective but probably on the order of a millisecond or more.

```
void uv walk (uv loop t* loop, uv walk cb walk cb, void* arg)
```

Walk the list of handles: walk cb will be executed with the given arg.

```
int uv_loop_fork (uv_loop_t* loop)
```

New in version 1.12.0.

Reinitialize any kernel state necessary in the child process after a fork(2) system call.

Previously started watchers will continue to be started in the child process.

It is necessary to explicitly call this function on every event loop created in the parent process that you plan to continue to use in the child, including the default loop (even if you don't continue to use it in the parent). This function must be called before calling  $uv\_run()$  or any other API function using the loop in the child. Failure to do so will result in undefined behaviour, possibly including duplicate events delivered to both parent and child or aborting the child process.

When possible, it is preferred to create a new loop in the child process instead of reusing a loop created in the parent. New loops created in the child process after the fork should not use this function.

This function is not implemented on Windows, where it returns UV\_ENOSYS.

**Caution:** This function is experimental. It may contain bugs, and is subject to change or removal. API and ABI stability is not guaranteed.

**Note:** On Mac OS X, if directory FS event handles were in use in the parent process *for any event loop*, the child process will no longer be able to use the most efficient FSEvent implementation. Instead, uses of directory FS event handles in the child will fall back to the same implementation used for files and on other kqueue-based systems.

**Caution:** On AIX and SunOS, FS event handles that were already started in the parent process at the time of forking will *not* deliver events in the child process; they must be closed and restarted. On all other platforms, they will continue to work normally without any further intervention.

**Caution:** Any previous value returned from :c:func'uv\_backend\_fd' is now invalid. That function must be called again to determine the correct backend file descriptor.

## uv\_handle\_t — Base handle

*uv\_handle\_t* is the base type for all libuv handle types.

Structures are aligned so that any libuv handle can be cast to *uv\_handle\_t*. All API functions defined here work with any handle type.

## **Data types**

#### uv handle t

The base libuv handle type.

#### uv\_handle\_type

The kind of the libuv handle.

```
typedef enum {
 UV\_UNKNOWN\_HANDLE = 0,
 UV_ASYNC,
 UV_CHECK,
 UV_FS_EVENT,
 UV_FS_POLL,
 UV_HANDLE,
 UV_IDLE,
 UV_NAMED_PIPE,
 UV_POLL,
 UV_PREPARE,
 UV_PROCESS,
 UV_STREAM,
 UV_TCP,
 UV_TIMER,
 UV_TTY,
 UV_UDP,
 UV_SIGNAL,
 UV_FILE,
 UV_HANDLE_TYPE_MAX
} uv_handle_type;
```

#### uv any handle

Union of all handle types.

```
void (*uv_alloc_cb) (uv_handle_t* handle, size_t suggested_size, uv_buf_t* buf)
```

Type definition for callback passed to  $uv\_read\_start()$  and  $uv\_udp\_recv\_start()$ . The user must allocate memory and fill the supplied  $uv\_buf\_t$  structure. If NULL is assigned as the buffer's base or 0 as its length, a UV ENOBUFS error will be triggered in the  $uv\_udp\_recv\_cb$  or the  $uv\_read\_cb$  callback.

A suggested size (65536 at the moment in most cases) is provided, but it's just an indication, not related in any way to the pending data to be read. The user is free to allocate the amount of memory they decide.

As an example, applications with custom allocation schemes such as using freelists, allocation pools or slab based allocators may decide to use a different size which matches the memory chunks they already have.

## Example:

```
void (*uv_close_cb) (uv_handle_t* handle)
```

Type definition for callback passed to uv\_close().

#### **Public members**

```
uv_loop_t* uv_handle_t.loop
```

Pointer to the uv\_loop\_t where the handle is running on. Readonly.

```
uv_handle_type uv_handle_t.type
```

The uv\_handle\_type, indicating the type of the underlying handle. Readonly.

```
void* uv handle t.data
```

Space for user-defined arbitrary data. libuv does not use this field.

## **API**

```
int uv is active(const uv handle t* handle)
```

Returns non-zero if the handle is active, zero if it's inactive. What "active" means depends on the type of handle:

- •A uv\_async\_t handle is always active and cannot be deactivated, except by closing it with uv\_close().
- •A uv\_pipe\_t, uv\_tcp\_t, uv\_udp\_t, etc. handle basically any handle that deals with i/o is active when it is doing something that involves i/o, like reading, writing, connecting, accepting new connections, etc.
- •A uv\_check\_t, uv\_idle\_t, uv\_timer\_t, etc. handle is active when it has been started with a call to uv\_check\_start(), uv\_idle\_start(), etc.

Rule of thumb: if a handle of type  $uv\_foo\_t$  has a  $uv\_foo\_start()$  function, then it's active from the moment that function is called. Likewise,  $uv\_foo\_stop()$  deactivates the handle again.

```
int uv_is_closing (const uv_handle_t* handle)
```

Returns non-zero if the handle is closing or closed, zero otherwise.

**Note:** This function should only be used between the initialization of the handle and the arrival of the close callback.

```
void uv_close (uv_handle_t* handle, uv_close_cb close_cb)
```

Request handle to be closed. *close\_cb* will be called asynchronously after this call. This MUST be called on each handle before memory is released.

Handles that wrap file descriptors are closed immediately but *close\_cb* will still be deferred to the next iteration of the event loop. It gives you a chance to free up any resources associated with the handle.

In-progress requests, like uv\_connect\_t or uv\_write\_t, are cancelled and have their callbacks called asynchronously with status=UV\_ECANCELED.

```
void uv_ref (uv_handle_t* handle)
```

Reference the given handle. References are idempotent, that is, if a handle is already referenced calling this function again will have no effect.

See Reference counting.

```
void uv unref(uv handle t* handle)
```

Un-reference the given handle. References are idempotent, that is, if a handle is not referenced calling this function again will have no effect.

See Reference counting.

```
int uv_has_ref (const uv_handle_t* handle)
```

Returns non-zero if the handle referenced, zero otherwise.

See Reference counting.

#### size t uv handle size (uv handle type type)

Returns the size of the given handle type. Useful for FFI binding writers who don't want to know the structure layout.

#### Miscellaneous API functions

The following API functions take a uv\_handle\_t argument but they work just for some handle types.

```
int uv send buffer size (uv handle t* handle, int* value)
```

Gets or sets the size of the send buffer that the operating system uses for the socket.

If \*value == 0, it will return the current send buffer size, otherwise it will use \*value to set the new send buffer size.

This function works for TCP, pipe and UDP handles on Unix and for TCP and UDP handles on Windows.

**Note:** Linux will set double the size and return double the size of the original set value.

```
int uv_recv_buffer_size (uv_handle_t* handle, int* value)
```

Gets or sets the size of the receive buffer that the operating system uses for the socket.

If \*value == 0, it will return the current receive buffer size, otherwise it will use \*value to set the new receive buffer size.

This function works for TCP, pipe and UDP handles on Unix and for TCP and UDP handles on Windows.

**Note:** Linux will set double the size and return double the size of the original set value.

```
int uv_fileno (const uv_handle_t* handle, uv_os_fd_t* fd)
```

Gets the platform dependent file descriptor equivalent.

The following handles are supported: TCP, pipes, TTY, UDP and poll. Passing any other handle type will fail with *UV\_EINVAL*.

If a handle doesn't have an attached file descriptor yet or the handle itself has been closed, this function will return  $UV\_EBADF$ .

**Warning:** Be very careful when using this function. libuv assumes it's in control of the file descriptor so any change to it may lead to malfunction.

## Reference counting

The libuv event loop (if run in the default mode) will run until there are no active *and* referenced handles left. The user can force the loop to exit early by unreferencing handles which are active, for example by calling <code>uv\_unref()</code> after calling <code>uv\_timer\_start()</code>.

A handle can be referenced or unreferenced, the refcounting scheme doesn't use a counter, so both operations are idempotent.

All handles are referenced when active by default, see  $uv\_is\_active()$  for a more detailed explanation on what being *active* involves.

## uv\_req\_t — Base request

*uv\_req\_t* is the base type for all libuv request types.

Structures are aligned so that any libuv request can be cast to *uv\_req\_t*. All API functions defined here work with any request type.

## **Data types**

#### uv\_req\_t

The base libuv request structure.

## uv\_any\_req

Union of all request types.

#### **Public members**

```
void* uv_req_t.data
```

Space for user-defined arbitrary data. libuv does not use this field.

### uv\_req\_type uv\_req\_t.type

Indicated the type of request. Readonly.

```
typedef enum {
    UV_UNKNOWN_REQ = 0,
    UV_REQ,
    UV_CONNECT,
    UV_WRITE,
    UV_SHUTDOWN,
    UV_UDP_SEND,
    UV_FS,
    UV_WORK,
    UV_GETADDRINFO,
    UV_GETNAMEINFO,
    UV_REQ_TYPE_PRIVATE,
    UV_REQ_TYPE_MAX,
} uv_req_type;
```

## **API**

```
int uv_cancel (uv_req_t* req)
```

Cancel a pending request. Fails if the request is executing or has finished executing.

Returns 0 on success, or an error code < 0 on failure.

Only cancellation of  $uv\_fs\_t$ ,  $uv\_getaddrinfo\_t$ ,  $uv\_getnameinfo\_t$  and  $uv\_work\_t$  requests is currently supported.

Cancelled requests have their callbacks invoked some time in the future. It's **not** safe to free the memory associated with the request until the callback is called.

Here is how cancellation is reported to the callback:

- •A uv fs t request has its req->result field set to UV ECANCELED.
- •A  $uv\_work\_t$ ,  $uv\_getaddrinfo\_t$  or c:type: $uv\_getnameinfo\_t$  request has its callback invoked with status ==  $UV\_ECANCELED$ .

```
size_t uv_req_size (uv_req_type type)
```

Returns the size of the given request type. Useful for FFI binding writers who don't want to know the structure layout.

## uv\_timer\_t — Timer handle

Timer handles are used to schedule callbacks to be called in the future.

## **Data types**

```
uv_timer_t
     Timer handle type.

void (*uv_timer_cb) (uv_timer_t* handle)
     Type definition for callback passed to uv_timer_start().
```

#### **Public members**

N/A

#### See also:

The uv\_handle\_t members also apply.

#### **API**

If *timeout* is zero, the callback fires on the next event loop iteration. If *repeat* is non-zero, the callback fires first after *timeout* milliseconds and then repeatedly after *repeat* milliseconds.

**Note:** Does not update the event loop's concept of "now". See uv\_update\_time() for more information.

```
int uv_timer_stop (uv_timer_t* handle)
```

Stop the timer, the callback will not be called anymore.

```
int uv_timer_again (uv_timer_t* handle)
```

Stop the timer, and if it is repeating restart it using the repeat value as the timeout. If the timer has never been started before it returns UV\_EINVAL.

```
void uv_timer_set_repeat (uv_timer_t* handle, uint64_t repeat)
```

Set the repeat interval value in milliseconds. The timer will be scheduled to run on the given interval, regardless of the callback execution duration, and will follow normal timer semantics in the case of a time-slice overrun.

For example, if a 50ms repeating timer first runs for 17ms, it will be scheduled to run again 33ms later. If other tasks consume more than the 33ms following the first timer callback, then the callback will run as soon as possible.

**Note:** If the repeat value is set from a timer callback it does not immediately take effect. If the timer was non-repeating before, it will have been stopped. If it was repeating, then the old repeat value will have been used to schedule the next timeout.

```
uint64_t uv_timer_get_repeat (const uv_timer_t* handle)

Get the timer repeat value.
```

#### See also:

The uv\_handle\_t API functions also apply.

## uv\_prepare\_t — Prepare handle

Prepare handles will run the given callback once per loop iteration, right before polling for i/o.

## **Data types**

```
uv_prepare_t
    Prepare handle type.

void (*uv_prepare_cb) (uv_prepare_t* handle)
    Type definition for callback passed to uv_prepare_start().
```

## **Public members**

N/A

## See also:

The uv\_handle\_t members also apply.

## **API**

## See also:

The uv\_handle\_t API functions also apply.

## uv check t - Check handle

Check handles will run the given callback once per loop iteration, right after polling for i/o.

## **Data types**

## **Public members**

N/A

#### See also:

The uv\_handle\_t members also apply.

#### **API**

## See also:

The uv\_handle\_t API functions also apply.

## uv\_idle\_t — Idle handle

Idle handles will run the given callback once per loop iteration, right before the uv\_prepare\_t handles.

**Note:** The notable difference with prepare handles is that when there are active idle handles, the loop will perform a zero timeout poll instead of blocking for i/o.

**Warning:** Despite the name, idle handles will get their callbacks called on every loop iteration, not when the loop is actually "idle".

## **Data types**

```
uv_idle_t
        Idle handle type.

void (*uv_idle_cb) (uv_idle_t* handle)
        Type definition for callback passed to uv_idle_start().
```

## **Public members**

N/A

#### See also:

The uv\_handle\_t members also apply.

#### **API**

#### See also:

The uv\_handle\_t API functions also apply.

## uv\_async\_t — Async handle

Async handles allow the user to "wakeup" the event loop and get a callback called from another thread.

## **Data types**

```
uv_async_t
    Async handle type.

void (*uv_async_cb) (uv_async_t* handle)
    Type definition for callback passed to uv_async_init().
```

### **Public members**

N/A

## See also:

The uv\_handle\_t members also apply.

## **API**

```
int uv_async_init (uv_loop_t* loop, uv_async_t* async, uv_async_cb async_cb)
Initialize the handle. A NULL callback is allowed.
```

**Returns** 0 on success, or an error code < 0 on failure.

**Note:** Unlike other handle initialization functions, it immediately starts the handle.

```
int uv_async_send (uv_async_t* async)
```

Wake up the event loop and call the async handle's callback.

**Returns** 0 on success, or an error code < 0 on failure.

**Note:** It's safe to call this function from any thread. The callback will be called on the loop thread.

**Warning:** libuv will coalesce calls to  $uv\_async\_send()$ , that is, not every call to it will yield an execution of the callback. For example: if  $uv\_async\_send()$  is called 5 times in a row before the callback is called, the callback will only be called once. If  $uv\_async\_send()$  is called again after the callback was called, it will be called again.

#### See also:

The uv\_handle\_t API functions also apply.

## uv\_poll\_t — Poll handle

Poll handles are used to watch file descriptors for readability, writability and disconnection similar to the purpose of poll(2).

The purpose of poll handles is to enable integrating external libraries that rely on the event loop to signal it about the socket status changes, like c-ares or libssh2. Using uv\_poll\_t for any other purpose is not recommended;  $uv\_tcp\_t$ ,  $uv\_udp\_t$ , etc. provide an implementation that is faster and more scalable than what can be achieved with  $uv\_poll\_t$ , especially on Windows.

It is possible that poll handles occasionally signal that a file descriptor is readable or writable even when it isn't. The user should therefore always be prepared to handle EAGAIN or equivalent when it attempts to read from or write to the fd.

It is not okay to have multiple active poll handles for the same socket, this can cause libuv to busyloop or otherwise malfunction.

The user should not close a file descriptor while it is being polled by an active poll handle. This can cause the handle to report an error, but it might also start polling another socket. However the fd can be safely closed immediately after a call to  $uv\_poll\_stop()$  or  $uv\_close()$ .

**Note:** On windows only sockets can be polled with poll handles. On Unix any file descriptor that would be accepted by poll(2) can be used.

**Note:** On AIX, watching for disconnection is not supported.

## **Data types**

```
uv_poll_t
     Poll handle type.

void (*uv_poll_cb) (uv_poll_i* handle, int status, int events)
     Type definition for callback passed to uv_poll_start().

uv_poll_event
    Poll event types
```

```
enum uv_poll_event {
    UV_READABLE = 1,
    UV_WRITABLE = 2,
    UV_DISCONNECT = 4,
    UV_PRIORITIZED = 8
};
```

#### **Public members**

N/A

#### See also:

The uv\_handle\_t members also apply.

#### **API**

```
int uv_poll_init (uv_loop_t* loop, uv_poll_t* handle, int fd)
```

Initialize the handle using a file descriptor.

Changed in version 1.2.2: the file descriptor is set to non-blocking mode.

```
int uv_poll_init_socket (uv_loop_t* loop, uv_poll_t* handle, uv_os_sock_t socket)
```

Initialize the handle using a socket descriptor. On Unix this is identical to  $uv\_poll\_init()$ . On windows it takes a SOCKET handle.

Changed in version 1.2.2: the socket is set to non-blocking mode.

```
int uv_poll_start (uv_poll_t* handle, int events, uv_poll_cb cb)
```

Starts polling the file descriptor. *events* is a bitmask made up of UV\_READABLE, UV\_WRITABLE, UV\_PRIORITIZED and UV\_DISCONNECT. As soon as an event is detected the callback will be called with *status* set to 0, and the detected events set on the *events* field.

The UV\_PRIORITIZED event is used to watch for sysfs interrupts or TCP out-of-band messages.

The UV\_DISCONNECT event is optional in the sense that it may not be reported and the user is free to ignore it, but it can help optimize the shutdown path because an extra read or write call might be avoided.

If an error happens while polling, *status* will be < 0 and corresponds with one of the UV\_E\* error codes (see *Error handling*). The user should not close the socket while the handle is active. If the user does that anyway, the callback *may* be called reporting an error status, but this is **not** guaranteed.

**Note:** Calling  $uv\_poll\_start()$  on a handle that is already active is fine. Doing so will update the events mask that is being watched for.

**Note:** Though UV\_DISCONNECT can be set, it is unsupported on AIX and as such will not be set on the *events* field in the callback.

Changed in version 1.9.0: Added the UV\_DISCONNECT event.

Changed in version 1.14.0: Added the UV\_PRIORITIZED event.

```
int uv_poll_stop(uv_poll_t* poll)
```

Stop polling the file descriptor, the callback will no longer be called.

## See also:

The uv\_handle\_t API functions also apply.

## uv\_signal\_t — Signal handle

Signal handles implement Unix style signal handling on a per-event loop bases.

Reception of some signals is emulated on Windows:

- SIGINT is normally delivered when the user presses CTRL+C. However, like on Unix, it is not generated when terminal raw mode is enabled.
- SIGBREAK is delivered when the user pressed CTRL + BREAK.
- SIGHUP is generated when the user closes the console window. On SIGHUP the program is given approximately 10 seconds to perform cleanup. After that Windows will unconditionally terminate it.
- SIGWINCH is raised whenever libuv detects that the console has been resized. SIGWINCH is emulated by libuv when the program uses a  $uv\_tty\_t$  handle to write to the console. SIGWINCH may not always be delivered in a timely manner; libuv will only detect size changes when the cursor is being moved. When a readable  $uv\_tty\_t$  handle is used in raw mode, resizing the console buffer will also trigger a SIGWINCH signal.

Watchers for other signals can be successfully created, but these signals are never received. These signals are: SIGILL, SIGABRT, SIGFPE, SIGSEGV, SIGTERM and SIGKILL.

Calls to raise() or abort() to programmatically raise a signal are not detected by libuv; these will not trigger a signal watcher.

**Note:** On Linux SIGRT0 and SIGRT1 (signals 32 and 33) are used by the NPTL pthreads library to manage threads. Installing watchers for those signals will lead to unpredictable behavior and is strongly discouraged. Future versions of libuv may simply reject them.

## **Data types**

```
uv_signal_t
        Signal handle type.

void (*uv_signal_cb) (uv_signal_t* handle, int signum)
        Type definition for callback passed to uv_signal_start().
```

```
Public members

int uv_signal_t.signum
    Signal being monitored by this handle. Readonly.

See also:

The uv_handle_t members also apply.

API
```

int uv\_signal\_init (uv\_loop\_t\* loop, uv\_signal\_t\* signal)

Initialize the handle.

```
int uv_signal_start (uv_signal_t* signal, uv_signal_cb cb, int signum)
```

Start the handle with the given callback, watching for the given signal.

```
int uv_signal_start_oneshot (uv_signal_t* signal, uv_signal_cb cb, int signum)
```

New in version 1.12.0.

Same functionality as uv\_signal\_start() but the signal handler is reset the moment the signal is received.

```
int uv_signal_stop (uv_signal_t* signal)
```

Stop the handle, the callback will no longer be called.

#### See also:

The uv\_handle\_t API functions also apply.

## uv\_process\_t — Process handle

Process handles will spawn a new process and allow the user to control it and establish communication channels with it using streams.

#### Data types

## uv\_process\_t

Process handle type.

#### uv\_process\_options\_t

Options for spawning the process (passed to uv\_spawn().

```
typedef struct uv_process_options_s {
    uv_exit_cb exit_cb;
    const char* file;
    char** args;
    char** env;
    const char* cwd;
    unsigned int flags;
    int stdio_count;
    uv_stdio_container_t* stdio;
    uv_uid_t uid;
    uv_gid_t gid;
} uv_process_options_t;
```

## void (\*uv\_exit\_cb) (uv\_process\_t\*, int64\_t exit\_status, int term\_signal)

Type definition for callback passed in *uv\_process\_options\_t* which will indicate the exit status and the signal that caused the process to terminate, if any.

## ${\tt uv\_process\_flags}$

Flags to be set on the flags field of uv\_process\_options\_t.

```
enum uv_process_flags {
    /*
    * Set the child process' user id.
    */
    UV_PROCESS_SETUID = (1 << 0),
    /*
    * Set the child process' group id.
    */
    UV_PROCESS_SETGID = (1 << 1),
    /*</pre>
```

```
* Do not wrap any arguments in quotes, or perform any other escaping, when
* converting the argument list into a command line string. This option is
* only meaningful on Windows systems. On Unix it is silently ignored.

*/

UV_PROCESS_WINDOWS_VERBATIM_ARGUMENTS = (1 << 2),

/*

* Spawn the child process in a detached state - this will make it a process
* group leader, and will effectively enable the child to keep running after
* the parent exits. Note that the child process will still keep the

* parent's event loop alive unless the parent process calls uv_unref() on

* the child's process handle.

*//

UV_PROCESS_DETACHED = (1 << 3),

/*

* Hide the subprocess console window that would normally be created. This
* option is only meaningful on Windows systems. On Unix it is silently
* ignored.

*/

UV_PROCESS_WINDOWS_HIDE = (1 << 4)

};
```

#### uv\_stdio\_container\_t

Container for each stdio handle or fd passed to a child process.

```
typedef struct uv_stdio_container_s {
   uv_stdio_flags flags;
   union {
      uv_stream_t* stream;
      int fd;
   } data;
} uv_stdio_container_t;
```

## uv\_stdio\_flags

Flags specifying how a stdio should be transmitted to the child process.

```
typedef enum {
    UV_IGNORE = 0x00,
    UV_CREATE_PIPE = 0x01,
    UV_INHERIT_FD = 0x02,
    UV_INHERIT_STREAM = 0x04,
    /*
    * When UV_CREATE_PIPE is specified, UV_READABLE_PIPE and UV_WRITABLE_PIPE
    * determine the direction of flow, from the child process' perspective. Both
    * flags may be specified to create a duplex data stream.
    */
    UV_READABLE_PIPE = 0x10,
    UV_WRITABLE_PIPE = 0x20
} uv_stdio_flags;
```

#### **Public members**

### uv\_process\_t.pid

The PID of the spawned process. It's set after calling uv\_spawn().

**Note:** The *uv\_handle\_t* members also apply.

#### uv\_process\_options\_t.exit\_cb

Callback called after the process exits.

### uv\_process\_options\_t.file

Path pointing to the program to be executed.

## uv\_process\_options\_t.args

Command line arguments. args[0] should be the path to the program. On Windows this uses *CreateProcess* which concatenates the arguments into a string this can cause some strange errors. See the UV\_PROCESS\_WINDOWS\_VERBATIM\_ARGUMENTS flag on uv\_process\_flags.

#### uv\_process\_options\_t.env

Environment for the new process. If NULL the parents environment is used.

## uv\_process\_options\_t.cwd

Current working directory for the subprocess.

## uv\_process\_options\_t.flags

Various flags that control how uv\_spawn() behaves. See uv\_process\_flags.

## uv\_process\_options\_t.stdio\_count

## uv\_process\_options\_t.stdio

The *stdio* field points to an array of *uv\_stdio\_container\_t* structs that describe the file descriptors that will be made available to the child process. The convention is that stdio[0] points to stdin, fd 1 is used for stdout, and fd 2 is stderr.

**Note:** On Windows file descriptors greater than 2 are available to the child process only if the child processes uses the MSVCRT runtime.

## uv\_process\_options\_t.uid

## uv\_process\_options\_t.gid

Libuv can change the child process' user/group id. This happens only when the appropriate bits are set in the flags fields.

**Note:** This is not supported on Windows, uv\_spawn() will fail and set the error to UV\_ENOTSUP.

#### uv stdio container t.flags

Flags specifying how the stdio container should be passed to the child. See uv\_stdio\_flags.

## uv\_stdio\_container\_t.data

Union containing either the stream or fd to be passed on to the child process.

#### API

## void uv\_disable\_stdio\_inheritance (void)

Disables inheritance for file descriptors / handles that this process inherited from its parent. The effect is that child processes spawned by this process don't accidentally inherit these handles.

It is recommended to call this function as early in your program as possible, before the inherited file descriptors can be closed or duplicated.

**Note:** This function works on a best-effort basis: there is no guarantee that libuv can discover all file descriptors that were inherited. In general it does a better job on Windows than it does on Unix.

## int uv\_spawn (uv\_loop\_t\* loop, uv\_process\_t\* handle, const uv\_process\_options\_t\* options)

Initializes the process handle and starts the process. If the process is successfully spawned, this function will return 0. Otherwise, the negative error code corresponding to the reason it couldn't spawn is returned.

Possible reasons for failing to spawn would include (but not be limited to) the file to execute not existing, not having permissions to use the setuid or setgid specified, or not having enough memory to allocate for the new process.

## int uv\_process\_kill (uv\_process\_t\* handle, int signum)

Sends the specified signal to the given process handle. Check the documentation on *uv\_signal\_t* — *Signal handle* for signal support, specially on Windows.

## int uv\_kill (int pid, int signum)

Sends the specified signal to the given PID. Check the documentation on *uv\_signal\_t* — *Signal handle* for signal support, specially on Windows.

#### See also:

The uv\_handle\_t API functions also apply.

## uv\_stream\_t — Stream handle

Stream handles provide an abstraction of a duplex communication channel.  $uv\_stream\_t$  is an abstract type, libuv provides 3 stream implementations in the for of  $uv\_tcp\_t$ ,  $uv\_pipe\_t$  and  $uv\_tty\_t$ .

## **Data types**

## uv\_stream\_t

Stream handle type.

#### uv\_connect\_t

Connect request type.

#### uv\_shutdown\_t

Shutdown request type.

## uv\_write\_t

Write request type. Careful attention must be paid when reusing objects of this type. When a stream is in non-blocking mode, write requests sent with uv\_write will be queued. Reusing objects at this point is undefined behaviour. It is safe to reuse the uv\_write t object only after the callback passed to uv\_write is fired.

```
void (*uv_read_cb) (uv_stream_t* stream, ssize_t nread, const uv_buf_t* buf)
Callback called when data was read on a stream.
```

nread is > 0 if there is data available or < 0 on error. When we've reached EOF, nread will be set to UV\_EOF. When nread < 0, the buf parameter might not point to a valid buffer; in that case buf.len and buf.base are both set to 0.

**Note:** *nread* might be 0, which does *not* indicate an error or EOF. This is equivalent to EAGAIN or EWOULDBLOCK under read (2).

The callee is responsible for stopping closing the stream when an error happens by calling  $uv\_read\_stop()$  or  $uv\_close()$ . Trying to read from the stream again is undefined.

The callee is responsible for freeing the buffer, libuv does not reuse it. The buffer may be a null buffer (where buf->base=NULL and buf->len=0) on error.

void (\*uv\_write\_cb) (uv\_write\_t\* req, int status)

Callback called after data was written on a stream. *status* will be 0 in case of success, < 0 otherwise.

void (\*uv connect cb) (uv connect t\* req, int status)

Callback called after a connection started by  $uv\_connect()$  is done. status will be 0 in case of success, < 0 otherwise.

void (\*uv\_shutdown\_cb) (uv\_shutdown\_t\* req, int status)

Callback called after a shutdown request has been completed. status will be 0 in case of success, < 0 otherwise.

void (\*uv\_connection\_cb) (uv\_stream\_t\* server, int status)

Callback called when a stream server has received an incoming connection. The user can accept the connection by calling  $uv\_accept()$ . status will be 0 in case of success, < 0 otherwise.

#### **Public members**

## size\_t uv\_stream\_t.write\_queue\_size

Contains the amount of queued bytes waiting to be sent. Readonly.

uv stream t\* uv connect t.handle

Pointer to the stream where this connection request is running.

uv\_stream\_t\* uv\_shutdown\_t.handle

Pointer to the stream where this shutdown request is running.

uv\_stream\_t\* uv\_write\_t.handle

Pointer to the stream where this write request is running.

uv\_stream\_t\* uv\_write\_t.send\_handle

Pointer to the stream being sent using this write request.

### See also:

The uv\_handle\_t members also apply.

## API

```
int uv_shutdown (uv_shutdown_t* req, uv_stream_t* handle, uv_shutdown_cb cb)
```

Shutdown the outgoing (write) side of a duplex stream. It waits for pending write requests to complete. The handle should refer to a initialized stream. req should be an uninitialized shutdown request struct. The cb is called after shutdown is complete.

int uv\_listen (uv\_stream\_t\* stream, int backlog, uv\_connection\_cb cb)

Start listening for incoming connections. *backlog* indicates the number of connections the kernel might queue, same as listen(2). When a new incoming connection is received the *uv* connection *cb* callback is called.

int uv\_accept (uv\_stream\_t\* server, uv\_stream\_t\* client)

This call is used in conjunction with  $uv\_listen()$  to accept incoming connections. Call this function after receiving a  $uv\_connection\_cb$  to accept the connection. Before calling this function the client handle must be initialized. < 0 return value indicates an error.

When the uv\_connection\_cb callback is called it is guaranteed that this function will complete successfully the first time. If you attempt to use it more than once, it may fail. It is suggested to only call this function once per uv\_connection\_cb call.

**Note:** *server* and *client* must be handles running on the same loop.

```
int uv_read_start (uv_stream_t* stream, uv_alloc_cb alloc_cb, uv_read_cb read_cb)
```

Read data from an incoming stream. The  $uv\_read\_cb$  callback will be made several times until there is no more data to read or  $uv\_read\_stop()$  is called.

```
int uv_read_stop(uv_stream_t*)
```

Stop reading data from the stream. The uv\_read\_cb callback will no longer be called.

This function is idempotent and may be safely called on a stopped stream.

```
int uv_write (uv_write_t* req, uv_stream_t* handle, const uv_buf_t bufs[], unsigned int nbufs, uv_write_cb cb)
```

Write data to stream. Buffers are written in order. Example:

```
void cb(uv_write_t* req, int status) {
    /* Logic which handles the write result */
}

uv_buf_t a[] = {
    { .base = "1", .len = 1 },
    { .base = "2", .len = 1 }
};

uv_buf_t b[] = {
    { .base = "3", .len = 1 },
    { .base = "4", .len = 1 }
};

uv_write_t req1;
uv_write_t req2;

/* writes "1234" */
uv_write(&req1, stream, a, 2, cb);
uv_write(&req2, stream, b, 2, cb);
```

**Note:** The memory pointed to by the buffers must remain valid until the callback gets called. This also holds for  $uv\_write2()$ .

```
int uv_write2 (uv_write_t* req, uv_stream_t* handle, const uv_buf_t bufs[], unsigned int nbufs, uv_stream_t* send_handle, uv_write_cb cb)
```

Extended write function for sending handles over a pipe. The pipe must be initialized with ipc == 1.

**Note:** *send\_handle* must be a TCP socket or pipe, which is a server or a connection (listening or connected state). Bound sockets or pipes will be assumed to be servers.

```
int uv_try_write(uv_stream_t* handle, const uv_buf_t bufs[], unsigned int nbufs)
```

Same as uv write(), but won't queue a write request if it can't be completed immediately.

Will return either:

- •> 0: number of bytes written (can be less than the supplied buffer size).
- •< 0: negative error code (UV\_EAGAIN is returned if no data can be sent immediately).

```
int uv_is_readable (const uv_stream_t* handle)
```

Returns 1 if the stream is readable, 0 otherwise.

```
int uv_is_writable (const uv_stream_t* handle)
```

Returns 1 if the stream is writable, 0 otherwise.

```
int uv_stream_set_blocking (uv_stream_t* handle, int blocking)
```

Enable or disable blocking mode for a stream.

When blocking mode is enabled all writes complete synchronously. The interface remains unchanged otherwise, e.g. completion or failure of the operation will still be reported through a callback which is made asynchronously.

**Warning:** Relying too much on this API is not recommended. It is likely to change significantly in the future

Currently only works on Windows for  $uv\_pipe\_t$  handles. On UNIX platforms, all  $uv\_stream\_t$  handles are supported.

Also libuv currently makes no ordering guarantee when the blocking mode is changed after write requests have already been submitted. Therefore it is recommended to set the blocking mode immediately after opening or creating the stream.

Changed in version 1.4.0: UNIX implementation added.

#### See also:

The uv\_handle\_t API functions also apply.

# uv\_tcp\_t — TCP handle

TCP handles are used to represent both TCP streams and servers.

```
uv_tcp_t is a 'subclass' of uv_stream_t.
```

#### Data types

```
uv_tcp_t
```

TCP handle type.

## **Public members**

N/A

## See also:

The uv\_stream\_t members also apply.

## **API**

## int uv tcp init (uv loop t\* loop, uv tcp t\* handle)

Initialize the handle. No socket is created as of yet.

## int uv\_tcp\_init\_ex (uv\_loop\_t\* loop, uv\_tcp\_t\* handle, unsigned int flags)

Initialize the handle with the specified flags. At the moment only the lower 8 bits of the *flags* parameter are used as the socket domain. A socket will be created for the given domain. If the specified domain is AF\_UNSPEC no socket is created, just like uv\_tcp\_init().

New in version 1.7.0.

## int uv\_tcp\_open (uv\_tcp\_t\* handle, uv\_os\_sock\_t sock)

Open an existing file descriptor or SOCKET as a TCP handle.

Changed in version 1.2.1: the file descriptor is set to non-blocking mode.

**Note:** The passed file descriptor or SOCKET is not checked for its type, but it's required that it represents a valid stream socket.

## int uv\_tcp\_nodelay (uv\_tcp\_t\* handle, int enable)

Enable TCP\_NODELAY, which disables Nagle's algorithm.

## int uv\_tcp\_keepalive (uv\_tcp\_t\* handle, int enable, unsigned int delay)

Enable / disable TCP keep-alive. *delay* is the initial delay in seconds, ignored when *enable* is zero.

## int uv\_tcp\_simultaneous\_accepts (uv\_tcp\_t\* handle, int enable)

Enable / disable simultaneous asynchronous accept requests that are queued by the operating system when listening for new TCP connections.

This setting is used to tune a TCP server for the desired performance. Having simultaneous accepts can significantly improve the rate of accepting connections (which is why it is enabled by default) but may lead to uneven load distribution in multi-process setups.

## int uv\_tcp\_bind (uv\_tcp\_t\* handle, const struct sockaddr\* addr, unsigned int flags)

Bind the handle to an address and port. *addr* should point to an initialized struct sockaddr\_in or struct sockaddr\_in6.

When the port is already taken, you can expect to see an UV\_EADDRINUSE error from either  $uv\_tcp\_bind()$ ,  $uv\_listen()$  or  $uv\_tcp\_connect()$ . That is, a successful call to this function does not guarantee that the call to  $uv\_listen()$  or  $uv\_tcp\_connect()$  will succeed as well.

flags can contain UV\_TCP\_IPV6ONLY, in which case dual-stack support is disabled and only IPv6 is used.

## int uv\_tcp\_getsockname (const uv\_tcp\_f\* handle, struct sockaddr\* name, int\* namelen)

Get the current address to which the handle is bound. *addr* must point to a valid and big enough chunk of memory, struct sockaddr\_storage is recommended for IPv4 and IPv6 support.

## int uv\_tcp\_getpeername (const uv\_tcp\_t\* handle, struct sockaddr\* name, int\* namelen)

Get the address of the peer connected to the handle. *addr* must point to a valid and big enough chunk of memory, struct sockaddr\_storage is recommended for IPv4 and IPv6 support.

```
int uv_tcp_connect (uv_connect_t* req, uv_tcp_t* handle, const struct sockaddr* addr, uv_connect_cb_cb)
```

Establish an IPv4 or IPv6 TCP connection. Provide an initialized TCP handle and an uninitialized uv\_connect\_t. addr should point to an initialized struct sockaddr\_in or struct sockaddr\_in6.

The callback is made when the connection has been established or when a connection error happened.

#### See also:

The uv\_stream\_t API functions also apply.

# uv\_pipe\_t — Pipe handle

Pipe handles provide an abstraction over local domain sockets on Unix and named pipes on Windows.

```
uv_pipe_t is a 'subclass' of uv_stream_t.
```

## **Data types**

#### uv\_pipe\_t

Pipe handle type.

#### **Public members**

N/A

#### See also:

The uv\_stream\_t members also apply.

## **API**

```
int uv_pipe_init (uv_loop_t* loop, uv_pipe_t* handle, int ipc)
```

Initialize a pipe handle. The *ipc* argument is a boolean to indicate if this pipe will be used for handle passing between processes.

```
int uv_pipe_open (uv_pipe_t* handle, uv_file file)
```

Open an existing file descriptor or HANDLE as a pipe.

Changed in version 1.2.1: the file descriptor is set to non-blocking mode.

**Note:** The passed file descriptor or HANDLE is not checked for its type, but it's required that it represents a valid pipe.

```
int uv_pipe_bind (uv_pipe_t* handle, const char* name)
```

Bind the pipe to a file path (Unix) or a name (Windows).

**Note:** Paths on Unix get truncated to sizeof(sockaddr\_un.sun\_path) bytes, typically between 92 and 108 bytes.

```
void uv_pipe_connect_(uv_connect_t* req, uv_pipe_t* handle, const char* name, uv_connect_cb cb)

Connect to the Unix domain socket or the named pipe.
```

**Note:** Paths on Unix get truncated to sizeof (sockaddr\_un.sun\_path) bytes, typically between 92 and 108 bytes.

```
int uv_pipe_getsockname (const uv_pipe_t* handle, char* buffer, size_t* size)
```

Get the name of the Unix domain socket or the named pipe.

A preallocated buffer must be provided. The size parameter holds the length of the buffer and it's set to the number of bytes written to the buffer on output. If the buffer is not big enough UV\_ENOBUFS will be returned and len will contain the required size.

Changed in version 1.3.0: the returned length no longer includes the terminating null byte, and the buffer is not null terminated.

```
int uv_pipe_getpeername (const uv_pipe_t* handle, char* buffer, size_t* size)
```

Get the name of the Unix domain socket or the named pipe to which the handle is connected.

A preallocated buffer must be provided. The size parameter holds the length of the buffer and it's set to the number of bytes written to the buffer on output. If the buffer is not big enough UV\_ENOBUFS will be returned and len will contain the required size.

New in version 1.3.0.

```
void uv_pipe_pending_instances (uv_pipe_t* handle, int count)
```

Set the number of pending pipe instance handles when the pipe server is waiting for connections.

**Note:** This setting applies to Windows only.

```
int uv_pipe_pending_count (uv_pipe_t* handle)
```

```
uv_handle_type uv_pipe_pending_type (uv_pipe_t* handle)
```

Used to receive handles over IPC pipes.

First - call uv\_pipe\_pending\_count(), if it's > 0 then initialize a handle of the given type, returned by uv\_pipe\_pending\_type() and call uv\_accept (pipe, handle).

#### See also:

The uv\_stream\_t API functions also apply.

## uv\_tty\_t — TTY handle

TTY handles represent a stream for the console.

```
uv_tty_t is a 'subclass' of uv_stream_t.
```

## **Data types**

## uv\_tty\_t

TTY handle type.

## uv\_tty\_mode\_t

New in version 1.2.0.

TTY mode type:

```
typedef enum {
    /* Initial/normal terminal mode */
    UV_TTY_MODE_NORMAL,
    /* Raw input mode (On Windows, ENABLE_WINDOW_INPUT is also enabled) */
    UV_TTY_MODE_RAW,
    /* Binary-safe I/O mode for IPC (Unix-only) */
```

```
UV_TTY_MODE_IO
} uv_tty_mode_t;
```

## **Public members**

N/A

#### See also:

The uv\_stream\_t members also apply.

## **API**

int uv\_tty\_init (uv\_loop\_t\* loop, uv\_tty\_t\* handle, uv\_file fd, int readable)

Initialize a new TTY stream with the given file descriptor. Usually the file descriptor will be:

- $\bullet 0 = stdin$
- $\bullet 1 = stdout$
- $\bullet 2 = stderr$

readable, specifies if you plan on calling uv\_read\_start() with this stream. stdin is readable, stdout is not.

On Unix this function will determine the path of the fd of the terminal using ttyname\_r(3), open it, and use it if the passed file descriptor refers to a TTY. This lets libuv put the tty in non-blocking mode without affecting other processes that share the tty.

This function is not thread safe on systems that don't support ioctl TIOCGPTN or TIOCPTYGNAME, for instance OpenBSD and Solaris.

Note: If reopening the TTY fails, libuv falls back to blocking writes for non-readable TTY streams.

Changed in version 1.9.0:: the path of the TTY is determined by ttyname\_r(3). In earlier versions libuv opened /dev/ttv instead.

Changed in version 1.5.0:: trying to initialize a TTY stream with a file descriptor that refers to a file returns *UV EINVAL* on UNIX.

```
int uv_tty_set_mode (uv_tty_t* handle, uv_tty_mode_t mode)
```

Changed in version 1.2.0:: the mode is specified as a uv\_tty\_mode\_t value.

Set the TTY using the specified terminal mode.

```
int uv_tty_reset_mode (void)
```

To be called when the program exits. Resets TTY settings to default values for the next process to take over.

This function is async signal-safe on Unix platforms but can fail with error code UV\_EBUSY if you call it when execution is inside  $uv\_tty\_set\_mode()$ .

```
int uv_tty_get_winsize (uv_tty_t* handle, int* width, int* height)
```

Gets the current Window size. On success it returns 0.

#### See also:

The uv stream t API functions also apply.

# uv\_udp\_t — UDP handle

UDP handles encapsulate UDP communication for both clients and servers.

## **Data types**

```
uv_udp_t
```

UDP handle type.

#### uv\_udp\_send\_t

UDP send request type.

#### uv\_udp\_flags

Flags used in uv\_udp\_bind() and uv\_udp\_recv\_cb..

```
enum uv_udp_flags {
    /* Disables dual stack mode. */
    UV_UDP_IPV6ONLY = 1,
    /*
    * Indicates message was truncated because read buffer was too small. The
    * remainder was discarded by the OS. Used in uv_udp_recv_cb.
    */
    UV_UDP_PARTIAL = 2,
    /*
    * Indicates if SO_REUSEADDR will be set when binding the handle in
    * uv_udp_bind.
    * This sets the SO_REUSEPORT socket flag on the BSDs and OS X. On other
    * Unix platforms, it sets the SO_REUSEADDR flag. What that means is that
    * multiple threads or processes can bind to the same address without error
    * (provided they all set the flag) but only the last one to bind will receive
    * any traffic, in effect "stealing" the port from the previous listener.
    */
    UV_UDP_REUSEADDR = 4
};
```

## void (\*uv\_udp\_send\_cb) (uv\_udp\_send\_t\* req, int status)

Type definition for callback passed to uv\_udp\_send(), which is called after the data was sent.

```
void (*uv_udp_recv_cb) (uv_udp_t* handle, ssize_t nread, const uv_buf_t* buf, const struct sock-addr* addr, unsigned flags)
```

Type definition for callback passed to  $uv\_udp\_recv\_start()$ , which is called when the endpoint receives data.

•handle: UDP handle

•nread: Number of bytes that have been received. 0 if there is no more data to read. You may discard or repurpose the read buffer. Note that 0 may also mean that an empty datagram was received (in this case addr is not NULL). < 0 if a transmission error was detected.

•buf: uv\_buf\_t with the received data.

•addr: struct sockaddr\* containing the address of the sender. Can be NULL. Valid for the duration of the callback only.

•flags: One or more or'ed UV\_UDP\_\* constants. Right now only UV\_UDP\_PARTIAL is used.

**Note:** The receive callback will be called with nread == 0 and addr == NULL when there is nothing to read, and with nread == 0 and addr != NULL when an empty UDP packet is received.

#### uv membership

Membership type for a multicast address.

```
typedef enum {
    UV_LEAVE_GROUP = 0,
    UV_JOIN_GROUP
} uv_membership;
```

#### **Public members**

#### size\_t uv\_udp\_t.send\_queue\_size

Number of bytes queued for sending. This field strictly shows how much information is currently queued.

#### size tuv udp t.send queue count

Number of send requests currently in the queue awaiting to be processed.

```
uv_udp_t* uv_udp_send_t.handle
```

UDP handle where this send request is taking place.

#### See also:

The uv\_handle\_t members also apply.

## API

```
int uv_udp_init (uv_loop_t* loop, uv_udp_t* handle)
```

Initialize a new UDP handle. The actual socket is created lazily. Returns 0 on success.

```
int uv_udp_init_ex (uv_loop_t* loop, uv_udp_t* handle, unsigned int flags)
```

Initialize the handle with the specified flags. At the moment the lower 8 bits of the *flags* parameter are used as the socket domain. A socket will be created for the given domain. If the specified domain is AF\_UNSPEC no socket is created, just like uv\_udp\_init().

New in version 1.7.0.

```
int uv_udp_open (uv_udp_t* handle, uv_os_sock_t sock)
```

Opens an existing file descriptor or Windows SOCKET as a UDP handle.

Unix only: The only requirement of the *sock* argument is that it follows the datagram contract (works in unconnected mode, supports sendmsg()/recvmsg(), etc). In other words, other datagram-type sockets like raw sockets or netlink sockets can also be passed to this function.

Changed in version 1.2.1: the file descriptor is set to non-blocking mode.

**Note:** The passed file descriptor or SOCKET is not checked for its type, but it's required that it represents a valid datagram socket.

```
int uv_udp_bind (uv_udp_t* handle, const struct sockaddr* addr, unsigned int flags)

Bind the UDP handle to an IP address and port.
```

## **Parameters**

- handle UDP handle. Should have been initialized with uv\_udp\_init().
- addr struct sockaddr\_in or struct sockaddr\_in6 with the address and port to bind to.
- flags Indicate how the socket will be bound, UV\_UDP\_IPV6ONLY and UV\_UDP\_REUSEADDR are supported.

**Returns** 0 on success, or an error code < 0 on failure.

int **uv\_udp\_getsockname** (const *uv\_udp\_t\* handle*, struct sockaddr\* *name*, int\* *namelen*) Get the local IP and port of the UDP handle.

#### **Parameters**

- handle UDP handle. Should have been initialized with uv udp init() and bound.
- name Pointer to the structure to be filled with the address data. In order to support IPv4 and IPv6 *struct sockaddr storage* should be used.
- namelen On input it indicates the data of the name field. On output it indicates how
  much of it was filled.

**Returns** 0 on success, or an error code < 0 on failure.

int uv\_udp\_set\_membership (uv\_udp\_t\* handle, const char\* multicast\_addr, const char\* interface\_addr, uv\_membership membership)

Set membership for a multicast address

#### **Parameters**

- handle UDP handle. Should have been initialized with uv\_udp\_init().
- multicast\_addr Multicast address to set membership for.
- interface\_addr Interface address.
- membership Should be UV\_JOIN\_GROUP or UV\_LEAVE\_GROUP.

**Returns** 0 on success, or an error code < 0 on failure.

```
int uv udp set multicast loop (uv udp t* handle, int on)
```

Set IP multicast loop flag. Makes multicast packets loop back to local sockets.

### Parameters

- handle UDP handle. Should have been initialized with uv\_udp\_init().
- on -1 for on, 0 for off.

**Returns** 0 on success, or an error code < 0 on failure.

```
int uv_udp_set_multicast_ttl (uv_udp_t* handle, int ttl)
Set the multicast ttl.
```

#### **Parameters**

- handle UDP handle. Should have been initialized with uv\_udp\_init().
- **ttl** 1 through 255.

**Returns** 0 on success, or an error code < 0 on failure.

int uv\_udp\_set\_multicast\_interface (uv\_udp\_t\* handle, const char\* interface\_addr)

Set the multicast interface to send or receive data on.

#### **Parameters**

- handle UDP handle. Should have been initialized with  $uv\_udp\_init$  ().
- interface addr interface address.

**Returns** 0 on success, or an error code < 0 on failure.

```
int uv_udp_set_broadcast (uv_udp_t* handle, int on)
```

Set broadcast on or off.

3.2. API documentation

#### **Parameters**

- handle UDP handle. Should have been initialized with uv udp init().
- on -1 for on, 0 for off.

**Returns** 0 on success, or an error code < 0 on failure.

```
int \ uv\_udp\_set\_ttl \ (uv\_udp\_t* \ handle, int \ ttl)
```

Set the time to live.

#### **Parameters**

- handle UDP handle. Should have been initialized with uv\_udp\_init().
- **ttl** 1 through 255.

**Returns** 0 on success, or an error code < 0 on failure.

```
int uv_udp_send (uv_udp_send_t* req, uv_udp_t* handle, const uv_buf_t bufs[], unsigned int nbufs, const struct sockaddr* addr, uv_udp_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_send_cb_
```

Send data over the UDP socket. If the socket has not previously been bound with  $uv\_udp\_bind()$  it will be bound to 0.0.0.0 (the "all interfaces" IPv4 address) and a random port number.

#### **Parameters**

- req UDP request handle. Need not be initialized.
- handle UDP handle. Should have been initialized with uv\_udp\_init().
- **bufs** List of buffers to send.
- **nbufs** Number of buffers in *bufs*.
- addr struct sockaddr\_in or struct sockaddr\_in6 with the address and port of the remote peer.
- **send\_cb** Callback to invoke when the data has been sent out.

**Returns** 0 on success, or an error code < 0 on failure.

```
int uv_udp_try_send (uv_udp_t* handle, const uv_buf_t bufs[], unsigned int nbufs, const struct sock-addr* addr)
```

Same as uv udp send(), but won't queue a send request if it can't be completed immediately.

**Returns** >= 0: number of bytes sent (it matches the given buffer size). < 0: negative error code (UV\_EAGAIN is returned when the message can't be sent immediately).

```
int uv_udp_recv_start (uv_udp_t* handle, uv_alloc_cb alloc_cb, uv_udp_recv_cb recv_cb)
```

Prepare for receiving data. If the socket has not previously been bound with  $uv\_udp\_bind()$  it is bound to 0.0.0.0 (the "all interfaces" IPv4 address) and a random port number.

#### **Parameters**

- handle UDP handle. Should have been initialized with uv\_udp\_init().
- alloc\_cb Callback to invoke when temporary storage is needed.
- recv\_cb Callback to invoke with received data.

**Returns** 0 on success, or an error code < 0 on failure.

```
int uv_udp_recv_stop (uv_udp_t* handle)
```

Stop listening for incoming datagrams.

## **Parameters**

• handle – UDP handle. Should have been initialized with uv\_udp\_init().

**Returns** 0 on success, or an error code < 0 on failure.

#### See also:

The uv\_handle\_t API functions also apply.

# uv\_fs\_event\_t — FS Event handle

FS Event handles allow the user to monitor a given path for changes, for example, if the file was renamed or there was a generic change in it. This handle uses the best backend for the job on each platform.

**Note:** For AIX, the non default IBM bos.ahafs package has to be installed. The AIX Event Infrastructure file system (ahafs) has some limitations:

- ahafs tracks monitoring per process and is not thread safe. A separate process must be spawned for each monitor for the same event.
- Events for file modification (writing to a file) are not received if only the containing folder is watched.

See documentation for more details.

# **Data types**

#### uv fs event t

FS Event handle type.

void (\*uv\_fs\_event\_cb) (uv\_fs\_event\_t\* handle, const char\* filename, int events, int status)

Callback passed to uv\_fs\_event\_start() which will be called repeatedly after the handle is started. If the handle was started with a directory the filename parameter will be a relative path to a file contained in the directory. The events parameter is an ORed mask of uv\_fs\_event elements.

## uv\_fs\_event

Event types that uv\_fs\_event\_t handles monitor.

```
enum uv_fs_event {
    UV_RENAME = 1,
    UV_CHANGE = 2
};
```

## uv\_fs\_event\_flags

Flags that can be passed to uv fs event start () to control its behavior.

```
enum uv_fs_event_flags {
    /*
    * By default, if the fs event watcher is given a directory name, we will
    * watch for all events in that directory. This flags overrides this behavior
    * and makes fs_event report only changes to the directory entry itself. This
    * flag does not affect individual files watched.
    * This flag is currently not implemented yet on any backend.

*/
UV_FS_EVENT_WATCH_ENTRY = 1,
    /*
    * By default uv_fs_event will try to use a kernel interface such as inotify
    * or kqueue to detect events. This may not work on remote file systems such
    * as NFS mounts. This flag makes fs_event fall back to calling stat() on a
    * regular interval.
```

```
* This flag is currently not implemented yet on any backend.
*/
UV_FS_EVENT_STAT = 2,
/*
    * By default, event watcher, when watching directory, is not registering
    * (is ignoring) changes in its subdirectories.
    * This flag will override this behaviour on platforms that support it.
    */
    UV_FS_EVENT_RECURSIVE = 4
};
```

## **Public members**

N/A

#### See also:

The uv\_handle\_t members also apply.

#### API

```
int uv_fs_event_init (uv_loop_t* loop, uv_fs_event_t* handle)
Initialize the handle.
```

int **uv\_fs\_event\_start** (*uv\_fs\_event\_t\* handle*, *uv\_fs\_event\_cb cb*, const char\* *path*, unsigned int *flags*)

Start the handle with the given callback, which will watch the specified *path* for changes. *flags* can be an ORed mask of *uv\_fs\_event\_flags*.

Note: Currently the only supported flag is UV\_FS\_EVENT\_RECURSIVE and only on OSX and Windows.

```
int uv_fs_event_stop (uv_fs_event_t* handle)
```

Stop the handle, the callback will no longer be called.

```
int uv_fs_event_getpath (uv_fs_event_t* handle, char* buffer, size_t* size)
```

Get the path being monitored by the handle. The buffer must be preallocated by the user. Returns 0 on success or an error code < 0 in case of failure. On success, *buffer* will contain the path and *size* its length. If the buffer is not big enough *UV\_ENOBUFS* will be returned and *size* will be set to the required size, including the null terminator.

Changed in version 1.3.0: the returned length no longer includes the terminating null byte, and the buffer is not null terminated.

Changed in version 1.9.0: the returned length includes the terminating null byte on *UV\_ENOBUFS*, and the buffer is null terminated on success.

#### See also:

The uv\_handle\_t API functions also apply.

# uv\_fs\_poll\_t — FS Poll handle

FS Poll handles allow the user to monitor a given path for changes. Unlike  $uv\_fs\_event\_t$ , fs poll handles use *stat* to detect when a file has changed so they can work on file systems where fs event handles can't.

## **Data types**

## uv\_fs\_poll\_t

FS Poll handle type.

void (\*uv\_fs\_poll\_cb) (uv\_fs\_poll\_t\* handle, int status, const uv\_stat\_t\* prev, const uv\_stat\_t\* curr)

Callback passed to  $uv_fs_poll_start()$  which will be called repeatedly after the handle is started, when any change happens to the monitored path.

The callback is invoked with status < 0 if path does not exist or is inaccessible. The watcher is not stopped but your callback is not called again until something changes (e.g. when the file is created or the error reason changes).

When status == 0, the callback receives pointers to the old and new  $uv\_stat\_t$  structs. They are valid for the duration of the callback only.

## **Public members**

N/A

#### See also:

The uv\_handle\_t members also apply.

#### **API**

```
int uv_fs_poll_init (uv_loop_t* loop, uv_fs_poll_t* handle)
Initialize the handle.
```

int uv\_fs\_poll\_start (uv\_fs\_poll\_t\* handle, uv\_fs\_poll\_cb poll\_cb, const char\* path, unsigned int interval)

Check the file at *path* for changes every *interval* milliseconds.

**Note:** For maximum portability, use multi-second intervals. Sub-second intervals will not detect all changes on many file systems.

```
int uv_fs_poll_stop (uv_fs_poll_t* handle)
```

Stop the handle, the callback will no longer be called.

```
int uv_fs_poll_getpath (uv_fs_poll_t* handle, char* buffer, size_t* size)
```

Get the path being monitored by the handle. The buffer must be preallocated by the user. Returns 0 on success or an error code < 0 in case of failure. On success, *buffer* will contain the path and *size* its length. If the buffer is not big enough *UV\_ENOBUFS* will be returned and *size* will be set to the required size.

Changed in version 1.3.0: the returned length no longer includes the terminating null byte, and the buffer is not null terminated.

Changed in version 1.9.0: the returned length includes the terminating null byte on *UV\_ENOBUFS*, and the buffer is null terminated on success.

## See also:

The uv\_handle\_t API functions also apply.

# File system operations

libuv provides a wide variety of cross-platform sync and async file system operations. All functions defined in this document take a callback, which is allowed to be NULL. If the callback is NULL the request is completed synchronously, otherwise it will be performed asynchronously.

All file operations are run on the threadpool. See *Thread pool work scheduling* for information on the threadpool size.

## **Data types**

#### uv\_fs\_t

File system request type.

## uv\_timespec\_t

Portable equivalent of struct timespec.

```
typedef struct {
  long tv_sec;
  long tv_nsec;
} uv_timespec_t;
```

#### uv\_stat\_t

Portable equivalent of struct stat.

```
typedef struct {
   uint64_t st_dev;
   uint64_t st_mode;
   uint64_t st_nlink;
   uint64_t st_uid;
   uint64_t st_gid;
   uint64_t st_rdev;
   uint64_t st_ino;
   uint64_t st_size;
   uint64_t st_blksize;
   uint64_t st_blocks;
   uint64_t st_flags;
   uint64_t st_gen;
   uv_timespec_t st_atim;
   uv_timespec_t st_mtim;
   uv_timespec_t st_ctim;
   uv_timespec_t st_birthtim;
} uv_stat_t;
```

#### uv\_fs\_type

File system request type.

```
typedef enum {
    UV_FS_UNKNOWN = -1,
    UV_FS_CUSTOM,
    UV_FS_OPEN,
    UV_FS_CLOSE,
    UV_FS_READ,
    UV_FS_WRITE,
    UV_FS_SENDFILE,
    UV_FS_STAT,
    UV_FS_LSTAT,
    UV_FS_FSTAT,
```

```
UV_FS_FTRUNCATE,
   UV FS UTIME,
   UV FS FUTIME,
   UV_FS_ACCESS,
   UV_FS_CHMOD,
   UV_FS_FCHMOD,
   UV_FS_FSYNC,
   UV_FS_FDATASYNC,
   UV_FS_UNLINK,
   UV_FS_RMDIR,
   UV_FS_MKDIR,
   UV_FS_MKDTEMP,
   UV_FS_RENAME,
   UV_FS_SCANDIR,
   UV_FS_LINK,
   UV_FS_SYMLINK,
   UV_FS_READLINK,
   UV_FS_CHOWN,
   UV_FS_FCHOWN,
   UV_FS_REALPATH,
   UV_FS_COPYFILE
} uv_fs_type;
```

#### uv\_dirent\_t

Cross platform (reduced) equivalent of struct dirent. Used in uv\_fs\_scandir\_next().

```
typedef enum {
    UV_DIRENT_UNKNOWN,
    UV_DIRENT_FILE,
    UV_DIRENT_DIR,
    UV_DIRENT_LINK,
    UV_DIRENT_FIFO,
    UV_DIRENT_SOCKET,
    UV_DIRENT_CHAR,
    UV_DIRENT_BLOCK
} uv_dirent_type_t;

typedef struct uv_dirent_s {
    const char* name;
    uv_dirent_type_t type;
} uv_dirent_type_t type;
```

## **Public members**

```
uv_loop_t* uv_fs_t.loop
```

Loop that started this request and where completion will be reported. Readonly.

```
uv_fs_type uv_fs_t.fs_type
FS request type.
```

const char\* uv\_fs\_t.path

Path affecting the request.

## ssize\_t uv\_fs\_t.result

Result of the request. < 0 means error, success otherwise. On requests such as  $uv\_fs\_read()$  or  $uv\_fs\_write()$  it indicates the amount of data that was read or written, respectively.

```
uv stat t uv fs t.statbuf
     Stores the result of uv_fs_stat () and other stat requests.
void* uv_fs_t.ptr
     Stores the result of uv_fs_readlink() and serves as an alias to statbuf.
See also:
The uv_req_t members also apply.
API
void uv_fs_req_cleanup (uv_fs_t* req)
     Cleanup request. Must be called after a request is finished to deallocate any memory libuv might have allocated.
int uv_fs_close (uv_loop_t* loop, uv_fs_t* req, uv_file file, uv_fs_cb cb)
     Equivalent to close(2).
int uv_fs_open (uv_loop_t* loop, uv_fs_t* req, const char* path, int flags, int mode, uv_fs_cb cb)
     Equivalent to open(2).
     Note: On Windows libuv uses CreateFileW and thus the file is always opened in binary mode. Because of this
     the O_BINARY and O_TEXT flags are not supported.
int uv fs read (uv loop t* loop, uv fs t* req, uv file file, const uv buf t bufs], unsigned int nbufs,
                  int64_t offset, uv_fs_cb cb)
     Equivalent to preadv(2).
int uv_fs_unlink (uv_loop_t* loop, uv_fs_t* req, const char* path, uv_fs_cb cb)
     Equivalent to unlink(2).
int uv_fs_write (uv_loop_t* loop, uv_fs_t* req, uv_file file, const uv_buf_t bufs[], unsigned int nbufs,
                    int64 t offset, uv fs cb cb)
     Equivalent to pwritev(2).
int uv_fs_mkdir (uv_loop_t* loop, uv_fs_t* req, const char* path, int mode, uv_fs_cb cb)
     Equivalent to mkdir(2).
     Note: mode is currently not implemented on Windows.
int uv_fs_mkdtemp (uv_loop_t* loop, uv_fs_t* req, const char* tpl, uv_fs_cb cb)
     Equivalent to mkdtemp(3).
     Note: The result can be found as a null terminated string at req->path.
int uv_fs_rmdir (uv_loop_t* loop, uv_fs_t* req, const char* path, uv_fs_cb cb)
     Equivalent to rmdir(2).
int uv_fs_scandir (uv_loop_t* loop, uv_fs_t* req, const char* path, int flags, uv_fs_cb cb)
int uv fs scandir next (uv fs t* req, uv dirent t* ent)
     Equivalent to scandir(3), with a slightly different API. Once the callback for the request is called, the user can
     use uv_fs_scandir_next () to get ent populated with the next directory entry data. When there are no
     more entries UV_EOF will be returned.
```

**Note:** Unlike *scandir*(3), this function does not return the "." and ".." entries.

**Note:** On Linux, getting the type of an entry is only supported by some file systems (btrfs, ext2, ext3 and ext4 at the time of this writing), check the getdents(2) man page.

int uv\_fs\_copyfile (uv\_loop\_t\* loop, uv\_fs\_t\* req, const char\* path, const char\* new\_path, int flags, uv\_fs\_cb cb)

Copies a file from path to new\_path. Supported flags are described below.

•*UV\_FS\_COPYFILE\_EXCL*: If present, *uv\_fs\_copyfile()* will fail with *UV\_EEXIST* if the destination path already exists. The default behavior is to overwrite the destination if it exists.

**Warning:** If the destination path is created, but an error occurs while copying the data, then the destination path is removed. There is a brief window of time between closing and removing the file where another process could access the file.

New in version 1.14.0.

```
int uv\_fs\_access(uv\_loop\_t*loop, uv\_fs\_t*req, const char* path, int mode, uv\_fs\_cb cb) Equivalent to access(2) on Unix. Windows uses GetFileAttributesW().
```

```
int uv_fs_chmod (uv_loop_t* loop, uv_fs_t* req, const char* path, int mode, uv_fs_cb cb)
```

```
int \mathbf{uv\_fs\_fchmod} (uv\_loop\_t^* loop, uv\_fs\_t^* req, uv\_file file, int mode, uv\_fs\_cb cb) Equivalent to chmod(2) and fchmod(2) respectively.
```

```
int \mathbf{uv\_fs\_utime} (uv\_loop\_t^* loop, uv\_fs\_t^* req, const char* path, double atime, double mtime, uv\_fs\_cb cb)
```

```
int \mathbf{uv\_fs\_futime} (uv\_loop\_t*loop, uv\_fs\_t*req, uv\_file file, double atime, double mtime, uv\_fs\_cb cb) Equivalent to utime(2) and futime(2) respectively.
```

**Note:** AIX: This function only works for AIX 7.1 and newer. It can still be called on older versions but will return UV ENOSYS.

Changed in version 1.10.0: sub-second precission is supported on Windows

int **uv\_fs\_link** (*uv\_loop\_t\* loop*, *uv\_fs\_t\* req*, const char\* *path*, const char\* *new\_path*, uv\_fs\_cb *cb*) Equivalent to link(2).

int **uv\_fs\_symlink** (*uv\_loop\_t\* loop*, *uv\_fs\_t\* req*, const char\* *path*, const char\* *new\_path*, int *flags*, uv\_fs\_cb *cb*) Equivalent to symlink(2).

**Note:** On Windows the *flags* parameter can be specified to control how the symlink will be created:

- •UV\_FS\_SYMLINK\_DIR: indicates that *path* points to a directory.
- •UV\_FS\_SYMLINK\_JUNCTION: request that the symlink is created using junction points.

```
int uv_fs_readlink (uv_loop_t* loop, uv_fs_t* req, const char* path, uv_fs_cb cb) Equivalent to readlink(2).
```

int **uv\_fs\_realpath** (*uv\_loop\_t\* loop*, *uv\_fs\_t\* req*, const char\* *path*, uv\_fs\_cb *cb*) Equivalent to realpath(3) on Unix. Windows uses GetFinalPathNameByHandle.

Warning: This function has certain platform-specific caveats that were discovered when used in Node.

- •macOS and other BSDs: this function will fail with UV\_ELOOP if more than 32 symlinks are found while resolving the given path. This limit is hardcoded and cannot be sidestepped.
- •Windows: while this function works in the common case, there are a number of corner cases where it doesn't:
  - -Paths in ramdisk volumes created by tools which sidestep the Volume Manager (such as ImDisk) cannot be resolved.
  - -Inconsistent casing when using drive letters.
  - -Resolved path bypasses subst'd drives.

While this function can still be used, it's not recommended if scenarios such as the above need to be supported.

The background story and some more details on these issues can be checked here.

**Note:** This function is not implemented on Windows XP and Windows Server 2003. On these systems, UV\_ENOSYS is returned.

New in version 1.8.0.

```
int uv_fs_chown (uv_loop_t* loop, uv_fs_t* req, const char* path, uv_uid_t uid, uv_gid_t gid, uv_fs_cb cb)
```

int **uv\_fs\_fchown** (*uv\_loop\_t\* loop*, *uv\_fs\_t\* req*, *uv\_file file*, uv\_uid\_t *uid*, uv\_gid\_t *gid*, uv\_fs\_cb *cb*) Equivalent to chown(2) and fchown(2) respectively.

**Note:** These functions are not implemented on Windows.

#### See also:

The uv\_req\_t API functions also apply.

## **Helper functions**

```
uv_os_fd_t uv_get_osfhandle (int fd)
```

For a file descriptor in the C runtime, get the OS-dependent handle. On UNIX, returns the fd intact. On Windows, this calls \_get\_osfhandle. Note that the return value is still owned by the C runtime, any attempts to close it or to use it after closing the fd may lead to malfunction.

New in version 1.12.0.

# Thread pool work scheduling

libuv provides a threadpool which can be used to run user code and get notified in the loop thread. This thread pool is internally used to run all file system operations, as well as getaddrinfo and getnameinfo requests.

Its default size is 4, but it can be changed at startup time by setting the UV\_THREADPOOL\_SIZE environment variable to any value (the absolute maximum is 128).

The threadpool is global and shared across all event loops. When a particular function makes use of the threadpool (i.e. when using  $uv\_queue\_work()$ ) libuv preallocates and initializes the maximum number of threads allowed by  $uv\_threadpool\_size$ . This causes a relatively minor memory overhead (~1MB for 128 threads) but increases the performance of threading at runtime.

**Note:** Note that even though a global thread pool which is shared across all events loops is used, the functions are not thread safe.

## **Data types**

```
uv_work_t
```

Work request type.

```
void (*uv_work_t* req)
```

Callback passed to uv\_queue\_work () which will be run on the thread pool.

```
void (*uv_after_work_cb) (uv_work_t* req, int status)
```

Callback passed to  $uv\_queue\_work()$  which will be called on the loop thread after the work on the thread-pool has been completed. If the work was cancelled using  $uv\_cancel()$  status will be UV\_ECANCELED.

## **Public members**

```
uv loop t* uv work t.loop
```

Loop that started this request and where completion will be reported. Readonly.

## See also:

The *uv\_req\_t* members also apply.

## **API**

```
int uv_queue_work (uv_loop_t* loop, uv_work_t* req, uv_work_cb work_cb, uv_after_work_cb after_work_cb)
```

Initializes a work request which will run the given *work\_cb* in a thread from the threadpool. Once *work\_cb* is completed, *after\_work\_cb* will be called on the loop thread.

This request can be cancelled with uv\_cancel().

#### See also:

The uv\_req\_t API functions also apply.

# **DNS** utility functions

libuv provides asynchronous variants of getaddrinfo and getnameinfo.

## **Data types**

## uv\_getaddrinfo\_t

getaddrinfo request type.

```
void (*uv_getaddrinfo_cb) (uv_getaddrinfo_t* req, int status, struct addrinfo* res)
```

Callback which will be called with the getaddrinfo request result once complete. In case it was cancelled, *status* will have a value of UV\_ECANCELED.

#### uv\_getnameinfo\_t

getnameinfo request type.

```
void (*uv_getnameinfo_cb) (uv_getnameinfo_t* req, int status, const char* hostname, const char* service)
```

Callback which will be called with the getnameinfo request result once complete. In case it was cancelled, *status* will have a value of UV\_ECANCELED.

## **Public members**

```
uv loop t* uv getaddrinfo t.loop
```

Loop that started this getaddrinfo request and where completion will be reported. Readonly.

```
struct addrinfo* uv_getaddrinfo_t.addrinfo
```

Pointer to a *struct addrinfo* containing the result. Must be freed by the user with *uv\_freeaddrinfo()*.

Changed in version 1.3.0: the field is declared as public.

```
uv_loop_t* uv_getnameinfo_t.loop
```

Loop that started this getnameinfo request and where completion will be reported. Readonly.

#### char[NI\_MAXHOST] uv\_getnameinfo\_t.host

Char array containing the resulting host. It's null terminated.

Changed in version 1.3.0: the field is declared as public.

## char[NI\_MAXSERV] uv\_getnameinfo\_t.service

Char array containing the resulting service. It's null terminated.

Changed in version 1.3.0: the field is declared as public.

#### See also:

The uv\_req\_t members also apply.

## **API**

int uv\_getaddrinfo (uv\_loop\_t\* loop, uv\_getaddrinfo\_t\* req, uv\_getaddrinfo\_cb getaddrinfo\_cb, const char\* node, const char\* service, const struct addrinfo\* hints)

Asynchronous getaddrinfo(3).

Either node or service may be NULL but not both.

hints is a pointer to a struct addrinfo with additional address type constraints, or NULL. Consult man -s 3 getaddrinfo for more details.

Returns 0 on success or an error code < 0 on failure. If successful, the callback will get called sometime in the future with the lookup result, which is either:

•status == 0, the res argument points to a valid *struct addrinfo*, or

•status < 0, the res argument is NULL. See the UV EAI \* constants.

Call uv\_freeaddrinfo() to free the addrinfo structure.

Changed in version 1.3.0: the callback parameter is now allowed to be NULL, in which case the request will run **synchronously**.

void **uv freeaddrinfo** (struct addrinfo\* *ai*)

Free the struct addrinfo. Passing NULL is allowed and is a no-op.

int  $uv\_getnameinfo$  ( $uv\_loop\_t*$  loop,  $uv\_getnameinfo\_t*$  req,  $uv\_getnameinfo\_cb$   $getnameinfo\_cb$ , const struct sockaddr\* addr, int flags)

Asynchronous getnameinfo(3).

Returns 0 on success or an error code < 0 on failure. If successful, the callback will get called sometime in the future with the lookup result. Consult *man -s 3 getnameinfo* for more details.

Changed in version 1.3.0: the callback parameter is now allowed to be NULL, in which case the request will run **synchronously**.

## See also:

The uv\_req\_t API functions also apply.

# Shared library handling

libuv provides cross platform utilities for loading shared libraries and retrieving symbols from them, using the following API.

## **Data types**

## uv\_lib\_t

Shared library data type.

## **Public members**

N/A

```
API
int uv_dlopen (const char* filename, uv_lib_t* lib)
     Opens a shared library. The filename is in utf-8. Returns 0 on success and -1 on error. Call uv_dlerror() to
     get the error message.
void uv dlclose(uv lib t* lib)
     Close the shared library.
int uv_dlsym (uv_lib_t* lib, const char* name, void** ptr)
     Retrieves a data pointer from a dynamic library. It is legal for a symbol to map to NULL. Returns 0 on success
     and -1 if the symbol was not found.
const char* uv dlerror (const uv lib t* lib)
     Returns the last uv_dlopen() or uv_dlsym() error message.
Threading and synchronization utilities
libuy provides cross-platform implementations for multiple threading and synchronization primitives. The API largely
follows the pthreads API.
Data types
```

```
uv_thread_t
     Thread data type.
void (*uv_thread_cb) (void* arg)
     Callback that is invoked to initialize thread execution. arg is the same value that was passed to
     uv thread create().
uv_key_t
     Thread-local key data type.
     Once-only initializer data type.
uv mutex t
     Mutex data type.
uv_rwlock_t
     Read-write lock data type.
uv sem t
     Semaphore data type.
uv_cond_t
     Condition data type.
```

### **API**

## **Threads**

uv\_barrier\_t

Barrier data type.

```
int uv_thread_create (uv_thread_t* tid, uv_thread_cb entry, void* arg)
     Changed in version 1.4.1: returns a UV_E* error code on failure
```

```
uv_thread_t uv_thread_self (void)
int uv_thread_join (uv_thread_t *tid)
int uv_thread_equal (const uv_thread_t* t1, const uv_thread_t* t2)
```

## Thread-local storage

Note: The total thread-local storage size may be limited. That is, it may not be possible to create many TLS keys.

```
int uv_key_create (uv_key_t* key)
void uv_key_delete (uv_key_t* key)
void* uv_key_get (uv_key_t* key)
void uv_key_set (uv_key_t* key, void* value)
```

## **Once-only initialization**

Runs a function once and only once. Concurrent calls to  $uv\_once()$  with the same guard will block all callers except one (it's unspecified which one). The guard should be initialized statically with the UV\_ONCE\_INIT macro.

```
void uv_once_t* guard, void (*callback)(void))
```

#### **Mutex locks**

Functions return 0 on success or an error code < 0 (unless the return type is void, of course).

```
int uv_mutex_init (uv_mutex_t* handle)
void uv_mutex_destroy (uv_mutex_t* handle)
void uv_mutex_lock (uv_mutex_t* handle)
int uv_mutex_trylock (uv_mutex_t* handle)
void uv_mutex_unlock (uv_mutex_t* handle)
```

## **Read-write locks**

Functions return 0 on success or an error code < 0 (unless the return type is void, of course).

```
int uv_rwlock_init (uv_rwlock_t* rwlock)

void uv_rwlock_destroy (uv_rwlock_t* rwlock)

void uv_rwlock_rdlock (uv_rwlock_t* rwlock)

int uv_rwlock_tryrdlock (uv_rwlock_t* rwlock)

void uv_rwlock_rdunlock (uv_rwlock_t* rwlock)

void uv_rwlock_wrlock (uv_rwlock_t* rwlock)

int uv_rwlock_trywrlock (uv_rwlock_t* rwlock)

void uv_rwlock_trywrlock (uv_rwlock_t* rwlock)

void uv_rwlock_trywrlock (uv_rwlock_t* rwlock)
```

3.2. API documentation 55

## **Semaphores**

```
Functions return 0 on success or an error code < 0 (unless the return type is void, of course). int uv_sem_init (uv_sem_t* sem, unsigned int value)
```

```
void uv_sem_destroy (uv_sem_t* sem)
void uv_sem_post (uv_sem_t* sem)
void uv_sem_wait (uv_sem_t* sem)
int uv_sem_trywait (uv_sem_t* sem)
```

#### **Conditions**

Functions return 0 on success or an error code < 0 (unless the return type is void, of course).

**Note:** Callers should be prepared to deal with spurious wakeups on uv\_cond\_wait() and uv\_cond\_timedwait().

```
int uv_cond_init (uv_cond_t* cond)
void uv_cond_destroy (uv_cond_t* cond)
void uv_cond_signal (uv_cond_t* cond)
void uv_cond_broadcast (uv_cond_t* cond)
void uv_cond_wait (uv_cond_t* cond, uv_mutex_t* mutex)
int uv_cond_timedwait (uv_cond_t* cond, uv_mutex_t* mutex, uint64_t timeout)
```

#### **Barriers**

Functions return 0 on success or an error code < 0 (unless the return type is void, of course).

**Note:**  $uv\_barrier\_wait$  () returns a value > 0 to an arbitrarily chosen "serializer" thread to facilitate cleanup, i.e.

```
if (uv_barrier_wait(&barrier) > 0)
    uv_barrier_destroy(&barrier);
```

```
int uv_barrier_init (uv_barrier_t* barrier, unsigned int count)
void uv_barrier_destroy (uv_barrier_t* barrier)
int uv_barrier_wait (uv_barrier_t* barrier)
```

## Miscellaneous utilities

This section contains miscellaneous functions that don't really belong in any other section.

## Data types

```
uv_buf_t
Buffer data type.

char* uv_buf_t.base
Pointer to the base of the buffer.

size_t uv_buf_t.len
Total bytes in the buffer.
```

Note: On Windows this field is ULONG.

```
void* (*uv_malloc_func) (size_t size)
    Replacement function for malloc(3). See uv_replace_allocator().
void* (*uv_realloc_func) (void* ptr, size_t size)
    Replacement function for realloc(3). See uv_replace_allocator().
void* (*uv_calloc_func) (size_t count, size_t size)
    Replacement function for calloc(3). See uv_replace_allocator().
void (*uv_free_func) (void* ptr)
    Replacement function for free(3). See uv_replace_allocator().
uv_file
    Cross platform representation of a file handle.
```

#### uv\_os\_sock\_t

Cross platform representation of a socket handle.

#### uv os fd t

Abstract representation of a file descriptor. On Unix systems this is a typedef of int and on Windows a HANDLE.

## uv\_rusage\_t

Data type for resource usage results.

```
typedef struct {
   uv_timeval_t ru_utime; /* user CPU time used */
   uv_timeval_t ru_stime; /* system CPU time used */
   uint64_t ru_maxrss; /* maximum resident set size */
   uint64_t ru_ixrss; /* integral shared memory size (X) */
   uint64_t ru_idrss; /* integral unshared data size (X) */
   uint64_t ru_isrss; /* integral unshared stack size (X) */
   uint64_t ru_minflt; /* page reclaims (soft page faults) (X) */
   uint64_t ru_majflt; /* page faults (hard page faults) */
uint64_t ru_nswap; /* swaps (X) */
   uint64_t ru_inblock; /* block input operations */
   uint64_t ru_oublock; /* block output operations */
   uint64_t ru_msgsnd; /* IPC messages sent (X) */
   uint64_t ru_msgrcv; /* IPC messages received (X) */
   uint64_t ru_nsignals; /* signals received (X) */
   uint64_t ru_nvcsw; /* voluntary context switches (X) */
   uint64_t ru_nivcsw; /* involuntary context switches (X) */
} uv_rusage_t;
```

Members marked with (X) are unsupported on Windows. See getrusage (2) for supported fields on Unix

## uv\_cpu\_info\_t

Data type for CPU information.

```
typedef struct uv_cpu_info_s {
   char* model;
   int speed;
   struct uv_cpu_times_s {
      uint64_t user;
      uint64_t nice;
      uint64_t sys;
      uint64_t idle;
      uint64_t irq;
   } cpu_times;
} uv_cpu_info_t;
```

## uv\_interface\_address\_t

Data type for interface addresses.

```
typedef struct uv_interface_address_s {
    char* name;
    char phys_addr[6];
    int is_internal;
    union {
        struct sockaddr_in address4;
        struct sockaddr_in6 address6;
    } address;
    union {
        struct sockaddr_in netmask4;
        struct sockaddr_in netmask4;
        struct sockaddr_in6 netmask6;
    } netmask;
} uv_interface_address_t;
```

#### uv passwd t

Data type for password file information.

```
typedef struct uv_passwd_s {
   char* username;
   long uid;
   long gid;
   char* shell;
   char* homedir;
} uv_passwd_t;
```

#### API

```
uv_handle_type uv_guess_handle (uv_file file)
```

Used to detect what type of stream should be used with a given file descriptor. Usually this will be used during initialization to guess the type of the stdio streams.

For isatty(3) equivalent functionality use this function and test for UV\_TTY.

```
int uv_replace_allocator(uv_malloc_func malloc_func, uv_realloc_func func, uv_calloc_func calloc_func, uv_free_func free_func)
```

New in version 1.6.0.

Override the use of the standard library's malloc(3), calloc(3), realloc(3), free(3), memory allocation functions.

This function must be called before any other libuv function is called or after all resources have been freed and thus libuv doesn't reference any allocated memory chunk.

On success, it returns 0, if any of the function pointers is NULL it returns UV\_EINVAL.

**Warning:** There is no protection against changing the allocator multiple times. If the user changes it they are responsible for making sure the allocator is changed while no memory was allocated with the previous allocator, or that they are compatible.

uv\_buf\_t uv\_buf\_init (char\* base, unsigned int len)

Constructor for *uv\_buf\_t*.

Due to platform differences the user cannot rely on the ordering of the *base* and *len* members of the uv\_buf\_t struct. The user is responsible for freeing *base* after the uv\_buf\_t is done. Return struct passed by value.

char\*\* uv\_setup\_args (int argc, char\*\* argv)

Store the program arguments. Required for getting / setting the process title.

int uv get process title (char\* buffer, size t size)

Gets the title of the current process. You *must* call *uv\_setup\_args* before calling this function. If *buffer* is *NULL* or *size* is zero, *UV\_EINVAL* is returned. If *size* cannot accommodate the process title and terminating *NULL* character, the function returns *UV\_ENOBUFS*.

**Warning:** uv\_get\_process\_title is not thread safe on any platform except Windows.

#### int uv\_set\_process\_title (const char\* title)

Sets the current process title. You *must* call *uv\_setup\_args* before calling this function. On platforms with a fixed size buffer for the process title the contents of *title* will be copied to the buffer and truncated if larger than the available space. Other platforms will return *UV\_ENOMEM* if they cannot allocate enough space to duplicate the contents of *title*.

**Warning:** *uv\_set\_process\_title* is not thread safe on any platform except Windows.

## int uv\_resident\_set\_memory (size\_t\* rss)

Gets the resident set size (RSS) for the current process.

int uv\_uptime (double\* uptime)

Gets the current system uptime.

int uv\_getrusage (uv\_rusage\_t\* rusage)

Gets the resource usage measures for the current process.

**Note:** On Windows not all fields are set, the unsupported fields are filled with zeroes. See *uv\_rusage\_t* for more details.

```
int uv_cpu_info (uv_cpu_info_t** cpu_infos, int* count)
```

Gets information about the CPUs on the system. The  $cpu\_infos$  array will have count elements and needs to be freed with  $uv\_free\_cpu\_info()$ .

void uv\_free\_cpu\_info (uv\_cpu\_info\_t\* cpu\_infos, int count)

Frees the *cpu\_infos* array previously allocated with *uv\_cpu\_info*().

## int uv\_interface\_addresses (uv\_interface\_address\_t\*\* addresses, int\* count)

Gets address information about the network interfaces on the system. An array of *count* elements is allocated and returned in *addresses*. It must be freed by the user, calling *uv\_free\_interface\_addresses()*.

```
void uv_free_interface_addresses (uv_interface_address_t* addresses, int count)
```

Free an array of  $uv\_interface\_address\_t$  which was returned by  $uv\_interface\_addresses$  ().

#### void **uv** loadavg (double avg[3])

Gets the load average. See: http://en.wikipedia.org/wiki/Load (computing)

**Note:** Returns [0,0,0] on Windows (i.e., it's not implemented).

int **uv** ip4 addr (const char\* ip, int port, struct sockaddr in\* addr)

Convert a string containing an IPv4 addresses to a binary structure.

int **uv\_ip6\_addr** (const char\* *ip*, int *port*, struct sockaddr\_in6\* *addr*)

Convert a string containing an IPv6 addresses to a binary structure.

int uv\_ip4\_name (const struct sockaddr\_in\* src, char\* dst, size\_t size)

Convert a binary structure containing an IPv4 address to a string.

int uv\_ip6\_name (const struct sockaddr\_in6\* src, char\* dst, size\_t size)

Convert a binary structure containing an IPv6 address to a string.

int **uv\_inet\_ntop** (int *af*, const void\* *src*, char\* *dst*, size\_t *size*)

int uv\_inet\_pton (int af, const char\* src, void\* dst)

Cross-platform IPv6-capable implementation of inet\_ntop(3) and inet\_pton(3). On success they return 0. In case of error the target *dst* pointer is unmodified.

int uv\_exepath (char\* buffer, size\_t\* size)

Gets the executable path.

int **uv\_cwd** (char\* buffer, size\_t\* size)

Gets the current working directory, and stores it in *buffer*. If the current working directory is too large to fit in *buffer*, this function returns *UV\_ENOBUFS*, and sets *size* to the required length, including the null terminator.

Changed in version 1.1.0: On Unix the path no longer ends in a slash.

Changed in version 1.9.0: the returned length includes the terminating null byte on *UV\_ENOBUFS*, and the buffer is null terminated on success.

int **uv chdir** (const char\* *dir*)

Changes the current working directory.

int uv\_os\_homedir (char\* buffer, size\_t\* size)

Gets the current user's home directory. On Windows,  $uv\_os\_homedir()$  first checks the USERPROFILE environment variable using GetEnvironmentVariableW(). If USERPROFILE is not set, GetUserProfileDirectoryW() is called. On all other operating systems,  $uv\_os\_homedir()$  first checks the HOME environment variable using getenv(3). If HOME is not set,  $getpwuid\_r(3)$  is called. The user's home directory is stored in buffer. When  $uv\_os\_homedir()$  is called, size indicates the maximum size of buffer. On success size is set to the string length of buffer. On  $UV\_ENOBUFS$  failure size is set to the required length for buffer, including the null byte.

**Warning:** *uv\_os\_homedir()* is not thread safe.

New in version 1.6.0.

int **uv\_os\_tmpdir** (char\* *buffer*, size\_t\* *size*)

Gets the temp directory. On Windows,  $uv\_os\_tmpdir()$  uses GetTempPathW(). On all other operating systems,  $uv\_os\_tmpdir()$  uses the first environment variable found in the ordered list TMPDIR, TMP, TEMP, and TEMPDIR. If none of these are found, the path "/tmp" is used, or, on Android, "/data/local/tmp" is used. The temp directory is stored in buffer. When  $uv\_os\_tmpdir()$  is called, size indicates the maximum size of buffer. On success size is set to the string length of buffer (which does not include the terminating null). On  $UV\_ENOBUFS$  failure size is set to the required length for buffer, including the null byte.

**Warning:** *uv\_os\_tmpdir()* is not thread safe.

New in version 1.9.0.

## int uv\_os\_get\_passwd(uv\_passwd\_t\* pwd)

Gets a subset of the password file entry for the current effective uid (not the real uid). The populated data includes the username, euid, gid, shell, and home directory. On non-Windows systems, all data comes from get-pwuid\_r(3). On Windows, uid and gid are set to -1 and have no meaning, and shell is NULL. After successfully calling this function, the memory allocated to pwd needs to be freed with  $uv\_os\_free\_passwd()$ .

New in version 1.9.0.

# void uv\_os\_free\_passwd (uv\_passwd\_t\* pwd)

Frees the pwd memory previously allocated with  $uv\_os\_get\_passwd()$ .

New in version 1.9.0.

## uint64\_t uv\_get\_total\_memory (void)

Gets memory information (in bytes).

#### uint64\_t uv\_hrtime (void)

Returns the current high-resolution real time. This is expressed in nanoseconds. It is relative to an arbitrary time in the past. It is not related to the time of day and therefore not subject to clock drift. The primary use is for measuring performance between intervals.

**Note:** Not every platform can support nanosecond resolution; however, this value will always be in nanoseconds.

## void uv\_print\_all\_handles (uv\_loop\_t\* loop, FILE\* stream)

Prints all handles associated with the given *loop* to the given *stream*.

Example:

The format is [flags] handle-type handle-address. For flags:

- R is printed for a handle that is referenced
- •A is printed for a handle that is active
- I is printed for a handle that is internal

Warning: This function is meant for ad hoc debugging, there is no API/ABI stability guarantees.

New in version 1.8.0.

```
void uv_print_active_handles (uv_loop_t* loop, FILE* stream)
```

This is the same as uv\_print\_all\_handles() except only active handles are printed.

Warning: This function is meant for ad hoc debugging, there is no API/ABI stability guarantees.

New in version 1.8.0.

int uv\_os\_getenv (const char\* name, char\* buffer, size\_t\* size)

Retrieves the environment variable specified by *name*, copies its value into *buffer*, and sets *size* to the string length of the value. When calling this function, *size* must be set to the amount of storage available in *buffer*, including the null terminator. If the environment variable exceeds the storage available in *buffer*, *UV\_ENOBUFS* is returned, and *size* is set to the amount of storage required to hold the value. If no matching environment variable exists, *UV\_ENOENT* is returned.

**Warning:** This function is not thread safe.

New in version 1.12.0.

int uv\_os\_setenv (const char\* name, const char\* value)

Creates or updates the environment variable specified by *name* with *value*.

Warning: This function is not thread safe.

New in version 1.12.0.

int uv os unsetenv (const char\* name)

Deletes the environment variable specified by *name*. If no such environment variable exists, this function returns successfully.

Warning: This function is not thread safe.

New in version 1.12.0.

int uv\_os\_gethostname (char\* buffer, size\_t\* size)

Returns the hostname as a null-terminated string in *buffer*, and sets *size* to the string length of the hostname. When calling this function, *size* must be set to the amount of storage available in *buffer*, including the null terminator. If the hostname exceeds the storage available in *buffer*, *UV\_ENOBUFS* is returned, and *size* is set to the amount of storage required to hold the value.

New in version 1.12.0.

# User guide

**Warning:** The contents of this guide have been recently incorporated into the libuv documentation and it hasn't gone through thorough review yet. If you spot a mistake please file an issue, or better yet, open a pull request!

## Introduction

This 'book' is a small set of tutorials about using libuv as a high performance evented I/O library which offers the same API on Windows and Unix.

It is meant to cover the main areas of libuv, but is not a comprehensive reference discussing every function and data structure. The official libuv documentation may be consulted for full details.

This book is still a work in progress, so sections may be incomplete, but I hope you will enjoy it as it grows.

#### Who this book is for

If you are reading this book, you are either:

- 1. a systems programmer, creating low-level programs such as daemons or network services and clients. You have found that the event loop approach is well suited for your application and decided to use libuv.
- 2. a node.js module writer, who wants to wrap platform APIs written in C or C++ with a set of (a)synchronous APIs that are exposed to JavaScript. You will use libuv purely in the context of node.js. For this you will require some other resources as the book does not cover parts specific to v8/node.js.

This book assumes that you are comfortable with the C programming language.

## **Background**

The node.js project began in 2009 as a JavaScript environment decoupled from the browser. Using Google's V8 and Marc Lehmann's libev, node.js combined a model of I/O – evented – with a language that was well suited to the style of programming; due to the way it had been shaped by browsers. As node.js grew in popularity, it was important to make it work on Windows, but libev ran only on Unix. The Windows equivalent of kernel event notification mechanisms like kqueue or (e)poll is IOCP. libuv was an abstraction around libev or IOCP depending on the platform, providing users an API based on libev. In the node-v0.9.0 version of libuv libev was removed.

Since then libuv has continued to mature and become a high quality standalone library for system programming. Users outside of node.js include Mozilla's Rust programming language, and a variety of language bindings.

This book and the code is based on libuv version v1.3.0.

#### Code

All the code from this book is included as part of the source of the book on Github. Clone/Download the book, then build libuy:

```
cd libuv
./autogen.sh
./configure
make
```

There is no need to make install. To build the examples run make in the code/directory.

## **Basics of libuv**

libuv enforces an **asynchronous**, **event-driven** style of programming. Its core job is to provide an event loop and callback based notifications of I/O and other activities. libuv offers core utilities like timers, non-blocking networking support, asynchronous file system access, child processes and more.

3.3. User guide 63

## **Event loops**

In event-driven programming, an application expresses interest in certain events and respond to them when they occur. The responsibility of gathering events from the operating system or monitoring other sources of events is handled by libuv, and the user can register callbacks to be invoked when an event occurs. The event-loop usually keeps running *forever*. In pseudocode:

```
while there are still events to process:
    e = get the next event
    if there is a callback associated with e:
        call the callback
```

Some examples of events are:

- File is ready for writing
- · A socket has data ready to be read
- · A timer has timed out

This event loop is encapsulated by uv\_run() – the end-all function when using libuv.

The most common activity of systems programs is to deal with input and output, rather than a lot of number-crunching. The problem with using conventional input/output functions (read, fprintf, etc.) is that they are **blocking**. The actual write to a hard disk or reading from a network, takes a disproportionately long time compared to the speed of the processor. The functions don't return until the task is done, so that your program is doing nothing. For programs which require high performance this is a major roadblock as other activities and other I/O operations are kept waiting.

One of the standard solutions is to use threads. Each blocking I/O operation is started in a separate thread (or in a thread pool). When the blocking function gets invoked in the thread, the processor can schedule another thread to run, which actually needs the CPU.

The approach followed by libuv uses another style, which is the **asynchronous, non-blocking** style. Most modern operating systems provide event notification subsystems. For example, a normal read call on a socket would block until the sender actually sent something. Instead, the application can request the operating system to watch the socket and put an event notification in the queue. The application can inspect the events at its convenience (perhaps doing some number crunching before to use the processor to the maximum) and grab the data. It is **asynchronous** because the application expressed interest at one point, then used the data at another point (in time and space). It is **non-blocking** because the application process was free to do other tasks. This fits in well with libuv's event-loop approach, since the operating system events can be treated as just another libuv event. The non-blocking ensures that other events can continue to be handled as fast as they come in 1.

**Note:** How the I/O is run in the background is not of our concern, but due to the way our computer hardware works, with the thread as the basic unit of the processor, libuv and OSes will usually run background/worker threads and/or polling to perform tasks in a non-blocking manner.

Bert Belder, one of the libuv core developers has a small video explaining the architecture of libuv and its background. If you have no prior experience with either libuv or libev, it is a quick, useful watch.

libuv's event loop is explained in more detail in the documentation.

## **Hello World**

With the basics out of the way, lets write our first libuv program. It does nothing, except start a loop which will exit immediately.

<sup>&</sup>lt;sup>1</sup> Depending on the capacity of the hardware of course.

## helloworld/main.c

```
#include <stdio.h>
   #include <stdlib.h>
2
   #include <uv.h>
3
   int main() {
5
       uv_loop_t *loop = malloc(sizeof(uv_loop_t));
6
       uv_loop_init(loop);
7
       printf("Now quitting.\n");
       uv_run(loop, UV_RUN_DEFAULT);
11
       uv_loop_close(loop);
12
       free (loop);
13
       return 0;
14
```

This program quits immediately because it has no events to process. A libuve event loop has to be told to watch out for events using the various API functions.

Starting with libuv v1.0, users should allocate the memory for the loops before initializing it with uv\_loop\_init(uv\_loop\_t \*). This allows you to plug in custom memory management. Remember to deinitialize the loop using uv\_loop\_close(uv\_loop\_t \*) and then delete the storage. The examples never close loops since the program quits after the loop ends and the system will reclaim memory. Production grade projects, especially long running systems programs, should take care to release correctly.

## **Default loop**

A default loop is provided by libuv and can be accessed using uv\_default\_loop(). You should use this loop if you only want a single loop.

Note: node.js uses the default loop as its main loop. If you are writing bindings you should be aware of this.

## **Error handling**

Initialization functions or synchronous functions which may fail return a negative number on error. Async functions that may fail will pass a status parameter to their callbacks. The error messages are defined as UV\_E\* constants.

You can use the uv\_strerror(int) and uv\_err\_name(int) functions to get a const\_char \* describing the error or the error name respectively.

I/O read callbacks (such as for files and sockets) are passed a parameter nread. If nread is less than 0, there was an error (UV\_EOF is the end of file error, which you may want to handle differently).

## **Handles and Requests**

libuv works by the user expressing interest in particular events. This is usually done by creating a **handle** to an I/O device, timer or process. Handles are opaque structs named as uv\_TYPE\_t where type signifies what the handle is used for.

3.3. User guide 65

#### libuv watchers

```
} uv_req_type;
/* Handle types. */
typedef struct uv_loop_s uv_loop_t;
typedef struct uv_handle_s uv_handle_t;
typedef struct uv_stream_s uv_stream_t;
typedef struct uv_tcp_s uv_tcp_t;
typedef struct uv_udp_s uv_udp_t;
typedef struct uv_pipe_s uv_pipe_t;
typedef struct uv_tty_s uv_tty_t;
typedef struct uv_poll_s uv_poll_t;
typedef struct uv_timer_s uv_timer_t;
typedef struct uv_prepare_s uv_prepare_t;
typedef struct uv_check_s uv_check_t;
typedef struct uv_idle_s uv_idle_t;
typedef struct uv_async_s uv_async_t;
typedef struct uv_process_s uv_process_t;
typedef struct uv_fs_event_s uv_fs_event_t;
typedef struct uv_fs_poll_s uv_fs_poll_t;
typedef struct uv_signal_s uv_signal_t;
/* Request types. */
typedef struct uv_req_s uv_req_t;
typedef struct uv_getaddrinfo_s uv_getaddrinfo_t;
typedef struct uv_getnameinfo_s uv_getnameinfo_t;
typedef struct uv_shutdown_s uv_shutdown_t;
typedef struct uv_write_s uv_write_t;
typedef struct uv_connect_s uv_connect_t;
typedef struct uv_udp_send_s uv_udp_send_t;
typedef struct uv_fs_s uv_fs_t;
typedef struct uv_work_s uv_work_t;
/* None of the above. */
```

Handles represent long-lived objects. Async operations on such handles are identified using **requests**. A request is short-lived (usually used across only one callback) and usually indicates one I/O operation on a handle. Requests are used to preserve context between the initiation and the callback of individual actions. For example, an UDP socket is represented by a uv\_udp\_t, while individual writes to the socket use a uv\_udp\_send\_t structure that is passed to the callback after the write is done.

Handles are setup by a corresponding:

```
uv_TYPE_init(uv_loop_t *, uv_TYPE_t *)
```

#### function.

Callbacks are functions which are called by libuv whenever an event the watcher is interested in has taken place. Application specific logic will usually be implemented in the callback. For example, an IO watcher's callback will receive the data read from a file, a timer callback will be triggered on timeout and so on.

## Idling

Here is an example of using an idle handle. The callback is called once on every turn of the event loop. A use case for idle handles is discussed in *Utilities*. Let us use an idle watcher to look at the watcher life cycle and see how

uv\_run() will now block because a watcher is present. The idle watcher is stopped when the count is reached and uv\_run() exits since no event watchers are active.

#### idle-basic/main.c

```
#include <stdio.h>
#include <uv.h>

int64_t counter = 0;

void wait_for_a_while(uv_idle_t* handle) {
    counter++;

    if (counter >= 10e6)
        uv_idle_stop(handle);
}

int main() {
    uv_idle_t idler;

    uv_idle_init(uv_default_loop(), &idler);
    uv_idle_start(&idler, wait_for_a_while);

    printf("Idling...\n");
    uv_run(uv_default_loop(), UV_RUN_DEFAULT);

    uv_loop_close(uv_default_loop());
    return 0;
}
```

## Storing context

In callback based programming style you'll often want to pass some 'context' – application specific information – between the call site and the callback. All handles and requests have a void\* data member which you can set to the context and cast back in the callback. This is a common pattern used throughout the C library ecosystem. In addition uv\_loop\_t also has a similar data member.

# **Filesystem**

Simple filesystem read/write is achieved using the uv\_fs\_\* functions and the uv\_fs\_t struct.

**Note:** The libuv filesystem operations are different from *socket operations*. Socket operations use the non-blocking operations provided by the operating system. Filesystem operations use blocking functions internally, but invoke these functions in a thread pool and notify watchers registered with the event loop when application interaction is required.

All filesystem functions have two forms - synchronous and asynchronous.

The *synchronous* forms automatically get called (and **block**) if the callback is null. The return value of functions is a *libuv error code*. This is usually only useful for synchronous calls. The *asynchronous* form is called when a callback is passed and the return value is 0.

3.3. User guide 67

## Reading/Writing files

A file descriptor is obtained using

flags and mode are standard Unix flags. libuv takes care of converting to the appropriate Windows flags.

File descriptors are closed using

```
int uv_fs_close(uv_loop_t* loop, uv_fs_t* req, uv_file file, uv_fs_cb cb)
```

Filesystem operation callbacks have the signature:

```
void callback(uv_fs_t* req);
```

Let's see a simple implementation of cat. We start with registering a callback for when the file is opened:

## uvcat/main.c - opening a file

```
void on_open(uv_fs_t *req) {
       // The request passed to the callback is the same as the one the call setup
2
       // function was passed.
3
       assert (req == &open_req);
       if (req->result >= 0) {
           iov = uv_buf_init(buffer, sizeof(buffer));
6
           uv_fs_read(uv_default_loop(), &read_req, req->result,
                      &iov, 1, -1, on_read);
9
10
       else {
11
           fprintf(stderr, "error opening file: %s\n", uv_strerror((int)req->result));
12
13
```

The result field of a uv\_fs\_t is the file descriptor in case of the uv\_fs\_open callback. If the file is successfully opened, we start reading it.

#### uvcat/main.c - read callback

```
void on_read(uv_fs_t *req) {
       if (req->result < 0) {</pre>
2
           fprintf(stderr, "Read error: %s\n", uv_strerror(req->result));
       else if (req->result == 0) {
           uv_fs_t close_req;
6
           // synchronous
           uv_fs_close(uv_default_loop(), &close_req, open_req.result, NULL);
8
       else if (req->result > 0) {
10
           iov.len = req->result;
11
           uv_fs_write(uv_default_loop(), &write_req, 1, &iov, 1, -1, on_write);
12
       }
13
   }
14
```

In the case of a read call, you should pass an *initialized* buffer which will be filled with data before the read callback is triggered. The uv\_fs\_\* operations map almost directly to certain POSIX functions, so EOF is indicated in this case by result being 0. In the case of streams or pipes, the UV\_EOF constant would have been passed as a status instead.

Here you see a common pattern when writing asynchronous programs. The uv\_fs\_close() call is performed synchronously. Usually tasks which are one-off, or are done as part of the startup or shutdown stage are performed synchronously, since we are interested in fast I/O when the program is going about its primary task and dealing with multiple I/O sources. For solo tasks the performance difference usually is negligible and may lead to simpler code.

Filesystem writing is similarly simple using uv\_fs\_write(). Your callback will be triggered after the write is complete. In our case the callback simply drives the next read. Thus read and write proceed in lockstep via callbacks.

#### uvcat/main.c - write callback

**Warning:** Due to the way filesystems and disk drives are configured for performance, a write that 'succeeds' may not be committed to disk yet.

We set the dominos rolling in main():

#### uvcat/main.c

```
int main(int argc, char **argv) {
    uv_fs_open(uv_default_loop(), &open_req, argv[1], O_RDONLY, 0, on_open);
    uv_run(uv_default_loop(), UV_RUN_DEFAULT);

uv_fs_req_cleanup(&open_req);
    uv_fs_req_cleanup(&read_req);
    uv_fs_req_cleanup(&write_req);
    return 0;
}
```

Warning: The uv\_fs\_req\_cleanup() function must always be called on filesystem requests to free internal memory allocations in libuv.

#### Filesystem operations

All the standard filesystem operations like unlink, rmdir, stat are supported asynchronously and have intuitive argument order. They follow the same patterns as the read/write/open calls, returning the result in the uv\_fs\_t. result field. The full list:

### Filesystem operations

```
UV_EXTERN int uv_os_gethostname(char* buffer, size_t* size);
typedef enum {
 UV_FS_UNKNOWN = -1,
  UV_FS_CUSTOM,
 UV_FS_OPEN,
  UV_FS_CLOSE,
  UV_FS_READ,
  UV_FS_WRITE,
  UV_FS_SENDFILE,
  UV_FS_STAT,
  UV_FS_LSTAT,
  UV_FS_FSTAT,
  UV_FS_FTRUNCATE,
  UV_FS_UTIME,
  UV_FS_FUTIME,
  UV_FS_ACCESS,
  UV_FS_CHMOD,
  UV_FS_FCHMOD,
  UV FS FSYNC,
  UV_FS_FDATASYNC,
  UV_FS_UNLINK,
  UV_FS_RMDIR,
  UV_FS_MKDIR,
  UV_FS_MKDTEMP,
  UV_FS_RENAME,
  UV FS SCANDIR,
  UV_FS_LINK,
 UV_FS_SYMLINK,
 UV_FS_READLINK,
 UV_FS_CHOWN,
 UV_FS_FCHOWN,
 UV_FS_REALPATH,
 UV_FS_COPYFILE
} uv_fs_type;
/* uv_fs_t is a subclass of uv_req_t. */
struct uv_fs_s {
 UV_REQ_FIELDS
 uv_fs_type fs_type;
 uv_loop_t* loop;
 uv_fs_cb cb;
 ssize_t result;
 void* ptr;
 const char* path;
 uv_stat_t statbuf; /* Stores the result of uv_fs_stat() and uv_fs_fstat(). */
 UV_FS_PRIVATE_FIELDS
} ;
UV_EXTERN void uv_fs_req_cleanup(uv_fs_t* req);
UV_EXTERN int uv_fs_close(uv_loop_t* loop,
                          uv_fs_t* req,
                          uv_file file,
                          uv_fs_cb cb);
UV_EXTERN int uv_fs_open(uv_loop_t* loop,
```

```
uv_fs_t* req,
                         const char* path,
                         int flags,
                         int mode,
                         uv_fs_cb cb);
UV_EXTERN int uv_fs_read(uv_loop_t* loop,
                         uv_fs_t* req,
                         uv_file file,
                         const uv_buf_t bufs[],
                         unsigned int nbufs,
                         int64_t offset,
                         uv_fs_cb cb);
UV_EXTERN int uv_fs_unlink(uv_loop_t* loop,
                           uv_fs_t* req,
                           const char* path,
                           uv_fs_cb cb);
UV_EXTERN int uv_fs_write(uv_loop_t* loop,
                          uv_fs_t* req,
                          uv_file file,
                          const uv_buf_t bufs[],
                          unsigned int nbufs,
                          int64_t offset,
                          uv_fs_cb cb);
* This flag can be used with uv_fs_copyfile() to return an error if the
* destination already exists.
#define UV_FS_COPYFILE_EXCL 0x0001
UV_EXTERN int uv_fs_copyfile(uv_loop_t* loop,
                             uv_fs_t* req,
                             const char* path,
                             const char* new_path,
                             int flags,
                             uv_fs_cb cb);
UV_EXTERN int uv_fs_mkdir(uv_loop_t* loop,
                          uv_fs_t* req,
                          const char* path,
                          int mode,
                          uv_fs_cb cb);
UV_EXTERN int uv_fs_mkdtemp(uv_loop_t* loop,
                            uv_fs_t* req,
                            const char* tpl,
                            uv_fs_cb cb);
UV_EXTERN int uv_fs_rmdir(uv_loop_t* loop,
                          uv_fs_t* req,
                          const char* path,
                          uv_fs_cb cb);
UV_EXTERN int uv_fs_scandir(uv_loop_t* loop,
                            uv_fs_t* req,
                            const char* path,
                            int flags,
                            uv_fs_cb cb);
UV_EXTERN int uv_fs_scandir_next(uv_fs_t* req,
                                 uv_dirent_t* ent);
UV_EXTERN int uv_fs_stat(uv_loop_t* loop,
```

#### **Buffers and Streams**

The basic I/O handle in libuv is the stream (uv\_stream\_t). TCP sockets, UDP sockets, and pipes for file I/O and IPC are all treated as stream subclasses.

Streams are initialized using custom functions for each subclass, then operated upon using

The stream based functions are simpler to use than the filesystem ones and libuv will automatically keep reading from a stream when uv\_read\_start() is called once, until uv\_read\_stop() is called.

The discrete unit of data is the buffer - uv\_buf\_t. This is simply a collection of a pointer to bytes (uv\_buf\_t.base) and the length (uv\_buf\_t.len). The uv\_buf\_t is lightweight and passed around by value. What does require management is the actual bytes, which have to be allocated and freed by the application.

```
Error: THIS PROGRAM DOES NOT ALWAYS WORK, NEED SOMETHING BETTER**
```

To demonstrate streams we will need to use uv\_pipe\_t. This allows streaming local files<sup>2</sup>. Here is a simple tee utility using libuv. Doing all operations asynchronously shows the power of evented I/O. The two writes won't block each other, but we have to be careful to copy over the buffer data to ensure we don't free a buffer until it has been written.

The program is to be executed as:

```
./uvtee <output_file>
```

We start off opening pipes on the files we require. libuv pipes to a file are opened as bidirectional by default.

## uvtee/main.c - read on pipes

```
int main(int argc, char **argv) {
       loop = uv_default_loop();
3
       uv_pipe_init(loop, &stdin_pipe, 0);
5
       uv_pipe_open(&stdin_pipe, 0);
6
       uv_pipe_init(loop, &stdout_pipe, 0);
       uv_pipe_open(&stdout_pipe, 1);
10
       uv_fs_t file_req;
11
       int fd = uv_fs_open(loop, &file_req, argv[1], O_CREAT | O_RDWR, 0644, NULL);
12
13
       uv_pipe_init(loop, &file_pipe, 0);
       uv_pipe_open(&file_pipe, fd);
14
15
       uv_read_start((uv_stream_t*)&stdin_pipe, alloc_buffer, read_stdin);
16
17
       uv_run(loop, UV_RUN_DEFAULT);
18
       return 0;
19
```

<sup>&</sup>lt;sup>2</sup> see *Pipes* 

The third argument of uv\_pipe\_init() should be set to 1 for IPC using named pipes. This is covered in *Processes*. The uv\_pipe\_open() call associates the pipe with the file descriptor, in this case 0 (standard input).

We start monitoring stdin. The alloc\_buffer callback is invoked as new buffers are required to hold incoming data. read\_stdin will be called with these buffers.

### uvtee/main.c - reading buffers

```
void alloc_buffer(uv_handle_t *handle, size_t suggested_size, uv_buf_t *buf) {
2
       *buf = uv_buf_init((char*) malloc(suggested_size), suggested_size);
4
   void read_stdin(uv_stream_t *stream, ssize_t nread, const uv_buf_t *buf) {
5
       if (nread < 0) {
6
           if (nread == UV_EOF) {
7
               // end of file
               uv_close((uv_handle_t *)&stdin_pipe, NULL);
10
               uv_close((uv_handle_t *)&stdout_pipe, NULL);
               uv_close((uv_handle_t *)&file_pipe, NULL);
11
12
       } else if (nread > 0) {
13
           write_data((uv_stream_t *)&stdout_pipe, nread, *buf, on_stdout_write);
14
           write_data((uv_stream_t *)&file_pipe, nread, *buf, on_file_write);
15
       }
17
       // OK to free buffer as write_data copies it.
18
       if (buf->base)
19
           free (buf->base):
20
```

The standard malloc is sufficient here, but you can use any memory allocation scheme. For example, node.js uses its own slab allocator which associates buffers with V8 objects.

The read callback nread parameter is less than 0 on any error. This error might be EOF, in which case we close all the streams, using the generic close function uv\_close() which deals with the handle based on its internal type. Otherwise nread is a non-negative number and we can attempt to write that many bytes to the output streams. Finally remember that buffer allocation and deallocation is application responsibility, so we free the data.

The allocation callback may return a buffer with length zero if it fails to allocate memory. In this case, the read callback is invoked with error UV\_ENOBUFS. libuv will continue to attempt to read the stream though, so you must explicitly call uv\_close() if you want to stop when allocation fails.

The read callback may be called with nread = 0, indicating that at this point there is nothing to be read. Most applications will just ignore this.

## uvtee/main.c - Write to pipe

```
typedef struct {
    uv_write_t req;
    uv_buf_t buf;
} write_req_t;

void free_write_req(uv_write_t *req) {
    write_req_t *wr = (write_req_t*) req;
}
```

```
free (wr->buf.base);
       free (wr);
10
11
   void on_stdout_write(uv_write_t *req, int status) {
12
       free_write_req(req);
   }
14
15
   void on_file_write(uv_write_t *req, int status) {
16
       free_write_req(req);
17
   }
18
19
   void write_data(uv_stream_t *dest, size_t size, uv_buf_t buf, uv_write_cb cb) {
20
       write_req_t *req = (write_req_t*) malloc(sizeof(write_req_t));
21
       req->buf = uv_buf_init((char*) malloc(size), size);
22
       memcpy(req->buf.base, buf.base, size);
23
       uv_write((uv_write_t*) req, (uv_stream_t*)dest, &req->buf, 1, cb);
24
   }
```

write\_data() makes a copy of the buffer obtained from read. This buffer does not get passed through to the write callback trigged on write completion. To get around this we wrap a write request and a buffer in write\_req\_t and unwrap it in the callbacks. We make a copy so we can free the two buffers from the two calls to write\_data independently of each other. While acceptable for a demo program like this, you'll probably want smarter memory management, like reference counted buffers or a pool of buffers in any major application.

**Warning:** If your program is meant to be used with other programs it may knowingly or unknowingly be writing to a pipe. This makes it susceptible to aborting on receiving a SIGPIPE. It is a good idea to insert:

```
signal(SIGPIPE, SIG_IGN)
```

in the initialization stages of your application.

### File change events

All modern operating systems provide APIs to put watches on individual files or directories and be informed when the files are modified. libuv wraps common file change notification libraries<sup>1</sup>. This is one of the more inconsistent parts of libuv. File change notification systems are themselves extremely varied across platforms so getting everything working everywhere is difficult. To demonstrate, I'm going to build a simple utility which runs a command whenever any of the watched files change:

```
./onchange <command> <file1> [file2] ...
```

The file change notification is started using uv\_fs\_event\_init():

# onchange/main.c - The setup

```
int main(int argc, char **argv) {
   if (argc <= 2) {
      fprintf(stderr, "Usage: %s <command> <file1> [file2 ...]\n", argv[0]);
      return 1;
```

<sup>&</sup>lt;sup>1</sup> inotify on Linux, FSEvents on Darwin, kqueue on BSDs, ReadDirectoryChangesW on Windows, event ports on Solaris, unsupported on Cygwin

```
6
       loop = uv_default_loop();
       command = argv[1];
       while (argc-- > 2) {
           fprintf(stderr, "Adding watch on \$s \n", argv[argc]);
11
           uv_fs_event_t *fs_event_req = malloc(sizeof(uv_fs_event_t));
12
           uv_fs_event_init(loop, fs_event_reg);
13
           // The recursive flag watches subdirectories too.
14
           uv_fs_event_start(fs_event_req, run_command, argv[argc], UV_FS_EVENT_
15
    →RECURSIVE);
       }
16
17
       return uv_run(loop, UV_RUN_DEFAULT);
18
```

The third argument is the actual file or directory to monitor. The last argument, flags, can be:

```
uv_file file,
};
uv_fs_event_private_fields
```

UV\_FS\_EVENT\_WATCH\_ENTRY and UV\_FS\_EVENT\_STAT don't do anything (yet). UV\_FS\_EVENT\_RECURSIVE will start watching subdirectories as well on supported platforms.

The callback will receive the following arguments:

- 1. uv\_fs\_event\_t \*handle The handle. The path field of the handle is the file on which the watch was set.
- 2. const char \*filename If a directory is being monitored, this is the file which was changed. Only non-null on Linux and Windows. May be null even on those platforms.
- 3. int flags one of UV\_RENAME or UV\_CHANGE, or a bitwise OR of both.
- 4. int status Currently 0.

In our example we simply print the arguments and run the command using system().

## onchange/main.c - file change notification callback

```
void run_command(uv_fs_event_t *handle, const char *filename, int events, int status)
   \hookrightarrow {
       char path[1024];
       size_t size = 1023;
       // Does not handle error if path is longer than 1023.
       uv_fs_event_getpath(handle, path, &size);
       path[size] = ' \0';
       fprintf(stderr, "Change detected in %s: ", path);
       if (events & UV_RENAME)
           fprintf(stderr, "renamed");
10
       if (events & UV_CHANGE)
11
           fprintf(stderr, "changed");
12
13
       fprintf(stderr, " %s\n", filename ? filename : "");
```

```
system(command);

| System(command);
```

# **Networking**

Networking in libuv is not much different from directly using the BSD socket interface, some things are easier, all are non-blocking, but the concepts stay the same. In addition libuv offers utility functions to abstract the annoying, repetitive and low-level tasks like setting up sockets using the BSD socket structures, DNS lookup, and tweaking various socket parameters.

The uv\_tcp\_t and uv\_udp\_t structures are used for network I/O.

**Note:** The code samples in this chapter exist to show certain libuv APIs. They are not examples of good quality code. They leak memory and don't always close connections properly.

## **TCP**

TCP is a connection oriented, stream protocol and is therefore based on the libuv streams infrastructure.

#### Server

Server sockets proceed by:

- 1. uv\_tcp\_init the TCP handle.
- 2. uv\_tcp\_bind it.
- 3. Call uv\_listen on the handle to have a callback invoked whenever a new connection is established by a client.
- 4. Use uv\_accept to accept the connection.
- 5. Use *stream operations* to communicate with the client.

Here is a simple echo server

## tcp-echo-server/main.c - The listen socket

```
uv_close((uv_handle_t*) client, on_close);

uv_close((uv_handle_t*) client, on_close);

int main() {
    loop = uv_default_loop();

    uv_tcp_t server;
    uv_tcp_init(loop, &server);

uv_ip4_addr("0.0.0.0", DEFAULT_PORT, &addr);

uv_ip4_addr("0.0.0.0", DEFAULT_PORT, &addr);
```

```
uv_tcp_bind(&server, (const struct sockaddr*)&addr, 0);
int r = uv_listen((uv_stream_t*) &server, DEFAULT_BACKLOG, on_new_connection);

if (r) {
    fprintf(stderr, "Listen error %s\n", uv_strerror(r));
    return 1;
}

return uv_run(loop, UV_RUN_DEFAULT);
}
```

You can see the utility function uv\_ip4\_addr being used to convert from a human readable IP address, port pair to the sockaddr\_in structure required by the BSD socket APIs. The reverse can be obtained using uv\_ip4\_name.

**Note:** There are uv\_ip6\_\* analogues for the ip4 functions.

Most of the setup functions are synchronous since they are CPU-bound. uv\_listen is where we return to libuv's callback style. The second arguments is the backlog queue – the maximum length of queued connections.

When a connection is initiated by clients, the callback is required to set up a handle for the client socket and associate the handle using uv\_accept. In this case we also establish interest in reading from this stream.

# tcp-echo-server/main.c - Accepting the client

```
free (buf->base);
2
   }
3
4
   void on_new_connection(uv_stream_t *server, int status) {
       if (status < 0) {
6
           fprintf(stderr, "New connection error %s\n", uv_strerror(status));
           // error!
8
           return;
9
       }
10
11
       uv_tcp_t *client = (uv_tcp_t*) malloc(sizeof(uv_tcp_t));
12
       uv_tcp_init(loop, client);
       if (uv_accept(server, (uv_stream_t*) client) == 0) {
           uv_read_start((uv_stream_t*) client, alloc_buffer, echo_read);
15
       }
```

The remaining set of functions is very similar to the streams example and can be found in the code. Just remember to call uv\_close when the socket isn't required. This can be done even in the uv\_listen callback if you are not interested in accepting the connection.

#### Client

Where you do bind/listen/accept on the server, on the client side it's simply a matter of calling uv\_tcp\_connect. The same uv\_connect\_cb style callback of uv\_listen is used by uv\_tcp\_connect. Try:

```
uv_tcp_t* socket = (uv_tcp_t*)malloc(sizeof(uv_tcp_t));
uv_tcp_init(loop, socket);
uv_connect_t* connect = (uv_connect_t*)malloc(sizeof(uv_connect_t));
```

```
struct sockaddr_in dest;
uv_ip4_addr("127.0.0.1", 80, &dest);
uv_tcp_connect(connect, socket, (const struct sockaddr*)&dest, on_connect);
```

where on\_connect will be called after the connection is established. The callback receives the uv\_connect\_t struct, which has a member .handle pointing to the socket.

#### **UDP**

The User Datagram Protocol offers connectionless, unreliable network communication. Hence libuv doesn't offer a stream. Instead libuv provides non-blocking UDP support via the  $uv\_udp\_t$  handle (for receiving) and  $uv\_udp\_send\_t$  request (for sending) and related functions. That said, the actual API for reading/writing is very similar to normal stream reads. To look at how UDP can be used, the example shows the first stage of obtaining an IP address from a DHCP server – DHCP Discover.

**Note:** You will have to run *udp-dhcp* as **root** since it uses well known port numbers below 1024.

## udp-dhcp/main.c - Setup and send UDP packets

```
uv_loop_t *loop;
2
   uv_udp_t send_socket;
3
   uv_udp_t recv_socket;
4
   int main() {
6
       loop = uv_default_loop();
7
       uv_udp_init(loop, &recv_socket);
       struct sockaddr_in recv_addr;
10
       uv_ip4_addr("0.0.0.0", 68, &recv_addr);
11
12
       uv_udp_bind(&recv_socket, (const struct sockaddr *)&recv_addr, UV_UDP_REUSEADDR);
       uv_udp_recv_start(&recv_socket, alloc_buffer, on_read);
13
14
       uv_udp_init(loop, &send_socket);
15
       struct sockaddr_in broadcast_addr;
16
       uv_ip4_addr("0.0.0.0", 0, &broadcast_addr);
17
       uv_udp_bind(&send_socket, (const struct sockaddr *)&broadcast_addr, 0);
       uv_udp_set_broadcast(&send_socket, 1);
19
20
       uv_udp_send_t send_req;
21
       uv_buf_t discover_msg = make_discover_msg();
22
23
       struct sockaddr_in send_addr;
24
       uv_ip4_addr("255.255.255.255", 67, &send_addr);
       uv_udp_send(&send_req, &send_socket, &discover_msg, 1, (const struct sockaddr *)&
   →send_addr, on_send);
27
       return uv_run(loop, UV_RUN_DEFAULT);
28
   }
```

Note: The IP address 0.0.0.0 is used to bind to all interfaces. The IP address 255.255.255.255 is a broadcast

address meaning that packets will be sent to all interfaces on the subnet. port 0 means that the OS randomly assigns a port.

First we setup the receiving socket to bind on all interfaces on port 68 (DHCP client) and start a read on it. This will read back responses from any DHCP server that replies. We use the UV\_UDP\_REUSEADDR flag to play nice with any other system DHCP clients that are running on this computer on the same port. Then we setup a similar send socket and use uv\_udp\_send to send a *broadcast message* on port 67 (DHCP server).

It is **necessary** to set the broadcast flag, otherwise you will get an EACCES error<sup>1</sup>. The exact message being sent is not relevant to this book and you can study the code if you are interested. As usual the read and write callbacks will receive a status code of < 0 if something went wrong.

Since UDP sockets are not connected to a particular peer, the read callback receives an extra parameter about the sender of the packet.

nread may be zero if there is no more data to be read. If addr is NULL, it indicates there is nothing to read (the callback shouldn't do anything), if not NULL, it indicates that an empty datagram was received from the host at addr. The flags parameter may be UV\_UDP\_PARTIAL if the buffer provided by your allocator was not large enough to hold the data. In this case the OS will discard the data that could not fit (That's UDP for you!).

## udp-dhcp/main.c - Reading packets

```
void on_read(uv_udp_t *req, ssize_t nread, const uv_buf_t *buf, const struct sockaddr,
   →*addr, unsigned flags) {
       if (nread < 0) {
2
           fprintf(stderr, "Read error %s\n", uv_err_name(nread));
           uv_close((uv_handle_t*) req, NULL);
           free (buf->base);
           return;
6
       }
       char sender[17] = \{ 0 \};
       uv_ip4_name((const struct sockaddr_in*) addr, sender, 16);
       fprintf(stderr, "Recv from %s\n", sender);
11
12
       // ... DHCP specific code
13
       unsigned int *as_integer = (unsigned int*)buf->base;
14
       unsigned int ipbin = ntohl(as_integer[4]);
15
       unsigned char ip[4] = \{0\};
       int i;
17
       for (i = 0; i < 4; i++)
18
           ip[i] = (ipbin >> i*8) & 0xff;
19
       fprintf(stderr, "Offered IP %d.%d.%d.%d\n", ip[3], ip[2], ip[1], ip[0]);
20
21
       free (buf->base);
22
       uv_udp_recv_stop(req);
23
```

### **UDP Options**

#### Time-to-live

The TTL of packets sent on the socket can be changed using uv\_udp\_set\_ttl.

<sup>&</sup>lt;sup>1</sup> http://beej.us/guide/bgnet/output/html/multipage/advanced.html#broadcast

## IPv6 stack only

IPv6 sockets can be used for both IPv4 and IPv6 communication. If you want to restrict the socket to IPv6 only, pass the UV\_UDP\_IPV6ONLY flag to uv\_udp\_bind<sup>2</sup>.

#### **Multicast**

A socket can (un)subscribe to a multicast group using:

```
size_t send_queue_size;
/*
 * Number of send requests currently in the queue awaiting to be processed.
 */
```

where membership is UV\_JOIN\_GROUP or UV\_LEAVE\_GROUP.

The concepts of multicasting are nicely explained in this guide.

Local loopback of multicast packets is enabled by default<sup>3</sup>, use uv\_udp\_set\_multicast\_loop to switch it off.

The packet time-to-live for multicast packets can be changed using uv\_udp\_set\_multicast\_ttl.

# **Querying DNS**

libuv provides asynchronous DNS resolution. For this it provides its own getaddrinfo replacement<sup>4</sup>. In the callback you can perform normal socket operations on the retrieved addresses. Let's connect to Freenode to see an example of DNS resolution.

#### dns/main.c

```
2
   int main() {
       loop = uv_default_loop();
3
4
       struct addrinfo hints;
5
       hints.ai_family = PF_INET;
6
       hints.ai_socktype = SOCK_STREAM;
7
       hints.ai_protocol = IPPROTO_TCP;
       hints.ai_flags = 0;
       uv_getaddrinfo_t resolver;
11
       fprintf(stderr, "irc.freenode.net is... ");
12
       int r = uv_getaddrinfo(loop, &resolver, on_resolved, "irc.freenode.net", "6667", &
13
   ⇔hints);
14
       if (r) {
15
           fprintf(stderr, "getaddrinfo call error %s\n", uv_err_name(r));
16
           return 1;
17
       }
```

<sup>&</sup>lt;sup>2</sup> on Windows only supported on Windows Vista and later.

<sup>&</sup>lt;sup>3</sup> http://www.tldp.org/HOWTO/Multicast-HOWTO-6.html#ss6.1

 $<sup>^4</sup>$  libuv use the system getaddrinfo in the libuv threadpool. libuv v0.8.0 and earlier also included c-ares as an alternative, but this has been removed in v0.9.0.

```
return uv_run(loop, UV_RUN_DEFAULT);
20 }
```

If uv\_getaddrinfo returns non-zero, something went wrong in the setup and your callback won't be invoked at all. All arguments can be freed immediately after uv\_getaddrinfo returns. The *hostname*, *servname* and *hints* structures are documented in the getaddrinfo man page. The callback can be NULL in which case the function will run synchronously.

In the resolver callback, you can pick any IP from the linked list of struct addrinfo(s). This also demonstrates uv\_tcp\_connect. It is necessary to call uv\_freeaddrinfo in the callback.

#### dns/main.c

```
void on_resolved(uv_getaddrinfo_t *resolver, int status, struct addrinfo *res) {
2
       if (status < 0) {
3
           fprintf(stderr, "getaddrinfo callback error \$s \n", uv_err_name(status));
           return;
       }
       char addr[17] = {' \setminus 0'};
       uv_ip4_name((struct sockaddr_in*) res->ai_addr, addr, 16);
       fprintf(stderr, "%s\n", addr);
10
11
       uv_connect_t *connect_req = (uv_connect_t*) malloc(sizeof(uv_connect_t));
12
       uv_tcp_t *socket = (uv_tcp_t*) malloc(sizeof(uv_tcp_t));
13
       uv_tcp_init(loop, socket);
14
15
       uv_tcp_connect(connect_req, socket, (const struct sockaddr*) res->ai_addr, on_
16
   →connect);
17
       uv_freeaddrinfo(res);
18
```

libuv also provides the inverse uv getnameinfo.

### **Network interfaces**

Information about the system's network interfaces can be obtained through libuv using uv\_interface\_addresses. This simple program just prints out all the interface details so you get an idea of the fields that are available. This is useful to allow your service to bind to IP addresses when it starts.

#### interfaces/main.c

```
#include <stdio.h>
#include <uv.h>

int main() {
    char buf[512];
    uv_interface_address_t *info;
    int count, i;

uv_interface_addresses(&info, &count);
```

```
i = count;
10
11
       printf("Number of interfaces: %d\n", count);
12
       while (i--) {
13
           uv_interface_address_t interface = info[i];
           printf("Name: %s\n", interface.name);
16
           printf("Internal? %s\n", interface.is_internal ? "Yes" : "No");
17
18
           if (interface.address.address4.sin_family == AF_INET) {
19
                uv_ip4_name(&interface.address.address4, buf, sizeof(buf));
20
                printf("IPv4 address: %s\n", buf);
21
22
           else if (interface.address.address4.sin_family == AF_INET6) {
23
                uv_ip6_name(&interface.address.address6, buf, sizeof(buf));
24
                printf("IPv6 address: %s\n", buf);
25
26
27
           printf("\n");
28
29
30
       uv_free_interface_addresses(info, count);
31
       return 0;
32
```

is\_internal is true for loopback interfaces. Note that if a physical interface has multiple IPv4/IPv6 addresses, the name will be reported multiple times, with each address being reported once.

# **Threads**

Wait a minute? Why are we on threads? Aren't event loops supposed to be **the way** to do *web-scale programming*? Well... no. Threads are still the medium in which processors do their jobs. Threads are therefore mighty useful sometimes, even though you might have to wade through various synchronization primitives.

Threads are used internally to fake the asynchronous nature of all of the system calls. libuv also uses threads to allow you, the application, to perform a task asynchronously that is actually blocking, by spawning a thread and collecting the result when it is done.

Today there are two predominant thread libraries: the Windows threads implementation and POSIX's pthreads. libuv's thread API is analogous to the pthreads API and often has similar semantics.

A notable aspect of libuv's thread facilities is that it is a self contained section within libuv. Whereas other features intimately depend on the event loop and callback principles, threads are complete agnostic, they block as required, signal errors directly via return values, and, as shown in the *first example*, don't even require a running event loop.

libuv's thread API is also very limited since the semantics and syntax of threads are different on all platforms, with different levels of completeness.

This chapter makes the following assumption: There is only one event loop, running in one thread (the main thread). No other thread interacts with the event loop (except using uv\_async\_send).

### Core thread operations

There isn't much here, you just start a thread using uv\_thread\_create() and wait for it to close using uv\_thread\_join().

#### thread-create/main.c

```
int main() {
   int tracklen = 10;
   uv_thread_t hare_id;
   uv_thread_t tortoise_id;
   uv_thread_create(&hare_id, hare, &tracklen);
   uv_thread_create(&tortoise_id, tortoise, &tracklen);

   uv_thread_join(&hare_id);
   uv_thread_join(&tortoise_id);
   return 0;
}
```

**Tip:** uv\_thread\_t is just an alias for pthread\_t on Unix, but this is an implementation detail, avoid depending on it to always be true.

The second parameter is the function which will serve as the entry point for the thread, the last parameter is a void \* argument which can be used to pass custom parameters to the thread. The function hare will now run in a separate thread, scheduled pre-emptively by the operating system:

### thread-create/main.c

```
void hare(void *arg) {
   int tracklen = *((int *) arg);

while (tracklen) {
     tracklen--;
     sleep(1);
     fprintf(stderr, "Hare ran another step\n");
}

fprintf(stderr, "Hare done running!\n");
}
```

Unlike pthread\_join() which allows the target thread to pass back a value to the calling thread using a second parameter, uv\_thread\_join() does not. To send values use *Inter-thread communication*.

### **Synchronization Primitives**

This section is purposely spartan. This book is not about threads, so I only catalogue any surprises in the libuv APIs here. For the rest you can look at the pthreads man pages.

#### **Mutexes**

The mutex functions are a **direct** map to the pthread equivalents.

### libuv mutex functions

```
UV_EXTERN void uv_loadavg(double avg[3]);

/*
 * Flags to be passed to uv_fs_event_start().
 */
```

The uv\_mutex\_init() and uv\_mutex\_trylock() functions will return 0 on success, and an error code otherwise.

If *libuv* has been compiled with debugging enabled, uv\_mutex\_destroy(), uv\_mutex\_lock() and uv\_mutex\_unlock() will abort() on error. Similarly uv\_mutex\_trylock() will abort if the error is anything other than EAGAIN or EBUSY.

Recursive mutexes are supported by some platforms, but you should not rely on them. The BSD mutex implementation will raise an error if a thread which has locked a mutex attempts to lock it again. For example, a construct like:

```
uv_mutex_lock(a_mutex);
uv_thread_create(thread_id, entry, (void *)a_mutex);
uv_mutex_lock(a_mutex);
// more things here
```

can be used to wait until another thread initializes some stuff and then unlocks a\_mutex but will lead to your program crashing if in debug mode, or return an error in the second call to uv\_mutex\_lock().

Note: Mutexes on linux support attributes for a recursive mutex, but the API is not exposed via libuv.

#### Locks

Read-write locks are a more granular access mechanism. Two readers can access shared memory at the same time. A writer may not acquire the lock when it is held by a reader. A reader or writer may not acquire a lock when a writer is holding it. Read-write locks are frequently used in databases. Here is a toy example.

## locks/main.c - simple rwlocks

```
#include <stdio.h>
   #include <uv.h>
   uv_barrier_t blocker;
   uv_rwlock_t numlock;
   int shared_num;
6
   void reader(void *n)
9
       int num = *(int *)n;
10
       int i;
11
       for (i = 0; i < 20; i++) {
12
           uv_rwlock_rdlock(&numlock);
13
           printf("Reader %d: acquired lock\n", num);
           printf("Reader %d: shared num = %d \setminus n", num, shared_num);
           uv_rwlock_rdunlock(&numlock);
16
           printf("Reader %d: released lock\n", num);
17
```

```
uv_barrier_wait(&blocker);
19
20
21
   void writer(void *n)
22
23
       int num = *(int *)n;
24
       int i;
25
       for (i = 0; i < 20; i++) {
26
            uv_rwlock_wrlock(&numlock);
27
            printf("Writer %d: acquired lock\n", num);
28
            shared_num++;
29
            printf("Writer %d: incremented shared num = %d\n", num, shared num);
30
            uv_rwlock_wrunlock(&numlock);
31
            printf("Writer %d: released lock\n", num);
32
33
       uv_barrier_wait(&blocker);
34
35
   int main()
38
       uv_barrier_init(&blocker, 4);
39
40
       shared_num = 0;
41
       uv_rwlock_init(&numlock);
42
       uv_thread_t threads[3];
44
45
       int thread_nums[] = \{1, 2, 1\};
46
       uv_thread_create(&threads[0], reader, &thread_nums[0]);
47
       uv_thread_create(&threads[1], reader, &thread_nums[1]);
48
49
       uv_thread_create(&threads[2], writer, &thread_nums[2]);
51
       uv_barrier_wait(&blocker);
52
       uv_barrier_destroy(&blocker);
53
54
       uv_rwlock_destroy(&numlock);
55
       return 0;
```

Run this and observe how the readers will sometimes overlap. In case of multiple writers, schedulers will usually give them higher priority, so if you add two writers, you'll see that both writers tend to finish first before the readers get a chance again.

We also use barriers in the above example so that the main thread can wait for all readers and writers to indicate they have ended.

#### **Others**

libuv also supports semaphores, condition variables and barriers with APIs very similar to their pthread counterparts.

In addition, libuv provides a convenience function uv\_once(). Multiple threads can attempt to call uv\_once() with a given guard and a function pointer, only the first one will win, the function will be called once and only once:

```
/* Initialize guard */
static uv_once_t once_only = UV_ONCE_INIT;
```

```
int i = 0;

void increment() {
    i++;
}

void thread1() {
    /* ... work */
    uv_once(once_only, increment);
}

void thread2() {
    /* ... work */
    uv_once(once_only, increment);
}

int main() {
    /* ... spawn threads */
}
```

After all threads are done, i == 1. libuv v0.11.11 onwards also added a uv\_key\_t struct and api for thread-local storage.

## libuv work queue

uv\_queue\_work () is a convenience function that allows an application to run a task in a separate thread, and have a callback that is triggered when the task is done. A seemingly simple function, what makes uv\_queue\_work () tempting is that it allows potentially any third-party libraries to be used with the event-loop paradigm. When you use event loops, it is *imperative to make sure that no function which runs periodically in the loop thread blocks when performing I/O or is a serious CPU hog*, because this means that the loop slows down and events are not being handled at full capacity.

However, a lot of existing code out there features blocking functions (for example a routine which performs I/O under the hood) to be used with threads if you want responsiveness (the classic 'one thread per client' server model), and getting them to play with an event loop library generally involves rolling your own system of running the task in a separate thread. libuv just provides a convenient abstraction for this.

Here is a simple example inspired by node.js is cancer. We are going to calculate fibonacci numbers, sleeping a bit along the way, but run it in a separate thread so that the blocking and CPU bound task does not prevent the event loop from performing other activities.

## queue-work/main.c - lazy fibonacci

```
void fib(uv_work_t *req) {
    int n = *(int *) req->data;

if (random() % 2)

    sleep(1);

else
    sleep(3);

long fib = fib_(n);

fprintf(stderr, "%dth fibonacci is %lu\n", n, fib);

void after_fib(uv_work_t *req, int status) {
```

```
fprintf(stderr, "Done calculating %dth fibonacci\n", *(int *) req->data);
}
```

The actual task function is simple, nothing to show that it is going to be run in a separate thread. The uv\_work\_t structure is the clue. You can pass arbitrary data through it using the void\* data field and use it to communicate to and from the thread. But be sure you are using proper locks if you are changing things while both threads may be running.

The trigger is uv\_queue\_work:

#### queue-work/main.c

```
int main() {
       loop = uv_default_loop();
2
       int data[FIB_UNTIL];
       uv_work_t req[FIB_UNTIL];
5
       int i;
6
       for (i = 0; i < FIB_UNTIL; i++) {</pre>
7
            data[i] = i;
            req[i].data = (void *) &data[i];
            uv_queue_work(loop, &req[i], fib, after_fib);
10
11
12
       return uv_run(loop, UV_RUN_DEFAULT);
13
14
```

The thread function will be launched in a separate thread, passed the uv\_work\_t structure and once the function returns, the *after* function will be called on the thread the event loop is running in. It will be passed the same structure.

For writing wrappers to blocking libraries, a common pattern is to use a baton to exchange data.

Since libuv version 0.9.4 an additional function, uv\_cancel(), is available. This allows you to cancel tasks on the libuv work queue. Only tasks that are yet to be started can be cancelled. If a task has already started executing, or it has finished executing, uv\_cancel() will fail.

uv\_cancel() is useful to cleanup pending tasks if the user requests termination. For example, a music player may queue up multiple directories to be scanned for audio files. If the user terminates the program, it should quit quickly and not wait until all pending requests are run.

Let's modify the fibonacci example to demonstrate uv\_cancel(). We first set up a signal handler for termination.

## queue-cancel/main.c

```
int main() {
    loop = uv_default_loop();

int data[FIB_UNTIL];
    int i;

for (i = 0; i < FIB_UNTIL; i++) {
        data[i] = i;
        fib_reqs[i].data = (void *) &data[i];
        uv_queue_work(loop, &fib_reqs[i], fib, after_fib);
}</pre>
```

```
uv_signal_t sig;
uv_signal_init(loop, &sig);
uv_signal_start(&sig, signal_handler, SIGINT);

return uv_run(loop, UV_RUN_DEFAULT);
}
```

When the user triggers the signal by pressing Ctrl+C we send uv\_cancel() to all the workers. uv\_cancel() will return 0 for those that are already executing or finished.

#### queue-cancel/main.c

```
void signal_handler(uv_signal_t *req, int signum)
{
    printf("Signal received!\n");
    int i;
    for (i = 0; i < FIB_UNTIL; i++) {
        uv_cancel((uv_req_t*) &fib_reqs[i]);
    }
    uv_signal_stop(req);
}</pre>
```

For tasks that do get cancelled successfully, the after function is called with status set to UV\_ECANCELED.

### queue-cancel/main.c

```
void after_fib(uv_work_t *req, int status) {
    if (status == UV_ECANCELED)
        fprintf(stderr, "Calculation of %d cancelled.\n", *(int *) req->data);
}
```

uv\_cancel() can also be used with uv\_fs\_t and uv\_getaddrinfo\_t requests. For the filesystem family of functions, uv fs t.errorno will be set to UV ECANCELED.

**Tip:** A well designed program would have a way to terminate long running workers that have already started executing. Such a worker could periodically check for a variable that only the main process sets to signal termination.

## Inter-thread communication

Sometimes you want various threads to actually send each other messages while they are running. For example you might be running some long duration task in a separate thread (perhaps using uv\_queue\_work) but want to notify progress to the main thread. This is a simple example of having a download manager informing the user of the status of running downloads.

### progress/main.c

```
uv_loop_t *loop;
uv_async_t async;
}
```

```
int main() {
5
       loop = uv_default_loop();
6
       uv_work_t req;
       int size = 10240;
       req.data = (void*) &size;
10
11
       uv_async_init(loop, &async, print_progress);
12
       uv_queue_work(loop, &req, fake_download, after);
13
14
       return uv_run(loop, UV_RUN_DEFAULT);
15
   }
```

The async thread communication works *on loops* so although any thread can be the message sender, only threads with libuv loops can be receivers (or rather the loop is the receiver). libuv will invoke the callback (print\_progress) with the async watcher whenever it receives a message.

Warning: It is important to realize that since the message send is <code>async</code>, the callback may be invoked immediately after <code>uv\_async\_send</code> is called in another thread, or it may be invoked after some time. libuv may also combine multiple calls to <code>uv\_async\_send</code> and invoke your callback only once. The only guarantee that libuv makes is <code>-</code> The callback function is called <code>at least once</code> after the call to <code>uv\_async\_send</code>. If you have no pending calls to <code>uv\_async\_send</code>, the callback won't be called. If you make two or more calls, and libuv hasn't had a chance to run the callback yet, it <code>may</code> invoke your callback <code>only once</code> for the multiple invocations of <code>uv\_async\_send</code>. Your callback will never be called twice for just one event.

### progress/main.c

```
double percentage;
2
   void fake_download(uv_work_t *req) {
3
4
       int size = *((int*) req->data);
       int downloaded = 0;
       while (downloaded < size) {</pre>
           percentage = downloaded*100.0/size;
           async.data = (void*) &percentage;
           uv_async_send(&async);
10
           sleep(1);
11
           downloaded += (200+random())%1000; // can only download max 1000bytes/sec,
12
                                                 // but at least a 200;
```

In the download function, we modify the progress indicator and queue the message for delivery with uv\_async\_send. Remember: uv\_async\_send is also non-blocking and will return immediately.

# progress/main.c

```
void print_progress(uv_async_t *handle) {
   double percentage = *((double*) handle->data);
   fprintf(stderr, "Downloaded %.2f%%\n", percentage);
```

The callback is a standard libuv pattern, extracting the data from the watcher.

Finally it is important to remember to clean up the watcher.

#### progress/main.c

```
void after(uv_work_t *req, int status) {
   fprintf(stderr, "Download complete\n");
   uv_close((uv_handle_t*) &async, NULL);
```

After this example, which showed the abuse of the data field, bnoordhuis pointed out that using the data field is not thread safe, and uv\_async\_send() is actually only meant to wake up the event loop. Use a mutex or rwlock to ensure accesses are performed in the right order.

Note: mutexes and rwlocks DO NOT work inside a signal handler, whereas uv\_async\_send does.

One use case where uv\_async\_send is required is when interoperating with libraries that require thread affinity for their functionality. For example in node.js, a v8 engine instance, contexts and its objects are bound to the thread that the v8 instance was started in. Interacting with v8 data structures from another thread can lead to undefined results. Now consider some node.js module which binds a third party library. It may go something like this:

1. In node, the third party library is set up with a JavaScript callback to be invoked for more information:

```
var lib = require('lib');
lib.on_progress(function() {
   console.log("Progress");
});
lib.do();
// do other stuff
```

- 2. lib.do is supposed to be non-blocking but the third party lib is blocking, so the binding uses uv\_queue\_work.
- 3. The actual work being done in a separate thread wants to invoke the progress callback, but cannot directly call into v8 to interact with JavaScript. So it uses uv\_async\_send.
- 4. The async callback, invoked in the main loop thread, which is the v8 thread, then interacts with v8 to invoke the JavaScript callback.

#### **Processes**

libuv offers considerable child process management, abstracting the platform differences and allowing communication with the child process using streams or named pipes.

A common idiom in Unix is for every process to do one thing and do it well. In such a case, a process often uses multiple child processes to achieve tasks (similar to using pipes in shells). A multi-process model with messages may also be easier to reason about compared to one with threads and shared memory.

A common refrain against event-based programs is that they cannot take advantage of multiple cores in modern computers. In a multi-threaded program the kernel can perform scheduling and assign different threads to different cores,

improving performance. But an event loop has only one thread. The workaround can be to launch multiple processes instead, with each process running an event loop, and each process getting assigned to a separate CPU core.

## Spawning child processes

The simplest case is when you simply want to launch a process and know when it exits. This is achieved using uv\_spawn.

### spawn/main.c

```
uv_loop_t *loop;
   uv_process_t child_req;
2
   uv_process_options_t options;
3
   int main() {
       loop = uv_default_loop();
       char* args[3];
       args[0] = "mkdir";
8
       args[1] = "test-dir";
       args[2] = NULL;
10
11
       options.exit_cb = on_exit;
12
       options.file = "mkdir";
13
       options.args = args;
14
15
       int r;
16
       if ((r = uv_spawn(loop, &child_req, &options))) {
17
            fprintf(stderr, "%s\n", uv_strerror(r));
18
            return 1;
19
20
        } else {
            fprintf(stderr, "Launched process with ID %d\n", child_req.pid);
21
22
23
       return uv_run(loop, UV_RUN_DEFAULT);
24
25
```

**Note:** options is implicitly initialized with zeros since it is a global variable. If you change options to a local variable, remember to initialize it to null out all unused fields:

```
uv_process_options_t options = {0};
```

The uv\_process\_t struct only acts as the handle, all options are set via uv\_process\_options\_t. To simply launch a process, you need to set only the file and args fields. file is the program to execute. Since uv\_spawn uses execvp internally, there is no need to supply the full path. Finally as per underlying conventions, the arguments array has to be one larger than the number of arguments, with the last element being NULL.

After the call to uv\_spawn, uv\_process\_t.pid will contain the process ID of the child process.

The exit callback will be invoked with the exit status and the type of signal which caused the exit.

### spawn/main.c

It is **required** to close the process watcher after the process exits.

## **Changing process parameters**

Before the child process is launched you can control the execution environment using fields in uv\_process\_options\_t.

### Change execution directory

Set uv\_process\_options\_t.cwd to the corresponding directory.

#### Set environment variables

uv\_process\_options\_t.env is a null-terminated array of strings, each of the form VAR=VALUE used to set up the environment variables for the process. Set this to NULL to inherit the environment from the parent (this) process.

### **Option flags**

Setting uv\_process\_options\_t.flags to a bitwise OR of the following flags, modifies the child process behaviour:

- UV\_PROCESS\_SETUID sets the child's execution user ID to uv\_process\_options\_t.uid.
- UV\_PROCESS\_SETGID sets the child's execution group ID to uv\_process\_options\_t.gid.

Changing the UID/GID is only supported on Unix, uv spawn will fail on Windows with UV ENOTSUP.

- UV\_PROCESS\_WINDOWS\_VERBATIM\_ARGUMENTS No quoting or escaping of uv\_process\_options\_t.args is done on Windows. Ignored on Unix.
- UV\_PROCESS\_DETACHED Starts the child process in a new session, which will keep running after the parent process exits. See example below.

### **Detaching processes**

Passing the flag UV\_PROCESS\_DETACHED can be used to launch daemons, or child processes which are independent of the parent so that the parent exiting does not affect it.

## detach/main.c

```
int main() {
       loop = uv_default_loop();
2
3
       char* args[3];
4
       args[0] = "sleep";
       args[1] = "100";
       args[2] = NULL;
       options.exit_cb = NULL;
9
       options.file = "sleep";
10
       options.args = args;
11
       options.flags = UV_PROCESS_DETACHED;
12
13
14
       if ((r = uv_spawn(loop, &child_req, &options))) {
15
           fprintf(stderr, "%s\n", uv_strerror(r));
16
           return 1;
17
       fprintf(stderr, "Launched sleep with PID %d\n", child_req.pid);
       uv_unref((uv_handle_t*) &child_req);
20
21
       return uv_run(loop, UV_RUN_DEFAULT);
22
```

Just remember that the handle is still monitoring the child, so your program won't exit. Use uv\_unref() if you want to be more *fire-and-forget*.

# Sending signals to processes

libuv wraps the standard kill(2) system call on Unix and implements one with similar semantics on Windows, with one caveat: all of SIGTERM, SIGINT and SIGKILL, lead to termination of the process. The signature of uv\_kill is:

```
uv_err_t uv_kill(int pid, int signum);
```

For processes started using libuv, you may use uv\_process\_kill instead, which accepts the uv\_process\_t watcher as the first argument, rather than the pid. In this case, **remember to call** uv close on the watcher.

### **Signals**

libuv provides wrappers around Unix signals with some Windows support as well.

Use uv\_signal\_init() to initialize a handle and associate it with a loop. To listen for particular signals on that handler, use uv\_signal\_start() with the handler function. Each handler can only be associated with one signal number, with subsequent calls to uv\_signal\_start() overwriting earlier associations. Use uv\_signal\_stop() to stop watching. Here is a small example demonstrating the various possibilities:

# signal/main.c

```
#include <stdio.h>
#include <stdlib.h>
#include <unistd.h>
#include <uv.h>

uv_loop_t* create_loop()
```

```
uv_loop_t *loop = malloc(sizeof(uv_loop_t));
8
       if (loop) {
         uv_loop_init(loop);
10
11
       return loop;
13
14
   void signal_handler(uv_signal_t *handle, int signum)
15
16
       printf("Signal received: %d\n", signum);
17
        uv_signal_stop(handle);
18
19
20
   // two signal handlers in one loop
21
   void thread1_worker(void *userp)
22
23
        uv_loop_t *loop1 = create_loop();
24
25
       uv_signal_t sigla, siglb;
26
       uv_signal_init(loop1, &sig1a);
27
       uv_signal_start(&sig1a, signal_handler, SIGUSR1);
28
29
       uv_signal_init(loop1, &sig1b);
30
       uv_signal_start(&sig1b, signal_handler, SIGUSR1);
32
       uv_run(loop1, UV_RUN_DEFAULT);
33
34
35
   // two signal handlers, each in its own loop
36
   void thread2_worker(void *userp)
37
       uv_loop_t *loop2 = create_loop();
       uv_loop_t *loop3 = create_loop();
40
41
       uv_signal_t sig2;
42
       uv_signal_init(loop2, &sig2);
43
44
       uv_signal_start(&sig2, signal_handler, SIGUSR1);
45
       uv_signal_t sig3;
46
        uv_signal_init(loop3, &sig3);
47
        uv_signal_start(&sig3, signal_handler, SIGUSR1);
48
49
        while (uv_run(loop2, UV_RUN_NOWAIT) || uv_run(loop3, UV_RUN_NOWAIT)) {
50
51
52
53
   int main()
54
55
       printf("PID %d\n", getpid());
56
57
       uv_thread_t thread1, thread2;
58
59
       uv_thread_create(&thread1, thread1_worker, 0);
60
       uv_thread_create(&thread2, thread2_worker, 0);
61
62
        uv_thread_join(&thread1);
63
       uv_thread_join(&thread2);
```

```
65 return 0;
66 }
```

**Note:** uv\_run(loop, UV\_RUN\_NOWAIT) is similar to uv\_run(loop, UV\_RUN\_ONCE) in that it will process only one event. UV\_RUN\_ONCE blocks if there are no pending events, while UV\_RUN\_NOWAIT will return immediately. We use NOWAIT so that one of the loops isn't starved because the other one has no pending activity.

Send SIGUSR1 to the process, and you'll find the handler being invoked 4 times, one for each uv\_signal\_t. The handler just stops each handle, so that the program exits. This sort of dispatch to all handlers is very useful. A server using multiple event loops could ensure that all data was safely saved before termination, simply by every loop adding a watcher for SIGINT.

### Child Process I/O

A normal, newly spawned process has its own set of file descriptors, with 0, 1 and 2 being stdin, stdout and stderr respectively. Sometimes you may want to share file descriptors with the child. For example, perhaps your applications launches a sub-command and you want any errors to go in the log file, but ignore stdout. For this you'd like to have stderr of the child be the same as the stderr of the parent. In this case, libuv supports *inheriting* file descriptors. In this sample, we invoke the test program, which is:

## proc-streams/test.c

```
#include <stdio.h>
int main()
{
    fprintf(stderr, "This is stderr\n");
    printf("This is stdout\n");
    return 0;
}
```

The actual program proc-streams runs this while sharing only stderr. The file descriptors of the child process are set using the stdio field in uv\_process\_options\_t. First set the stdio\_count field to the number of file descriptors being set. uv\_process\_options\_t.stdio is an array of uv\_stdio\_container\_t, which is:

where flags can have several values. Use UV\_IGNORE if it isn't going to be used. If the first three stdio fields are marked as UV\_IGNORE they'll redirect to /dev/null.

Since we want to pass on an existing descriptor, we'll use UV\_INHERIT\_FD. Then we set the fd to stderr.

#### proc-streams/main.c

```
2
   int main() {
       loop = uv_default_loop();
3
       /* ... */
5
6
       options.stdio_count = 3;
7
       uv_stdio_container_t child_stdio[3];
       child_stdio[0].flags = UV_IGNORE;
       child_stdio[1].flags = UV_IGNORE;
10
       child_stdio[2].flags = UV_INHERIT_FD;
11
       child_stdio[2].data.fd = 2;
12
       options.stdio = child_stdio;
13
14
       options.exit_cb = on_exit;
15
       options.file = args[0];
16
       options.args = args;
17
18
       int r;
19
       if ((r = uv_spawn(loop, &child_req, &options))) {
20
           fprintf(stderr, "%s\n", uv_strerror(r));
21
22
           return 1;
24
       return uv_run(loop, UV_RUN_DEFAULT);
25
   }
```

If you run proc-stream you'll see that only the line "This is stderr" will be displayed. Try marking stdout as being inherited and see the output.

It is dead simple to apply this redirection to streams. By setting flags to UV\_INHERIT\_STREAM and setting data.stream to the stream in the parent process, the child process can treat that stream as standard I/O. This can be used to implement something like CGI.

A sample CGI script/executable is:

## cgi/tick.c

```
#include <stdio.h>
#include <unistd.h>

int main() {
   int i;
   for (i = 0; i < 10; i++) {
       printf("tick\n");
       fflush(stdout);
       sleep(1);
   }
   printf("BOOM!\n");
   return 0;
}</pre>
```

The CGI server combines the concepts from this chapter and *Networking* so that every client is sent ten ticks after which that connection is closed.

### cgi/main.c

```
void on_new_connection(uv_stream_t *server, int status) {
2
       if (status == -1) {
3
           // error!
4
5
           return;
6
       uv_tcp_t *client = (uv_tcp_t*) malloc(sizeof(uv_tcp_t));
8
       uv_tcp_init(loop, client);
       if (uv_accept(server, (uv_stream_t*) client) == 0) {
10
           invoke_cgi_script(client);
       else {
13
           uv_close((uv_handle_t*) client, NULL);
14
```

Here we simply accept the TCP connection and pass on the socket (stream) to invoke\_cgi\_script.

#### cgi/main.c

```
2
       args[1] = NULL;
3
       /\star ... finding the executable path and setting up arguments ... \star/
4
5
       options.stdio_count = 3;
6
       uv_stdio_container_t child_stdio[3];
       child_stdio[0].flags = UV_IGNORE;
       child_stdio[1].flags = UV_INHERIT_STREAM;
       child_stdio[1].data.stream = (uv_stream_t*) client;
10
       child_stdio[2].flags = UV_IGNORE;
11
       options.stdio = child_stdio;
12
13
       options.exit_cb = cleanup_handles;
14
15
       options.file = args[0];
       options.args = args;
16
17
       // Set this so we can close the socket after the child process exits.
18
       child_req.data = (void*) client;
19
       int r;
20
       if ((r = uv_spawn(loop, &child_req, &options))) {
21
            fprintf(stderr, "\$s\n", uv_strerror(r));
```

The stdout of the CGI script is set to the socket so that whatever our tick script prints, gets sent to the client. By using processes, we can offload the read/write buffering to the operating system, so in terms of convenience this is great. Just be warned that creating processes is a costly task.

### **Pipes**

libuv's uv\_pipe\_t structure is slightly confusing to Unix programmers, because it immediately conjures up | and pipe(7). But uv\_pipe\_t is not related to anonymous pipes, rather it is an IPC mechanism. uv\_pipe\_t can be backed by a Unix Domain Socket or Windows Named Pipe to allow multiple processes to communicate. This is discussed below.

## Parent-child IPC

A parent and child can have one or two way communication over a pipe created by settings uv\_stdio\_container\_t.flags to a bit-wise combination of UV\_CREATE\_PIPE and UV\_READABLE\_PIPE or UV\_WRITABLE\_PIPE. The read/write flag is from the perspective of the child process.

### **Arbitrary process IPC**

Since domain sockets<sup>1</sup> can have a well known name and a location in the file-system they can be used for IPC between unrelated processes. The D-BUS system used by open source desktop environments uses domain sockets for event notification. Various applications can then react when a contact comes online or new hardware is detected. The MySQL server also runs a domain socket on which clients can interact with it.

When using domain sockets, a client-server pattern is usually followed with the creator/owner of the socket acting as the server. After the initial setup, messaging is no different from TCP, so we'll re-use the echo server example.

#### pipe-echo-server/main.c

```
void remove_sock(int sig) {
       uv_fs_t req;
2
       uv_fs_unlink(loop, &req, PIPENAME, NULL);
       exit(0);
   }
6
   int main() {
       loop = uv_default_loop();
8
       uv_pipe_t server;
10
       uv_pipe_init(loop, &server, 0);
11
12
       signal(SIGINT, remove_sock);
13
14
       int r;
15
       if ((r = uv_pipe_bind(&server, PIPENAME))) {
16
           fprintf(stderr, "Bind error %s\n", uv_err_name(r));
17
           return 1;
18
19
       if ((r = uv_listen((uv_stream_t*) &server, 128, on_new_connection))) {
           fprintf(stderr, "Listen error %s\n", uv_err_name(r));
21
           return 2;
22
23
       return uv_run(loop, UV_RUN_DEFAULT);
24
```

We name the socket echo. sock which means it will be created in the local directory. This socket now behaves no different from TCP sockets as far as the stream API is concerned. You can test this server using socat:

```
$ socat - /path/to/socket
```

A client which wants to connect to a domain socket will use:

<sup>&</sup>lt;sup>1</sup> In this section domain sockets stands in for named pipes on Windows as well.

where name will be echo. sock or similar.

## Sending file descriptors over pipes

The cool thing about domain sockets is that file descriptors can be exchanged between processes by sending them over a domain socket. This allows processes to hand off their I/O to other processes. Applications include load-balancing servers, worker processes and other ways to make optimum use of CPU. libuv only supports sending **TCP sockets or other pipes** over pipes for now.

To demonstrate, we will look at a echo server implementation that hands of clients to worker processes in a round-robin fashion. This program is a bit involved, and while only snippets are included in the book, it is recommended to read the full code to really understand it.

The worker process is quite simple, since the file-descriptor is handed over to it by the master.

#### multi-echo-server/worker.c

```
uv_loop_t *loop;
uv_pipe_t queue;
int main() {
    loop = uv_default_loop();

    uv_pipe_init(loop, &queue, 1 /* ipc */);
    uv_pipe_open(&queue, 0);
    uv_read_start((uv_stream_t*)&queue, alloc_buffer, on_new_connection);
    return uv_run(loop, UV_RUN_DEFAULT);
}
```

queue is the pipe connected to the master process on the other end, along which new file descriptors get sent. It is important to set the ipc argument of uv\_pipe\_init to 1 to indicate this pipe will be used for inter-process communication! Since the master will write the file handle to the standard input of the worker, we connect the pipe to stdin using uv pipe open.

## multi-echo-server/worker.c

```
void on_new_connection(uv_stream_t *q, ssize_t nread, const uv_buf_t *buf) {
       if (nread < 0) {
2
           if (nread != UV EOF)
3
                fprintf(stderr, "Read error %s\n", uv_err_name(nread));
4
           uv_close((uv_handle_t*) q, NULL);
           return;
6
       }
8
       uv_pipe_t *pipe = (uv_pipe_t*) q;
       if (!uv_pipe_pending_count(pipe)) {
10
           fprintf(stderr, "No pending count\n");
11
           return;
12
       }
13
14
       uv_handle_type pending = uv_pipe_pending_type(pipe);
15
       assert (pending == UV_TCP);
16
17
       uv_tcp_t *client = (uv_tcp_t*) malloc(sizeof(uv_tcp_t));
```

```
uv_tcp_init(loop, client);
19
       if (uv_accept(q, (uv_stream_t*) client) == 0) {
20
           uv_os_fd_t fd;
21
           uv_fileno((const uv_handle_t*) client, &fd);
22
           fprintf(stderr, "Worker %d: Accepted fd %d\n", getpid(), fd);
23
           uv_read_start((uv_stream_t*) client, alloc_buffer, echo_read);
       }
25
       else {
26
           uv_close((uv_handle_t*) client, NULL);
27
28
   }
```

First we call uv\_pipe\_pending\_count () to ensure that a handle is available to read out. If your program could deal with different types of handles, uv\_pipe\_pending\_type() can be used to determine the type. Although accept seems odd in this code, it actually makes sense. What accept traditionally does is get a file descriptor (the client) from another file descriptor (The listening socket). Which is exactly what we do here. Fetch the file descriptor (client) from queue. From this point the worker does standard echo server stuff.

Turning now to the master, let's take a look at how the workers are launched to allow load balancing.

#### multi-echo-server/main.c

```
struct child_worker {
    uv_process_t req;
    uv_process_options_t options;
    uv_pipe_t pipe;
} *workers;
```

The child\_worker structure wraps the process, and the pipe between the master and the individual process.

#### multi-echo-server/main.c

100

```
void setup_workers() {
       round_robin_counter = 0;
       // ...
       // launch same number of workers as number of CPUs
6
       uv_cpu_info_t *info;
       int cpu_count;
       uv_cpu_info(&info, &cpu_count);
       uv_free_cpu_info(info, cpu_count);
10
11
       child_worker_count = cpu_count;
12
13
       workers = calloc(sizeof(struct child_worker), cpu_count);
14
       while (cpu_count--) {
16
           struct child_worker *worker = &workers[cpu_count];
17
           uv_pipe_init(loop, &worker->pipe, 1);
18
           uv_stdio_container_t child_stdio[3];
19
           child_stdio[0].flags = UV_CREATE_PIPE | UV_READABLE_PIPE;
20
21
           child_stdio[0].data.stream = (uv_stream_t*) &worker->pipe;
           child_stdio[1].flags = UV_IGNORE;
```

```
child_stdio[2].flags = UV_INHERIT_FD;
23
           child_stdio[2].data.fd = 2;
24
25
           worker->options.stdio = child_stdio;
26
           worker->options.stdio_count = 3;
           worker->options.exit_cb = close_process_handle;
29
           worker->options.file = args[0];
30
           worker->options.args = args;
31
32
           uv_spawn(loop, &worker->req, &worker->options);
33
           fprintf(stderr, "Started worker %d\n", worker->req.pid);
35
```

In setting up the workers, we use the nifty libuv function uv\_cpu\_info to get the number of CPUs so we can launch an equal number of workers. Again it is important to initialize the pipe acting as the IPC channel with the third argument as 1. We then indicate that the child process' stdin is to be a readable pipe (from the point of view of the child). Everything is straightforward till here. The workers are launched and waiting for file descriptors to be written to their standard input.

It is in on\_new\_connection (the TCP infrastructure is initialized in main()), that we accept the client socket and pass it along to the next worker in the round-robin.

#### multi-echo-server/main.c

```
void on_new_connection(uv_stream_t *server, int status) {
       if (status == -1) {
2
           // error!
3
           return;
       uv_tcp_t *client = (uv_tcp_t*) malloc(sizeof(uv_tcp_t));
       uv_tcp_init(loop, client);
       if (uv_accept(server, (uv_stream_t*) client) == 0) {
9
           uv_write_t *write_req = (uv_write_t*) malloc(sizeof(uv_write_t));
11
           dummy_buf = uv_buf_init("a", 1);
           struct child_worker *worker = &workers[round_robin_counter];
12
           uv_write2(write_req, (uv_stream_t*) &worker->pipe, &dummy_buf, 1, (uv_stream_
13
   \hookrightarrowt*) client, NULL);
           round_robin_counter = (round_robin_counter + 1) % child_worker_count;
14
       }
15
       else {
           uv_close((uv_handle_t*) client, NULL);
17
18
   }
```

The uv\_write2 call handles all the abstraction and it is simply a matter of passing in the handle (client) as the right argument. With this our multi-process echo server is operational.

Thanks to Kyle for pointing out that uv\_write2 () requires a non-empty buffer even when sending handles.

# **Advanced event loops**

libuv provides considerable user control over event loops, and you can achieve interesting results by juggling multiple loops. You can also embed libuv's event loop into another event loop based library – imagine a Qt based UI, and Qt's event loop driving a libuv backend which does intensive system level tasks.

## Stopping an event loop

uv\_stop() can be used to stop an event loop. The earliest the loop will stop running is *on the next iteration*, possibly later. This means that events that are ready to be processed in this iteration of the loop will still be processed, so uv\_stop() can't be used as a kill switch. When uv\_stop() is called, the loop won't block for i/o on this iteration. The semantics of these things can be a bit difficult to understand, so let's look at uv\_run() where all the control flow occurs.

### src/unix/core.c - uv\_run

```
int uv_backend_fd(const uv_loop_t* loop) {
2
     return loop->backend_fd;
3
4
5
6
   int uv_backend_timeout(const uv_loop_t* loop) {
7
     if (loop->stop_flag != 0)
       return 0;
10
     if (!uv_has_active_handles(loop) && !uv_has_active_reqs(loop))
11
12
13
     if (!QUEUE_EMPTY(&loop->idle_handles))
14
       return 0;
15
16
     if (!QUEUE_EMPTY(&loop->pending_queue))
17
       return 0;
18
19
     if (loop->closing_handles)
20
       return 0;
21
```

stop\_flag is set by uv\_stop(). Now all libuv callbacks are invoked within the event loop, which is why invoking uv\_stop() in them will still lead to this iteration of the loop occurring. First libuv updates timers, then runs pending timer, idle and prepare callbacks, and invokes any pending I/O callbacks. If you were to call uv\_stop() in any of them, stop\_flag would be set. This causes uv\_backend\_timeout() to return 0, which is why the loop does not block on I/O. If on the other hand, you called uv\_stop() in one of the check handlers, I/O has already finished and is not affected.

uv\_stop() is useful to shutdown a loop when a result has been computed or there is an error, without having to ensure that all handlers are stopped one by one.

Here is a simple example that stops the loop and demonstrates how the current iteration of the loop still takes places.

### uvstop/main.c

```
#include <stdio.h>
   #include <uv.h>
2
3
   int64_t counter = 0;
   void idle_cb(uv_idle_t *handle) {
6
       printf("Idle callback\n");
7
       counter++;
       if (counter \geq = 5) {
10
            uv_stop(uv_default_loop());
11
            printf("uv_stop() called\n");
12
       }
13
14
15
   void prep_cb(uv_prepare_t *handle) {
16
       printf("Prep callback\n");
17
18
19
   int main() {
20
21
       uv_idle_t idler;
22
       uv_prepare_t prep;
23
       uv_idle_init(uv_default_loop(), &idler);
24
       uv_idle_start(&idler, idle_cb);
25
26
       uv_prepare_init(uv_default_loop(), &prep);
27
       uv_prepare_start(&prep, prep_cb);
28
       uv_run(uv_default_loop(), UV_RUN_DEFAULT);
30
31
32
       return 0;
33
```

#### **Utilities**

This chapter catalogues tools and techniques which are useful for common tasks. The libev man page already covers some patterns which can be adopted to libuv through simple API changes. It also covers parts of the libuv API that don't require entire chapters dedicated to them.

#### **Timers**

Timers invoke the callback after a certain time has elapsed since the timer was started. libuv timers can also be set to invoke at regular intervals instead of just once.

Simple use is to init a watcher and start it with a timeout, and optional repeat. Timers can be stopped at any time.

```
uv_timer_t timer_req;
uv_timer_init(loop, &timer_req);
uv_timer_start(&timer_req, callback, 5000, 2000);
```

will start a repeating timer, which first starts 5 seconds (the timeout) after the execution of uv\_timer\_start, then repeats every 2 seconds (the repeat). Use:

```
uv_timer_stop(&timer_req);
```

to stop the timer. This can be used safely from within the callback as well.

The repeat interval can be modified at any time with:

```
uv_timer_set_repeat(uv_timer_t *timer, int64_t repeat);
```

which will take effect **when possible**. If this function is called from a timer callback, it means:

- If the timer was non-repeating, the timer has already been stopped. Use uv\_timer\_start again.
- If the timer is repeating, the next timeout has already been scheduled, so the old repeat interval will be used once more before the timer switches to the new interval.

The utility function:

```
int uv_timer_again(uv_timer_t *)
```

applies **only to repeating timers** and is equivalent to stopping the timer and then starting it with both initial timeout and repeat set to the old repeat value. If the timer hasn't been started it fails (error code UV\_EINVAL) and returns -1.

An actual timer example is in the reference count section.

## **Event loop reference count**

The event loop only runs as long as there are active handles. This system works by having every handle increase the reference count of the event loop when it is started and decreasing the reference count when stopped. It is also possible to manually change the reference count of handles using:

```
void uv_ref(uv_handle_t*);
void uv_unref(uv_handle_t*);
```

These functions can be used to allow a loop to exit even when a watcher is active or to use custom objects to keep the loop alive.

The latter can be used with interval timers. You might have a garbage collector which runs every X seconds, or your network service might send a heartbeat to others periodically, but you don't want to have to stop them along all clean exit paths or error scenarios. Or you want the program to exit when all your other watchers are done. In that case just unref the timer immediately after creation so that if it is the only watcher running then uv\_run will still exit.

This is also used in node.js where some libuv methods are being bubbled up to the JS API. A uv\_handle\_t (the superclass of all watchers) is created per JS object and can be ref/unrefed.

#### ref-timer/main.c

```
uv_loop_t *loop;
uv_timer_t gc_req;
uv_timer_t fake_job_req;
int main() {
   loop = uv_default_loop();
```

```
uv_timer_init(loop, &gc_req);
uv_unref((uv_handle_t*) &gc_req);

uv_timer_start(&gc_req, gc, 0, 2000);

// could actually be a TCP download or something
uv_timer_init(loop, &fake_job_req);
uv_timer_start(&fake_job_req, fake_job, 9000, 0);
return uv_run(loop, UV_RUN_DEFAULT);
}
```

We initialize the garbage collector timer, then immediately unref it. Observe how after 9 seconds, when the fake job is done, the program automatically exits, even though the garbage collector is still running.

#### **Idler pattern**

The callbacks of idle handles are invoked once per event loop. The idle callback can be used to perform some very low priority activity. For example, you could dispatch a summary of the daily application performance to the developers for analysis during periods of idleness, or use the application's CPU time to perform SETI calculations:) An idle watcher is also useful in a GUI application. Say you are using an event loop for a file download. If the TCP socket is still being established and no other events are present your event loop will pause (block), which means your progress bar will freeze and the user will face an unresponsive application. In such a case queue up and idle watcher to keep the UI operational.

## idle-compute/main.c

```
uv_loop_t *loop;
   uv_fs_t stdin_watcher;
2
   uv_idle_t idler;
   char buffer[1024];
   int main() {
6
       loop = uv_default_loop();
7
8
       uv_idle_init(loop, &idler);
10
       uv_buf_t buf = uv_buf_init(buffer, 1024);
11
       uv_fs_read(loop, &stdin_watcher, 0, &buf, 1, -1, on_type);
       uv_idle_start(&idler, crunch_away);
13
       return uv_run(loop, UV_RUN_DEFAULT);
14
15
```

Here we initialize the idle watcher and queue it up along with the actual events we are interested in. crunch\_away will now be called repeatedly until the user types something and presses Return. Then it will be interrupted for a brief amount as the loop deals with the input data, after which it will keep calling the idle callback again.

## idle-compute/main.c

```
void crunch_away(uv_idle_t* handle) {
    // Compute extra-terrestrial life
    // fold proteins
    // computer another digit of PI
```

```
// or similar
fprintf(stderr, "Computing PI...\n");
// just to avoid overwhelming your terminal emulator
uv_idle_stop(handle);
}
```

#### Passing data to worker thread

When using uv\_queue\_work you'll usually need to pass complex data through to the worker thread. The solution is to use a struct and set uv\_work\_t.data to point to it. A slight variation is to have the uv\_work\_t itself as the first member of this struct (called a baton<sup>1</sup>). This allows cleaning up the work request and all the data in one free call.

```
struct ftp_baton {
    uv_work_t req;
    char *host;
    int port;
    char *username;
    char *password;
}
```

```
ftp_baton *baton = (ftp_baton*) malloc(sizeof(ftp_baton));
baton->req.data = (void*) baton;
baton->host = strdup("my.webhost.com");
baton->port = 21;
// ...
uv_queue_work(loop, &baton->req, ftp_session, ftp_cleanup);
```

Here we create the baton and queue the task.

Now the task function can extract the data it needs:

```
void ftp_session(uv_work_t *req) {
   ftp_baton *baton = (ftp_baton*) req->data;

fprintf(stderr, "Connecting to %s\n", baton->host);

void ftp_cleanup(uv_work_t *req) {
   ftp_baton *baton = (ftp_baton*) req->data;

free(baton->host);
   // ...
   free(baton);
}
```

We then free the baton which also frees the watcher.

 $<sup>^1\</sup> I\ was\ first\ introduced\ to\ the\ term\ baton\ in\ this\ context,\ in\ Konstantin\ K\"afer's\ excellent\ slides\ on\ writing\ node.js\ bindings-http://kkaefer.github.\ com/node-cpp-modules/\#baton$ 

## External I/O with polling

Usually third-party libraries will handle their own I/O, and keep track of their sockets and other files internally. In this case it isn't possible to use the standard stream I/O operations, but the library can still be integrated into the libuve event loop. All that is required is that the library allow you to access the underlying file descriptors and provide functions that process tasks in small increments as decided by your application. Some libraries though will not allow such access, providing only a standard blocking function which will perform the entire I/O transaction and only then return. It is unwise to use these in the event loop thread, use the libuv-work-queue instead. Of course, this will also mean losing granular control on the library.

The uv\_poll section of libuv simply watches file descriptors using the operating system notification mechanism. In some sense, all the I/O operations that libuv implements itself are also backed by uv\_poll like code. Whenever the OS notices a change of state in file descriptors being polled, libuv will invoke the associated callback.

Here we will walk through a simple download manager that will use libcurl to download files. Rather than give all control to libcurl, we'll instead be using the libuv event loop, and use the non-blocking, async multi interface to progress with the download whenever libuv notifies of I/O readiness.

## uvwget/main.c - The setup

```
#include <assert.h>
2
   #include <stdio.h>
   #include <stdlib.h>
3
   #include <uv.h>
4
   #include <curl/curl.h>
5
   uv_loop_t *loop;
   CURLM *curl_handle;
   uv_timer_t timeout;
10
11
   int main(int argc, char **argv) {
12
        loop = uv_default_loop();
13
14
15
        if (argc <= 1)
            return 0;
16
17
        if (curl_global_init(CURL_GLOBAL_ALL)) {
18
            fprintf(stderr, "Could not init cURL\n");
19
            return 1;
20
        }
21
22
       uv_timer_init(loop, &timeout);
23
24
       curl_handle = curl_multi_init();
25
        curl_multi_setopt(curl_handle, CURLMOPT_SOCKETFUNCTION, handle_socket);
26
        curl_multi_setopt(curl_handle, CURLMOPT_TIMERFUNCTION, start_timeout);
27
        while (argc-- > 1) {
29
            add_download(argv[argc], argc);
30
31
32
        uv_run(loop, UV_RUN_DEFAULT);
33
        curl_multi_cleanup(curl_handle);
34
        return 0;
35
```

The way each library is integrated with libuv will vary. In the case of libcurl, we can register two callbacks. The socket callback handle\_socket is invoked whenever the state of a socket changes and we have to start polling it. start\_timeout is called by libcurl to notify us of the next timeout interval, after which we should drive libcurl forward regardless of I/O status. This is so that libcurl can handle errors or do whatever else is required to get the download moving.

Our downloader is to be invoked as:

```
$ ./uvwget [url1] [url2] ...
```

So we add each argument as an URL

#### uvwget/main.c - Adding urls

```
void add_download(const char *url, int num) {
2
       char filename[50];
       sprintf(filename, "%d.download", num);
       FILE *file;
5
6
       file = fopen(filename, "w");
7
       if (file == NULL) {
            fprintf(stderr, "Error opening %s\n", filename);
            return;
       }
11
12
       CURL *handle = curl_easy_init();
13
       curl_easy_setopt(handle, CURLOPT_WRITEDATA, file);
14
       curl_easy_setopt(handle, CURLOPT_URL, url);
15
       curl_multi_add_handle(curl_handle, handle);
16
       fprintf(stderr, "Added download \$s \rightarrow \$s \ n", url, filename);
17
18
```

We let libcurl directly write the data to a file, but much more is possible if you so desire.

start\_timeout will be called immediately the first time by libcurl, so things are set in motion. This simply starts a libuv timer which drives curl\_multi\_socket\_action with CURL\_SOCKET\_TIMEOUT whenever it times out. curl\_multi\_socket\_action is what drives libcurl, and what we call whenever sockets change state. But before we go into that, we need to poll on sockets whenever handle\_socket is called.

#### uvwget/main.c - Setting up polling

```
curl_context = (curl_context_t*) socketp;
12
            }
13
            else {
14
                curl_context = create_curl_context(s);
15
                curl_multi_assign(curl_handle, s, (void *) curl_context);
            }
        }
18
19
       switch (action) {
20
            case CURL_POLL_IN:
21
                uv_poll_start(&curl_context->poll_handle, UV_READABLE, curl_perform);
22
23
            case CURL_POLL_OUT:
24
                uv_poll_start(&curl_context->poll_handle, UV_WRITABLE, curl_perform);
25
                break;
26
            case CURL_POLL_REMOVE:
27
                if (socketp) {
28
                     uv_poll_stop(&((curl_context_t*)socketp)->poll_handle);
29
                     destroy_curl_context((curl_context_t*) socketp);
                     curl_multi_assign(curl_handle, s, NULL);
31
32
                break;
33
            default:
34
                abort();
35
37
       return 0;
38
39
```

We are interested in the socket fd s, and the action. For every socket we create a uv\_poll\_t handle if it doesn't exist, and associate it with the socket using curl\_multi\_assign. This way socketp points to it whenever the callback is invoked.

In the case that the download is done or fails, libcurl requests removal of the poll. So we stop and free the poll handle.

Depending on what events libcurl wishes to watch for, we start polling with UV\_READABLE or UV\_WRITABLE. Now libuv will invoke the poll callback whenever the socket is ready for reading or writing. Calling uv\_poll\_start multiple times on the same handle is acceptable, it will just update the events mask with the new value. curl\_perform is the crux of this program.

#### uvwget/main.c - Driving libcurl.

```
void curl_perform(uv_poll_t *req, int status, int events) {
       uv_timer_stop(&timeout);
2
       int running_handles;
3
       int flags = 0;
4
       if (status < 0)
                                              flags = CURL_CSELECT_ERR;
       if (!status && events & UV_READABLE) flags |= CURL_CSELECT_IN;
6
       if (!status && events & UV_WRITABLE) flags |= CURL_CSELECT_OUT;
       curl_context_t *context;
10
       context = (curl_context_t*)req;
11
12
       curl_multi_socket_action(curl_handle, context->sockfd, flags, &running_handles);
13
       check_multi_info();
14
```

15

The first thing we do is to stop the timer, since there has been some progress in the interval. Then depending on what event triggered the callback, we set the correct flags. Then we call <code>curl\_multi\_socket\_action</code> with the socket that progressed and the flags informing about what events happened. At this point libcurl does all of its internal tasks in small increments, and will attempt to return as fast as possible, which is exactly what an evented program wants in its main thread. libcurl keeps queueing messages into its own queue about transfer progress. In our case we are only interested in transfers that are completed. So we extract these messages, and clean up handles whose transfers are done.

#### uvwget/main.c - Reading transfer status.

```
void check_multi_info(void) {
       char *done_url;
2
       CURLMsg *message;
3
       int pending;
       while ((message = curl_multi_info_read(curl_handle, &pending))) {
           switch (message->msg) {
           case CURLMSG_DONE:
                curl_easy_getinfo(message->easy_handle, CURLINFO_EFFECTIVE_URL,
                                 &done url);
10
                printf("%s DONE\n", done_url);
11
12
                curl_multi_remove_handle(curl_handle, message->easy_handle);
13
                curl_easy_cleanup(message->easy_handle);
14
                break;
15
16
           default:
17
                fprintf(stderr, "CURLMSG default\n");
                abort();
20
       }
21
22
```

## **Check & Prepare watchers**

**TODO** 

## **Loading libraries**

libuv provides a cross platform API to dynamically load shared libraries. This can be used to implement your own plugin/extension/module system and is used by node.js to implement require() support for bindings. The usage is quite simple as long as your library exports the right symbols. Be careful with sanity and security checks when loading third party code, otherwise your program will behave unpredictably. This example implements a very simple plugin system which does nothing except print the name of the plugin.

Let us first look at the interface provided to plugin authors.

## plugin/plugin.h

```
#ifndef UVBOOK_PLUGIN_SYSTEM
#define UVBOOK_PLUGIN_SYSTEM

// Plugin authors should use this to register their plugins with mfp.
void mfp_register(const char *name);

#endif
```

You can similarly add more functions that plugin authors can use to do useful things in your application<sup>2</sup>. A sample plugin using this API is:

#### plugin/hello.c

```
#include "plugin.h"

void initialize() {
    mfp_register("Hello World!");
}
```

Our interface defines that all plugins should have an initialize function which will be called by the application. This plugin is compiled as a shared library and can be loaded by running our application:

```
$ ./plugin libhello.dylib
Loading libhello.dylib
Registered plugin "Hello World!"
```

**Note:** The shared library filename will be different depending on platforms. On Linux it is libhello.so.

This is done by using uv\_dlopen to first load the shared library libhello.dylib. Then we get access to the initialize function using uv\_dlsym and invoke it.

#### plugin/main.c

```
#include "plugin.h"
2
   typedef void (*init_plugin_function)();
   void mfp_register(const char *name) {
6
       fprintf(stderr, "Registered plugin \"%s\"\n", name);
7
   int main(int argc, char **argv) {
9
       if (argc == 1) {
10
           fprintf(stderr, "Usage: %s [plugin1] [plugin2] ...\n", argv[0]);
11
           return 0;
13
14
       uv_lib_t *lib = (uv_lib_t*) malloc(sizeof(uv_lib_t));
```

<sup>&</sup>lt;sup>2</sup> mfp is My Fancy Plugin

```
while (--argc) {
16
            fprintf(stderr, "Loading %s\n", argv[argc]);
17
            if (uv_dlopen(argv[argc], lib)) {
18
                fprintf(stderr, "Error: %s\n", uv_dlerror(lib));
19
                continue;
            }
21
22
            init_plugin_function init_plugin;
23
            if (uv_dlsym(lib, "initialize", (void **) &init_pluqin)) {
24
                fprintf(stderr, "dlsym error: %s\n", uv_dlerror(lib));
25
                continue;
26
27
28
            init_plugin();
29
        }
30
31
       return 0:
32
   }
```

uv\_dlopen expects a path to the shared library and sets the opaque uv\_lib\_t pointer. It returns 0 on success, -1 on error. Use uv\_dlerror to get the error message.

uv\_dlsym stores a pointer to the symbol in the second argument in the third argument. init\_plugin\_function is a function pointer to the sort of function we are looking for in the application's plugins.

#### TTY

Text terminals have supported basic formatting for a long time, with a pretty standardised command set. This formatting is often used by programs to improve the readability of terminal output. For example <code>grep --colour</code>. libuv provides the <code>uv\_tty\_t</code> abstraction (a stream) and related functions to implement the ANSI escape codes across all platforms. By this I mean that libuv converts ANSI codes to the Windows equivalent, and provides functions to get terminal information.

The first thing to do is to initialize a uv\_tty\_t with the file descriptor it reads/writes from. This is achieved with:

```
int uv_tty_init(uv_loop_t*, uv_tty_t*, uv_file fd, int readable)
```

Set readable to true if you plan to use uv\_read\_start() on the stream.

It is then best to use uv\_tty\_set\_mode to set the mode to *normal* which enables most TTY formatting, flow-control and other settings. Other modes are also available.

Remember to call uv\_tty\_reset\_mode when your program exits to restore the state of the terminal. Just good manners. Another set of good manners is to be aware of redirection. If the user redirects the output of your command to a file, control sequences should not be written as they impede readability and grep. To check if the file descriptor is indeed a TTY, call uv\_guess\_handle with the file descriptor and compare the return value with UV\_TTY.

Here is a simple example which prints white text on a red background:

#### tty/main.c

```
#include <stdio.h>
#include <string.h>
#include <unistd.h>
#include <uv.h>
```

```
uv_loop_t *loop;
6
   uv_tty_t tty;
   int main() {
       loop = uv_default_loop();
       uv_tty_init(loop, &tty, 1, 0);
       uv_tty_set_mode(&tty, UV_TTY_MODE_NORMAL);
12
13
       if (uv_quess_handle(1) == UV_TTY) {
14
           uv_write_t req;
15
           uv_buf_t buf;
16
           buf.base = "\033[41;37m";
17
           buf.len = strlen(buf.base);
18
            uv_write(&req, (uv_stream_t*) &tty, &buf, 1, NULL);
19
       }
20
21
       uv_write_t req;
22
       uv_buf_t buf;
23
       buf.base = "Hello TTY\n";
24
       buf.len = strlen(buf.base);
25
       uv_write(&req, (uv_stream_t*) &tty, &buf, 1, NULL);
26
       uv_tty_reset_mode();
27
       return uv_run(loop, UV_RUN_DEFAULT);
28
29
```

The final TTY helper is uv\_tty\_get\_winsize() which is used to get the width and height of the terminal and returns 0 on success. Here is a small program which does some animation using the function and character position escape codes.

## tty-gravity/main.c

```
#include <stdio.h>
   #include <string.h>
2
   #include <unistd.h>
   #include <uv.h>
   uv_loop_t *loop;
6
   uv_tty_t tty;
7
   uv_timer_t tick;
   uv_write_t write_req;
   int width, height;
   int pos = 0;
11
   char *message = " Hello TTY ";
12
13
   void update(uv_timer_t *req) {
14
       char data[500];
15
       uv_buf_t buf;
17
       buf.base = data;
18
       buf.len = sprintf(data, "\033[2J\033[H\033[dB\033[dB\033[dB\033[42;37m%s",
19
                                 pos,
20
                                  (unsigned long) (width-strlen(message))/2,
21
22
                                 message);
23
       uv_write(&write_req, (uv_stream_t*) &tty, &buf, 1, NULL);
24
       pos++;
```

```
if (pos > height) {
26
            uv_tty_reset_mode();
27
            uv_timer_stop(&tick);
28
29
       }
   }
   int main() {
32
       loop = uv_default_loop();
33
34
       uv_tty_init(loop, &tty, 1, 0);
35
       uv_tty_set_mode(&tty, 0);
36
37
       if (uv_tty_get_winsize(&tty, &width, &height)) {
38
            fprintf(stderr, "Could not get TTY information\n");
39
            uv_tty_reset_mode();
40
            return 1;
41
       }
42
43
       fprintf(stderr, "Width %d, height %d\n", width, height);
44
       uv_timer_init(loop, &tick);
45
       uv_timer_start(&tick, update, 200, 200);
46
       return uv_run(loop, UV_RUN_DEFAULT);
47
```

The escape codes are:

Code	Meaning
2 J	Clear part of the screen, 2 is entire screen
Н	Moves cursor to certain position, default top-left
n B	Moves cursor down by n lines
n C	Moves cursor right by n columns
m	Obeys string of display settings, in this case green background (40+2), white text (30+7)

As you can see this is very useful to produce nicely formatted output, or even console based arcade games if that tickles your fancy. For fancier control you can try neurses.

## **About**

Nikhil Marathe started writing this book one afternoon (June 16, 2012) when he didn't feel like programming. He had recently been stung by the lack of good documentation on libuv while working on node-taglib. Although reference documentation was present, there were no comprehensive tutorials. This book is the output of that need and tries to be accurate. That said, the book may have mistakes. Pull requests are encouraged.

Nikhil is indebted to Marc Lehmann's comprehensive man page about libev which describes much of the semantics of the two libraries.

This book was made using Sphinx and vim.

**Note:** In 2017 the libuv project incorporated the Nikhil's work into the official documentation and it's maintained there henceforth.

# **Upgrading**

Migration guides for different libuv versions, starting with 1.0.

# libuv 0.10 -> 1.0.0 migration guide

Some APIs changed quite a bit throughout the 1.0.0 development process. Here is a migration guide for the most significant changes that happened after 0.10 was released.

#### Loop initialization and closing

In libuv 0.10 (and previous versions), loops were created with  $uv\_loop\_new$ , which allocated memory for a new loop and initialized it; and destroyed with  $uv\_loop\_delete$ , which destroyed the loop and freed the memory. Starting with 1.0, those are deprecated and the user is responsible for allocating the memory and then initializing the loop.

libuy 0.10

```
uv_loop_t* loop = uv_loop_new();
...
uv_loop_delete(loop);
```

#### libuv 1.0

```
uv_loop_t* loop = malloc(sizeof *loop);
uv_loop_init(loop);
...
uv_loop_close(loop);
free(loop);
```

**Note:** Error handling was omitted for brevity. Check the documentation for  $uv\_loop\_init()$  and  $uv\_loop\_close()$ .

#### **Error handling**

Error handling had a major overhaul in libuv 1.0. In general, functions and status parameters would get 0 for success and -1 for failure on libuv 0.10, and the user had to use *uv\_last\_error* to fetch the error code, which was a positive number.

In 1.0, functions and status parameters contain the actual error code, which is 0 for success, or a negative number in case of error.

libuv 0.10

```
... assume 'server' is a TCP server which is already listening
r = uv_listen((uv_stream_t*) server, 511, NULL);
if (r == -1) {
  uv_err_t err = uv_last_error(uv_default_loop());
  /* err.code contains UV_EADDRINUSE */
}
```

libuv 1.0

3.4. Upgrading 115

```
... assume 'server' is a TCP server which is already listening
r = uv_listen((uv_stream_t*) server, 511, NULL);
if (r < 0) {
   /* r contains UV_EADDRINUSE */
}</pre>
```

#### Threadpool changes

In libuv 0.10 Unix used a threadpool which defaulted to 4 threads, while Windows used the *QueueUserWorkItem* API, which uses a Windows internal threadpool, which defaults to 512 threads per process.

In 1.0, we unified both implementations, so Windows now uses the same implementation Unix does. The threadpool size can be set by exporting the UV THREADPOOL SIZE environment variable. See *Thread pool work scheduling*.

## Allocation callback API change

In libuv 0.10 the callback had to return a filled  $uv\_buf\_t$  by value:

```
uv_buf_t alloc_cb(uv_handle_t* handle, size_t size) {
   return uv_buf_init(malloc(size), size);
}
```

In libuv 1.0 a pointer to a buffer is passed to the callback, which the user needs to fill:

```
void alloc_cb(uv_handle_t* handle, size_t size, uv_buf_t* buf) {
   buf->base = malloc(size);
   buf->len = size;
}
```

#### Unification of IPv4 / IPv6 APIs

libuv 1.0 unified the IPv4 and IPv6 APIS. There is no longer a uv\_tcp\_bind and uv\_tcp\_bind6 duality, there is only uv\_tcp\_bind() now.

IPv4 functions took struct sockaddr\_in structures by value, and IPv6 functions took struct sockaddr\_in6. Now functions take a struct sockaddr\* (note it's a pointer). It can be stack allocated.

libuy 0.10

```
struct sockaddr_in addr = uv_ip4_addr("0.0.0.0", 1234);
...
uv_tcp_bind(&server, addr)
```

#### libuv 1.0

```
struct sockaddr_in addr;
uv_ip4_addr("0.0.0.0", 1234, &addr)
...
uv_tcp_bind(&server, (const struct sockaddr*) &addr, 0);
```

The IPv4 and IPv6 struct creating functions  $(uv\_ip4\_addr())$  and  $uv\_ip6\_addr())$  have also changed, make sure you check the documentation.

..note:: This change applies to all functions that made a distinction between IPv4 and IPv6 addresses.

## Streams / UDP data receive callback API change

The streams and UDP data receive callbacks now get a pointer to a uv\_buf\_t buffer, not a structure by value.

#### libuv 0.10

#### libuv 1.0

## Receiving handles over pipes API change

In libuv 0.10 (and earlier versions) the *uv\_read2\_start* function was used to start reading data on a pipe, which could also result in the reception of handles over it. The callback for such function looked like this:

In libuv 1.0, uv\_read2\_start was removed, and the user needs to check if there are pending handles using uv\_pipe\_pending\_count() and uv\_pipe\_pending\_type() while in the read callback:

3.4. Upgrading 117

```
}
...
}
```

#### Extracting the file descriptor out of a handle

While it wasn't supported by the API, users often accessed the libuv internals in order to get access to the file descriptor of a TCP handle, for example.

```
fd = handle->io_watcher.fd;
```

This is now properly exposed through the *uv\_fileno()* function.

# uv\_fs\_readdir rename and API change

 $uv\_fs\_readdir$  returned a list of strings in the req->ptr field upon completion in libuv 0.10. In 1.0, this function got renamed to  $uv\_fs\_scandir()$ , since it's actually implemented using scandir(3).

In addition, instead of allocating a full list strings, the user is able to get one result at a time by using the  $uv\_fs\_scandir\_next()$  function. This function does not need to make a roundtrip to the threadpool, because libuv will keep the list of *dents* returned by scandir(3) around.

CHAPTER 4	4
-----------	---

Downloads

libuv can be downloaded from here.

CHAPTER	5
---------	---

Installation

Installation instructions can be found in the README.

U	uv_connect_t.handle (C member), 32
uv_accept (C function), 32	uv_connection_cb (C type), 32
uv_after_work_cb (C type), 51	uv_cpu_info (C function), 59
uv_alloc_cb (C type), 17	uv_cpu_info_t (C type), 57
uv_any_handle (C type), 17	uv_cwd (C function), 60
uv_any_req (C type), 20	uv_default_loop (C function), 15
uv_async_cb (C type), 24	uv_dirent_t (C type), 47
uv_async_init (C function), 24	uv_disable_stdio_inheritance (C function), 30
uv_async_send (C function), 24	uv_dlclose (C function), 54
uv_async_t (C type), 24	uv_dlerror (C function), 54
uv_backend_fd (C function), 15	uv_dlopen (C function), 54
uv_backend_timeout (C function), 15	uv_dlsym (C function), 54
uv_barrier_destroy (C function), 56	UV_E2BIG (C macro), 9
uv_barrier_init (C function), 56	UV_EACCES (C macro), 9
uv_barrier_t (C type), 54	UV_EADDRINUSE (C macro), 9
uv_barrier_wait (C function), 56	UV_EADDRNOTAVAIL (C macro), 9
uv_buf_init (C function), 59	UV_EAFNOSUPPORT (C macro), 9
uv_buf_t (C type), 57	UV_EAGAIN (C macro), 9
uv_buf_t.uv_buf_t.base (C member), 57	UV_EAI_ADDRFAMILY (C macro), 9
uv_buf_t.uv_buf_t.len (C member), 57	UV_EAI_AGAIN (C macro), 9
uv_calloc_func (C type), 57	UV_EAI_BADFLAGS (C macro), 9
uv_cancel (C function), 20	UV_EAI_BADHINTS (C macro), 9
uv_chdir (C function), 60	UV_EAI_CANCELED (C macro), 9
uv_check_cb (C type), 23	UV_EAI_FAIL (C macro), 9
uv_check_init (C function), 23	UV_EAI_FAMILY (C macro), 10
uv_check_start (C function), 23	UV_EAI_MEMORY (C macro), 10
uv_check_stop (C function), 23	UV_EAI_NODATA (C macro), 10
uv_check_t (C type), 23	UV_EAI_NONAME (C macro), 10
uv_close (C function), 18	UV_EAI_OVERFLOW (C macro), 10
uv_close_cb (C type), 17	UV_EAI_PROTOCOL (C macro), 10
uv_cond_broadcast (C function), 56	UV_EAI_SERVICE (C macro), 10
uv_cond_destroy (C function), 56	UV_EAI_SOCKTYPE (C macro), 10
uv_cond_init (C function), 56	UV_EALREADY (C macro), 10
uv_cond_signal (C function), 56	UV_EBADF (C macro), 10
uv_cond_t (C type), 54	UV_EBUSY (C macro), 10
uv_cond_timedwait (C function), 56	UV_ECANCELED (C macro), 10
uv_cond_wait (C function), 56	UV_ECHARSET (C macro), 10
uv_connect_cb (C type), 32	UV_ECONNABORTED (C macro), 10
uv_connect_t (C type), 31	UV_ECONNREFUSED (C macro), 10
	UV_ECONNRESET (C macro), 10

UV_EDESTADDRREQ (C macro), 10	uv_freeaddrinfo (C function), 53
UV_EEXIST (C macro), 10	uv_fs_access (C function), 49
UV_EFAULT (C macro), 10	uv_fs_chmod (C function), 49
UV_EFBIG (C macro), 10	uv_fs_chown (C function), 50
UV_EHOSTUNREACH (C macro), 10	uv_fs_close (C function), 48
UV_EINTR (C macro), 11	uv_fs_copyfile (C function), 49
UV_EINVAL (C macro), 11	uv_fs_event (C type), 43
UV_EIO (C macro), 11	uv_fs_event_cb (C type), 43
UV_EISCONN (C macro), 11	uv_fs_event_flags (C type), 43
UV_EISDIR (C macro), 11	uv_fs_event_getpath (C function), 44
UV_ELOOP (C macro), 11	uv_fs_event_init (C function), 44
UV_EMFILE (C macro), 11	uv_fs_event_start (C function), 44
UV_EMLINK (C macro), 12	uv_fs_event_stop (C function), 44
UV_EMSGSIZE (C macro), 11	uv_fs_event_t (C type), 43
UV_ENAMETOOLONG (C macro), 11	uv_fs_fchmod (C function), 49
UV_ENETDOWN (C macro), 11	uv_fs_fchown (C function), 50
UV_ENETUNREACH (C macro), 11	uv_fs_fdatasync (C function), 49
UV_ENFILE (C macro), 11	uv_fs_fstat (C function), 49
UV_ENOBUFS (C macro), 11	uv_fs_fsync (C function), 49
UV_ENODEV (C macro), 11	uv_fs_ftruncate (C function), 49
UV_ENOENT (C macro), 11	uv_fs_futime (C function), 49
UV_ENOMEM (C macro), 11	uv_fs_link (C function), 50
UV_ENONET (C macro), 11	uv_fs_lstat (C function), 49
UV_ENOPROTOOPT (C macro), 11	uv_fs_mkdir (C function), 48
UV_ENOSPC (C macro), 11	uv_fs_mkdtemp (C function), 48
UV_ENOSYS (C macro), 11	uv_fs_open (C function), 48
UV_ENOTCONN (C macro), 11	uv_fs_poll_cb (C type), 45
UV_ENOTDIR (C macro), 12	uv_fs_poll_getpath (C function), 45
UV_ENOTEMPTY (C macro), 12	uv_fs_poll_init (C function), 45
UV_ENOTSOCK (C macro), 12	uv_fs_poll_start (C function), 45
UV_ENOTSUP (C macro), 12	uv_fs_poll_stop (C function), 45
UV_ENXIO (C macro), 12	uv_fs_poll_t (C type), 45
UV_EOF (C macro), 12	uv_fs_read (C function), 48
UV_EPERM (C macro), 12	uv_fs_readlink (C function), 50
UV_EPIPE (C macro), 12	uv_fs_realpath (C function), 50
UV_EPROTO (C macro), 12	uv_fs_rename (C function), 49
UV_EPROTONOSUPPORT (C macro), 12	uv_fs_req_cleanup (C function), 48
UV_EPROTOTYPE (C macro), 12	uv_fs_rmdir (C function), 48
UV_ERANGE (C macro), 12	uv_fs_scandir (C function), 48
UV_EROFS (C macro), 12	uv_fs_scandir_next (C function), 48
uv_err_name (C function), 13	uv_fs_sendfile (C function), 49
UV_ESHUTDOWN (C macro), 12	uv_fs_stat (C function), 49
UV_ESPIPE (C macro), 12	uv_fs_symlink (C function), 50
UV_ESRCH (C macro), 12	uv_fs_t (C type), 46
UV_ETIMEDOUT (C macro), 12	uv_fs_t.fs_type (C member), 47
UV_ETXTBSY (C macro), 12	uv_fs_t.loop (C member), 47
UV_EXDEV (C macro), 12	uv_fs_t.path (C member), 47
uv_exepath (C function), 60	uv_fs_t.ptr (C member), 48
uv_exit_cb (C type), 28	uv_fs_t.result (C member), 47
uv_file (C type), 57	uv_fs_t.statbuf (C member), 47
uv_fileno (C function), 19	uv_fs_type (C type), 46
uv_free_cpu_info (C function), 59	uv_fs_unlink (C function), 48
uv_free_func (C type), 57	uv_fs_utime (C function), 49
uv_free_interface_addresses (C function), 59	uv_fs_write (C function), 48
aiointerface_addresses (C function), 57	215_wite (2 failed oil), 10

uv_loop_init (C function), 14
uv_loop_size (C function), 15
uv_loop_t (C type), 14
uv_loop_t.data (C member), 14
uv_malloc_func (C type), 57
uv_membership (C type), 39
uv_mutex_destroy (C function), 55
uv_mutex_init (C function), 55
uv_mutex_lock (C function), 55
uv_mutex_t (C type), 54
uv_mutex_trylock (C function), 55
uv_mutex_unlock (C function), 55
uv_now (C function), 15
uv_once (C function), 55
uv_once_t (C type), 54
uv_os_fd_t (C type), 57
uv_os_free_passwd (C function), 61
uv_os_get_passwd (C function), 61
uv_os_getenv (C function), 62
uv_os_gethostname (C function), 62
uv_os_homedir (C function), 60
uv_os_setenv (C function), 62
uv_os_sock_t (C type), 57
uv_os_tmpdir (C function), 60
uv_os_unsetenv (C function), 62
uv_passwd_t (C type), 58
uv_pipe_bind (C function), 36
uv_pipe_connect (C function), 36
uv_pipe_getpeername (C function), 37
uv_pipe_getsockname (C function), 36
uv_pipe_init (C function), 36
uv_pipe_open (C function), 36
uv_pipe_pending_count (C function), 37
uv_pipe_pending_instances (C function), 37
uv_pipe_pending_type (C function), 37
uv_pipe_t (C type), 36
uv_poll_cb (C type), 25
uv_poll_event (C type), 25
uv_poll_init (C function), 26
uv_poll_init_socket (C function), 26
uv_poll_start (C function), 26
uv_poll_stop (C function), 26
uv_poll_t (C type), 25
uv_prepare_cb (C type), 22
uv_prepare_init (C function), 22
uv_prepare_start (C function), 22
uv_prepare_stop (C function), 22
uv_prepare_t (C type), 22
uv_print_active_handles (C function), 61
uv_print_all_handles (C function), 61
uv_process_flags (C type), 28
uv_process_kill (C function), 31
uv_process_options_t (C type), 28
uv_process_options_t.args (C member), 30

uv_process_options_t.cwd (C member), 30	uv_signal_t (C type), 27
uv_process_options_t.env (C member), 30	uv_signal_t.signum (C member), 27
uv_process_options_t.exit_cb (C member), 30	uv_spawn (C function), 31
uv_process_options_t.file (C member), 30	uv_stat_t (C type), 46
uv_process_options_t.flags (C member), 30	uv_stdio_container_t (C type), 29
uv_process_options_t.nags (C member), 30	uv_stdio_container_t.data (C member), 30
uv_process_options_t.stdio (C member), 30	uv_stdio_container_t.tdata (C member), 30
uv_process_options_t.stdio_count (C member), 30	uv_stdio_flags (C type), 29
uv_process_options_t.uid (C member), 30	uv_stop (C function), 15
uv_process_options_t.uid (C member), 30 uv_process_t (C type), 28	uv_stream_set_blocking (C function), 34
uv_process_t.pid (C member), 29	uv_stream_t (C type), 31
uv_queue_work (C function), 52	uv_stream_t.write_queue_size (C member), 32
uv_read_cb (C type), 31	uv_strerror (C function), 13
uv_read_start (C function), 33	uv_tcp_bind (C function), 35
uv_read_stop (C function), 33	uv_tcp_connect (C function), 35
uv_realloc_func (C type), 57	uv_tcp_getpeername (C function), 35
uv_recv_buffer_size (C function), 19	uv_tcp_getsockname (C function), 35
uv_ref (C function), 18	uv_tcp_init (C function), 35
uv_replace_allocator (C function), 58	uv_tcp_init_ex (C function), 35
uv_req_size (C function), 20	uv_tcp_keepalive (C function), 35
uv_req_t (C type), 20	uv_tcp_nodelay (C function), 35
uv_req_t.data (C member), 20	uv_tcp_open (C function), 35
uv_req_t.type (C member), 20	uv_tcp_simultaneous_accepts (C function), 35
uv_resident_set_memory (C function), 59	uv_tcp_t (C type), 34
uv_run (C function), 15	uv_thread_cb (C type), 54
uv_run_mode (C type), 14	uv_thread_create (C function), 54
uv_rusage_t (C type), 57	uv_thread_equal (C function), 55
uv_rwlock_destroy (C function), 55	uv_thread_join (C function), 55
uv_rwlock_init (C function), 55	uv_thread_self (C function), 54
uv_rwlock_rdlock (C function), 55	uv_thread_t (C type), 54
uv_rwlock_rdunlock (C function), 55	uv_timer_again (C function), 21
uv_rwlock_t (C type), 54	uv_timer_cb (C type), 21
uv_rwlock_tryrdlock (C function), 55	uv_timer_get_repeat (C function), 22
uv_rwlock_trywrlock (C function), 55	uv_timer_init (C function), 21
uv_rwlock_wrlock (C function), 55	uv_timer_set_repeat (C function), 21
uv_rwlock_wrunlock (C function), 55	uv_timer_start (C function), 21
uv_sem_destroy (C function), 56	uv_timer_stop (C function), 21
uv_sem_init (C function), 56	uv_timer_t (C type), 21
uv_sem_post (C function), 56	uv_timespec_t (C type), 46
uv_sem_t (C type), 54	uv_translate_sys_error (C function), 13
uv_sem_trywait (C function), 56	uv_try_write (C function), 33
uv_sem_wait (C function), 56	uv_tty_get_winsize (C function), 38
uv_send_buffer_size (C function), 19	uv_tty_init (C function), 38
uv_set_process_title (C function), 59	uv_tty_mode_t (C type), 37
uv_setup_args (C function), 59	uv_tty_reset_mode (C function), 38
uv_shutdown (C function), 32	uv_tty_set_mode (C function), 38
uv_shutdown_cb (C type), 32	uv_tty_t (C type), 37
uv_shutdown_t (C type), 31	uv_udp_bind (C function), 40
uv_shutdown_t.handle (C member), 32	uv_udp_flags (C type), 39
uv_signal_cb (C type), 27	uv_udp_getsockname (C function), 41
uv_signal_init (C function), 27	uv_udp_init (C function), 40
uv_signal_start (C function), 27	uv_udp_init_ex (C function), 40
uv_signal_start_oneshot (C function), 28	uv_udp_open (C function), 40
uv_signal_stop (C function), 28	uv_udp_recv_cb (C type), 39
av_51811a1_5top (C function), 20	a aap_100 - (0 type), 3)

```
uv udp recv start (C function), 42
uv_udp_recv_stop (C function), 42
uv udp send (C function), 42
uv_udp_send_cb (C type), 39
uv_udp_send_t (C type), 39
uv udp send t.handle (C member), 40
uv udp set broadcast (C function), 41
uv_udp_set_membership (C function), 41
uv udp set multicast interface (C function), 41
uv_udp_set_multicast_loop (C function), 41
uv_udp_set_multicast_ttl (C function), 41
uv_udp_set_ttl (C function), 42
uv_udp_t (C type), 39
uv_udp_t.send_queue_count (C member), 40
uv_udp_t.send_queue_size (C member), 40
uv_udp_try_send (C function), 42
UV_UNKNOWN (C macro), 12
uv unref (C function), 18
uv_update_time (C function), 15
uv uptime (C function), 59
uv_version (C function), 13
UV VERSION HEX (C macro), 13
UV_VERSION_IS_RELEASE (C macro), 13
UV VERSION MAJOR (C macro), 13
UV_VERSION_MINOR (C macro), 13
UV VERSION PATCH (C macro), 13
uv_version_string (C function), 13
UV_VERSION_SUFFIX (C macro), 13
uv_walk (C function), 16
uv_walk_cb (C type), 14
uv_work_cb (C type), 51
uv_work_t (C type), 51
uv_work_t.loop (C member), 51
uv_write (C function), 33
uv write2 (C function), 33
uv_write_cb (C type), 32
uv write t (C type), 31
uv_write_t.handle (C member), 32
uv_write_t.send_handle (C member), 32
```