hessio 2015-04-01

Generated by Doxygen 1.8.5

Thu Jun 25 2015 15:03:22

Contents

1	Intro	oduction	1
	1.1	Introduction to the eventio/hessio libraries.	1
	1.2	Eventio format documentation	2
	1.3	Utility and test programs in the hessio module	2
2	Mod	dule Index	3
	2.1	Modules	3
3	Data	a Structure Index	5
	3.1	Data Structures	5
4	File	Index	9
	4.1	File List	9
5	Mod	dule Documentation	13
	5.1	The add_histograms program	13
		5.1.1 Detailed Description	13
		5.1.2 Function Documentation	13
		5.1.2.1 main	13
	5.2	The best_of program	14
		5.2.1 Detailed Description	15
	5.3	The fcat program	16
		5.3.1 Detailed Description	16
	5.4	The list_histogram program	17
		5.4.1 Detailed Description	17
		5.4.2 Function Documentation	17
		5.4.2.1 main	17
	5.5	The read_hess sensitivity comparison tool	18
		5.5.1 Detailed Description	18
	5.6	The check_trgmask program	19
		5.6.1 Detailed Description	19
	5.7	The extract_hess program	20
		5.7.1 Detailed Description	20

iv CONTENTS

	5.7.2	Function Documentation	20
		5.7.2.1 main	20
5.8	The ge	n_trgmask program	21
	5.8.1	Detailed Description	21
5.9	The me	erge_simtel program	22
	5.9.1	Detailed Description	23
	5.9.2	Function Documentation	23
		5.9.2.1 check_autoload_trgmask	23
	5.9.3	Variable Documentation	23
		5.9.3.1 map_to	23
		5.9.3.2 tel_idx	23
		5.9.3.3 tel_idx_out	23
5.10	The rea	ad_hess (aka read_simtel, read_cta) program	24
	5.10.1	Detailed Description	25
	5.10.2	Macro Definition Documentation	25
		5.10.2.1 CALIB_SCALE	25
		5.10.2.2 CALIB_SCALE	25
	5.10.3	Function Documentation	25
		5.10.3.1 main	25
		5.10.3.2 stop_signal_function	26
5.11	The rea	ad_hess_nr program	27
	5.11.1	Detailed Description	27
	5.11.2	Macro Definition Documentation	27
		5.11.2.1 CALIB_SCALE	27
	5.11.3	Function Documentation	27
		5.11.3.1 calibrate_pixel_amplitude	27
		5.11.3.2 main	28
		5.11.3.3 stop_signal_function	28
5.12	The hd	ata2hbook program (cvt2)	29
	5.12.1	Detailed Description	29
	5.12.2	Function Documentation	29
		5.12.2.1 main	29
5.13	The hd	ata2root program (cvt3)	30
	5.13.1	Detailed Description	30
Data	Structi	ure Documentation	31
6.1		ot Reference	31
6.2		et Reference	31
6.3		ntuple Struct Reference	31
0.0	6.3.1	Detailed Description	33
	0.5.1	Detailed Description	JJ

6

CONTENTS

6.3.2 Fie	eld Doci	umentation
6.3	3.2.1	acceptance
6.3	3.2.2	alt 33
6.3	3.2.3	alt_true
6.3	3.2.4	az 34
6.3	3.2.5	az_true
6.3	3.2.6	chi2_e
6.3	3.2.7	lg_e 34
6.3	3.2.8	lg_e_true
6.3	3.2.9	mdisp
6.3	3.2.10	mscrl
6.3	3.2.11	mscrw
6.3	3.2.12	n_fail
6.3	3.2.13	n_img
6.3	3.2.14	n_pix
6.3	3.2.15	n_trg
6.3	3.2.16	n_tsl0
6.3	3.2.17	primary
6.3	3.2.18	rcm
6.3	3.2.19	run
6.3	3.2.20	sig_e
6.3	3.2.21	sig_mscrl
6.3	3.2.22	sig_mscrw
6.3	3.2.23	sig_theta
6.3	3.2.24	sig_xmax
6.3	3.2.25	theta
6.3	3.2.26	tslope
6.3	3.2.27	tsphere
6.3	3.2.28	weight
6.3	3.2.29	xc
6.3	3.2.30	xc_true
6.3	3.2.31	xfirst_true
6.3	3.2.32	xmax
6.3	3.2.33	xmax_true
6.3	3.2.34	yc
6.3	3.2.35	yc_true
best_value	Struct	Reference
Binary_Inte	erface_(Chain Struct Reference
bunch Struc	ıct Refe	rence
6.6.1 Det	tailed D	Description

6.46.56.6

vi CONTENTS

6.7	compa	ct_bunch S	Struct Reference	40
	6.7.1	Detailed I	Description	40
6.8	Config_	_Binary_Ite	em_Interface Struct Reference	40
	6.8.1	Detailed I	Description	41
	6.8.2	Field Doo	cumentation	41
		6.8.2.1	copy_func	41
		6.8.2.2	delete_func	41
		6.8.2.3	elem_size	41
		6.8.2.4	io_item_type	42
		6.8.2.5	list_func	42
		6.8.2.6	new_func	42
		6.8.2.7	read_func	42
		6.8.2.8	readtext_func	42
		6.8.2.9	write_func	42
6.9	config_	specific_d	data Struct Reference	42
6.10	ConfigE	BlockStruc	ct Struct Reference	. 42
	6.10.1	Detailed I	Description	43
6.11	ConfigE	Boundary I	Union Reference	43
	6.11.1	Detailed I	Description	. 44
6.12	ConfigI	DataPointe	er Union Reference	44
	6.12.1	Detailed I	Description	44
6.13	ConfigI	ntern Stru	uct Reference	44
	6.13.1	Detailed I	Description	45
	6.13.2	Field Doo	cumentation	46
		6.13.2.1	bound	46
		6.13.2.2	elem_size	46
		6.13.2.3	itype	46
		6.13.2.4	lbound_hard	46
		6.13.2.5	lbound_soft	46
		6.13.2.6	locked	46
		6.13.2.7	ubound_hard	46
		6.13.2.8	ubound_soft	46
		6.13.2.9	values	46
6.14	Configl	temStruct	Struct Reference	47
	6.14.1	Detailed I	Description	48
	6.14.2	Field Doo	cumentation	48
		6.14.2.1	data	48
		6.14.2.2	flags	48
			function	
		6.14.2.4	initial	48

CONTENTS vii

		6.14.2.5 internal	48
		6.14.2.6 lbound	48
		6.14.2.7 name	48
		6.14.2.8 res1	49
		6.14.2.9 res2	49
		6.14.2.10 size	49
		6.14.2.11 type	49
		6.14.2.12 ubound	49
		6.14.2.13 validate	49
6.15	Config\	Values Struct Reference	49
	6.15.1	Detailed Description	50
	6.15.2	Field Documentation	50
		6.15.2.1 binary_config	50
		6.15.2.2 data_changed	50
		6.15.2.3 data_saved	50
		6.15.2.4 elem_size	50
		6.15.2.5 elements	50
		6.15.2.6 itype	50
		6.15.2.7 list_mod	51
		6.15.2.8 max_mod	51
		6.15.2.9 mod_flag	51
		6.15.2.10 name	51
		6.15.2.11 nmod	51
		6.15.2.12 section	51
6.16	ebias_c	cor_data Struct Reference	51
6.17	ev_reg	_chain Struct Reference	52
	6.17.1	Detailed Description	52
6.18	hess_a	Il_data_struct Struct Reference	52
	6.18.1	Detailed Description	53
6.19	hess_c	amera_organisation_struct Struct Reference	54
	6.19.1	Detailed Description	54
6.20	hess_c	amera_settings_struct Struct Reference	54
	6.20.1	Detailed Description	55
	6.20.2	Field Documentation	55
		6.20.2.1 mirror_area	55
6.21	hess_c	amera_software_setting_struct Struct Reference	56
	6.21.1	Detailed Description	56
	6.21.2	Field Documentation	56
		6.21.2.1 zero_sup_mode	56
6.22	hess_c	entral_event_data_struct Struct Reference	57

viii CONTENTS

	6.22.1 D	etailed De	escription				 	 	 	 	58
	6.22.2 F	ield Docui	mentation				 	 	 	 	58
	6	.22.2.1 t	eldata_patt	ern			 	 	 	 	58
	6	.22.2.2 t	eltrg_patter	n			 	 	 	 	58
	6	.22.2.3 t	eltrg_time				 	 	 	 	58
6.23	hess_eve	ent_data_s	struct Struct	Refere	nce .		 	 	 	 	58
	6.23.1 D	etailed De	escription				 	 	 	 	59
6.24	hess_lase	er_calib_d	lata_struct \$	Struct R	leferenc	e	 	 	 	 	59
	6.24.1 D	etailed De	escription				 	 	 	 	60
	6.24.2 F	ield Docui	mentation				 	 	 	 	60
	6	.24.2.1 c	alib				 	 	 	 	60
	6	.24.2.2 n	max_int_frac	o			 	 	 	 	60
	6	.24.2.3 n	max_pixtm_	frac .			 	 	 	 	60
6.25	hess_mc_	_event_str	ruct Struct F	Referen	ce		 	 	 	 	61
	6.25.1 D	etailed De	escription				 	 	 	 	61
	6.25.2 F	ield Docui	mentation				 	 	 	 	62
	6	.25.2.1 a	aweight				 	 	 	 	62
6.26	hess_mc	_pe_list S	truct Refere	ence .			 	 	 	 	62
	6.26.1 D	etailed De	escription				 	 	 	 	62
6.27	hess_mc_	_pe_sum_	_struct Struc	ct Refer	ence .		 	 	 	 	62
	6.27.1 D	etailed De	escription				 	 	 	 	63
	6.27.2 F	ield Docui	mentation				 	 	 	 	63
	6	.27.2.1 p	hotons_atn	n_qe .			 	 	 	 	63
6.28	hess_mc_	_photons	Struct Refe	rence			 	 	 	 	63
			escription								64
6.29	hess_mc	_run_head	der_struct S	Struct R	eferenc	е	 	 	 	 	64
	6.29.1 D	etailed De	escription				 	 	 	 	65
	6.29.2 F	ield Docui	mentation				 	 	 	 	66
	6	.29.2.1 s	shower_pro	g_id .			 	 	 	 	66
6.30			profile_struc								66
	6.30.1 D	etailed De	escription				 	 	 	 	66
	6.30.2 F	ield Docui	mentation				 	 	 	 	66
	6	.30.2.1 id	d				 	 	 	 	66
6.31	hess_mc_	_shower_s	struct Struc	t Refere	ence .		 	 	 	 	67
	6.31.1 D	etailed De	escription				 	 	 	 	68
	6.31.2 F		mentation								68
	6	.31.2.1 p	orimary_id				 	 	 	 	68
			max								68
6.32	hess_pixe	el_calibrat	ed_struct S	truct Re	eference	e	 	 	 	 	68
6.33	hess_pixe	el_disable	d_struct Str	uct Ref	erence		 	 	 	 	69

CONTENTS

	6.33.1 Detailed Description	69
6.34	hess_pixel_list Struct Reference	69
	6.34.1 Detailed Description	70
	6.34.2 Field Documentation	70
	6.34.2.1 code	70
6.35	hess_pixel_setting_struct Struct Reference	70
	6.35.1 Detailed Description	71
6.36	hess_pixel_timing_struct Struct Reference	71
	6.36.1 Field Documentation	72
	6.36.1.1 granularity	72
	6.36.1.2 pulse_sum_glob	72
	6.36.1.3 pulse_sum_loc	72
	6.36.1.4 threshold	72
	6.36.1.5 time_level	72
	6.36.1.6 timval	72
6.37	hess_pointing_correction_struct Struct Reference	73
	6.37.1 Detailed Description	73
6.38	hess_run_end_mc_statistics_struct Struct Reference	73
	6.38.1 Detailed Description	73
6.39	hess_run_end_statistics_struct Struct Reference	73
	6.39.1 Detailed Description	74
6.40	hess_run_header_struct Struct Reference	74
	6.40.1 Detailed Description	75
	6.40.2 Field Documentation	75
	6.40.2.1 conv_depth	75
	6.40.2.2 conv_ref_pos	75
	6.40.2.3 direction	75
	6.40.2.4 offset_fov	75
	6.40.2.5 reverse_flag	76
	6.40.2.6 run	76
	6.40.2.7 run_type	76
	6.40.2.8 tel_pos	76
	6.40.2.9 tracking_mode	76
6.41	hess_shower_parameter Struct Reference	76
	6.41.1 Detailed Description	77
6.42	hess_tel_event_adc_struct Struct Reference	77
	6.42.1 Detailed Description	78
6.43	hess_tel_event_data_struct Struct Reference	79
	6.43.1 Detailed Description	80
6.44	hess_tel_image_struct Struct Reference	80

CONTENTS

	6.44.1	Detailed Description	82
	6.44.2	Field Documentation	82
		6.44.2.1 l	82
		6.44.2.2 num_hot	82
		6.44.2.3 phi	82
		6.44.2.4 tm_slope	82
		6.44.2.5 x	82
6.45	hess_te	el_monitor_struct Struct Reference	82
	6.45.1	Detailed Description	85
	6.45.2	Field Documentation	85
		6.45.2.1 coinc_count	85
		6.45.2.2 current	85
		6.45.2.3 drawer_temp	85
6.46	hess_ti	me_struct Struct Reference	85
	6.46.1	Detailed Description	86
6.47	hess_tr	acking_event_data_struct Struct Reference	86
	6.47.1	Detailed Description	86
6.48	hess_tr	racking_setup_struct Struct Reference	86
	6.48.1	Detailed Description	87
	6.48.2	Field Documentation	87
		6.48.2.1 range_low_az	87
6.49	histogra	am Struct Reference	87
	6.49.1	Detailed Description	89
	6.49.2	Field Documentation	89
		6.49.2.1 entries	89
		6.49.2.2 next	89
		6.49.2.3 overflow	89
		6.49.2.4 overflow_2d	89
		6.49.2.5 tentries	89
		6.49.2.6 type	89
		6.49.2.7 underflow	90
		6.49.2.8 underflow_2d	90
6.50	Histogr	am_Extension Struct Reference	90
	6.50.1	Detailed Description	90
	6.50.2	Field Documentation	91
		6.50.2.1 ddata	91
6.51	Histogr	am_Parameters Union Reference	91
	6.51.1	Detailed Description	91
	6.51.2	Field Documentation	92
		6.51.2.1 integer	92

CONTENTS xi

	6.51.2.2 inverse_binwidth	92
	6.51.2.3 real	92
6.52	history_struct Struct Reference	92
	6.52.1 Detailed Description	93
6.53	histstat Struct Reference	93
	6.53.1 Detailed Description	93
6.54	incpath Struct Reference	93
	6.54.1 Detailed Description	94
6.55	linked_string Struct Reference	94
	6.55.1 Detailed Description	94
6.56	map_tel_struct Struct Reference	94
	6.56.1 Detailed Description	95
6.57	moments Struct Reference	95
	6.57.1 Detailed Description	96
6.58	momstat Struct Reference	96
	6.58.1 Detailed Description	96
6.59	next_file_struct Struct Reference	96
6.60	photo_electron Struct Reference	97
	6.60.1 Detailed Description	97
	6.60.2 Field Documentation	97
	6.60.2.1 atime	97
	6.60.2.2 lambda	97
	6.60.2.3 pixel	97
6.61	range_list_struct Struct Reference	98
6.62	shower_extra_parameters Struct Reference	98
	6.62.1 Detailed Description	98
	6.62.2 Field Documentation	99
	6.62.2.1 fparam	99
	6.62.2.2 id	99
	6.62.2.3 iparam	99
	6.62.2.4 is_set	99
	6.62.2.5 nfparam	99
	6.62.2.6 niparam	99
	6.62.2.7 weight	99
6.63	tel_type_param Struct Reference	99
6.64	telescope_list Struct Reference	100
6.65	trgmask_entry Struct Reference	100
6.66	trgmask_hash_set Struct Reference	101
6.67	trgmask_set Struct Reference	101
6.68	user_parameters Struct Reference	02

xii CONTENTS

		6.68.1	Field Documentation
			6.68.1.1 calib_scale
			6.68.1.2 camera_clipping_deg
			6.68.1.3 clip_amp
			6.68.1.4 d_integ_param
			6.68.1.5 d_sp_idx
			6.68.1.6 impact_range
			6.68.1.7 integ_no_rescale
			6.68.1.8 integ_param
			6.68.1.9 integrator
			6.68.1.10 min_amp
			6.68.1.11 min_pix
			6.68.1.12 min_tel_img
			6.68.1.13 r_nb
			6.68.1.14 tailcut_low
			6.68.1.15 theta_escale
			6.68.1.16 user_flags
	6.69	warn_s	pecific_data Struct Reference
		6.69.1	Detailed Description
		6.69.2	Field Documentation
			6.69.2.1 logfname
7	File I	Docume	entation 107
•	7.1		stograms.c File Reference
	7.1	7.1.1	Detailed Description
	7 2		f.c File Reference
	7.2	7.2.1	Detailed Description
		7.2.2	Function Documentation
		1.2.2	7.2.2.1 heighx
			7.2.2.2 init_atmprof
			7.2.2.3 interp
			7.2.2.4 refidx
			7.2.2.5 rhofx
			7.2.2.6 rpol
			7.2.2.7 thickx
	7.3	basic r	ntuple.h File Reference
		7.3.1	Detailed Description
		7.3.2	Function Documentation
			/.3.2.1 list ntuple
	7.4	best of	7.3.2.1 list_ntuple

CONTENTS xiii

	7.4.1	Detailed	Description	 	 	 	 	 	 	. 115
7.5	camera	a_image.c	File Reference	 	 	 	 	 	 	. 115
	7.5.1	Detailed	Description	 	 	 	 	 	 	. 116
	7.5.2	Function	Documentation	 	 	 	 	 	 	. 116
		7.5.2.1	find_neighbours .	 	 	 	 	 	 	. 116
		7.5.2.2	hesscam_ps_plot	 	 	 	 	 	 	. 116
		7.5.2.3	print_pix_col	 	 	 	 	 	 	. 117
	7.5.3	Variable I	Documentation	 	 	 	 	 	 	. 117
		7.5.3.1	alt_az_arrow	 	 	 	 	 	 	. 117
		7.5.3.2	ps_begin_page1 .	 	 	 	 	 	 	. 118
		7.5.3.3	ps_begin_page2 .	 	 	 	 	 	 	. 118
		7.5.3.4	ps_end_page	 	 	 	 	 	 	. 118
		7.5.3.5	ps_head1	 	 	 	 	 	 	. 118
		7.5.3.6	ps_trailer	 	 	 	 	 	 	. 118
7.6	check_	trgmask.c	File Reference	 	 	 	 	 	 	. 118
	7.6.1	Detailed	Description	 	 	 	 	 	 	. 119
7.7	current	.c File Ref	erence	 	 	 	 	 	 	. 119
	7.7.1	Detailed	Description	 	 	 	 	 	 	. 120
	7.7.2	Function	Documentation	 	 	 	 	 	 	. 121
		7.7.2.1	current_localtime .	 	 	 	 	 	 	. 121
		7.7.2.2	current_time	 	 	 	 	 	 	. 121
		7.7.2.3	mkgmtime	 	 	 	 	 	 	. 121
		7.7.2.4	reset_local_offset	 	 	 	 	 	 	. 121
		7.7.2.5	set_current_offset	 	 	 	 	 	 	. 121
		7.7.2.6	set_local_offset .	 	 	 	 	 	 	. 122
		7.7.2.7	time_string	 	 	 	 	 	 	. 122
7.8	current	.h File Ref	erence	 	 	 	 	 	 	. 122
	7.8.1	Detailed	Description	 	 	 	 	 	 	. 123
	7.8.2	Function	Documentation	 	 	 	 	 	 	. 123
		7.8.2.1	current_localtime .	 	 	 	 	 	 	. 123
		7.8.2.2	current_time	 	 	 	 	 	 	. 124
		7.8.2.3	mkgmtime	 	 	 	 	 	 	. 124
		7.8.2.4	reset_local_offset	 	 	 	 	 	 	. 124
		7.8.2.5	set_current_offset	 	 	 	 	 	 	. 124
		7.8.2.6	set_local_offset .	 	 	 	 	 	 	. 125
		7.8.2.7	time_string	 	 	 	 	 	 	. 125
7.9	cvt2.c l	File Refere	ence	 	 	 	 	 	 	. 125
	7.9.1	Detailed	Description	 	 	 	 	 	 	. 126
7.10	cvt3.cc	File Refer	ence	 	 	 	 	 	 	. 126
	7.10.1	Detailed	Description	 	 	 	 	 	 	. 127

XIV

7.11	dhsort.	c File Refe	erence			 	 	 	 	 		127
	7.11.1	Detailed	Description			 	 	 	 	 		128
	7.11.2	Function	Documentati	on		 	 	 	 	 		128
		7.11.2.1	dhsort			 	 	 	 	 		128
7.12	eventio	_registry.c	: File Referen	ce		 	 	 	 	 		128
	7.12.1	Detailed	Description			 	 	 	 	 		129
	7.12.2	Function	Documentati	on		 	 	 	 	 		129
		7.12.2.1	find_ev_reg	_std		 	 	 	 	 		129
		7.12.2.2	read_eventi	o_registr	y	 	 	 	 	 		130
		7.12.2.3	set_ev_reg_	_std		 	 	 	 	 		130
7.13	eventio	_registry.h	File Referer	ice		 	 	 	 	 		130
	7.13.1	Detailed	Description			 	 	 	 	 		131
	7.13.2	Function	Documentati	on		 	 	 	 	 		131
		7.13.2.1	find_ev_reg	_std		 	 	 	 	 		131
		7.13.2.2	read_eventi	o_registr	y	 	 	 	 	 		131
		7.13.2.3	set_ev_reg_	_std		 	 	 	 	 		132
7.14	extract	_hess.c Fil	le Reference			 	 	 	 	 		132
	7.14.1	Detailed	Description			 	 	 	 	 		132
7.15	fcat.c F	ile Refere	nce			 	 	 	 	 		133
	7.15.1	Detailed	Description			 	 	 	 	 		133
7.16	fileope	n.c File Re	ference			 	 	 	 	 		133
	7.16.1	Detailed	Description			 	 	 	 	 		135
	7.16.2	Function	Documentati	on		 	 	 	 	 		136
		7.16.2.1	addexepath			 	 	 	 	 		136
		7.16.2.2	addpath .			 	 	 	 	 		136
		7.16.2.3	cmp_popen			 	 	 	 	 		136
		7.16.2.4	disable_per	missive_	pipes	 	 	 	 	 		136
		7.16.2.5	enable_peri	missive_	oipes	 	 	 	 	 		136
		7.16.2.6	exe_popen			 	 	 	 	 		136
		7.16.2.7	fileclose .			 	 	 	 	 		137
		7.16.2.8	fileopen			 	 	 	 	 		137
		7.16.2.9	freeexepath			 	 	 	 	 		137
		7.16.2.10	freepath .			 	 	 	 	 		137
		7.16.2.11	initpath			 	 	 	 	 		137
		7.16.2.12	listpath			 	 	 	 	 		137
			set_permiss									
		7.16.2.14	uri_popen			 	 	 	 	 		137
	7.16.3	Variable I	Documentation	on		 	 	 	 	 		138
		7.16.3.1	permissive_	pipes .		 	 	 	 	 		138
		7.16.3.2	root_exe_pa	ath		 	 	 	 	 		138

CONTENTS xv

		7.16.3.3 root_path	8
7.17	fileoper	.h File Reference	8
	7.17.1	Detailed Description	9
	7.17.2	Function Documentation	9
		7.17.2.1 addexepath	19
		7.17.2.2 addpath	9
		7.17.2.3 disable_permissive_pipes	19
		7.17.2.4 enable_permissive_pipes	19
		7.17.2.5 fileclose	9
		7.17.2.6 fileopen	0
		7.17.2.7 initpath	-0
		7.17.2.8 listpath	-0
		7.17.2.9 set_permissive_pipes	-0
7.18	gen_loc	kup.c File Reference	-0
	7.18.1	Detailed Description	2
	7.18.2	Function Documentation	2
		7.18.2.1 fill_gaps	2
7.19	gen_trg	mask.c File Reference	3
	7.19.1	Detailed Description	3
7.20	hconfig	c File Reference	3
	7.20.1	Detailed Description	6
	7.20.2	Function Documentation	8
		7.20.2.1 build_config	8
		7.20.2.2 find_config_item	8
		7.20.2.3 get_config_filename	8
		7.20.2.4 get_config_preprocessor	9
		7.20.2.5 init_config	0
		7.20.2.6 read_config_lines	0
		7.20.2.7 read_config_status	0
		7.20.2.8 reconfig	1
		7.20.2.9 reload_config	1
		7.20.2.10 set_config_filename	1
		7.20.2.11 set_config_history	1
		7.20.2.12 set_config_preprocessor	2
		7.20.2.13 set_config_stack	2
	7.20.3	Variable Documentation	2
		7.20.3.1 config_defaults	2
		7.20.3.2 default_config	2
		7.20.3.3 first_config_block	3
7.21	hconfig	h File Reference	3

xvi CONTENTS

7.21.1	Detailed Description							
7.21.2	Macro Definition Documentation							
	7.21.2.1 _STR							
	7.21.2.2 CFG_MUTEX							
7.21.3	Function Documentation							
	7.21.3.1 abbrev							
	7.21.3.2 build_config							
	7.21.3.3 config_binary_convert_data							
	7.21.3.4 config_binary_read_text							
	7.21.3.5 config_binary_text_length							
	7.21.3.6 config_binary_write_name							
	7.21.3.7 config_binary_write_text							
	7.21.3.8 find_config_item							
	7.21.3.9 get_config_filename							
	7.21.3.10 get_config_preprocessor							
	7.21.3.11 getword							
	7.21.3.12 init_config							
	7.21.3.13 read_config_lines							
	7.21.3.14 read_config_status							
	7.21.3.15 reconfig							
	7.21.3.16 reload_config							
	7.21.3.17 set_config_filename							
	7.21.3.18 set_config_history							
	7.21.3.19 set_config_preprocessor							
	7.21.3.20 set_config_stack							
hessio_	doc.h File Reference							
7.22.1	Detailed Description							
histogra	am.c File Reference							
7.23.1	Detailed Description							
7.23.2	Macro Definition Documentation							
	7.23.2.1 HistOutput							
7.23.3	Function Documentation							
	7.23.3.1 add_histogram							
	7.23.3.2 alloc_2d_int_histogram							
	7.23.3.3 alloc_2d_real_histogram							
	7.23.3.4 alloc_int_histogram							
	7.23.3.5 alloc_real_histogram							
	7.23.3.6 allocate_histogram							
	7.23.3.7 book_1d_histogram							
	7.23.3.8 book_histogram							
	7.21.3 7.21.3 hessio_ 7.22.1 histogra 7.23.1 7.23.2							

CONTENTS xvii

		7.23.3.9 book_int_histogram
		7.23.3.10 clear_histogram
		7.23.3.11 describe_histogram
		7.23.3.12 display_2d_histogram
		7.23.3.13 display_all_histograms
		7.23.3.14 display_histogram
		7.23.3.15 fast_stat_histogram
		7.23.3.16 fill_2d_int_histogram
		7.23.3.17 fill_2d_real_histogram
		7.23.3.18 fill_2d_weighted_histogram
		7.23.3.19 fill_histogram
		7.23.3.20 fill_histogram_by_ident
		7.23.3.21 fill_int_histogram
		7.23.3.22 fill_real_histogram
		7.23.3.23 fill_weighted_histogram
		7.23.3.24 free_all_histograms
		7.23.3.25 free_histo_contents
		7.23.3.26 free_histogram
		7.23.3.27 get_first_histogram
		7.23.3.28 get_histogram_by_ident
		7.23.3.29 histogram_hashing
		7.23.3.30 histogram_matching
		7.23.3.31 histogram_to_lookup
		7.23.3.32 list_histograms
		7.23.3.33 locate_histogram_fraction
		7.23.3.34 lookup_int
		7.23.3.35 lookup_real
		7.23.3.36 print_histogram
		7.23.3.37 set_first_histogram
		7.23.3.38 sort_histograms
		7.23.3.39 stat_histogram
		7.23.3.40 unlink_histogram
	7.23.4	Variable Documentation
		7.23.4.1 primetab
7.24	histogra	am.h File Reference
	7.24.1	Detailed Description
	7.24.2	Typedef Documentation
		7.24.2.1 HISTCOUNT
		7.24.2.2 HISTVALUE_REAL
	7.24.3	Function Documentation

xviii CONTENTS

7.24.3.1 add_histogram
7.24.3.2 alloc_2d_int_histogram
7.24.3.3 alloc_2d_real_histogram
7.24.3.4 alloc_int_histogram
7.24.3.5 alloc_moments
7.24.3.6 alloc_real_histogram
7.24.3.7 allocate_histogram
7.24.3.8 book_1d_histogram
7.24.3.9 book_histogram
7.24.3.10 book_int_histogram
7.24.3.11 clear_histogram
7.24.3.12 clear_moments
7.24.3.13 describe_histogram
7.24.3.14 display_all_histograms
7.24.3.15 display_histogram
7.24.3.16 fast_stat_histogram
7.24.3.17 fill_2d_int_histogram
7.24.3.18 fill_2d_real_histogram
7.24.3.19 fill_2d_weighted_histogram
7.24.3.20 fill_histogram
7.24.3.21 fill_histogram_by_ident
7.24.3.22 fill_int_histogram
7.24.3.23 fill_mean
7.24.3.24 fill_mean_and_sigma
7.24.3.25 fill_moments
7.24.3.26 fill_real_histogram
7.24.3.27 fill_real_mean
7.24.3.28 fill_real_mean_and_sigma
7.24.3.29 fill_real_moments
7.24.3.30 fill_weighted_histogram
7.24.3.31 free_all_histograms
7.24.3.32 free_histogram
7.24.3.33 free_moments
7.24.3.34 get_first_histogram
7.24.3.35 get_histogram_by_ident
7.24.3.36 histogram_hashing
7.24.3.37 histogram_matching
7.24.3.38 histogram_to_lookup
7.24.3.39 list_histograms
7.24.3.40 locate_histogram_fraction

CONTENTS xix

	7.24.3.41 lookup_int
	7.24.3.42 lookup_real
	7.24.3.43 print_histogram
	7.24.3.44 set_first_histogram
	7.24.3.45 sort_histograms
	7.24.3.46 stat_histogram
	7.24.3.47 stat_moments
	7.24.3.48 unlink_histogram
7.25 history.	h File Reference
7.25.1	Detailed Description
7.26 initial.h	File Reference
7.26.1	Detailed Description
7.27 io_hes	s.c File Reference
7.27.1	Detailed Description
7.27.2	Function Documentation
	7.27.2.1 check_hessio_max
	7.27.2.2 find_tel_idx
	7.27.2.3 print_hess_pixcalib
	7.27.2.4 read_hess_pixcalib
	7.27.2.5 set_tel_idx
	7.27.2.6 set_tel_idx_ref
	7.27.2.7 write_hess_event
	7.27.2.8 write_hess_laser_calib
	7.27.2.9 write_hess_mc_event
	7.27.2.10 write_hess_mc_pe_sum
	7.27.2.11 write_hess_mc_shower
	7.27.2.12 write_hess_pixcalib
	7.27.2.13 write_hess_run_stat
	7.27.2.14 write_hess_shower
	7.27.2.15 write_hess_tel_monitor
	7.27.2.16 write_hess_teladc_samples
	7.27.2.17 write_hess_teladc_sums
	7.27.2.18 write_hess_televent
7.28 io_hes	s.h File Reference
7.28.1	Detailed Description
7.28.2	Macro Definition Documentation
	7.28.2.1 H_CHECK_MAX
	7.28.2.2 H_MAX_FSHAPE
	7.28.2.3 H_MAX_HOTPIX
	7.28.2.4 H_MAX_PIX_TIMES

CONTENTS

	7.28.2.5 H_MAX_PROFILE	19
	7.28.2.6 H_MAX_SLICES	19
	7.28.2.7 HI_GAIN	19
	7.28.2.8 LO_GAIN	19
	7.28.2.9 PIX_TIME_PEAKPOS_TYPE	19
	7.28.2.10 PIX_TIME_STARTPOS_ABS_TYPE	19
	7.28.2.11 PIX_TIME_STARTPOS_REL_TYPE	19
	7.28.2.12 PIX_TIME_WIDTH_ABS_TYPE	19
	7.28.2.13 PIX_TIME_WIDTH_REL_TYPE	20
7.28.3	Function Documentation	20
	7.28.3.1 check_hessio_max	20
io_histo	ogram.c File Reference	20
7.29.1	Detailed Description	21
7.29.2	Function Documentation	21
	7.29.2.1 print_histograms	21
	7.29.2.2 read_histograms	21
	7.29.2.3 read_histograms_x	22
	7.29.2.4 write_histograms	22
io_histo	ogram.h File Reference	22
7.30.1	Detailed Description	23
7.30.2	Function Documentation	24
	7.30.2.1 print_histograms	24
	7.30.2.2 read_histograms	24
	7.30.2.3 read_histograms_x	24
	7.30.2.4 write_histograms	25
io_histo	ory.c File Reference	25
7.31.1	Detailed Description	26
7.31.2	Variable Documentation	27
	7.31.2.1 cmdline	27
	7.31.2.2 cmdtime	27
	7.31.2.3 configs	27
io_histo	ory.h File Reference	27
7.32.1	Detailed Description	28
io_simt	el.c File Reference	28
7.33.1	Detailed Description	30
7.33.2	Function Documentation	31
	7.33.2.1 begin_read_tel_array	31
	7.33.2.2 begin_write_tel_array	31
	7.33.2.3 clear_shower_extra_parameters	31
	7.33.2.4 end_read_tel_array	31
	io_histo 7.29.1 7.29.2 io_histo 7.30.1 7.30.2 io_histo 7.31.1 7.31.2 io_histo 7.32.1 io_simt 7.33.1	7.28.2.6 H_MAX_SLICES 2 7.28.2.7 HI_GAIN 2 7.28.2.8 LO_GAIN 2 7.28.2.9 PIX_TIME_PEAKPOS_TYPE 2 7.28.2.10 PIX_TIME_STARTPOS_ABS_TYPE 2 7.28.2.11 PIX_TIME_WIDTH_ABS_TYPE 2 7.28.2.13 PIX_TIME_WIDTH_ABS_TYPE 2 7.28.3 Function Documentation 22 7.28.3.1 check_hessio_max 22 io_histogram.c File Reference 22 7.29.1 pention Documentation 22 7.29.2.1 print_histograms 22 7.29.2.2 read_histograms 22 7.29.2.3 read_histograms 22 7.29.2.4 write_histograms 22 7.30.1 Detailed Description 22 7.30.2 Function Documentation 22 7.30.2 Function Documentation 22 7.30.2.1 print_histograms 22 7.30.2.2 read_histograms 22 7.30.2.3 read_histograms 22 7.30.2.4 write_histograms 2

CONTENTS xxi

		7.33.2.5 end_write_tel_array
		7.33.2.6 init_shower_extra_parameters
		7.33.2.7 print_camera_layout
		7.33.2.8 print_photo_electrons
		7.33.2.9 print_tel_block
		7.33.2.10 print_tel_offset
		7.33.2.11 print_tel_photons
		7.33.2.12 print_tel_pos
		7.33.2.13 read_camera_layout
		7.33.2.14 read_input_lines
		7.33.2.15 read_photo_electrons
		7.33.2.16 read_shower_longitudinal
		7.33.2.17 read_tel_array_end
		7.33.2.18 read_tel_array_head
		7.33.2.19 read_tel_block
		7.33.2.20 read_tel_offset
		7.33.2.21 read_tel_offset_w
		7.33.2.22 read_tel_photons
		7.33.2.23 read_tel_pos
		7.33.2.24 write_camera_layout
		7.33.2.25 write_input_lines
		7.33.2.26 write_photo_electrons
		7.33.2.27 write_shower_longitudinal
		7.33.2.28 write_tel_array_end
		7.33.2.29 write_tel_array_head
		7.33.2.30 write_tel_block
		7.33.2.31 write_tel_compact_photons
		7.33.2.32 write_tel_offset
		7.33.2.33 write_tel_offset_w
		7.33.2.34 write_tel_photons
		7.33.2.35 write_tel_pos
	7.33.3	Variable Documentation
		7.33.3.1 private_shower_extra_parameters
7.34	io_trgm	nask.c File Reference
	7.34.1	Detailed Description
	7.34.2	Function Documentation
		7.34.2.1 find_trgmask
		7.34.2.2 print_hashed_trgmasks
		7.34.2.3 trgmask_fill_hashed
		7.34.2.4 trgmask_scan_log

xxii CONTENTS

7.35	io_trgm	nask.h File I	Reference	 	 . 245
	7.35.1	Detailed D	escription	 	 . 246
	7.35.2	Macro Def	inition Documentation	 	 . 246
		7.35.2.1	IO_TYPE_HESS_XTRGMASK	 	 . 246
	7.35.3	Function D	Occumentation	 	 . 246
		7.35.3.1	find_trgmask	 	 . 246
		7.35.3.2	print_hashed_trgmasks	 	 . 246
		7.35.3.3	trgmask_fill_hashed	 	 . 246
		7.35.3.4	trgmask_scan_log	 	 . 247
7.36	list_his	tograms.c F	ile Reference	 	 . 247
	7.36.1	Detailed D	escription	 	 . 247
7.37	mc_tel.	h File Refe	rence	 	 . 248
	7.37.1	Detailed D	escription	 	 . 251
	7.37.2	Function D	Occumentation	 	 . 251
		7.37.2.1	begin_read_tel_array	 	 . 251
		7.37.2.2	begin_write_tel_array	 	 . 252
		7.37.2.3	clear_shower_extra_parameters	 	 . 252
		7.37.2.4	end_read_tel_array	 	 . 252
		7.37.2.5	end_write_tel_array	 	 . 252
		7.37.2.6	init_shower_extra_parameters	 	 . 253
		7.37.2.7	print_camera_layout	 	 . 254
		7.37.2.8	print_photo_electrons	 	 . 254
		7.37.2.9	print_tel_block	 	 . 254
		7.37.2.10	print_tel_offset	 	 . 254
		7.37.2.11	print_tel_photons	 	 . 255
		7.37.2.12	print_tel_pos	 	 . 255
		7.37.2.13	read_camera_layout	 	 . 255
		7.37.2.14	read_input_lines	 	 . 256
		7.37.2.15	read_photo_electrons	 	 . 256
		7.37.2.16	read_shower_longitudinal	 	 . 256
		7.37.2.17	read_tel_array_end	 	 . 257
		7.37.2.18	read_tel_array_head	 	 . 257
		7.37.2.19	read_tel_block	 	 . 257
		7.37.2.20	read_tel_offset	 	 . 258
		7.37.2.21	read_tel_offset_w	 	 . 258
		7.37.2.22	read_tel_photons	 	 . 258
		7.37.2.23	read_tel_pos	 	 . 259
		7.37.2.24	write_camera_layout	 	 . 259
		7.37.2.25	write_input_lines	 	 . 259
		7.37.2.26	write_photo_electrons	 	 . 260

CONTENTS xxiii

7.37.2.27 write_shower_longitudinal	. 260
7.37.2.28 write_tel_array_end	. 260
7.37.2.29 write_tel_array_head	. 261
7.37.2.30 write_tel_block	. 261
7.37.2.31 write_tel_compact_photons	. 261
7.37.2.32 write_tel_offset	. 262
7.37.2.33 write_tel_offset_w	. 262
7.37.2.34 write_tel_photons	. 263
7.37.2.35 write_tel_pos	. 263
7.38 merge_simtel.c File Reference	. 263
7.38.1 Detailed Description	. 265
7.39 moments.c File Reference	. 266
7.39.1 Detailed Description	. 267
7.39.2 Function Documentation	. 267
7.39.2.1 alloc_moments	. 267
7.39.2.2 clear_moments	. 268
7.39.2.3 fill_mean	. 268
7.39.2.4 fill_mean_and_sigma	. 268
7.39.2.5 fill_moments	. 268
7.39.2.6 fill_real_mean	. 268
7.39.2.7 fill_real_mean_and_sigma	. 269
7.39.2.8 fill_real_moments	. 269
7.39.2.9 free_moments	. 269
7.39.2.10 stat_moments	. 269
7.40 read_hess.c File Reference	. 270
7.40.1 Detailed Description	. 271
7.41 read_hess_nr.c File Reference	. 274
7.41.1 Detailed Description	. 275
7.42 rec_tools.h File Reference	. 276
7.42.1 Detailed Description	. 277
7.42.2 Function Documentation	. 277
7.42.2.1 angle_between	. 277
7.42.2.2 angles_to_offset	. 277
7.42.2.3 cam_to_ref	. 277
7.42.2.4 get_shower_trans_matrix	. 278
7.42.2.5 intersect_lines	. 278
7.42.2.6 line_point_distance	. 278
7.42.2.7 offset_to_angles	. 278
7.42.2.8 shower_geometric_reconstruction	. 278
7.43 reconstruct.c File Reference	. 279

xxiv CONTENTS

	7.43.1	Detailed Description							
	7.43.2	Macro Definition Documentation							
		7.43.2.1 CALIB_SCALE							
	7.43.3	Function Documentation							
		7.43.3.1 calibrate_amplitude							
		7.43.3.2 calibrate_pixel_amplitude							
		7.43.3.3 clean_image_tailcut							
		7.43.3.4 find_neighbours							
		7.43.3.5 global_peak_integration							
		7.43.3.6 image_reconstruct							
		7.43.3.7 local_peak_integration							
		7.43.3.8 nb_peak_integration							
		7.43.3.9 pixel_integration							
		7.43.3.10 pixel_timing_analysis							
		7.43.3.11 reconstruct							
		7.43.3.12 second_moments							
		7.43.3.13 select_calibration_channel							
		7.43.3.14 set_disabled_pixels							
		7.43.3.15 simple_integration							
7.44	rh_sens	s_comp.cc File Reference							
	7.44.1	Detailed Description							
7.45	rndm2.	h File Reference							
	7.45.1	Detailed Description							
7.46	straux.	File Reference							
	7.46.1	Detailed Description							
	7.46.2	Function Documentation							
		7.46.2.1 abbrev							
		7.46.2.2 getword							
		7.46.2.3 stricmp							
7.47	straux.h	n File Reference							
	7.47.1	Detailed Description							
	7.47.2	Function Documentation							
		7.47.2.1 abbrev							
		7.47.2.2 getword							
		7.47.2.3 stricmp							
7.48	tohbool	k.c File Reference							
	7.48.1	Detailed Description							
7.49	toroot.c	cc File Reference							
	7.49.1	Detailed Description							
	7.49.2	Function Documentation							

CONTENTS xxv

		7.49.2.1	convert_histograms_to_root	296
		7.49.2.2	histogram_to_root	297
7.50	user_a	nalysis.c F	ile Reference	297
	7.50.1	Detailed I	Description	301
	7.50.2	Function	Documentation	301
		7.50.2.1	ebias_correction	301
		7.50.2.2	eval_cut_param	301
		7.50.2.3	expected_max_distance	301
		7.50.2.4	expected_max_height	302
		7.50.2.5	img_norm	302
		7.50.2.6	interp	303
		7.50.2.7	prog_path	303
		7.50.2.8	rpol	303
		7.50.2.9	user_done	304
		7.50.2.10	user_event_fill	304
		7.50.2.11	user_finish	305
		7.50.2.12	user_get_type	305
		7.50.2.13	user_mc_event_fill	305
		7.50.2.14	user_mc_shower_fill	305
		7.50.2.15	user_set_clipping	305
		7.50.2.16	user_set_flags	305
		7.50.2.17	user_set_length_max_cut	305
		7.50.2.18	user_set_tel_type_param_by_str	306
		7.50.2.19	user_set_theta_escale	306
		7.50.2.20	user_set_width_max_cut	306
	7.50.3	Variable [Documentation	306
		7.50.3.1	opt_theta_cut	306
		7.50.3.2	telescope_type	306
7.51	warning	g.c File Re	ference	306
	7.51.1	Detailed I	Description	308
	7.51.2	Function	Documentation	308
		7.51.2.1	flush_output	308
		7.51.2.2	set_aux_warning_function	308
		7.51.2.3	set_log_file	309
		7.51.2.4	set_logging_function	309
		7.51.2.5	set_output_function	309
		7.51.2.6	set_warning	309
		7.51.2.7	warn_f_output_text	310
		7.51.2.8	warn_f_warning	311
		7.51.2.9	warning_status	311

XXVI

Index			316
	7.52.2.9	warning_status	315
	7.52.2.8		
	7.52.2.7	warn_f_output_text	314
	7.52.2.6	set_warning	314
	7.52.2.5	set_output_function	314
	7.52.2.4	set_logging_function	314
	7.52.2.3	set_log_file	313
	7.52.2.2	set_aux_warning_function	313
	7.52.2.1	flush_output	313
7.52.2	Function	Documentation	313
7.52.1	Detailed	Description	313
7.52 warnir	ng.h File Re	eference	312
	7.51.3.1	warn_defaults	311
7.51.3	Variable	Documentation	311

Chapter 1

Introduction

1.1 Introduction to the eventio/hessio libraries.

The hessio libraries include a number of components which are heavily used in CORSIKA/sim_telarray (sim_hessarray) simulations but also in some of the H.E.S.S. DAQ components. The basic components go back much further in history and were used for the DAQ of the CRT (Cosmic Ray Tracking) experiment, starting in 1991, and the HEGRA stereoscopic system of Cherenkov telescopes, starting in 1996. The library is thus also known under its original name: eventio library. The major components of the package include:

- The eventio data storage method with programming interfaces in C and C++.
- The eventio based high-level interfaces for shower simulations in the IACT interface to CORSIKA.
- The eventio based high-level interfaces for H.E.S.S. raw data and H.E.S.S./CTA simulations, as used by the sim_telarray program.
- A memory and speed efficient package for 1-D and 2-D histograms with full multi-threading support.
- The eventio based storage of the above histograms and conversion programs from the eventio format to PAW (HBOOK) and ROOT formats.
- A software run-time configuration interface named hconfig with a cpp-like preprocessor, also with full multithreading support.

The hessic libraries are normally built in several variants:

- libhessio The variant optimised for single-threaded C programs. It has no multi-threading support and should not be used in multi-threaded DAQ environments. For simulations performed in a single thread, this variant provides optimum performance because no time is wasted in protecting critical sections by mutexes etc.
- libhessio_r The variant with full multi-threading support. Because of the overhead of protecting critical sections, it is not the optimal variant for single-threaded programs but (if linked with the POSIX threading library), will work for both multi-threaded and single-threaded programs. Linking: -lhessio_r -lpthread
- libhessio++ Like libhessio it offers no multi-threading support. In addition to libhessio it offers also the C++ interfaces to the eventio data format. As such, it requires linking with the C++ Standard Library. Single-threaded C++ programs would normally be linked against this variant: -lhessio++
- libhessio++_r offers everything of libhessio_r plus the C++ interfaces to the eventio data format. Multi-threaded C++ programs would normally be linked against this variant: -lhessio++_r -lpthread

2 Introduction

All of these libraries can be built as shared libraries and as static libraries, thus adding up to a total of eight libraries installed. Depending on definitions in the Makefile, the building of static libraries may be skipped by default.

The main documentation web page for this module can be found at

http://www.mpi-hd.mpg.de/hfm/~bernlohr/HESS/Software/hessio/

1.2 Eventio format documentation

1.3 Utility and test programs in the hessio module

A make install in the hessio module will, apart from the different variants of the library, install a number of programs. These include

- testio: A test program for the C programming interface. Should be run once if you go to a new platform or compiler.
- TestIO: A test program for the C++ programming interface. Should be run once if you go to a new platform or compiler. The output file generated should also be bitwise identical to that from the C interface test program.
- listio: Lists eventio data blocks in a data file or stream. Can also show the sub-block hierarchy.
- statio: Count the number of eventio top-level data blocks of each type and the total amount of (uncompressed) data for each block type. Also showing the version numbers involved.
- filterio: Select or deselect given types of eventio top-level data blocks between input or output, not requiring any support for the structure of the data block types.
- fcat: Like the standard 'cat' program but accepting any file type known by the fileopen() function as input, with decompression as implied by the filetype extension.
- read_hess: Reads output files generated by sim_hessarray and may optionally redo the image cleaning and shower reconstruction. It may be most useful to quickly visualize the images in the data file. Also called read cta or read simtel.
- gen_lookup: Process the histograms generated by read_hess to obtain lookup tables for width, length, energy, angular resolution, etc., which are used for further processing with read_hess.
- list_histograms: Show histograms embedded into an eventio file which can be either a dedicated histogram file or a general data file with any number of histogram blocks.
- add_histograms: Add up multiple occurences of matching histograms (in ID, type, limits, and size) from one or multiple files into a new histogram file, independent of any format conversion.
- hdata2hbook: Converts from the eventio histogram format to the HBOOK/Paw format. Histogram blocks
 can be anywhere in a data file. You can also add up identical histograms from different input files before
 exporting.
- hdata2root: Converts from the eventio histogram format to the ROOT format. Like hdata2hbook.
- gen_trgmask: Fixing a problem with 2012/13 versions of sim_telarray for camera configurations with multiple types of triggers where the information on which type of trigger fired got lost. This tool recovers this information from the log files. Not needed for new simulations (nor for old ones which could only have one type of trigger).
- check_trgmask: Check the camera trigger type bit patterns generated by the gen_trgmask tool for consistency.

Chapter 2

Module Index

2.1 Modules

Here is a list of all modules:

The add_histograms program
The best_of program
The fcat program
The list_histogram program
The read_hess sensitivity comparison tool
The check_trgmask program
The extract_hess program
The gen_trgmask program
The merge_simtel program
The read_hess (aka read_simtel, read_cta) program
The read_hess_nr program
The hdata2hbook program (cvt2)
The hdata2root program (cvt3)

Module Index

Chapter 3

Data Structure Index

3.1 Data Structures

Here a	are the	data	structures	with	briet	description	١S

A	31
В	31
basic_ntuple	
A struct with basic per-shower parameters, to be used as an n-tuple in the event selection	31
best_value	38
Binary_Interface_Chain	39
bunch	
Photons collected in bunches of identical direction, position, time, and wavelength	39
compact_bunch	
The compact_bunch struct is equivalent to the bunch struct except that we try to use less memory	40
Config_Binary_Item_Interface	
Interface definitions for binary-only items	40
config_specific_data	42
ConfigBlockStruct	
Configuration is organized in sections	42
ConfigBoundary	
Configuration value may have optional lower and/or upper bounds	43
ConfigDataPointer	
This union of pointers allows convenient access of various types of data	44
ConfigIntern	
Configuration elements used only internally	44
ConfigItemStruct	
Configuration as used in definitions of configuration blocks	47
ConfigValues	
Configuration values and supporting data passed to user functions	49
ebias_cor_data	51
ev_reg_chain	
Use a double-linked list for the registry	52
hess_all_data_struct	
Container for all H.E.S.S	52
hess_camera_organisation_struct	
Logical organisation of camera electronics channels	54
hess_camera_settings_struct	
Definition of camera optics settings	54
hess_camera_software_setting_struct	
Software settings used in camera process	56
hess_central_event_data_struct	
Central trigger event data	57

6 Data Structure Index

hess_event_data_struct	
All data for one event	58
hess_laser_calib_data_struct	
Laser calibration data	59
hess_mc_event_struct	
Monte Carlo event-specific data	61
Photo-electrons from Monte Carlo individually	62
hess_mc_pe_sum_struct	
Sums of photo-electrons in MC (total and per pixel)	62
hess_mc_photons Photons from Monte Carlo	63
hess_mc_run_header_struct	0.4
MC run header	64
hess_mc_shower_profile_struct Monto Carlo shower profile (cort of histogram)	66
Monte Carlo shower profile (sort of histogram)	66
hess_mc_shower_struct Shower specific data	67
hess_pixel_calibrated_struct	68
hess pixel disabled struct	00
Pixels disabled in HV and/or trigger	69
hess_pixel_list	•
Lists of pixels (triggered, selected, etc.)	69
hess_pixel_setting_struct	
Settings of pixel HV and thresholds	70
hess_pixel_timing_struct	71
hess_pointing_correction_struct	
Pointing correction parameters	73
hess_run_end_mc_statistics_struct	
MC end-of-run statistics	73
hess_run_end_statistics_struct	
End-of-run statistics	73
hess_run_header_struct	
Run header common to measured and simulated data	74
hess_shower_parameter	70
Reconstructed shower parameters	76
hess_tel_event_adc_struct	77
ADC data (either sampled or sum mode)	77
hess_tel_event_data_struct	70
Event raw and image data from one telescope	79
Image parameters	80
hess_tel_monitor_struct	00
Monitoring data	82
hess time struct	-
Breakdown of time into seconds since 1970.0 and nanoseconds	85
hess_tracking_event_data_struct	
Tracking data interpolated for one event and one telescope	86
hess_tracking_setup_struct	
Definition of tracking parameters	86
histogram	
A complete 1-D or 2-D histogram with control and data elements	87
Histogram_Extension	
A histogram extension only allocated for weighted histograms	90
Histogram_Parameters	
Parameters defining the usable range of coordinates	91
history_struct	~ -
Use to build a linked list of configuration history	92

3.1 Data Structures 7

histstat	
Statistics element for histogram analysis	93
incpath	
An element in a linked list of include paths	93
linked_string	
The linked_string is mainly used to keep CORSIKA input	94
map_tel_struct	
Structure with per output telescope information keeping track of prerequisites	94
moments	
Numbers to be summed up to obtain the moments	95
momstat	
First, second, and higher moments of a 1-D histogram	96
next_file_struct	96
photo_electron	
A photo-electron produced by a photon hitting a pixel	97
range_list_struct	98
shower_extra_parameters	
Extra shower parameters of unspecified nature	98
tel_type_param	99
telescope_list	100
3 =7	100
trgmask_hash_set	101
trgmask_set	101
user_parameters	102
warn_specific_data	
A struct used to store thread-specific data	105

8 Data Structure Index

Chapter 4

File Index

4.1 File List

Here is a list of all documented files with brief descriptions:

add_hist	tograms.c	
	Utility program for adding up matching histograms	107
atmprof.	c	
	A stripped-down version of the interpolation of atmospheric profiles from the atmo.c file of the CORSIKA IACT/ATMO package	108
atmprof	i.h	??
basic_nt		
	Desclaration of the basic_ntuple struct	111
best_of.	cc	
	Tool for extracting best values from listings of 'rh3' sensitivity evaluations	113
camera_	_image.c	
	Plot a camera image from H.E.S.S	115
camera	_image.h	??
check_ti	rgmask.c	
	Check consistency of 'trgmask' files produced with gen_trgmask for the CTA prod-2 data sets	
	produced in 2013	118
current.c		
	Code to insert current time string into warnings	119
current.h		
	Header file for optional current time add-on to warning.c	122
cvt2.c		
	Utility program for converting histograms to HBOOK format	125
cvt3.cc		
	Conversion of eventio histograms to ROOT format	126
dhsort.c		
	Dhsort - double type number heapsort	
dhsort.l		??
eventio_	registry.c	
	Register and enquire about well-known I/O block types	128
eventio_	registry.h	
	Register and enquire about well-known I/O block types	
_	_version.h	??
extract_		
_	Extract part of the H.E.S.S	132
fcat.c		
	Trivial test and utility program for the fileopen/fileclose functions	133
fileopen		
	Allow searching of files in declared include paths (fopen replacement)	133

10 File Index

fileopen.h	
Function prototypes for fileopen.c	138
Generate image shape and energy lookups for user analysis in read_hess	140
A utility program for fixing problems with simulation data which does not have the correct bit pattern of telescope triggers but the correct pattern can be extracted from the log files	143
hconfig.c Configuration control and procedure call interface	143
hconfig.h Declare hconfig structures and functions	153
hessio_doc.h Add an introduction to doxygen-generated documentation	162
histogram.c Manage, fill, and display one- and two-dimensional histograms	162
histogram.h Declarations for handling one- and two-dimensional histograms	180
history.h Keep blocks of history in the data (like command line of programs operating on the data,)	201
initial.h Indentification of the system and including some basic include file	202
io_hess.c Writing and reading of H.E.S.S	204
io_hess.h Definition and structures for H.E.S.S	213
io_histogram.c This file implements I/O for 1-D and 2-D histograms	220
io_histogram.h Declarations for eventio I/O of histograms	222
io_history.c Record history of configuration settings/commands	
io_history.h Record history of configuration settings/commands	227
io_simtel.c	
io_trgmask.c EventIO plus helper functions for trigger type bit patterns extracted from sim_telarray log files	220
(only relevant for simulations with multiple trigger types using sim_telarray versions before mid-2013)	242
io_trgmask.h EventIO plus helper functions for trigger type bit patterns extracted from sim telarray log files	
(only relevant for simulations with multiple trigger types using sim_telarray versions before mid-2013)	245
list_histograms.c	
mc_tel.h Definitions and structures for CORSIKA Cherenkov light interface	
merge_simtel.c A program for merging events from separate telescope simulations of the same showers	
moments.c	
Calculate mean, rms, skewness, and kurtosis of data read_hess.c	266
A program reading simulated data, optionally analysing the data, and also optionally also writing summary ("DST") data	270
read_hess_nr.c A skeleton program reading H.E.S.S	274
rec_tools.h Tools for shower geometric reconstruction	276

4.1 File List

reconstruct.c		
Secon	nd moments type image analysis	279
reconstruct.h		??
rh_sens_comp.	.cc	
	oine a few basic columns from two sensitivity and and other performance listing files as uced by the rh3 utility and then optimized by the best_of utility	288
rndm2.h		
Proto	types for random number generators adapted from HEP Random C++ code	289
straux.c		
Check	k for abbreviations of strings and get words from strings	290
straux.h		
Check	k for abbreviations of strings and get words from strings	293
tohbook.c		
Conve	ert my histograms to HBOOK (PAW) histograms	294
tohbook.h .		??
toroot.cc		
Funct	tions for conversion of eventio histograms to ROOT format	295
toroot.hh		??
user_analysis.d		
Code	for analysis of simulated (and reconstructed) showers within the framework of the read	
hess	program	297
user_analysis	.h	??
warning.c		
Pass	warning messages to the screen or a usr function as set up	306
warning.h		
Pass	warning messages to the screen or a usr function as set up	312

12 File Index

Chapter 5

Module Documentation

5.1 The add_histograms program

Functions

- void syntax (const char *prgm)
- int main (int argc, char **argv)

 Main program.

5.1.1 Detailed Description

5.1.2 Function Documentation

5.1.2.1 int main (int argc, char ** argv)

Main program.

Main program function of read_hess.c program.

References display_all_histograms(), histogram::entries, get_first_histogram(), getword(), histogram::ident, histogram::nbins, histogram::nbins_2d, histogram::next, sort_histograms(), histogram::title, histogram::type, verbose, and write_all_histograms().

5.2 The best_of program

One type is before the addition of 68% and 80% angular resolution values.

Data Structures

· struct best value

Enumerations

```
enum SpecType {
 SPEC_NONE = -1, SPEC_GAMMA = 0, SPEC_ELECTRON = 1, SPEC_PROTON = 101,
 SPEC_HE = 402, SPEC_CNO = 1407, SPEC_SI = 2814, SPEC_IRON = 5626,
 SPEC NONE = -1, SPEC GAMMA = 0, SPEC ELECTRON = 1, SPEC PROTON = 101,
 SPEC HE = 402, SPEC CNO = 1407, SPEC SI = 2814, SPEC IRON = 5626,
 SPEC GAMMA = 0, SPEC ELECTRON = 1, SPEC PROTON = 101, SPEC HE = 402,
 SPEC GAMMA = 0, SPEC ELECTRON = 1, SPEC PROTON = 101, SPEC HE = 402,
 SPEC NONE = -1, SPEC GAMMA = 0, SPEC ELECTRON = 1, SPEC PROTON = 101,
 SPEC HE = 402, SPEC CNO = 1407, SPEC SI = 2814, SPEC IRON = 5626,
 SPEC_NONE = -1, SPEC_GAMMA = 0, SPEC_ELECTRON = 1, SPEC_PROTON = 101,
 SPEC_HE = 402, SPEC_CNO = 1407, SPEC_SI = 2814, SPEC_IRON = 5626,
 SPEC_NONE = -1, SPEC_GAMMA = 0, SPEC_ELECTRON = 1, SPEC_PROTON = 101,
 SPEC_HE = 402, SPEC_CNO = 1407, SPEC_SI = 2814, SPEC_IRON = 5626 }
enum espec t {
 OLD E POWERLAW = 1, NEW E POWERLAW = 2, NEW E PL LGN1 = 3, NEW E PL LGN2 = 4,
 OLD E POWERLAW = 1, NEW E POWERLAW = 2, NEW E PL LGN1 = 3, NEW E PL LGN2 = 4,
 OLD E POWERLAW = 1, NEW E POWERLAW = 2, NEW E PL LGN1 = 3, NEW E PL LGN2 = 4,
 OLD E POWERLAW = 1, NEW E POWERLAW = 2, NEW E PL LGN1 = 3, NEW E PL LGN2 = 4,
 OLD_E_POWERLAW = 1, NEW_E_POWERLAW = 2, NEW_E_PL_LGN1 = 3, NEW_E_PL_LGN2 = 4 }
enum BestChoice {
 BestDiff =1, BestIntegral =2, BestAngle =3, BestEres =4,
 BestRate =5, BestCombined =6 }
```

Functions

- string particle type (SpecType sp)
- double Crab Unit (double E)
- static double **cu** (double x)
- double Crab_Unit_int (double E)
- double ergs (double E)
- static double **f50** (double x)
- static double fsp50 (double x)
- double Flux_req50_south (double E)
- double Flux_req50_E2erg_south (double E)
- double Flux_req50_CU_south (double E)
- static double fn50 (double x)
- static double fnsp50 (double x)
- double Flux_req50_north (double E)
- double Flux_req50_E2erg_north (double E)
- double Flux_req50_CU_north (double E)
- static double f5 (double x)
- static double fsp5 (double x)
- double Flux req5 south (double E)
- double Flux_req5_E2erg_south (double E)

- double Flux_req5_CU_south (double E)
- static double fn5 (double x)
- static double **fnsp5** (double x)
- double Flux_req5_north (double E)
- double Flux req5 E2erg north (double E)
- double Flux_req5_CU_north (double E)
- static double **f05** (double x)
- static double fsp05 (double x)
- double Flux req05 south (double E)
- double Flux req05 E2erg south (double E)
- double Flux req05 CU south (double E)
- static double fn05 (double x)
- static double fnsp05 (double x)
- double Flux_req05_north (double E)
- double Flux_req05_E2erg_north (double E)
- double Flux_req05_CU_north (double E)
- static double **fd50** (double x)
- static double fdes50 (double x)
- double Flux goal50 south (double E)
- double Flux_goal50_E2erg_south (double E)
- double Flux_goal50_CU_south (double E)
- static double fnd50 (double x)
- static double fndes50 (double x)
- double Flux goal50 north (double E)
- double Flux goal50 E2erg north (double E)
- double Flux_goal50_CU_north (double E)
- double Angular_resolution_req (double E)
- double Angular_resolution_goal (double E)
- static double eresb (double E)
- double Energy_resolution_req (double E)
- static double **eresdb** (double E)
- double Energy_resolution_goal (double E)
- double flux_int (SpecType sp, double E1, double E2)
- double lima17 (double on, double off, double alpha)
- bool matching_required_diffsens (int calc_pput, bool with_flux, double E, double diff_sens)
- bool matching_required_performance (int calc_pput, bool with_flux, double E, double diff_sens, double angres, double eres)
- bool matching_required_angres (double E, double angres)
- bool matching_required_eres (double E, double eres)
- int main (int argc, char **argv)

Variables

- static double sce = 1.6022
- static double sca = 1e-4
- static double sc = sce*sca
- espec_t espec_type = OLD_E_POWERLAW

5.2.1 Detailed Description

One type is before the addition of 68% and 80% angular resolution values. Another one is after addition of angular resolution but before addition of the energy resolution, and the third one is after the energy resolution got added to the output. The different formats are recognized by the presence and position of the histogram number (12056 to 12064 normally) on which the sensitivity evaluation is mainly based.

5.3 The fcat program

Macros

• #define BSIZE 8192

Functions

• int main (int argc, char **argv)

5.3.1 Detailed Description

5.4 The list_histogram program

Functions

• int main (int argc, char **argv)

Main program.

5.4.1 Detailed Description

5.4.2 Function Documentation

5.4.2.1 int main (int argc, char ** argv)

Main program.

References display_all_histograms(), display_histogram(), histogram::entries, get_first_histogram(), get_histogram-by_ident(), histogram::nbins, histogram::nbins_2d, histogram::next, print_histogram(), sort_histograms(), histogram::title, histogram::type, and verbose.

5.5 The read_hess sensitivity comparison tool

Syntax: rh_sens_comp file1 file2.

Functions

- string pad_to (const string &s, size_t nmin)
- vector< vector< string > > read_table (const char *fname, size_t n_min)
- int main (int argc, char **argv)

5.5.1 Detailed Description

Syntax: rh_sens_comp file1 file2. One of the two input files can be standard input (specified as '-'); output goes to standard output. Needs the stdtools and hessio[++] libraries for building.

5.6 The check_trgmask program

Functions

- int main (int argc, char **argv)
- 5.6.1 Detailed Description

5.7 The extract_hess program

Functions

static void syntax (char *program)
 Show program syntax.

 int main (int arge, char **argv)

Main program.

Variables

· static int interrupted

5.7.1 Detailed Description

5.7.2 Function Documentation

5.7.2.1 int main (int argc, char ** argv)

Main program.

Main program function of extract_hess.c program.

References fileclose(), fileopen(), and syntax().

5.8 The gen_trgmask program

Functions

- void **syntax** (char *prgname)
- int **main** (int argc, char **argv)

5.8.1 Detailed Description

5.9 The merge_simtel program

Data Structures

· struct map tel struct

Structure with per output telescope information keeping track of prerequisites.

Functions

static void syntax (const char *program)

Show program syntax.

• int find_in_tel_idx (int tel_id, int ifile)

Offset of an input telescope of given ID within the input structures.

• int find out tel idx (int tel id, int ifile)

Offset of an input telescope of given ID within the output structures.

int find mapped telescope (int tel id, int ifile)

Mapping from telescope ID on input to telescope ID on output, with check.

• int write io block to file (IO BUFFER *iobuf, FILE *f)

Write an I/O block as-is to another file than foreseen for the I/O buffer.

- int check_for_delayed_write (IO_ITEM_HEADER *item_header, int ifile, AllHessData *hsdata_out, IO_BU-FFER *iobuf_out)
- int merge_data_from_io_block (IO_BUFFER *iobuf, IO_ITEM_HEADER *item_header, int ifile, AllHessData *hsdata, AllHessData *hsdata_out, IO_BUFFER *iobuf_out)

Processing and merging of I/O blocks from the two input files, hopefully presented in the right order.

int check_autoload_trgmask (const char *input_fname, IO_BUFFER *iobuf, int ifile)

Check for a 'trgmask.gz' file matching the given input data file name and, if it exists, extract the corrected trigger bit patterns from it.

- void **print_process_status** (int prev_type1, int this_type1, int prev_type2, int this_type2)
- int read_map (const char *map_fname)
- int main (int argc, char **argv)

Main program.

Variables

- · static int interrupted
- static int verbose = 0
- struct map tel struct map tel [H MAX TEL]
- int map_to [2][H_MAX_TEL+1]

Mapping structures from input telescope ID to output telescope ID.

• int tel_idx [2][H_MAX_TEL+1]

Mapping from telescope IDs to offsets in the data structures, first for input telescope IDs.

int tel_idx_out [H_MAX_TEL+1]

Mapping from output telescope ID to offset in output data structures.

- int ntel1
- · int ntel2
- · int ntel
- int nrtel1
- · int nrtel2
- long **event1** = -1
- long event2 = 0
- long ev hess event = 0
- long ev_pe_sum = 0

For delayed writing.

- int run1 = -1
- int run2 = -1
- int min_trg = 2
- static struct trgmask_set * tms [2] = { NULL, NULL }
- static struct trgmask_hash_set * ths [2] = { NULL, NULL }
- static int **events** [2] = { 0, 0 }
- static int **mcshowers** [2] = { 0, 0 }
- static int **mcevents** [2] = { 0, 0 }
- static int max_list = 999

5.9.1 Detailed Description

5.9.2 Function Documentation

5.9.2.1 int check autoload trgmask (const char * input fname, IO BUFFER * iobuf, int ifile)

Check for a 'trgmask.gz' file matching the given input data file name and, if it exists, extract the corrected trigger bit patterns from it.

(Note: this is only relevant for multi-trigger data produced with a bug in recording the trigger bit pattern.)

We do not need to merge the contents of this file since the trigger bit patterns are corrected after reading the data.

References fileclose(), fileopen(), read trgmask(), and trgmask fill hashed().

Referenced by main().

5.9.3 Variable Documentation

```
5.9.3.1 int map_to[2][H_MAX_TEL+1]
```

Mapping structures from input telescope ID to output telescope ID.

Not mapped telescopes are defined by output telescope ID of -1. The telescope ID to which a given input telescope ID should get mapped.

Referenced by find mapped telescope(), and find out tel idx().

```
5.9.3.2 int tel_idx[2][H_MAX_TEL+1]
```

Mapping from telescope IDs to offsets in the data structures, first for input telescope IDs.

We restrict the ID/index mapping here to well behaved cases (0<ID<=H_MAX_TEL). An index value of -1 indicates a non-existant/ignored telescope. Where is a telescope of given ID in the input data structures?

Referenced by find_in_tel_idx(), find_out_tel_idx(), main(), and merge_data_from_io_block().

```
5.9.3.3 int tel_idx_out[H_MAX_TEL+1]
```

Mapping from output telescope ID to offset in output data structures.

Where is a telescope of given ID in the output data structures?

Referenced by find_out_tel_idx(), and merge_data_from_io_block().

5.10 The read_hess (aka read_simtel, read_cta) program

Data Structures

- · struct next file struct
- · struct range_list_struct

Macros

#define CALIB_SCALE 0.92

The factor needed to transform from mean p.e.

• #define CALIB SCALE 0.92

The factor needed to transform from mean p.e.

Typedefs

- · typedef struct next file struct NextFile
- typedef struct range_list_struct RangeList
- typedef struct next_file_struct NextFile

Functions

• void stop_signal_function (int isig)

Stop the program gracefully when it catches an INT or TERM signal.

- static void init_rand (int is)
- double grand48 (double mean, double sigma)

Like RandFlat() from rndm2.c but using the drand48 engine.

static void mc_event_fill (AllHessData *hsdata, double d_sp_idx)

Fill histogram(s) for DST writing which require all MC shower and event data and which cannot be filled from DST level >= 2 data.

• static int write dst histos (IO BUFFER *iobuf2)

Write histograms for DST book-keeping and clear them afterwards.

- static void show_run_summary (AllHessData *hsdata, int nev, int ntrg, double plidx, double wsum_all, double wsum_trg, double rmax_x, double rmax_y, double rmax_r)
- static void syntax (char *program)

Show program syntax.

- NextFile * add_next_file (const char *fn, NextFile *nxt)
- RangeList * add_range (long f, long t, RangeList *rl)
- int is_in_range (long n, RangeList *rl)
- int main (int argc, char **argv)

Main program.

Variables

- struct basic_ntuple bnt
- · static int interrupted
- static int dst_processing
- · static int g48 set
- static double g48_next
- · struct basic ntuple bnt
- · static int interrupted
- · static int dst_processing

5.10.1 Detailed Description

5.10.2 Macro Definition Documentation

5.10.2.1 #define CALIB SCALE 0.92

The factor needed to transform from mean p.e.

units to units of the single-p.e. peak: Depends on the collection efficiency, the asymmetry of the single p.e. amplitude distribution and the electronic noise added to the signals.

5.10.2.2 #define CALIB SCALE 0.92

The factor needed to transform from mean p.e.

units to units of the single-p.e. peak: Depends on the collection efficiency, the asymmetry of the single p.e. amplitude distribution and the electronic noise added to the signals.

Referenced by main().

5.10.3 Function Documentation

5.10.3.1 int main (int argc, char ** argv)

Main program.

Main program function of read hess.c program.

References hess_shower_parameter::Alt, hess_mc_shower_struct::altitude, hess_tel_image_struct::amplitude, angle_between(), hess_shower_parameter::Az, hess_mc_shower_struct::azimuth, book_histogram(), hess_laser-_calib_data_struct::calib, CALIB_SCALE, calibrate_amplitude(), calibrate_pixel_amplitude(), hess_event_data-_struct::central, user_parameters::clip_amp, hess_tel_image_struct::clip_amp, hess_mc_shower_struct::cmax, hess tel image struct::cut id, Histogram Extension::ddata, hess mc shower struct::emax, hess shower parameter::energy, hess mc shower struct::energy, hess mc event struct::event, histogram::extension, fileclose(), fileopen(), fill_histogram(), fill_histogram_by_ident(), find_tel_idx(), find_trgmask(), free_histogram(), get_histogram_by_ident(), getword(), grand48(), H_CHECK_MAX, H_MAX_TEL, hesscam_ps_plot(), hess_mc_shower struct::hmax, hess tel image struct::hot amp, hess tel image struct::hot pixel, hess tel event data struct::image_pixels, hess_tel_event_data_struct::img, IO_TYPE_HESS_XTRGMASK, hess_tel_event_adc_struct-::known, hess_pixel_calibrated_struct::known, hess_tel_image_struct::known, hess_tel_image_struct::l, basic_ntuple::lg_e, line_point_distance(), list_ntuple(), user_parameters::lref, hess_tel_event_data_struct::max_image_sets, mc event fill(), hess mc event struct::mc pesum, user parameters::min amp, user parameters::min pix, user parameters::minfrac, hess shower parameter::mscl, hess shower parameter::mscw, basic ntuple::n img, hess run header struct::ntel, hess laser calib data struct::num gains, hess tel image struct::num hot, hess tel event data struct::num image sets, hess shower parameter::num img, hess camera settings struct::num-_mirrors, hess_mc_pe_sum_struct::num_pe, hess_tel_monitor_struct::num_ped_slices, hess_laser_calib_data_struct::num_pixels, hess_event_data_struct::num_tel, hess_central_event_data_struct::num_teltrg, hess_shower_parameter::num_trg, hess_tel_image_struct::phi, hess_tel_event_data_struct::pixcal, hess_pixel_list::pixels, hess_tel_event_data_struct::pixels, hess_t _tel_image_struct::pixels, hess_tel_event_data_struct::pixtm, hess_mc_shower_struct::primary_id, print_hess-_calib_event(), print_hess_camorgan(), print_hess_camsettings(), print_hess_event(), print_hess_laser_calib(), print_hess_mc_event(), print_hess_mc_pe_sum(), print_hess_mc_phot(), print_hess_mc_run_stat(), print_hess_mc_phot(), print_hess_mc_run_stat(), print_hess_mc_phot(), print_hess_mc_run_stat(), print_hess_mc_phot(), print_hess_mc_run_stat(), print_hess_mc _mc_shower(), print_hess_mcrunheader(), print_hess_pixelset(), print_hess_run_stat(), print_hess_runheader(), print hess tel monitor(), print histograms(), print tel block(), print tel offset(), print tel photons(), print tel pos(), print trgmask(), hess tel event data struct::raw, RAWDATA FLAG, read hess calib event(), read hess-_camorgan(), read_hess_camsettings(), read_hess_camsoftset(), read_hess_event(), read_hess_laser_calib(), read hess mc event(), read hess mc pe sum(), read hess mc phot(), read hess mc run stat(), read hessmc shower(), read hess mcrunheader(), read hess pixeldis(), read hess pixelset(), read hess pointingcor(), read hess run stat(), read hess runheader(), read hess tel monitor(), read hess trackset(), read histograms(), read_input_lines(), read_trgmask(), reconstruct(), hess_shower_parameter::result_bits, hess_run_header_struct-::run, select_calibration_channel(), set_disabled_pixels(), hess_event_data_struct::shower, hess_mc_run_header-

_struct::spectral_index, stop_signal_function(), syntax(), user_parameters::tailcut_low, hess_run_header_struct-::tel id, hess camera settings struct::tel id, hess camera organisation struct::tel id, hess pixel setting struct-::tel_id, hess_pixel_disabled_struct::tel_id, hess_camera_software_setting_struct::tel_id, hess_tracking_setup_struct::tel_id, hess_pointing_correction_struct::tel_id, hess_tel_event_adc_struct::tel_id, hess_pixel_timing_struct-::tel_id, hess_pixel_calibrated_struct::tel_id, hess_tel_image_struct::tel_id, hess_tel_event_data_struct::tel_id, hess tracking event data struct::tel id, hess tel monitor struct::tel id, hess laser calib data struct::tel id, tel idx, hess run header struct::tel pos, hess event data struct::teldata, hess central event data struct::teltrg list, hess central event data struct::teltrg type mask, hess event data struct::trackdata, trgmask entry::trg mask, user parameters::trg req, trgmask fill hashed(), user get type(), user set clipamp(), user set clipping(), userset de2 cut(), user set de cut(), user set flags(), user set histogram file(), user set hmax cut(), user set-_impact_range(), user_set_length_max_cut(), user_set_lookup_file(), user_set_max_core_distance(), user_set_ _max_theta(), user_set_min_amp(), user_set_min_pix(), user_set_reco_flag(), user_set_shape_cuts(), user_set_spectrum(), user_set_tail_cuts(), user_set_tel_img(), user_set_tel_list(), user_set_tel_type_param_by_str(), user_set_telescope_type(), user_set_theta_escale(), user_set_trg_req(), user_set_true_impact_range(), user_set_trg_req(), user_set_true_impact_range(), user_set_trg_req(), user_set_trg_r _width_max_cut(), verbose, hess_tel_image_struct::w, which_telescope_type(), write_dst_histos(), write_hess_event(), write_hess_mc_event(), write_hess_mc_pe_sum(), write_hess_mc_shower(), write_histograms(), hess_tel image struct::x, hess shower parameter::xc, hess mc event struct::xcore, hess shower parameter::xmax, hess mc shower struct::xmax, hess tel image struct::y, hess shower parameter::yc, hess mc event struct-::ycore, and hess_tel_event_adc_struct::zero_sup_mode.

5.10.3.2 void stop_signal_function (int isig)

Stop the program gracefully when it catches an INT or TERM signal.

Parameters

isig	Signal number.

Returns

(none)

5.11 The read_hess_nr program

Macros

- #define UNUSED
- #define CALIB SCALE 0.92

The factor needed to transform from mean p.e.

#define UNUSED

Functions

- double calibrate_pixel_amplitude (AllHessData *hsdata, int itel, int ipix, int dummy, double cdummy)

 Calibrate a single pixel amplitude, for cameras with two gains per pixel.
- double calibrate_pixel_amplitude (AllHessData *hsdata, int itel, int ipix, _UNUSED_ int dummy, _UNUSED_ D double cdummy)
- void stop_signal_function (int isig)

Stop the program gracefully when it catches an INT or TERM signal.

- static void **show_run_summary** (AllHessData *hsdata, int nev, int ntrg, double plidx, double wsum_all, double wsum_trg, double rmax_x, double rmax_y, double rmax_r)
- static void syntax (char *program)

Show program syntax.

int main (int argc, char **argv)

Main program.

Variables

- · static int interrupted
- · static int interrupted

5.11.1 Detailed Description

5.11.2 Macro Definition Documentation

5.11.2.1 #define CALIB SCALE 0.92

The factor needed to transform from mean p.e.

units to units of the single-p.e. peak: Depends on the collection efficiency, the asymmetry of the single p.e. amplitude distribution and the electronic noise added to the signals.

Referenced by main().

5.11.3 Function Documentation

5.11.3.1 double calibrate_pixel_amplitude (AllHessData * hsdata, int itel, int ipix, int dummy, double cdummy)

Calibrate a single pixel amplitude, for cameras with two gains per pixel.

This version does not include amplitude clipping nor obtaining amplitudes from the pixel timing data structure.

Returns

Pixel amplitude in peak p.e. units.

Referenced by hesscam_ps_plot(), main(), and user_event_fill().

5.11.3.2 int main (int argc, char ** argv)

Main program.

Main program function of read_hess.c program.

References hess shower parameter::Alt, hess mc shower struct::altitude, hess tel image struct::amplitude, angle between(), hess shower parameter::Az, hess mc shower struct::azimuth, CALIB SCALE, calibrate pixelamplitude(), hess mc shower struct::cmax, Histogram Extension::ddata, hess mc shower struct::emax, hessshower parameter::energy, hess mc shower struct::energy, hess mc event struct::event, histogram::extension, fileclose(), fileopen(), find tel idx(), H CHECK MAX, hesscam ps plot(), hess mc shower struct::hmax, hess-_tel_image_struct::hot_amp, hess_tel_image_struct::hot_pixel, hess_tel_event_data_struct::image_pixels, hess-_tel_event_data_struct::img, hess_tel_image_struct::l, line_point_distance(), hess_tel_event_data_struct::max_image sets, hess mc event struct::mc pesum, hess shower parameter::mscl, hess shower parameter::mscw, hess_run_header_struct::ntel, hess_tel_image_struct::num_hot, hess_tel_event_data_struct::num_image_sets, hess_shower_parameter::num_img, hess_mc_pe_sum_struct::num_pe, hess_tel_monitor_struct::num_ped_slices, hess_event_data_struct::num_tel, hess_shower_parameter::num_trg, hess_tel_image_struct::phi, hess_shower_parameter::num_trg, hess_shower_parameter::nu pixel list::pixels, hess tel image struct::pixels, hess tel event data struct::pixtm, hess mc shower struct-::primary_id, print_hess_camorgan(), print_hess_camsettings(), print_hess_event(), print_hess_laser_calib(), print_hess_event() _hess_mc_event(), print_hess_mc_pe_sum(), print_hess_mc_run_stat(), print_hess_mc_shower(), print_hess_mcrunheader(), print_hess_pixelset(), print_hess_run_stat(), print_hess_runheader(), print_hess_tel_monitor(), print tel block(), print tel photons(), hess tel event data struct::raw, read hess calib event(), read hess camorgan(), read_hess_camsettings(), read_hess_camsoftset(), read_hess_event(), read_hess_laser_calib(), read_hess_mc_event(), read_hess_mc_pe_sum(), read_hess_mc_phot(), read_hess_mc_run_stat(), read_hes _mc_shower(), read_hess_mcrunheader(), read_hess_pixeldis(), read_hess_pixelset(), read_hess_pointingcor(), read hess run stat(), read hess runheader(), read hess tel monitor(), read hess trackset(), read histograms(), read_input_lines(), user_parameters::reco_flag, hess_shower_parameter::result_bits, hess_run_header_struct-::run, hess_event_data_struct::shower, hess_mc_run_header_struct::spectral_index, stop_signal_function(), syntax(), hess run header struct::tel id, hess camera settings struct::tel id, hess camera organisation struct::telid, hess pixel setting struct::tel id, hess pixel disabled struct::tel id, hess camera software setting struct-::tel_id, hess_tracking_setup_struct::tel_id, hess_pointing_correction_struct::tel_id, hess_tel_event_adc_struct-::tel id, hess pixel timing struct::tel id, hess tel image struct::tel id, hess tel event data struct::tel id, hesstracking event data struct::tel id, hess tel monitor struct::tel id, hess laser calib data struct::tel id, hess run header struct::tel pos, hess event data struct::teldata, hess event data struct::trackdata, verbose, hess tel_image_struct::w, hess_tel_image_struct::x, hess_shower_parameter::xc, hess_mc_event_struct::xcore, hess_shower_parameter::xmax, hess_mc_shower_struct::xmax, hess_tel_image_struct::y, hess_shower_parameter::yc, and hess_mc_event_struct::ycore.

5.11.3.3 void stop_signal_function (int isig)

Stop the program gracefully when it catches an INT or TERM signal.

Parameters

isig | Signal number.

Returns

(none)

5.12 The hdata2hbook program (cvt2)

Functions

• int main (int argc, char **argv)

Main program.

5.12.1 Detailed Description

5.12.2 Function Documentation

5.12.2.1 int main (int argc, char ** argv)

Main program.

References display_all_histograms(), histogram::entries, get_first_histogram(), histogram::ident, histogram::nbins, histogram::nbins_2d, histogram::next, sort_histograms(), histogram::title, histogram::type, verbose, and write_all_histograms().

5.13 The hdata2root program (cvt3)

Functions

- int read_file (IO_BUFFER *iobuf, const char *fname, int add_flag, int list_flag)
- int main (int argc, char **argv)

5.13.1 Detailed Description

Chapter 6

Data Structure Documentation

6.1 A Struct Reference

Data Fields

- double a
- int **b**
- char c
- float f
- int **i**

The documentation for this struct was generated from the following files:

- xx.c
- xx.cc

6.2 B Struct Reference

Data Fields

- double a
- int **b**
- char c
- · float f
- int **i**

The documentation for this struct was generated from the following file:

• xx.cc

6.3 basic_ntuple Struct Reference

A struct with basic per-shower parameters, to be used as an n-tuple in the event selection.

```
#include <basic_ntuple.h>
```

Data Fields

· int primary

Primary particle ID.

· int run

Simulation run number.

int event

Event number (100*shower number + array number)

· double weight

Event weight, not to be used for selection (based on true energy).

• double lg_e_true

log10(true energy of primary).

· double xfirst_true

Atmospheric depth of first interaction.

• double xmax_true

True shower maximum atmospheric depth (not well defined with few particles).

· double xc true

True core position at detection level (x coordinate).

· double yc_true

True core position at detection level (y coordinate).

· double az_true

True shower direction (Azimuth).

· double alt true

True shower direction (Altitude).

· double xc

Reconstructed core position at detection level (x coordinate).

· double yc

Reconstructed core position at detection level (y coordinate).

double az

Reconstructed shower direction (Azimuth).

double alt

Reconstructed shower direction (Altitude).

double rcm

Mean core distance of telescopes used in reconstruction.

· double mdisp

Mean DISP (1.

· double theta

Angle between source position and rec.

• double sig_theta

R.m.s.

· double mscrw

Mean scaled reduced width.

• double sig_mscrw

R.m.s.

• double mscrl

Mean scaled reduced length.

double sig_mscrl

R.m.s.

· double xmax

Depth of shower maximum.

• double sig_xmax

R.m.s.

• double lg_e

Log10 of reconstructed energy.

double sig_e

Relative error estimate on E (NOT the r.m.s.

· double chi2_e

Consistency of individual energy estimates as reduced chi**2 value.

· double tslope

Core distance corrected mean time slope (deg/ns/100 m).

· double tsphere

R.m.s.

size_t n_img

Number of used images.

size_t n_trg

Number of triggered telescopes.

size_t n_fail

Number of failed triggers (telescopes expected to trigger).

size_t n_tsl0

Number of images with zero time slope well outside light pool.

size_t n_pix

Total number of used pixels in all used images.

· size t acceptance

Event acceptance level by standard selection scheme (0: no; 1: shape cuts; 2: +angular cut; 3: +dE cut; 4: +dE2 cut; 5: +Hmax cut.

6.3.1 Detailed Description

A struct with basic per-shower parameters, to be used as an n-tuple in the event selection.

6.3.2 Field Documentation

6.3.2.1 size_t basic_ntuple::acceptance

Event acceptance level by standard selection scheme (0: no; 1: shape cuts; 2: +angular cut; 3: +dE cut; 4: +dE2 cut; 5: +Hmax cut.

Referenced by list_ntuple(), and user_event_fill().

6.3.2.2 double basic_ntuple::alt

Reconstructed shower direction (Altitude).

Referenced by list_ntuple(), and user_event_fill().

6.3.2.3 double basic_ntuple::alt_true

True shower direction (Altitude).

```
6.3.2.4 double basic_ntuple::az
Reconstructed shower direction (Azimuth).
Referenced by list_ntuple(), and user_event_fill().
6.3.2.5 double basic_ntuple::az_true
True shower direction (Azimuth).
Referenced by list_ntuple(), and user_event_fill().
6.3.2.6 double basic_ntuple::chi2_e
Consistency of individual energy estimates as reduced chi**2 value.
Referenced by list_ntuple(), and user_event_fill().
6.3.2.7 double basic_ntuple::lg_e
Log10 of reconstructed energy.
Referenced by list_ntuple(), main(), and user_event_fill().
6.3.2.8 double basic_ntuple::lg_e_true
log10(true energy of primary).
Referenced by list_ntuple(), and user_event_fill().
6.3.2.9 double basic_ntuple::mdisp
Mean DISP (1.
-width/length) of usable images.
Referenced by list_ntuple(), and user_event_fill().
6.3.2.10 double basic_ntuple::mscrl
Mean scaled reduced length.
Referenced by list_ntuple(), and user_event_fill().
6.3.2.11 double basic_ntuple::mscrw
Mean scaled reduced width.
Referenced by list_ntuple(), and user_event_fill().
6.3.2.12 size_t basic_ntuple::n_fail
Number of failed triggers (telescopes expected to trigger).
```

6.3.2.13 size_t basic_ntuple::n_img Number of used images. Referenced by list ntuple(), main(), and user event fill(). 6.3.2.14 size_t basic_ntuple::n_pix Total number of used pixels in all used images. Referenced by list_ntuple(), and user_event_fill(). 6.3.2.15 size_t basic_ntuple::n_trg Number of triggered telescopes. Referenced by list_ntuple(), and user_event_fill(). 6.3.2.16 size_t basic_ntuple::n_tsl0 Number of images with zero time slope well outside light pool. Referenced by list_ntuple(), and user_event_fill(). 6.3.2.17 int basic_ntuple::primary Primary particle ID. Referenced by list_ntuple(), and user_event_fill(). 6.3.2.18 double basic_ntuple::rcm Mean core distance of telescopes used in reconstruction. Referenced by list_ntuple(), and user_event_fill(). 6.3.2.19 int basic_ntuple::run Simulation run number. Referenced by list_ntuple(), and user_event_fill(). 6.3.2.20 double basic_ntuple::sig_e Relative error estimate on E (NOT the r.m.s. of individual estimates). Referenced by list_ntuple(), and user_event_fill(). 6.3.2.21 double basic_ntuple::sig_mscrl R.m.s. of scaled reduced lengths of indvidual images.

Generated on Thu Jun 25 2015 15:03:22 for hessio by Doxygen

```
double basic_ntuple::sig_mscrw
R.m.s.
of scaled reduced widths of individual images.
Referenced by list_ntuple(), and user_event_fill().
6.3.2.23 double basic_ntuple::sig_theta
R.m.s.
of theta of telescopes pairs (if > 2 tel.).
Referenced by list_ntuple(), and user_event_fill().
6.3.2.24 double basic_ntuple::sig_xmax
R.m.s.
of Xmax from individual telescopes/images.
Referenced by list_ntuple(), and user_event_fill().
6.3.2.25 double basic_ntuple::theta
Angle between source position and rec.
shower direction.
Referenced by list_ntuple(), and user_event_fill().
6.3.2.26 double basic_ntuple::tslope
Core distance corrected mean time slope (deg/ns/100 m).
Referenced by list ntuple(), and user event fill().
6.3.2.27
         double basic_ntuple::tsphere
R.m.s.
of trigger times from spherical propagation from shower max.
Referenced by list ntuple(), and user event fill().
6.3.2.28 double basic_ntuple::weight
Event weight, not to be used for selection (based on true energy).
Referenced by list_ntuple(), and user_event_fill().
6.3.2.29 double basic_ntuple::xc
Reconstructed core position at detection level (x coordinate).
```

6.3.2.30 double basic_ntuple::xc_true True core position at detection level (x coordinate). Referenced by list_ntuple(), and user_event_fill(). 6.3.2.31 double basic_ntuple::xfirst_true Atmospheric depth of first interaction. Referenced by list_ntuple(), and user_event_fill(). 6.3.2.32 double basic_ntuple::xmax Depth of shower maximum. Referenced by list_ntuple(), and user_event_fill(). 6.3.2.33 double basic_ntuple::xmax_true True shower maximum atmospheric depth (not well defined with few particles). Referenced by list_ntuple(), and user_event_fill(). 6.3.2.34 double basic_ntuple::yc Reconstructed core position at detection level (y coordinate). Referenced by list_ntuple(), and user_event_fill(). 6.3.2.35 double basic_ntuple::yc_true

True core position at detection level (y coordinate).


Referenced by list_ntuple(), and user_event_fill().

The documentation for this struct was generated from the following file:

• basic_ntuple.h

6.4 best_value Struct Reference

Collaboration diagram for best_value:



Public Member Functions

• **best_value** (int k, double v, int qtr, const string &t, double aeff, double vlgE, double vlgE1, double vlgE2, double vds, double vbr=0., double vgr=0., double var=0., double ver=0., double nb=0.)

Data Fields

- int kbin
- double best
- int **q**
- string text
- double A

effective area (for gammas)


- double IgE
- · double IgE1
- double IgE2
- · double diff_sens
- double bg_rate
- double gamma_rate
- · double angres
- double eres
- double n gamma cu
- double nint_gamma_cu
- double **n_bg**
- double nint_bg

The documentation for this struct was generated from the following file:

• best_of.cc

6.5 Binary_Interface_Chain Struct Reference

Collaboration diagram for Binary_Interface_Chain:



Data Fields

struct

Config_Binary_Item_Interface * interface

• struct Binary_Interface_Chain * next

The documentation for this struct was generated from the following file:

· hconfig.c

6.6 bunch Struct Reference

Photons collected in bunches of identical direction, position, time, and wavelength.

```
#include <mc_tel.h>
```

Data Fields

· float photons

Number of photons in bunch.

- float x
- float y

Arrival position relative to telescope (cm)

- float cx
- float cy

Direction cosines of photon direction.

float ctime

Arrival time (ns)

· float zem

Height of emission point above sea level (cm)

float lambda

Wavelength in nanometers or 0.

6.6.1 Detailed Description

Photons collected in bunches of identical direction, position, time, and wavelength.

The wavelength will normally be unspecified as produced by CORSIKA (lambda=0).

The documentation for this struct was generated from the following file:

· mc tel.h

6.7 compact_bunch Struct Reference

The compact_bunch struct is equivalent to the bunch struct except that we try to use less memory.

```
#include <mc tel.h>
```

Data Fields

```
· short photons
```

ph*100

- short x
- short y

x,y*10 (mm)

- short cx
- · short cy

cx,cy*30000

· short ctime

ctime* 10 (0.1ns) after subtracting offset

short log_zem

log10(zem)*1000

· short lambda

(nm) or 0

6.7.1 Detailed Description

The compact_bunch struct is equivalent to the bunch struct except that we try to use less memory.

And that has a number of limitations: 1) Bunch sizes must be less than 327. 2) photon impact points in a horizontal plane through the centre of each detector sphere must be less than 32.7 m from the detector centre in both x and y coordinates. Thus, $\sec(z)*R<32.7$ m is required, with 'z' being the zenith angle and 'R' the radius of the detecor sphere. When accounting for multiple scattering and Cherenkov emission angles, the actual limit is reached even earlier than that. 3) Only times within 3.27 microseconds from the time, when the primary particle propagated with the speed of light would cross the altitude of the sphere centre, can be treated. For large zenith angle observations this limits horizontal core distances to about 1000 m. For efficiency reasons, no checks are made on these limits.

The documentation for this struct was generated from the following file:

· mc tel.h

6.8 Config Binary Item Interface Struct Reference

Interface definitions for binary-only items.

```
#include <hconfig.h>
```

Data Fields

· int io_item_type

The eventio item type.

int elem_size

The size of the elements.

void *(* new_func)(int nelem, int item_type)

The function to be called for allocating elements.

int(* delete_func)(void *ptr, int nelem, int item_type)

The function to be called for deleting elements.

• int(* read_func)(void *bin_item, IO_BUFFER *iobuf, int item_type)

The function to be called for reading elements from buffer.

• int(* write_func)(void *bin_item, IO_BUFFER *iobuf, int item_type)

The function to be called for writing elements to buffer.

int(* readtext_func)(void *bin_item, char *text, int item_type)

The function to be called for reading elements from text line.

int(* list_func)(void *bin_item, int item_type)

The optional function for listing element contents.

• int(* copy func)(void *bin item to, void *bin item from, int io type)

The optional function for copying elements.

6.8.1 Detailed Description

Interface definitions for binary-only items.

Binary-only items are structures, classes, or unions which can only be filled via dedicated functions (methods) and not via the standard text-input.

This structure defines available interface methods. The item type is always passed to the functions, in case that a function can handle more than one type.

6.8.2 Field Documentation

6.8.2.1 int(* Config_Binary_Item_Interface::copy_func)(void *bin_item_to, void *bin_item_from, int io_type)

The optional function for copying elements.

This is only needed if the element includes pointers to external or dynamically allocated material.

Referenced by define_config_binary_interface().

6.8.2.2 int(* Config_Binary_Item_Interface::delete_func)(void *ptr, int nelem, int item_type)

The function to be called for deleting elements.

Referenced by define_config_binary_interface().

6.8.2.3 int Config_Binary_Item_Interface::elem_size

The size of the elements.

Referenced by define_config_binary_interface(), and init_config().

6.8.2.4 int Config_Binary_Item_Interface::io_item_type

The eventio item type.

Referenced by define_config_binary_interface(), find_config_binary_interface(), and init_config().

6.8.2.5 int(* Config_Binary_Item_Interface::list_func)(void *bin_item, int item_type)

The optional function for listing element contents.

Referenced by define_config_binary_interface().

6.8.2.6 void*(* Config_Binary_Item_Interface::new_func)(int nelem, int item_type)

The function to be called for allocating elements.

Referenced by define_config_binary_interface(), and init_config().

6.8.2.7 int(* Config_Binary_Item_Interface::read_func)(void *bin_item, IO_BUFFER *iobuf, int item_type)

The function to be called for reading elements from buffer.

Referenced by define config binary interface().

6.8.2.8 int(* Config_Binary_Item_Interface::readtext_func)(void *bin_item, char *text, int item_type)

The function to be called for reading elements from text line.

Referenced by define_config_binary_interface().

6.8.2.9 int(* Config_Binary_Item_Interface::write_func)(void *bin_item, IO_BUFFER *iobuf, int item_type)

The function to be called for writing elements to buffer.

Referenced by define_config_binary_interface().

The documentation for this struct was generated from the following file:

• hconfig.h

6.9 config_specific_data Struct Reference

Data Fields

• char default_section [65]


The documentation for this struct was generated from the following file:

· hconfig.c

6.10 ConfigBlockStruct Struct Reference

Configuration is organized in sections.

Collaboration diagram for ConfigBlockStruct:



Data Fields

- const char * section
- struct ConfigItemStruct * items
- struct ConfigBlockStruct * next
- int flag

6.10.1 Detailed Description

Configuration is organized in sections.

CONFIG_BLOCK used for bookkeeping of that.

The documentation for this struct was generated from the following file:

· hconfig.c

6.11 ConfigBoundary Union Reference

Configuration value may have optional lower and/or upper bounds.

#include <hconfig.h>

Data Fields

- · long Ival
- · unsigned long ulval
- double * rval

6.11.1 Detailed Description

Configuration value may have optional lower and/or upper bounds.

The documentation for this union was generated from the following file:

· hconfig.h

6.12 ConfigDataPointer Union Reference

This union of pointers allows convenient access of various types of data.

```
#include <hconfig.h>
```

Data Fields

- void * anything
- char * cdata
- unsigned char * ucdata
- short * sdata
- unsigned short * usdata
- int * idata
- unsigned int * uidata
- long * ldata
- unsigned long * uldata
- float * fdata
- double * ddata

6.12.1 Detailed Description

This union of pointers allows convenient access of various types of data.

The documentation for this union was generated from the following file:


· hconfig.h

6.13 ConfigIntern Struct Reference

Configuration elements used only internally.

```
#include <hconfig.h>
```

Collaboration diagram for ConfigIntern:



Data Fields

· int itype

Parameter type code.

int elem_size

Size of elements in bytes.

• int locked

Set to 1 if locked.

• int bound

Bits 0-3 set if lower soft, upper soft,.

• union ConfigBoundary Ibound_soft

Used for checking new values.

• union ConfigBoundary ubound_soft

Used for checking new values.

union ConfigBoundary Ibound_hard

Used for checking new values.

• union ConfigBoundary ubound_hard

Used for checking new values.

• struct ConfigValues values

Passed to user function.

struct

Config_Binary_Item_Interface * bin_interface

• int bin_alloc_elements

6.13.1 Detailed Description

Configuration elements used only internally.

6.13.2 Field Documentation 6.13.2.1 int ConfigIntern::bound Bits 0-3 set if lower soft, upper soft,. lower hard, or upper hard bound present. 6.13.2.2 int ConfigIntern::elem_size Size of elements in bytes. Referenced by init_config(). 6.13.2.3 int ConfigIntern::itype Parameter type code. Referenced by display_config_current(), display_config_item(), do_config(), init_config(), and set_config_values(). 6.13.2.4 union ConfigBoundary ConfigIntern::lbound_hard Used for checking new values. 6.13.2.5 union ConfigBoundary ConfigIntern::lbound_soft Used for checking new values. 6.13.2.6 int ConfigIntern::locked Set to 1 if locked. Referenced by display_config_item(), and reconfig(). 6.13.2.7 union ConfigBoundary ConfigIntern::ubound_hard Used for checking new values.

6.13.2.8 union ConfigBoundary ConfigIntern::ubound_soft

Used for checking new values.

6.13.2.9 struct ConfigValues ConfigIntern::values

Passed to user function.

Referenced by display_config_item(), do_config(), and init_config().

The documentation for this struct was generated from the following file:


· hconfig.h

6.14 ConfigItemStruct Struct Reference

Configuration as used in definitions of configuration blocks.

#include <hconfig.h>

Collaboration diagram for ConfigItemStruct:



Data Fields

• const char * name

Parameter/function name.

const char * type

Data/function type.

· int size

Number of elements.

void * data

Data pointer or NULL.

PFIX function

Associated function or NULL.

const char * initial

Initial values/argument or NULL.

const char * Ibound

Lower bound (soft,hard) on values or NULL.

const char * ubound

Upper bound (soft,hard) on values or NULL.

int flags

Additional flag bits.

· PFISS validate

Function to validate if change is possible or NULL.

void * res1

Placeholder to keep structure size the same.

void * res2

Not used.

· struct ConfigIntern internal

Internal data.

6.14.1 Detailed Description

Configuration as used in definitions of configuration blocks.

6.14.2 Field Documentation

6.14.2.1 void* ConfigltemStruct::data

Data pointer or NULL.

Referenced by display_config_current(), do_config(), init_config(), and set_config_values().

6.14.2.2 int ConfightemStruct::flags

Additional flag bits.

Referenced by display_config_item(), do_config(), init_config(), and set_config_values().

6.14.2.3 PFIX ConfightemStruct::function

Associated function or NULL.

Referenced by display_config_item(), and do_config().

6.14.2.4 const char* ConfigltemStruct::initial

Initial values/argument or NULL.

Referenced by display_config_item(), and init_config().

6.14.2.5 struct ConfigIntern ConfigItemStruct::internal

Internal data.

Referenced by display_config_current(), display_config_item(), do_config(), init_config(), reconfig(), and set_config_values().

6.14.2.6 const char* ConfigltemStruct::lbound

Lower bound (soft,hard) on values or NULL.

Referenced by display_config_item(), init_config(), and set_config_values().

6.14.2.7 const char* ConfigltemStruct::name

Parameter/function name.

Referenced by display_config_item(), do_config(), f_show_config(), find_config_item(), init_config(), reconfig(), and set_config_values().

6.14.2.8 void* ConfigItemStruct::res1

Placeholder to keep structure size the same.

6.14.2.9 void* ConfightemStruct::res2

Not used.

6.14.2.10 int ConfigltemStruct::size

Number of elements.

Referenced by display_config_current(), display_config_item(), do_config(), init_config(), and set_config_values().

6.14.2.11 const char* ConfigltemStruct::type

Data/function type.

Referenced by display_config_item(), do_config(), and init_config().

6.14.2.12 const char* ConfigltemStruct::ubound

Upper bound (soft,hard) on values or NULL.

Referenced by display_config_item(), init_config(), and set_config_values().

6.14.2.13 PFISS ConfightemStruct::validate

Function to validate if change is possible or NULL.

The documentation for this struct was generated from the following file:

· hconfig.h

6.15 ConfigValues Struct Reference

Configuration values and supporting data passed to user functions.

#include <hconfig.h>

Data Fields

void * data_changed

Pointer to the updated values.

void * data_saved

Pointer to the saved values.

· int max mod

How many elements can, at most, be modified.

int nmod

How many have been modified.

int * list mod

List of indices to modified elements.

unsigned char * mod_flag

Vector of size max_mod indicating modified elements.

· int itype

Internal item type representation.

• const char * name

The name of the element.

• const char * section

The section to which it belongs.

· int elements

The number of elements it has.

• int elem_size

The size of one element in bytes.

· int binary_config

Set to one if binary configuration was used.

6.15.1 Detailed Description

Configuration values and supporting data passed to user functions.

6.15.2 Field Documentation

6.15.2.1 int ConfigValues::binary_config

Set to one if binary configuration was used.

6.15.2.2 void* ConfigValues::data_changed

Pointer to the updated values.

Referenced by init_config().

6.15.2.3 void* ConfigValues::data_saved

Pointer to the saved values.

Referenced by do_config(), and init_config().

6.15.2.4 int ConfigValues::elem_size

The size of one element in bytes.

Referenced by display_config_item(), do_config(), and init_config().

6.15.2.5 int ConfigValues::elements

The number of elements it has.

Referenced by init_config().

6.15.2.6 int ConfigValues::itype

Internal item type representation.

Referenced by init_config().

6.15.2.7 int * ConfigValues::list_mod

List of indices to modified elements.

Referenced by do_config(), and init_config().

6.15.2.8 int ConfigValues::max_mod

How many elements can, at most, be modified.

Referenced by do_config(), and init_config().

6.15.2.9 unsigned char* ConfigValues::mod_flag

Vector of size max_mod indicating modified elements.

Referenced by do_config(), and init_config().

6.15.2.10 const char* ConfigValues::name

The name of the element.

Referenced by init_config().

6.15.2.11 int ConfigValues::nmod

How many have been modified.

Referenced by do_config().

6.15.2.12 const char* ConfigValues::section

The section to which it belongs.

Referenced by init_config().

The documentation for this struct was generated from the following file:

· hconfig.h

6.16 ebias_cor_data Struct Reference

Data Fields

- int ndat
- double * IgE
- double * IgDE

The documentation for this struct was generated from the following file:

· user_analysis.c

6.17 ev_reg_chain Struct Reference

Use a double-linked list for the registry.

Collaboration diagram for ev_reg_chain:



Data Fields

• struct ev_reg_entry * entry

The current entry.

- struct ev_reg_chain * prev
- struct ev_reg_chain * next

6.17.1 Detailed Description

Use a double-linked list for the registry.

The documentation for this struct was generated from the following file:


• eventio_registry.c

6.18 hess_all_data_struct Struct Reference

Container for all H.E.S.S.

#include <io_hess.h>

Collaboration diagram for hess_all_data_struct:



Data Fields

- RunHeader run header
- MCRunHeader mc_run_header
- CameraSettings camera_set [H_MAX_TEL]
- CameraOrganisation camera_org [H_MAX_TEL]
- PixelSetting pixel_set [H_MAX_TEL]
- PixelDisabled pixel_disabled [H_MAX_TEL]
- CameraSoftSet cam_soft_set [H_MAX_TEL]
- TrackingSetup tracking_set [H_MAX_TEL]
- PointingCorrection point_cor [H_MAX_TEL]
- FullEvent event
- MCShower mc_shower
- MCEvent mc_event
- TelMoniData tel_moni [H_MAX_TEL]
- LasCalData tel_lascal [H_MAX_TEL]
- RunStat run_stat
- MCRunStat mc_run_stat

6.18.1 Detailed Description

Container for all H.E.S.S.

data

The documentation for this struct was generated from the following file:

· io_hess.h

6.19 hess_camera_organisation_struct Struct Reference

Logical organisation of camera electronics channels.

```
#include <io hess.h>
```

Data Fields

· int tel id

Telescope ID.

int num_pixels

Number of pixels in camera.

• int num_drawers

Number of drawers (mechanical units) in camera.

· int num gains

Number of gains per PM.

· int num_sectors

Number of sectors (trigger groups).

• int drawer [H_MAX_PIX]

Drawer assignment for each pixel.

- int card [H MAX PIX][H MAX GAINS]
- int chip [H MAX PIX][H MAX GAINS]
- int channel [H_MAX_PIX][H_MAX_GAINS]
- int nsect [H_MAX_PIX]

Number of sectors (trigger groups) for trigger(s).

• int sectors [H_MAX_PIX][H_MAX_PIXSECTORS]

Pixels in sectors (trigger groups).

• int sector_type [H_MAX_SECTORS]

0: majority, 1: analog sum, 2: digital sum

• double sector_threshold [H_MAX_SECTORS]

Multiplicity or sum threshold applied to sector. [mV ?].

double sector_pixthresh [H_MAX_SECTORS]

Pixel threshold for majority or clipping limit for sum triggers. [mV ?].

6.19.1 Detailed Description

Logical organisation of camera electronics channels.

The documentation for this struct was generated from the following file:

• io_hess.h

6.20 hess_camera_settings_struct Struct Reference

Definition of camera optics settings.

```
#include <io_hess.h>
```

Data Fields

· int tel id

Telescope ID.

int num_pixels

Number of pixels in camera.

double xpix [H_MAX_PIX]

Pixel x position in camera [m].

double ypix [H_MAX_PIX]

Pixel y position in camera [m].

double zpix [H_MAX_PIX]

Pixel z position w.r.t. focal plane in camera center [m]. {new}.

double nxpix [H_MAX_PIX]

Pixel pointing direction (nx,ny,1) x component. {new}.

double nypix [H_MAX_PIX]

Pixel pointing direction (nx,ny,1) y component. {new}.

double area [H_MAX_PIX]

Pixel active area ([$m^{\wedge}2$]).

• double size [H MAX PIX]

Pixel diameter (flat-to-flat, [m]).

int pixel_shape [H_MAX_PIX]

Pixel shape type (0: circ., 1,3: hex, 2: square, -1: unknown). {new}.

· double cam_rot

Rotation angle of camera (counter-clock-wise from back side for prime focus camera).

· double flen

Focal length of optics [m].

• int num_mirrors

Number of mirror tiles.

• double mirror_area

Total area of individual mirrors corrected for inclination [m^{\wedge} 2].

· int curved surface

0 for flat surface, 1 for curved surface. {new}

• int pixels_parallel

0 if (some) pixels are inclined, 1 if all pixels are parallel {new}

int common_pixel_shape

instead of individual pixel shape if al pixels are the same. {new}

6.20.1 Detailed Description

Definition of camera optics settings.

6.20.2 Field Documentation

6.20.2.1 double hess_camera_settings_struct::mirror_area

Total area of individual mirrors corrected for inclination [m $^{\wedge}$ 2].

Referenced by read_hess_camsettings(), user_init(), which_telescope_type(), and write_hess_camsettings().

The documentation for this struct was generated from the following file:

· io_hess.h

6.21 hess_camera_software_setting_struct Struct Reference

Software settings used in camera process.

```
#include <io_hess.h>
```

Data Fields

• int tel id

The telescope ID number (1 ... n)

- · int dyn_trig_mode
- int dyn_trig_threshold
- int dyn_HV_mode
- int dyn_HV_threshold
- · int data_red_mode

The desired data reduction mode.

int zero_sup_mode

The desired zero suppression mode.

· int zero_sup_num_thr

The number of thresholds to be used by z.s.

• int zero_sup_thresholds [10]

Threshold values to be used by z.s.

- · int unbiased scale
- int dyn_ped_mode
- int dyn_ped_events
- int dyn_ped_period

[ms]

· int monitor_cur_period

[ms]

• int report_cur_period

[ms]

· int monitor_HV_period

[ms]

int report_HV_period

[ms]

6.21.1 Detailed Description

Software settings used in camera process.

6.21.2 Field Documentation

6.21.2.1 int hess_camera_software_setting_struct::zero_sup_mode

The desired zero suppression mode.

The mode actually used may depend on the data.

Referenced by read_hess_camsoftset(), and write_hess_camsoftset().

The documentation for this struct was generated from the following file:


• io_hess.h

6.22 hess_central_event_data_struct Struct Reference

Central trigger event data.

#include <io_hess.h>

Collaboration diagram for hess_central_event_data_struct:



Data Fields

int glob_count

Global event count.

HTime cpu_time

CPU time at central trigger station.

• HTime gps_time

GPS time at central trigger station.

int teltrg_pattern

Bit pattern of telescopes having sent a trigger signal to the central station.

• int teldata_pattern

Bit pattern of telescopes having sent event data that could be merged.

· int num_teltrg

How many telescopes triggered.

int teltrg_list [H_MAX_TEL]

List of IDs of triggered telescopes.

float teltrg_time [H_MAX_TEL]

Relative time of trigger signal.

int teltrg_type_mask [H_MAX_TEL]

Bit mask which type of trigger fired.

float teltrg_time_by_type [H_MAX_TEL][3]

Time of trigger separate for each type.

• int num_teldata

Number of telescopes expected to have data.

• int teldata_list [H_MAX_TEL]

List of IDs of telescopes with data.

6.22.1 Detailed Description

Central trigger event data.

6.22.2 Field Documentation

6.22.2.1 int hess_central_event_data_struct::teldata_pattern

Bit pattern of telescopes having sent event data that could be merged.

(Historical; only useful for small no. of telescopes.)

Referenced by calibrate_amplitude(), merge_data_from_io_block(), read_hess_centralevent(), read_hess_event(), and write_hess_centralevent().

6.22.2.2 int hess_central_event_data_struct::teltrg_pattern

Bit pattern of telescopes having sent a trigger signal to the central station.

(Historical; only useful for small no. of telescopes.)

Referenced by calibrate_amplitude(), merge_data_from_io_block(), read_hess_centralevent(), read_hess_event(), and write_hess_centralevent().

6.22.2.3 float hess_central_event_data_struct::teltrg_time[H_MAX_TEL]

Relative time of trigger signal.

after correction for nominal delay [ns].

The documentation for this struct was generated from the following file:


• io_hess.h

6.23 hess_event_data_struct Struct Reference

All data for one event.

#include <io_hess.h>

Collaboration diagram for hess_event_data_struct:



Data Fields

• int num_tel

Number of telescopes in run.

· CentralEvent central

Central trigger data and data pattern.

TelEvent teldata [H_MAX_TEL]

Raw and/or image data.

TrackEvent trackdata [H_MAX_TEL]

Interpolated tracking data.

· ShowerParameters shower

Reconstructed shower parameters.

• int num_teldata

Number of telescopes for which we actually have data.

• int teldata_list [H_MAX_TEL]

List of IDs of telescopes with data.

6.23.1 Detailed Description

All data for one event.

The documentation for this struct was generated from the following file:

· io_hess.h

6.24 hess_laser_calib_data_struct Struct Reference

Laser calibration data.

#include <io_hess.h>

Data Fields

· int known

Are the calibration values known?

int tel id

Telescope ID.

· int num_pixels

Number of pixels.

· int num gains

Number of gains.

· int lascal id

Laser calibration ID.

• double calib [H_MAX_GAINS][H_MAX_PIX]

ADC to laser/LED p.e.

double max_int_frac [H_MAX_GAINS]

Maximum fraction of the signal which can be in the fixed integration window.

double max_pixtm_frac [H_MAX_GAINS]

Maximum fraction of the signal which can be in the pixel timing integration.

double tm_calib [H_MAX_GAINS][H_MAX_PIX]

6.24.1 Detailed Description

Laser calibration data.

6.24.2 Field Documentation

6.24.2.1 double hess_laser_calib_data_struct::calib[H MAX GAINS][H_MAX_PIX]

ADC to laser/LED p.e.

conversion, in [mean p.e.], details depending on calibration procedure.

Referenced by calibrate_amplitude(), calibrate_pixel_amplitude(), main(), read_hess_laser_calib(), and write_hess_laser_calib().

6.24.2.2 double hess_laser_calib_data_struct::max_int_frac[H_MAX_GAINS]

Maximum fraction of the signal which can be in the fixed integration window.

Referenced by read hess laser calib(), and write hess laser calib().

6.24.2.3 double hess_laser_calib_data_struct::max_pixtm_frac[H_MAX_GAINS]

Maximum fraction of the signal which can be in the pixel timing integration.

Referenced by read_hess_laser_calib(), and write_hess_laser_calib().

The documentation for this struct was generated from the following file:


· io_hess.h

6.25 hess_mc_event_struct Struct Reference

Monte Carlo event-specific data.

#include <io_hess.h>

Collaboration diagram for hess_mc_event_struct:



Data Fields

int event

Event number -> global counter.

· int shower_num

Shower number as in shower structure.

· double xcore

Core position w.r.t. array reference point [m],.

· double ycore

$$x -> N, y -> W.$$

· double aweight

Area weight (units: [m**2]) in case of non-uniform sampling, normally counted in the shower plane and normalized such that the sum over all events for a shower should, on average, be the area over which core offsets are thrown (see also num_use and core_range in MCRunHeader).

double photons [H_MAX_TEL]

The CORSIKA photon sum into fiducial volume.

• struct hess_mc_pe_sum_struct mc_pesum

Numbers of / sums of photo-electrons.

• struct hess_mc_photons mc_photons [H_MAX_TEL]

Raw simulated photons.

struct hess_mc_pe_list mc_pe_list [H_MAX_TEL]

List of detected photo-electrons.

6.25.1 Detailed Description

Monte Carlo event-specific data.

6.25.2 Field Documentation

6.25.2.1 double hess_mc_event_struct::aweight

Area weight (units: [m**2]) in case of non-uniform sampling, normally counted in the shower plane and normalized such that the sum over all events for a shower should, on average, be the area over which core offsets are thrown (see also num use and core range in MCRunHeader).

It may be zero for uniform sampling.

Referenced by merge_data_from_io_block(), read_hess_mc_event(), and write_hess_mc_event().

The documentation for this struct was generated from the following file:

· io hess.h

6.26 hess_mc_pe_list Struct Reference

Photo-electrons from Monte Carlo individually.

```
#include <io_hess.h>
```

Data Fields

int npe

The number of all photo-electrons in the telescope.

· int pixels

The number of pixels in the camera.

· int flags

Bit 0: with amplitudes, bit 1: includes NSB.

• int pe count [H MAX PIX]

The numbers of p.e. at each pixel.

int itstart [H_MAX_PIX]

The start index for each pixel in the sequential atimes vector.

· double * atimes

The list of start times of all photo-eletrons.

• double * amplitudes

Optional list of matching amplitudes [mean p.e.].

• int max_npe

How many p.e. we can store in the atimes (+amplitudes) vector(s).

6.26.1 Detailed Description

Photo-electrons from Monte Carlo individually.

The documentation for this struct was generated from the following file:

· io_hess.h

6.27 hess mc pe sum struct Struct Reference

Sums of photo-electrons in MC (total and per pixel).

```
#include <io_hess.h>
```

Data Fields

· int event

Event number -> global counter.

· int shower_num

Shower number as in shower structure.

• int num tel

Number of telescopes simulated.

int num_pe [H_MAX_TEL]

Number of photo-electrons per telescope.

int num_pixels [H_MAX_TEL]

Pixels per telescope or 0.

int pix_pe [H_MAX_TEL][H_MAX_PIX]

Photo-electrons per pixel (without NSB).

double photons [H_MAX_TEL]

The sum of the photon content of all bunches.

double photons_atm [H_MAX_TEL]

Photons surviving atmospheric transmission.

double photons_atm_3_6 [H_MAX_TEL]

Photons surv. atm. tr. in the 300 to 600 nm range.

• double photons_atm_400 [H_MAX_TEL]

Photons surv. atm. tr. in the 350 to 450 nm range.

double photons_atm_qe [H_MAX_TEL]

Photons surviving atmospheric transmission, mirror reflectivity (except funnel), and Q.E.

6.27.1 Detailed Description

Sums of photo-electrons in MC (total and per pixel).

6.27.2 Field Documentation

6.27.2.1 double hess_mc_pe_sum_struct::photons_atm_qe[H_MAX_TEL]

Photons surviving atmospheric transmission, mirror reflectivity (except funnel), and Q.E.

Referenced by merge_data_from_io_block(), read_hess_mc_event(), read_hess_mc_pe_sum(), and write_hess_mc_pe_sum().

The documentation for this struct was generated from the following file:


· io hess.h

6.28 hess_mc_photons Struct Reference

Photons from Monte Carlo.

#include <io_hess.h>

Collaboration diagram for hess_mc_photons:



Data Fields

• struct bunch * bunches

Bunches of photons.

· int nbunches

How many photon bunches we have at this telescope.

• int max_bunches

How many we can store in 'bunches' vector above.

· double photons

The sum of the photon content of all bunches.

6.28.1 Detailed Description

Photons from Monte Carlo.

The documentation for this struct was generated from the following file:

· io_hess.h

6.29 hess_mc_run_header_struct Struct Reference

MC run header.

```
#include <io_hess.h>
```

Data Fields

int shower_prog_id

Recorded data:

• int shower_prog_vers

version * 1000

time_t shower_prog_start

Time when shower simulation of run started (CORSIKA: only date)

· int detector_prog_id

sim_telarray=1, ...

int detector_prog_vers

version * 1000

· time t detector prog start

Time when detector simulation of run started.

· double obsheight

Height of simulated observation level.

· int num showers

Number of showers (intended to be) simulated.

· int num use

Number of uses of each shower.

int core_pos_mode

Core position fixed/circular/rectangular/...

• double core_range [2]

rmin+rmax or dx+dy [m].

• double az_range [2]

Range of shower azimuth [rad, N-> E].

• double alt_range [2]

Range of shower altitude [rad].

· int diffuse

Diffuse mode off/on.

• double viewcone [2]

Min.+max. opening angle for diffuse mode [degrees] (was always in degrees despite earlier '[rad]' comment).

double E range [2]

Energy range [TeV] of simulated showers.

double spectral_index

Power-law spectral index of spectrum (<0).

• double B_total

Total geomagnetic field assumed [microT].

• double B_inclination

Inclination of geomagnetic field [rad].

• double B_declination

Declination of geomagnetic field [rad].

• double injection_height

Height of particle injection [m].

double fixed_int_depth

Fixed depth of first interaction or 0 [g/cm\2].

· int atmosphere

Atmospheric model number.

- int corsika_iact_options
- int corsika_low_E_model
- · int corsika high E model
- double corsika_bunchsize
- double corsika_wlen_min
- double corsika_wlen_max
- int corsika_low_E_detail
- int corsika_high_E_detail

6.29.1 Detailed Description

MC run header.

6.29.2 Field Documentation

6.29.2.1 int hess_mc_run_header_struct::shower_prog_id

Recorded data:

CORSIKA=1, ALTAI=2, KASCADE=3, MOCCA=4.

Referenced by read_hess_mcrunheader(), and write_hess_mcrunheader().

The documentation for this struct was generated from the following file:

· io_hess.h

6.30 hess_mc_shower_profile_struct Struct Reference

Monte Carlo shower profile (sort of histogram).

```
#include <io_hess.h>
```

Data Fields

• int id

Type of profile (also determines units below).

• int num_steps

Number of histogram steps.

· int max_steps

Number of allowed steps as allocated for content.

· double start

Start of ordinate ([m] or [g/cm²])

• double end

End of it.

· double binsize

(End-Start)/num_steps; not saved

double * content

Histogram contents (allocated on demand).

6.30.1 Detailed Description

Monte Carlo shower profile (sort of histogram).

6.30.2 Field Documentation

6.30.2.1 int hess_mc_shower_profile_struct::id

Type of profile (also determines units below).

Temptative definitions:

- 1000*k + 1: Profile of all charged particles.
- 1000*k + 2: Profile of electrons+positrons.
- 1000*k + 3: Profile of muons.

- 1000*k + 4: Profile of hadrons.
- 1000*k + 10: Profile of Cherenkov photon emission [1/m].

The value of k specifies the binning:

- k = 0: The profile is in terms of atmospheric depth along the shower axis.
- k = 1: in terms of vertical atmospheric depth.
- k = 2: in terms of altitude [m] above sea level.

Referenced by read hess mc shower(), and write hess mc shower().

The documentation for this struct was generated from the following file:


• io_hess.h

6.31 hess_mc_shower_struct Struct Reference

Shower specific data.

#include <io_hess.h>

Collaboration diagram for hess_mc_shower_struct:



Data Fields

- · int shower num
- · int primary_id

Particle ID of primary.

· double energy

primary energy [TeV]

· double azimuth

Azimuth (N->E) [rad].

· double altitude

Altitude [rad].

· double depth_start

Atmospheric depth where particle started [g/cm $^{\wedge}$ 2].

· double h_first_int

height of first interaction a.s.l. [m]

· double xmax

Atmospheric depth of shower maximum [g/cm\^2], derived from all charged particles.

· double hmax

Height of shower maximum [m] in xmax.

· double emax

Atm. depth of maximum in electron number.

· double cmax

Atm. depth of max. in Cherenkov photon emission.

• int num_profiles

Number of profiles filled.

- ShowerProfile profile [H_MAX_PROFILE]
- struct shower_extra_parameters extra_parameters

6.31.1 Detailed Description

Shower specific data.

6.31.2 Field Documentation

6.31.2.1 int hess_mc_shower_struct::primary_id

Particle ID of primary.

Was in CORSIKA convention where detector_prog_vers in MC run header was 0, and is now 0 (gamma), 1(e-), 2(mu-), 100*A+Z for nucleons and nuclei, negative for antimatter.

Referenced by hesscam_ps_plot(), main(), merge_data_from_io_block(), read_hess_mc_shower(), user_event_fill(), user_finish(), user_init(), and write_hess_mc_shower().

6.31.2.2 double hess_mc_shower_struct::xmax

Atmospheric depth of shower maximum [g/cm²], derived from all charged particles.

Referenced by main(), read_hess_mc_shower(), second_moments(), user_event_fill(), and write_hess_mc_shower().

The documentation for this struct was generated from the following file:

• io_hess.h

6.32 hess_pixel_calibrated_struct Struct Reference

Data Fields

· int known

is calibrated pixel data known?

int tel_id

Telescope ID.

· int num pixels

Pixels in camera: list should be in this range.

int int_method

-2 (timing local peak), -1 (timing global peak), >=0 (integration scheme, if known)

int list_known

Was list of significant pixels filled in? 1: use list, 2: all pixels significant.

· int list_size

Size of the list of available pixels (with list mode).

int pixel_list [H_MAX_PIX]

List of available pixels (with list mode).

uint8_t significant [H_MAX_PIX]

Was amplitude large enough to record it?

float pixel_pe [H_MAX_PIX]

Calibrated & flat-fielded pixel intensity [p.e.].

The documentation for this struct was generated from the following file:

· io hess.h

6.33 hess_pixel_disabled_struct Struct Reference

Pixels disabled in HV and/or trigger.

```
#include <io_hess.h>
```

Data Fields

• int tel id

The telescope ID number (1 ... n)

- int num_trig_disabled
- int trigger_disabled [H MAX PIX]
- int num_HV_disabled
- int **HV_disabled** [H_MAX_PIX]

6.33.1 Detailed Description

Pixels disabled in HV and/or trigger.

The documentation for this struct was generated from the following file:

• io hess.h

6.34 hess_pixel_list Struct Reference

Lists of pixels (triggered, selected, etc.)

```
#include <io_hess.h>
```

Data Fields

int code

Indicates what sort of list this is: 0 (triggered pixel), 1 (selected pixel), ...

int pixels

The size of the pixels in this list.

int pixel_list [H_MAX_PIX]

The actual list of pixel numbers.

6.34.1 Detailed Description

Lists of pixels (triggered, selected, etc.)

6.34.2 Field Documentation

```
6.34.2.1 int hess_pixel_list::code
```

Indicates what sort of list this is: 0 (triggered pixel), 1 (selected pixel), ...

Referenced by merge data from io block(), read hess pixel list(), and write hess pixel list().

The documentation for this struct was generated from the following file:

· io_hess.h

6.35 hess_pixel_setting_struct Struct Reference

Settings of pixel HV and thresholds.

```
#include <io_hess.h>
```

Data Fields

· int tel id

The telescope ID number (1 ... n)

- · int setup_id
- int trigger_mode
- int min_pixel_mult

The minimum number of pixels in a camera.

int num_pixels

Local copy of the number of pixels.

int pixel_HV_DAC [H_MAX_PIX]

High voltage DAC values set.

int num_drawers

Local copy of the number of drawers in the camera.

int threshold_DAC [H_MAX_DRAWERS]

Threshold DAC values set.

- int ADC_start [H_MAX_DRAWERS]
- int ADC_count [H_MAX_DRAWERS]
- double time_slice

Width of readout time slice (i.e. one sample) [ns].

• int sum_bins

Standard integration over so many time slices.

· int nrefshape

Number of following reference pulse shapes (num_gains or 0)

· int Irefshape

Length of following reference pulse shape(s).

double refshape [H_MAX_GAINS][H_MAX_FSHAPE]

Reference pulse shape(s).

· double ref_step

Time step between refshape entries [ns].

6.35.1 Detailed Description

Settings of pixel HV and thresholds.

The documentation for this struct was generated from the following file:

· io_hess.h

6.36 hess_pixel_timing_struct Struct Reference

Data Fields

· int known

is pixel timing data known?

• int tel_id

Telescope ID.

• int num_pixels

Pixels in camera: list should be in this range.

· int num_gains

Number of different gains per pixel.

int list_type

0: not set; 1: individual pixels; 2: pixel ranges.

· int list size

The size of the pixels in this list.

int pixel_list [2 *H_MAX_PIX]

The actual list of pixel numbers.

· int threshold

Minimum base-to-peak raw amplitude difference applied in pixel selection.

int before_peak

Number of bins before peak being summed up.

· int after_peak

Number of bins after peak being summed up.

• int num_types

How many different types of times can we store?

int time_type [H_MAX_PIX_TIMES]

Which types come in which order.

float time_level [H_MAX_PIX_TIMES]

The width and startpos types apply.

· float granularity

Actually stored are the following timvals divided by granularity, as 16-bit integers.

float peak_global

Camera-wide (mean) peak position [time slices].

• float timval [H_MAX_PIX][H_MAX_PIX_TIMES]

Only the first 'pixels'.

int pulse_sum_loc [H_MAX_GAINS][H_MAX_PIX]

Amplitude sum around.

• int pulse_sum_glob [H_MAX_GAINS][H_MAX_PIX]

Amplitude sum around.

6.36.1 Field Documentation

6.36.1.1 float hess_pixel_timing_struct::granularity

Actually stored are the following timvals divided by granularity, as 16-bit integers.

Set this to e.g. 0.25 for a 0.25 time slice stepping.

Referenced by merge_data_from_io_block(), read_hess_pixtime(), and write_hess_pixtime().

6.36.1.2 int hess_pixel_timing_struct::pulse_sum_glob[H_MAX_GAINS][H_MAX_PIX]

Amplitude sum around.

global peak; for all pixels. Ped. subtracted. Only present if before&after_peak>=0 and if list is of size>0 (otherwise no peak).

Referenced by calibrate_amplitude(), calibrate_pixel_amplitude(), merge_data_from_io_block(), read_hess_pixtime(), and write_hess_pixtime().

6.36.1.3 int hess_pixel_timing_struct::pulse_sum_loc[H_MAX_GAINS][H_MAX_PIX]

Amplitude sum around.

local peak, for pixels in list. Ped. subtr. Only present if before&after_peak>=0.

Referenced by calibrate_amplitude(), calibrate_pixel_amplitude(), merge_data_from_io_block(), read_hess_pixtime(), and write hess pixtime().

6.36.1.4 int hess_pixel_timing_struct::threshold

Minimum base-to-peak raw amplitude difference applied in pixel selection.

Referenced by calibrate_amplitude(), calibrate_pixel_amplitude(), merge_data_from_io_block(), read_hess_pixtime(), and write_hess_pixtime().

6.36.1.5 float hess_pixel_timing_struct::time_level[H_MAX_PIX_TIMES]

The width and startpos types apply.

above some fraction from base to peak.

Referenced by merge_data_from_io_block(), pixel_timing_analysis(), read_hess_pixtime(), and write_hess_pixtime().

6.36.1.6 float hess_pixel_timing_struct::timval[H_MAX_PIX][H_MAX_PIX_TIMES]

Only the first 'pixels'.

elements are actually filled and stored. Others are undefined.

 $Referenced \ by \ build_list_for_hess_pixtime(), \ calibrate_amplitude(), \ calibrate_pixel_amplitude(), \ merge_data_from_io_block(), \ pixel_timing_analysis(), \ read_hess_pixtime(), \ write_hess_pixtime(), \ and \ write_hess_televent().$

The documentation for this struct was generated from the following file:

· io_hess.h

6.37 hess_pointing_correction_struct Struct Reference

Pointing correction parameters.

```
#include <io_hess.h>
```

Data Fields

• int tel id

The telescope ID number (1 ... n)

- int function_type
- int num_param
- double pointing_param [20]

6.37.1 Detailed Description

Pointing correction parameters.

The documentation for this struct was generated from the following file:

· io_hess.h

6.38 hess_run_end_mc_statistics_struct Struct Reference

MC end-of-run statistics.

```
#include <io_hess.h>
```

Data Fields

• int run_num

Run number.

int num_showers

Number of simulated showers found.

• int num_events

Number of MC events found.

6.38.1 Detailed Description

MC end-of-run statistics.

The documentation for this struct was generated from the following file:

• io_hess.h

6.39 hess_run_end_statistics_struct Struct Reference

End-of-run statistics.

```
#include <io_hess.h>
```

Data Fields

· int run num

Run number.

· int num tel

Number of telescopes used.

int tel_ids [H_MAX_TEL]

IDs of all telescopes.

· int num_central_trig

Number of system triggers.

• int num_local_trig [H_MAX_TEL]

Number of local telescope triggers.

int num_local_sys_trig [H_MAX_TEL]

Number of valid telescope triggers.

• int num_events [H_MAX_TEL]

Number of events read out.

6.39.1 Detailed Description

End-of-run statistics.

The documentation for this struct was generated from the following file:

• io_hess.h

6.40 hess_run_header_struct Struct Reference

Run header common to measured and simulated data.

```
#include <io_hess.h>
```

Data Fields

• int run

Recorded data:

• time_t time

Time of run start [UTC sec since 1970.0].

• int run_type

Data/pedestal/laser/muon run or MC run: MC run: -1, Data run: 1, Pedestal run: 2, Laser run: 3, Muon run: 4.

· int tracking_mode

Tracking/pointing mode: 0: Az/Alt, 1: R.A.

· int reverse_flag

Normal or reverse tracking: 0: Normal, 1: reverse.

· double direction [2]

Tracking/pointing direction in [radians]: [0]=Azimuth, [1]=Altitude in mode 0, [0]=R.A., [1]=Declination in mode 1.

double offset_fov [2]

Offset of pointing dir.

· double conv_depth

Atmospheric depth of convergence point.

• double conv_ref_pos [2]

Reference position for convergent pointing.

• int ntel

Number of telescopes involved.

int tel_id [H_MAX_TEL]

ID numbers of telescopes used in this run.

double tel_pos [H_MAX_TEL][3]

x,y,z positions of the telescopes [m].

int min_tel_trig

Minimum number of tel. in system trigger.

· int duration

Nominal duration of run [s].

• char * target

Primary target object name.

• char * observer

Observer(s) starting or supervising run.

int max_len_target

For internal data handling only:

• int max len observer

6.40.1 Detailed Description

Run header common to measured and simulated data.

6.40.2 Field Documentation

6.40.2.1 double hess_run_header_struct::conv_depth

Atmospheric depth of convergence point.

Referenced by merge_data_from_io_block(), read_hess_runheader(), and write_hess_runheader().

6.40.2.2 double hess_run_header_struct::conv_ref_pos[2]

Reference position for convergent pointing.

X,y in [m] at the telescope reference height.

Referenced by merge data from io block(), read hess runheader(), and write hess runheader().

6.40.2.3 double hess_run_header_struct::direction[2]

Tracking/pointing direction in [radians]: [0]=Azimuth, [1]=Altitude in mode 0, [0]=R.A., [1]=Declination in mode 1.

Referenced by mc_event_fill(), merge_data_from_io_block(), read_hess_runheader(), shower_reconstruct(), user_init(), and write_hess_runheader().

6.40.2.4 double hess_run_header_struct::offset_fov[2]

Offset of pointing dir.

in camera f.o.v. divided by focal length, i.e. converted to [radians]: [0]=Camera x (downwards in normal pointing, i.e. increasing Alt, [1]=Camera y -> Az).

Referenced by merge_data_from_io_block(), read_hess_runheader(), and write_hess_runheader().

6.40.2.5 int hess_run_header_struct::reverse_flag

Normal or reverse tracking: 0: Normal, 1: reverse.

Referenced by merge_data_from_io_block(), read_hess_runheader(), and write_hess_runheader().

6.40.2.6 int hess_run_header_struct::run

Recorded data:

Run number.

Referenced by hesscam_ps_plot(), main(), merge_data_from_io_block(), read_hess_runheader(), user_event_fill(), and write_hess_runheader().

6.40.2.7 int hess_run_header_struct::run_type

Data/pedestal/laser/muon run or MC run: MC run: -1, Data run: 1, Pedestal run: 2, Laser run: 3, Muon run: 4.

Referenced by merge_data_from_io_block(), read_hess_runheader(), and write_hess_runheader().

6.40.2.8 double hess_run_header_struct::tel_pos[H_MAX_TEL][3]

x,y,z positions of the telescopes [m].

x is counted from array reference position towards North, y towards West, z upwards.

Referenced by hesscam_ps_plot(), main(), merge_data_from_io_block(), read_hess_runheader(), second_moments(), shower reconstruct(), user event fill(), user init(), and write hess runheader().

6.40.2.9 int hess_run_header_struct::tracking_mode

Tracking/pointing mode: 0: Az/Alt, 1: R.A.

/Dec. 2000

Referenced by mc_event_fill(), merge_data_from_io_block(), read_hess_runheader(), and write_hess_runheader().

The documentation for this struct was generated from the following file:

· io_hess.h

6.41 hess_shower_parameter Struct Reference

Reconstructed shower parameters.

#include <io_hess.h>

Data Fields

- int known
- int num trg

Number of telescopes contributing to central trigger.

· int num read

Number of telescopes read out.

int num_img

Number of images used for shower parameters.

• int img_pattern

Bit pattern of which telescopes were used (for small no. of telescopes only).

• int img list [H MAX TEL]

With more than 16 or 32 telescopes, we can only use the list.

· int result bits

Bit pattern of what results are available: Bits 0 + 1: direction + errors Bits 2 + 3: core position + errors Bits 4 + 5: mean scaled image shape + errors Bits 6 + 7: energy + error Bits 8 + 9: shower maximum + error.

• double Az

Azimuth angle [radians from N-> E].

double Alt

Altitude [radians].

double err_dir1

Error estimate in nominal plane X direction (| Alt) [rad].

double err dir2

Error estimate in nominal plane Y direction (|| Az) [rad].

double err_dir3

2

• double xc

X core position [m].

double yc

Y core position [m].

· double err core1

Error estimate in X coordinate [m].

• double err core2

Error estimate in Y coordinate [m].

· double err_core3

?

· double mscl

Mean scaled image length [gammas \sim 1 (HEGRA-style) or \sim 0 (HESS-style)].

- double err_mscl
- · double mscw

Mean scaled image width [gammas \sim 1 (HEGRA-style) or \sim 0 (HESS-style)].

- · double err_mscw
- · double energy

Primary energy [TeV], assuming a gamma.

- · double err_energy
- · double xmax

Atmospheric depth of shower maximum [g/cm²].

double err_xmax

6.41.1 Detailed Description

Reconstructed shower parameters.

The documentation for this struct was generated from the following file:

• io_hess.h

6.42 hess tel event adc struct Struct Reference

ADC data (either sampled or sum mode)

```
#include <io_hess.h>
```

Data Fields

· int known

Must be set to 1 if and only if raw data is available.

• int tel id

Must match the expected telescope ID when reading.

· int num pixels

The number of pixels in the camera (as in configuration)

· int num gains

The number of different gains per pixel (2 for HESS).

• int num_samples

The number of samples (time slices) recorded.

int zero_sup_mode

The desired or used zero suppression mode.

· int data red mode

The desired or used data reduction mode.

· int offset_hg8

The offset to be used in shrinking high-gain data.

· int scale hg8

The scale factor (denominator) in shrinking h-g data.

· int threshold

Threshold (in high gain) for recording low-gain data.

• int list_known

Was list of significant pixels filled in?

int list_size

Size of the list of available pixels (with list mode).

int adc_list [H_MAX_PIX]

List of available pixels (with list mode).

uint8_t significant [H_MAX_PIX]

Was amplitude large enough to record it? Bit 0: sum, 1: samples.

• uint8_t adc_known [H_MAX_GAINS][H_MAX_PIX]

Was individual channel recorded? Bit 0: sum, 1: samples, 2: ADC was in saturation.

uint32_t adc_sum [H_MAX_GAINS][H_MAX_PIX]

Sum of ADC values.

uint16_t adc_sample [H_MAX_GAINS][H_MAX_PIX][H_MAX_SLICES]

Pulses sampled.

6.42.1 Detailed Description

ADC data (either sampled or sum mode)

The documentation for this struct was generated from the following file:


· io_hess.h

6.43 hess_tel_event_data_struct Struct Reference

Event raw and image data from one telescope.

#include <io_hess.h>

Collaboration diagram for hess_tel_event_data_struct:



Data Fields

- int known
- int tel_id

The telescope ID number (1 ... n)

• int loc_count

The counter for local triggers.

int glob_count

The counter for system triggers.

• HTime cpu_time

Camera CPU system time of event.

· HTime gps_time

GPS time of event, if any.

· int trg_source

1=internal (event data) or 2=external (calib data).

int num_list_trgsect

Number of trigger groups (sectors) listed.

int list_trgsect [H_MAX_SECTORS]

List of triggered groups (sectors).

• int known_time_trgsect

Are the trigger times known? (0/1)

double time_trgsect [H_MAX_SECTORS]

Times when trigger groups (as in list) fired.

· int readout_mode

Sum mode (0) or sample mode (1 ... 255, normally: 1).

• int num_image_sets

how many 'img' sets are available.

int max_image_sets

how many 'img' sets were allocated.

AdcData * raw

Pointer to raw data, if any.

PixelTiming * pixtm

Optional pixel (pulse shape) timing.

• ImgData * img

Pointer to second moments, if any.

• PixelCalibrated * pixcal

Pointer to calibrated pixel intensities, if available.

int num_phys_addr

(not used)

• int phys_addr [4 *H_MAX_DRAWERS]

(not used)

• PixelList trigger_pixels

List of triggered pixels.

• PixelList image_pixels

Pixels included in (first) image.

6.43.1 Detailed Description

Event raw and image data from one telescope.

The documentation for this struct was generated from the following file:

• io_hess.h

6.44 hess_tel_image_struct Struct Reference

Image parameters.

```
#include <io_hess.h>
```

Data Fields

• int known

is image data known?

int tel_id

Telescope ID.

· int pixels

number of pixels used for image

int cut_id

For which set of tail-cuts was used.

· double amplitude

Image amplitude (="SIZE") [mean p.e.].

· double clip_amp

6.44 hess_tel_image_struct Struct Reference Pixel amplitude clipping level [mean p.e.] or zero for no clipping. · int num_sat Number of pixels in saturation (ADC saturation or dedicated clipping). double x Position. · double x err Error on x (0: error not known, <0: x not known) [rad]. double y Y position (c.o.g.) [rad], corrected for any camera rotation. • double y_err Error on y (0: error not known, <0: y not known) [rad]. · double phi Orientation. · double phi err Error on phi (0: error not known, <0: phi not known) [rad]. double I Shape. double l_err Error on length (0: error not known, <0: I not known) [rad]. · double w Width (minor axis) [rad]. • double w_err Error on width (0: error not known, <0: w not known) [rad]. · double skewness Skewness, indicating asymmetry of image. · double skewness err Error (0: error not known, <0: skewness not known) · double kurtosis Kurtosis, indicating sharpness of peak of image. · double kurtosis_err Error (0: error not known, < 0: kurtosis not known) · int num_conc Number of hottest pixels used for concentration. · double concentration Fraction of total amplitude in num_conc hottest pixels. Timing. R.m.s. average residual time after slope correction. [ns]. Average pulse width (50% of peak or time over threshold) [ns].

 double tm_slope · double tm residual · double tm width1 · double tm width2 Average pulse width (20% of peak or 0) [ns]. double tm_rise Average pixel rise time (or 0) [ns]. · int num hot Individual pixels. int hot_pixel [H_MAX_HOTPIX] Pixel IDs of hotest pixels.

double hot amp [H MAX HOTPIX]

Amplitudes of hotest pixels [mean p.e.].

6.44.1 Detailed Description

Image parameters.

6.44.2 Field Documentation

6.44.2.1 double hess_tel_image_struct::I

Shape.

Length (major axis) [rad]

Referenced by hesscam_ps_plot(), main(), read_hess_telimage(), second_moments(), shower_reconstruct(), user_event_fill(), and write_hess_telimage().

6.44.2.2 int hess tel image struct::num_hot

Individual pixels.

Number of hottest pixels individually saved

Referenced by main(), read_hess_telimage(), user_event_fill(), and write_hess_telimage().

6.44.2.3 double hess_tel_image_struct::phi

Orientation.

Angle of major axis w.r.t. x axis [rad], corrected for any camera rotation.

Referenced by hesscam_ps_plot(), main(), pixel_timing_analysis(), read_hess_telimage(), second_moments(), shower_reconstruct(), user_event_fill(), and write_hess_telimage().

6.44.2.4 double hess_tel_image_struct::tm_slope

Timing.

Slope in peak times along major axis as given by phi. [ns/rad]

Referenced by pixel_timing_analysis(), read_hess_telimage(), user_event_fill(), and write_hess_telimage().

6.44.2.5 double hess_tel_image_struct::x

Position.

X position (c.o.g.) [rad], corrected for any camera rotation.

Referenced by hesscam_ps_plot(), main(), pixel_timing_analysis(), read_hess_telimage(), second_moments(), shower_reconstruct(), user_event_fill(), and write_hess_telimage().

The documentation for this struct was generated from the following file:


• io_hess.h

6.45 hess_tel_monitor_struct Struct Reference

Monitoring data.

#include <io_hess.h>

Collaboration diagram for hess_tel_monitor_struct:



Data Fields

· int known

Status etc., pedestals, DC, HV.

• int new_parts

What of that is new.

• int tel id

Telescope ID number.

• int num_sectors

Number of sector available for trigger (default trigger).

• int num_pixels

Number of pixels in camera.

• int num_drawers

Number of drawers in camera.

- int num_gains
- int num_ped_slices

How many slices have been added for pedestal.

int num_drawer_temp

Number of temperatures per drawer.

• int num_camera_temp

Number of other temperatures monitored.

int monitor_id

Incremented with each update.

· HTime moni_time

Time when last monitoring data was sent.

- HTime status_time
- · HTime trig_time

Time when last trigger monitor data was read.

• HTime ped_noise_time

Time when pedestals + noise were determined.

HTime hv_temp_time

Time when hv+currents+temp. were all read out.

· HTime dc rate time

Time when DC current + pixels scalers were read.

HTime set_hv_thr_time

Time when HV + thresholds where set.

HTime set_daq_time

Time when DAQ parameters where set.

· int status_bits

Lid, HV, trigger, readout, drawers, fans.

· long coinc_count

These have to be obtained from the camera trigger electronics (first trigger type only)

· long event_count

Count of events read out.

· double event rate

Average event rate [Hz].

· double data_rate

Average rate of packed data [MB/s].

· double trigger rate

Camera average local trigger rate [Hz].

• double sector_rate [H_MAX_SECTORS]

Sector trigger rate [Hz].

· double mean_significant

These are computed by the readout software:

double pedestal [H MAX GAINS][H MAX PIX]

Average pedestal on ADC sums.

double noise [H_MAX_GAINS][H_MAX_PIX]

Average noise on ADC sums.

• uint16 t current [H MAX PIX]

These numbers need mapping from drawers+channel to pixel id:

• uint16_t scaler [H_MAX_PIX]

ADC values of pixel trigger rate.

uint16_t hv_v_mon [H_MAX_PIX]

ADC values of HV voltage monitor.

uint16_t hv_i_mon [H_MAX_PIX]

ADC values of HV current monitor.

uint16_t hv_dac [H_MAX_PIX]

DAC values of HV settings.

uint16_t thresh_dac [H_MAX_DRAWERS]

Thresholds set in each drawer.

• uint8_t trig_set [H_MAX_PIX]

Set if pixel excluded from trigger.

uint8_t hv_set [H_MAX_PIX]

Set if HV switched off for pixel.

• uint8_t hv_stat [H_MAX_PIX]

Set if HV switched off for pixel.

• short drawer_temp [H_MAX_DRAWERS][H_MAX_D_TEMP]

That is left in its raw order:

short camera_temp [H_MAX_C_TEMP]

ADC values.

· uint16_t daq_conf

As set by CNTRLDaq message.

- uint16_t daq_scaler_win
- uint16_t daq_nd
- · uint16_t daq_acc
- uint16_t daq_nl

6.45.1 Detailed Description

Monitoring data.

6.45.2 Field Documentation

6.45.2.1 long hess_tel_monitor_struct::coinc_count

These have to be obtained from the camera trigger electronics (first trigger type only)

Count of pixel coincidences (local triggers).

Referenced by read_hess_tel_monitor(), and write_hess_tel_monitor().

6.45.2.2 uint16_t hess_tel_monitor_struct::current[H_MAX_PIX]

These numbers need mapping from drawers+channel to pixel id:

ADC values of DC current.

Referenced by read_hess_tel_monitor(), and write_hess_tel_monitor().

6.45.2.3 short hess_tel_monitor_struct::drawer_temp[H_MAX_DRAWERS][H_MAX_D_TEMP]

That is left in its raw order:

ADC values.

Referenced by read_hess_tel_monitor(), and write_hess_tel_monitor().

The documentation for this struct was generated from the following file:

· io_hess.h

6.46 hess_time_struct Struct Reference

Breakdown of time into seconds since 1970.0 and nanoseconds.

```
#include <io hess.h>
```

Data Fields

- · long seconds
- long nanoseconds

6.46.1 Detailed Description

Breakdown of time into seconds since 1970.0 and nanoseconds.

The documentation for this struct was generated from the following file:

· io_hess.h

6.47 hess_tracking_event_data_struct Struct Reference

Tracking data interpolated for one event and one telescope.

```
#include <io_hess.h>
```

Data Fields

• int tel_id

The telescope ID number (1 ... n)

· double azimuth_raw

Raw azimuth angle [radians from N->E].

· double altitude raw

Raw altitude angle [radians].

· double azimuth_cor

Azimuth corrected for pointing errors.

double altitude_cor

Azimuth corrected for pointing errors.

int raw_known

Set if raw angles are known.

• int cor_known

Set if corrected angles are known.

6.47.1 Detailed Description

Tracking data interpolated for one event and one telescope.

The documentation for this struct was generated from the following file:

• io_hess.h

6.48 hess_tracking_setup_struct Struct Reference

Definition of tracking parameters.

```
#include <io_hess.h>
```

Data Fields

• int tel_id

Telescope ID.

- int known
- int drive_type_az

0 for now.

• int drive_type_alt

0 for now.

double zeropoint_az

Offsets subtracted from the values reported.

· double zeropoint_alt

by hardware before calculating 'raw' angles [rad].

· double sign az

This is -1 if hardware counts the other way than.

· double sign_alt

we do, and +1 otherwise.

double resolution_az

Typical resolution expected [rad].

· double resolution_alt

Typical resolution expected [rad].

• double range_low_az

Note: The values may be outside the [0...2*pi[range.

- · double range low alt
- double range_high_az
- · double range high alt
- double park_pos_az
- double park_pos_alt

6.48.1 Detailed Description

Definition of tracking parameters.

This is a copy of the configuration given to the tracking computers. Note: all angles are in radians. This block should not be needed for event analysis.

6.48.2 Field Documentation

6.48.2.1 double hess_tracking_setup_struct::range_low_az

Note: The values may be outside the [0...2*pi[range.

Referenced by read_hess_trackset(), and write_hess_trackset().

The documentation for this struct was generated from the following file:


· io hess.h

6.49 histogram Struct Reference

A complete 1-D or 2-D histogram with control and data elements.

#include <histogram.h>

Collaboration diagram for histogram:



Data Fields

• char * title

Histogram title (optional)

· long ident

Histogram ID number (optional)

- union Histogram_Parameters specific
- union Histogram_Parameters specific_2d
- int nbins

Number of histogram bins.

• int nbins_2d

Same for 2nd coordinate of 2-D.

unsigned long entries

No.

• unsigned long tentries

No.

• unsigned long underflow

No.

• unsigned long underflow_2d

Same in 2nd coord of 2-D histo.

· unsigned long overflow

Nο

• unsigned long overflow_2d

Same in 2nd coord of 2-D histo.

• unsigned long * counts

Pointer to histogram data.

· char type

'I' for integer histogram,

• struct histogram * previous

References to neighbours in.

struct histogram * next

linked list of histograms.

• struct Histogram Extension * extension

Extension for weighted histos.

6.49.1 Detailed Description

A complete 1-D or 2-D histogram with control and data elements.

6.49.2 Field Documentation

6.49.2.1 unsigned long histogram::entries

No.

of entries, incl. u.f./o.f.

Referenced by clear_histogram(), display_2d_histogram(), display_histogram(), fast_stat_histogram(), fill_2d_int_histogram(), fill_2d_real_histogram(), fill_2d_weighted_histogram(), fill_int_histogram(), fill_real_histogram(), fill_weighted_histogram(), histogram_to_lookup(), histogram_to_root(), list_histograms(), main(), print_histogram(), read histograms x(), stat histogram(), write dst histos(), and write histograms().

6.49.2.2 struct histogram* histogram::next

linked list of histograms.

Referenced by convert_histograms_to_root(), display_all_histograms(), free_all_histograms(), get_histograms_by_ident(), histogram_hashing(), initialize_histogram(), list_histograms(), main(), set_first_histogram(), sort_histograms(), unlink_histogram(), and write_histograms().

6.49.2.3 unsigned long histogram::overflow

No.

of entries above range

Referenced by add_histogram(), clear_histogram(), display_2d_histogram(), display_histogram(), fill_2d_int_histogram(), fill_2d_real_histogram(), fill_2d_weighted_histogram(), fill_int_histogram(), fill_real_histogram(), fill_weighted_histogram(), histogram_to_lookup(), histogram_to_root(), locate_histogram_fraction(), print_histogram(), read_histograms_x(), and write_histograms().

6.49.2.4 unsigned long histogram::overflow_2d

Same in 2nd coord of 2-D histo.

Referenced by add_histogram(), clear_histogram(), display_2d_histogram(), fill_2d_int_histogram(), fill_2d_real_histogram(), fill_2d_weighted_histogram(), histogram_to_root(), read_histograms_x(), and write_histograms().

6.49.2.5 unsigned long histogram::tentries

No.

of entries, without """

Referenced by clear_histogram(), display_histogram(), fast_stat_histogram(), fill_2d_int_histogram(), fill_2d_real_histogram(), fill_2d_weighted_histogram(), fill_int_histogram(), fill_real_histogram(), fill_weighted_histogram(), histogram_to_lookup(), list_histograms(), lookup_int(), lookup_real(), print_histogram(), read_histograms_x(), stat_histogram(), and write_histograms().

6.49.2.6 char histogram::type

'I' for integer histogram,

'i' for int. lookup table, 'R' for floating point histogr. 'r' for fl. p. lookup table, 'F'/'D' for single/double pre-cision weighted histograms.

Referenced by add_histogram(), aux_alloc_histogram(), clear_histogram(), display_2d_histogram(), display_-histogram(), fast_stat_histogram(), fill_2d_int_histogram(), fill_2d_real_histogram(), fill_2d_weighted_histogram(), fill_histogram(), fill_int_histogram(), fill_real_histogram(), fill_weighted_histogram(), histogram_matching(), histogram_to_lookup(), histogram_to_root(), list_histograms(), locate_histogram_fraction(), lookup_int(), lookup_real(), main(), print_histogram(), read_histograms_x(), set_ebias_correction(), stat_histogram(), and write_histograms().

6.49.2.7 unsigned long histogram::underflow

No.

of entries below range

Referenced by add_histogram(), clear_histogram(), display_2d_histogram(), display_histogram(), fill_2d_int_histogram(), fill_2d_real_histogram(), fill_2d_weighted_histogram(), fill_int_histogram(), fill_real_histogram(), fill_weighted_histogram(), histogram_to_lookup(), histogram_to_root(), locate_histogram_fraction(), print_histogram(), read_histograms_x(), and write_histograms().

6.49.2.8 unsigned long histogram::underflow_2d

Same in 2nd coord of 2-D histo.

Referenced by add_histogram(), clear_histogram(), display_2d_histogram(), fill_2d_int_histogram(), fill_2d_real_histogram(), fill_2d_weighted_histogram(), histogram_to_root(), read_histograms_x(), and write_histograms().

The documentation for this struct was generated from the following file:

· histogram.h

6.50 Histogram_Extension Struct Reference

A histogram extension only allocated for weighted histograms.

```
#include <histogram.h>
```

Data Fields

· double content all

Sum of all contents.

· double content inside

Sum of contents within range.

• double content_outside [8]

Contents outside range.

• float * fdata

Data of each bin (ix+nx*iy)

double * ddata

in one of two precisions.

6.50.1 Detailed Description

A histogram extension only allocated for weighted histograms.

6.50.2 Field Documentation

6.50.2.1 double* Histogram_Extension::ddata

in one of two precisions.

Referenced by add_histogram(), aux_alloc_histogram(), clear_histogram(), display_2d_histogram(), fill_gaps(), fill_weighted_histogram(), free_histo_contents(), gen_image_lookups(), histogram_to_root(), img_norm(), main(), print_histogram(), read_histograms_x(), set_ebias_correction(), stat_histogram(), and user_init().

The documentation for this struct was generated from the following file:

· histogram.h

6.51 Histogram_Parameters Union Reference

Parameters defining the usable range of coordinates.

```
#include <histogram.h>
```

Data Fields

```
struct {
    double lower limit
      Lower limit of histogram range.
    double upper_limit
      Upper limit of histogram range.
    double sum
      Sum of all values.
    double tsum
      Sum of values within range.
    double inverse binwidth
      1.
 } real
     Histogram parameters if it is some sort of 'F' or 'D' type.
struct {
    long lower limit
      Lower limit of histogram range.
    long upper_limit
      Upper limit of histogram range.
    long sum
      Sum of all values.
    long tsum
      Sum of values within range.
    long width
      Width of histogram range.
 } integer
```

Histogram parameters if it is some sort of 'I' (int) type.

6.51.1 Detailed Description

Parameters defining the usable range of coordinates.

6.51.2 Field Documentation

6.51.2.1 struct { ... } Histogram_Parameters::integer

Histogram parameters if it is some sort of 'I' (int) type.

Needed for integer-type limits.

Referenced by add_histogram(), alloc_2d_int_histogram(), alloc_int_histogram(), clear_histogram(), display_2d-histogram(), fist_stat_histogram(), fill_2d_int_histogram(), fill_int_histogram(), histogram_matching(), histogram_to_root(), locate_histogram_fraction(), lookup_int(), print_histogram(), read_histograms_x(), stat_histogram(), and write_histograms().

6.51.2.2 double Histogram_Parameters::inverse_binwidth

1.

/(width_of_one_bin)

Referenced by allocate_histogram(), fill_2d_real_histogram(), fill_2d_weighted_histogram(), fill_real_histogram(), fill_weighted_histogram(), and lookup_real().

6.51.2.3 struct { ... } Histogram_Parameters::real

Histogram parameters if it is some sort of 'F' or 'D' type.

Needed for real-type limits.

Referenced by add_histogram(), allocate_histogram(), clear_histogram(), display_2d_histogram(), display_histogram(), fill_2d_real_histogram(), fill_2d_weighted_histogram(), fill_gaps(), fill_real_histogram(), fill_weighted_histogram(), gen_image_lookups(), histogram_matching(), histogram_to_root(), img_norm(), locate_histogram_fraction(), lookup_real(), print_histogram(), read_histograms_x(), set_ebias_correction(), stat_histogram(), and write_histograms().


The documentation for this union was generated from the following file:

· histogram.h

6.52 history_struct Struct Reference

Use to build a linked list of configuration history.

Collaboration diagram for history_struct:



Data Fields

- char * text
- time_t time

Configuration test.

struct history_struct * next

Time when the configuration was entered.

6.52.1 Detailed Description

Use to build a linked list of configuration history.

The documentation for this struct was generated from the following file:

· io_history.c

6.53 histstat Struct Reference

Statistics element for histogram analysis.

```
#include <histogram.h>
```

Data Fields

- · double mean
- · double mean 2d
- double tmean
- double tmean 2d
- · double hmean
- · double hmean_2d
- · double sigma
- · double sigma_2d
- double median
- · double median_2d

6.53.1 Detailed Description

Statistics element for histogram analysis.

The documentation for this struct was generated from the following file:

· histogram.h

6.54 incpath Struct Reference

An element in a linked list of include paths.

Collaboration diagram for incpath:



Data Fields

• char * path

The path name.

struct incpath * next

The next element.

6.54.1 Detailed Description

An element in a linked list of include paths.

The documentation for this struct was generated from the following file:


• fileopen.c

6.55 linked_string Struct Reference

The linked_string is mainly used to keep CORSIKA input.

```
#include <mc_tel.h>
```

Collaboration diagram for linked_string:



Data Fields

- char * text
- struct linked_string * next

6.55.1 Detailed Description

The linked_string is mainly used to keep CORSIKA input.

The documentation for this struct was generated from the following file:

• mc_tel.h

6.56 map_tel_struct Struct Reference

Structure with per output telescope information keeping track of prerequisites.

Data Fields

• int tel_id

Telescope ID on output.

int ifn

Input file number (1 or 2)

int inp_id

Telescope ID on input.

• int inp_itel

Sequential telescope count on input.

· int have_camset

Have camera_settings for this telescope.

int have_camorg

Have camera organisation for this telescope.

int have_pixset

Have pixel settings for this telescope.

int have_pixdis

Have pixels disabled for this telescope (optional)

· int have camsoft

Have camera software settings for this telescope.

int have_pointcor

Have pointing correction for this telescope.

· int have_trackset

Have tracking settings for this telescope.

6.56.1 Detailed Description

Structure with per output telescope information keeping track of prerequisites.

The documentation for this struct was generated from the following file:

• merge_simtel.c

6.57 moments Struct Reference

Numbers to be summed up to obtain the moments.

#include <histogram.h>

Data Fields

- double lower_limit
- double upper_limit
- · double sum
- double tsum
- double sum2
- · double tsum2
- double sum3
- double tsum3
- double sum4
- · double tsum4
- · unsigned long entries
- unsigned long tentries
- int level

6.57.1 Detailed Description

Numbers to be summed up to obtain the moments.

The documentation for this struct was generated from the following file:

· histogram.h

6.58 momstat Struct Reference

First, second, and higher moments of a 1-D histogram.

```
#include <histogram.h>
```

Data Fields

- · double mean
- · double sigma
- · double skewness
- · double kurtosis
- · double tmean
- double tsigma
- · double tskewness
- · double tkurtosis

6.58.1 Detailed Description


First, second, and higher moments of a 1-D histogram.

The documentation for this struct was generated from the following file:

· histogram.h

6.59 next_file_struct Struct Reference

Collaboration diagram for next_file_struct:



Data Fields

- char * fname
- struct next_file_struct * next

The documentation for this struct was generated from the following files:

- · read_hess.c
- · read_hess_cc.cc

6.60 photo_electron Struct Reference

A photo-electron produced by a photon hitting a pixel.

```
#include <mc_tel.h>
```

Data Fields

• int pixel

The pixel that was hit.

• int lambda

The wavelength of the photon.

· double atime

The time [ns] when the photon hit the pixel.

6.60.1 Detailed Description

A photo-electron produced by a photon hitting a pixel.

6.60.2 Field Documentation

6.60.2.1 double photo_electron::atime

The time [ns] when the photon hit the pixel.

6.60.2.2 int photo_electron::lambda

The wavelength of the photon.

6.60.2.3 int photo_electron::pixel


The pixel that was hit.

The documentation for this struct was generated from the following file:

• mc_tel.h

6.61 range_list_struct Struct Reference

Collaboration diagram for range list struct:



Data Fields

- · long from
- · long to
- struct range_list_struct * next

The documentation for this struct was generated from the following file:

· read_hess.c

6.62 shower_extra_parameters Struct Reference

Extra shower parameters of unspecified nature.

```
#include <mc_tel.h>
```

Data Fields

· long id

May identify to the user what the parameters should mean.

· int is_set

May be reset after writing the parameter block and must thus be set to 1 for each shower for which the extra parameters should get recorded.

· double weight

To be used if the weight of a shower may change during processing, e.g.

size_t niparam

Number of extra integer parameters.

int * iparam

Space for extra integer parameters, at least of size niparam.

size_t nfparam

Number of extra floating-point parameters.

float * fparam

Space for extra floats, at least of size nfparam.

6.62.1 Detailed Description

Extra shower parameters of unspecified nature.

Useful for things to be used like in the event header but which may only become available while processing a shower. Should be initialized with the init_shower_extra_parameters(int ni_max, int nf_max) function.

6.62.2 Field Documentation

6.62.2.1 float* shower_extra_parameters::fparam

Space for extra floats, at least of size nfparam.

Referenced by clear shower extra parameters(), and init shower extra parameters().

6.62.2.2 long shower_extra_parameters::id

May identify to the user what the parameters should mean.

Referenced by clear_shower_extra_parameters(), and init_shower_extra_parameters().

6.62.2.3 int* shower_extra_parameters::iparam

Space for extra integer parameters, at least of size niparam.

Referenced by clear shower extra parameters(), and init shower extra parameters().

6.62.2.4 int shower_extra_parameters::is_set

May be reset after writing the parameter block and must thus be set to 1 for each shower for which the extra parameters should get recorded.

Referenced by clear_shower_extra_parameters(), init_shower_extra_parameters(), and write_hess_mc_shower().

6.62.2.5 size_t shower_extra_parameters::nfparam

Number of extra floating-point parameters.

Referenced by clear_shower_extra_parameters(), and init_shower_extra_parameters().

6.62.2.6 size_t shower_extra_parameters::niparam

Number of extra integer parameters.

Referenced by clear_shower_extra_parameters(), and init_shower_extra_parameters().

6.62.2.7 double shower_extra_parameters::weight

To be used if the weight of a shower may change during processing, e.g.

when shower processing can be aborted depending on how quickly the electromagnetic component builds up and the remaining showers may have a larger weight to compensate for that. For backwards compatibility this should be set to 1.0 when no additional weight is needed.

Referenced by clear_shower_extra_parameters(), and init_shower_extra_parameters().

The documentation for this struct was generated from the following file:

· mc tel.h

6.63 tel_type_param Struct Reference

Data Fields

- int min_tel_id
- int max_tel_id
- · double mirror_area
- · double flen
- · int num pixels

The documentation for this struct was generated from the following file:

• user_analysis.c

6.64 telescope_list Struct Reference

Data Fields


- · size t min tel
- size_t ntel
- int * tel_id

The documentation for this struct was generated from the following file:

• user_analysis.c

6.65 trgmask_entry Struct Reference

Collaboration diagram for trgmask_entry:



Data Fields

· long event

The event number.

• int tel_id

The telescope ID number.

· int trg_mask

The trigger mask bit pattern which got messed up in data files.

struct trgmask_entry * next


Can be used in arrays but also in linked lists.

The documentation for this struct was generated from the following file:

• io_trgmask.h

6.66 trgmask_hash_set Struct Reference

Collaboration diagram for trgmask_hash_set:



Data Fields

- long run
- struct trgmask_entry * h_e [TRGMASK_PRIME]


 Start of linked list for each possible hash value.

The documentation for this struct was generated from the following file:

· io_trgmask.h

6.67 trgmask_set Struct Reference

Collaboration diagram for trgmask_set:



Data Fields

- long run
- size_t num_entries

struct trgmask_entry * mask

The documentation for this struct was generated from the following file:

· io trgmask.h

6.68 user parameters Struct Reference

Data Fields

```
struct {
   int user flags
      1: HESS-style analysis standard cuts; 2: hard cuts; 3: loose cuts.
   int min pix
      The minimum number of significant pixels in usable images.
   int reco_flag
      Reconstruction level flag.
   int min_tel_img
      Minimum and maximum number of usable images for events used in analysis.
    int max tel img
   int Iref
      Which pixel's amplitude is used as reference.
   int integrator
      The type of pixel intensity integration scheme.
    int integ param [2]
      Integration-scheme-specific integer parameters, typically:
    int integ_thresh [2]
      Integer type thresholds for significance in ADC units (one per gain)
   int integ no rescale
      Set to 1 if integration over small window should not rescale for fraction of single p.e.
   int trg req
      Required trigger type (bit pattern: bit 0 = majo, 1=asum, 2=dsum)
 } i
struct {
    double source_offset_deg
    double d_sp_idx
      Difference between generated MC spectrum (e.g.
    double min amp
      The minimum amplitude [ peak p.e.
    double tailcut low
      The lower and upper tail cuts for the standard two-level tail-cut scheme.
    double tailcut high
    double minfrac
      Minimum fraction of reference amplitude is needed.
    double max theta deg
    double theta_scale
    double de2_cut_param [4]
    double mscrw min [4]
    double mscrw max [4]
    double mscrl_min [4]
    double mscrl_max [4]
    double eres cut param [4]
    double hmax cut param
    double min_theta_deg
    double camera_clipping_deg
```

```
Pixel outside this radius (if > 0) should be ignored in image reconstruction.
         double theta escale [4]
           If the angular acceptance deviates from the 80% containment.
         double clip_amp
           Pixel intensity clipped to this value after calibration, if this param is not zero.
         double d integ param [2][4]
           Integration-scheme- and gain-specific floating-point parameters.
         double calib scale
           Calibration scale from mean-p.e.
        double r nb [3]
           Radii for initial neighbour pixel search.
        double r_ne
           Radius for extending significant pixels in image cleaning [pixel diameter].
        double impact_range [3]
           [0]: maximum distance of array center from shower axis, [1],[2]: max.
        double true_impact_range [3]
           As for impact ranhe.
        double max core distance
      } d
6.68.1 Field Documentation
6.68.1.1 double user_parameters::calib_scale
Calibration scale from mean-p.e.
units to experimental units (0.0: like HESS).
Referenced by calibrate_amplitude(), and calibrate_pixel_amplitude().
6.68.1.2 double user_parameters::camera_clipping_deg
Pixel outside this radius (if > 0) should be ignored in image reconstruction.
Referenced by set disabled pixels(), and user set clipping().
6.68.1.3 double user_parameters::clip_amp
Pixel intensity clipped to this value after calibration, if this param is not zero.
Referenced by calibrate_amplitude(), calibrate_pixel_amplitude(), main(), reconstruct(), second_moments(), user_-
event_fill(), and user_set_clipamp().
6.68.1.4 double user_parameters::d_integ_param[2][4]
Integration-scheme- and gain-specific floating-point parameters.
6.68.1.5 double user_parameters::d_sp_idx
Difference between generated MC spectrum (e.g.
E^{-2.0}) and assumed source spectrum (e.g. E^{-2.5}), e.g. case d_sp_idx = -0.5.
Referenced by user_event_fill(), user_mc_event_fill(), and user_set_spectrum().
```

6.68.1.6 double user_parameters::impact_range[3]

[0]: maximum distance of array center from shower axis, [1],[2]: max.

|x|,|y| of core in ground plane.

Referenced by user_event_fill(), and user_set_impact_range().

6.68.1.7 int user_parameters::integ_no_rescale

Set to 1 if integration over small window should not rescale for fraction of single p.e.

trace.

6.68.1.8 int user_parameters::integ_param[2]

Integration-scheme-specific integer parameters, typically:

number of bins to integrate and some offset value from start or back from detected peak.

Referenced by pixel integration().

6.68.1.9 int user_parameters::integrator

The type of pixel intensity integration scheme.

0: none (implicitly all samples), 1: simple, 2: around global peak, 3: around local peak, 4: around peak in neighbour pixels.

Referenced by pixel_integration(), and reconstruct().

6.68.1.10 double user_parameters::min_amp

The minimum amplitude [peak p.e.

] of images usable for the analysis.

Referenced by main(), shower_reconstruct(), user_event_fill(), user_init(), and user_set_min_amp().

6.68.1.11 int user_parameters::min_pix

The minimum number of significant pixels in usable images.

Referenced by main(), user_event_fill(), user_init(), and user_set_min_pix().

6.68.1.12 int user_parameters::min_tel_img

Minimum and maximum number of usable images for events used in analysis.

Referenced by user_event_fill(), user_init(), and user_set_tel_img().

6.68.1.13 double user_parameters::r_nb[3]

Radii for initial neighbour pixel search.

Maximum search radii for neighbours [pixel diameter]

6.68.1.14 double user_parameters::tailcut_low

The lower and upper tail cuts for the standard two-level tail-cut scheme.

Referenced by main(), user_init(), and user_set_tail_cuts().

6.68.1.15 double user_parameters::theta_escale[4]

If the angular acceptance deviates from the 80% containment.

Referenced by user_event_fill(), and user_set_theta_escale().

6.68.1.16 int user_parameters::user_flags

1: HESS-style analysis standard cuts; 2: hard cuts; 3: loose cuts.

Referenced by user_event_fill(), user_init(), user_set_flags(), and user_set_max_theta().

The documentation for this struct was generated from the following file:

· user_analysis.h

6.69 warn_specific_data Struct Reference

A struct used to store thread-specific data.

Data Fields

- · int warninglevel
- · int warningmode
- char output_buffer [2048]
- const char * logfname

The name of the log file.

- char saved_logfname [256]
- · int buffered
- FILE * logfile
- void(* log_function)(const char *, const char *, int, int)
- void(* output_function)(const char *)
- char *(* aux_function)(void)
- · int recursive

6.69.1 Detailed Description

A struct used to store thread-specific data.

6.69.2 Field Documentation

6.69.2.1 const char* warn_specific_data::logfname

The name of the log file.

Used only when opening the file.

Referenced by set_log_file(), and warn_f_warning().

The documentation for this struct was generated from the following file:

• warning.c

Chapter 7


File Documentation

7.1 add_histograms.c File Reference

Utility program for adding up matching histograms.

```
#include "initial.h"
#include "histogram.h"
#include "io_basic.h"
#include "io_histogram.h"
#include "fileopen.h"
#include "straux.h"
```

Include dependency graph for add_histograms.c:



Functions

- void syntax (const char *prgm)
- int main (int argc, char **argv)

 Main program.

7.1.1 Detailed Description

Utility program for adding up matching histograms.

```
Syntax: add_histograms [ -x id1, \dots] input_files \dots -o output_file
```

108 File Documentation

The histograms may be within multiple I/O blocks of the input file. Matching histograms will be added up, unless set to be excluded with the '-x' option. Only non-empty histograms are written to output.

Author

Konrad Bernloehr

Date

```
CVS $Date: 2014/06/24 14:29:40 $
```

Version


```
CVS $Revision: 1.2 $
```

7.2 atmprof.c File Reference

A stripped-down version of the interpolation of atmospheric profiles from the atmo.c file of the CORSIKA IACT/AT-MO package.

```
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <math.h>
#include <unistd.h>
#include "atmprof.h"
#include "fileopen.h"
```

Include dependency graph for atmprof.c:



Macros

• #define MAX_PROFILE 50

Functions

• static void interp (double x, double *v, int n, int *ipl, double *rpl)

Linear interpolation with binary search algorithm.

• static double rpol (double *x, double *y, int n, double xp)

Linear interpolation with binary search algorithm.

static char * find_elsewhere (const char *fname, char *bf, size_t sz)

Find the atmospheric profiles elsewhere (in the sim_telarray configuration).

• int init atmprof (int atmosphere)

Initialize atmospheric profiles.

double rhofx (double height)

Density of the atmosphere as a function of altitude.

• double thickx (double height)

Atmospheric thickness [g/cm**2] as a function of altitude.

· double refidx (double height)

Index of refraction as a function of altitude [cm].

double heighx (double thick)

Altitude [m] as a function of atmospheric thickness [g/cm**2].

Variables

- · static int current_atmosphere
- · static int num_prof
- static double **p_alt** [MAX_PROFILE]
- static double **p_log_alt** [MAX_PROFILE]
- static double **p_log_rho** [MAX_PROFILE]
- static double **p_rho** [MAX_PROFILE]
- static double p_log_thick [MAX_PROFILE]
- static double p_log_n1 [MAX_PROFILE]
- static double top_of_atmosphere = 112.83e3
- static double **bottom_of_atmosphere** = 0.

7.2.1 Detailed Description

A stripped-down version of the interpolation of atmospheric profiles from the atmo.c file of the CORSIKA IACT/AT-MO package. The main differences are a) parameters are passed by value instead of FORTRAN by-reference way, b) the height is measured in meters.

The CORSIKA built-in profiles are not handled here.

Author

Konrad Bernloehr

Date

```
CVS $Date: 2010/07/20 13:37:47 $
```

Version

```
CVS $Revision: 1.6 $
```

7.2.2 Function Documentation

7.2.2.1 double heighx (double thick)

Altitude [m] as a function of atmospheric thickness [g/cm**2].

Parameters

thick	atmospheric thickness [g/cm**2]

Returns

altitude [m]

References rpol().

110 File Documentation

7.2.2.2 int init_atmprof (int atmosphere)

Initialize atmospheric profiles.

Atmospheric models are read in from text-format tables. For the interpolation of relevant parameters (density, thickness, index of refraction, ...) all parameters are transformed such that linear interpolation can be easily used.

Parameters

atmosphere	Atmosphere number, to be expanded to the table file name.

Returns

```
0 (OK) or -1 (error, e.g. table available)
```

References fileopen(), and find_elsewhere().

Referenced by user_event_fill().

7.2.2.3 static void interp (double x, double *v, int n, int *ipl, double *rpl) [static]

Linear interpolation with binary search algorithm.

Linear interpolation between data point in sorted (i.e. monotonic ascending or descending) order. This function determines between which two data points the requested coordinate is and where between them. If the given coordinate is outside the covered range, the value for the corresponding edge is returned.

A binary search algorithm is used for fast interpolation.

Parameters

X	Input: the requested coordinate
V	Input: tabulated coordinates at data points
n	Input: number of data points
ipl	Output: the number of the data point following the requested coordinate in the given sorting
	$(1 \le ipl \le n-1)$
rpl	Output: the fraction $(x-v[ipl-1])/(v[ipl]-v[ipl-1])$ with $0 \le rpl \le 1$

Referenced by rpol().

7.2.2.4 double refidx (double height)

Index of refraction as a function of altitude [cm].

Parameters

height	altitude [m]

Returns

index of refraction

References rpol().

Referenced by user_event_fill().

7.2.2.5 double rhofx (double height)

Density of the atmosphere as a function of altitude.

Parameters

height	altitude [m]
--------	--------------

Returns

density [g/cm**3]

References rpol().

7.2.2.6 static double rpol (double * x, double * y, int n, double xp) [static]

Linear interpolation with binary search algorithm.

Linear interpolation between data point in sorted (i.e. monotonic ascending or descending) order. The resulting interpolated value is returned as a return value.

This function calls interp() to find out where to interpolate.

Parameters

X	Input: Coordinates for data table
У	Input: Corresponding values for data table
n	Input: Number of data points
хр	Input: Coordinate of requested value

Returns

Interpolated value

References interp().

Referenced by heighx(), refidx(), rhofx(), and thickx().

7.2.2.7 double thickx (double height)

Atmospheric thickness [g/cm**2] as a function of altitude.

Parameters

height	altitude [m]

Returns

thickness [g/cm**2]

References rpol().


Referenced by user_event_fill().

7.3 basic_ntuple.h File Reference

Desclaration of the basic_ntuple struct.

112 File Documentation

This graph shows which files directly or indirectly include this file:



Data Structures

struct basic_ntuple

A struct with basic per-shower parameters, to be used as an n-tuple in the event selection.

Functions

int list_ntuple (FILE *f, const struct basic_ntuple *b, int wtr)

List the parameters useful for event selection plus some more parameters which should not be used for event selection.

7.3.1 Detailed Description

Desclaration of the basic_ntuple struct.

7.3.2 Function Documentation

7.3.2.1 int list_ntuple (FILE * f, const struct basic_ntuple * b, int wtr)

List the parameters useful for event selection plus some more parameters which should not be used for event selection.

Parameters

f	Output file, to be opened beforehand.
b	Pointer to the struct containing all the relevant numbers.
wtr	Non-zero on first call to write also true MC parameters.

References basic_ntuple::acceptance, basic_ntuple::alt, basic_ntuple::alt_true, basic_ntuple::az, basic_ntuple::az_true, basic_ntuple::chi2_e, basic_ntuple::event, basic_ntuple::lg_e, basic_ntuple::lg_e_true, basic_ntuple::mdisp, basic_ntuple::mscrl, basic_ntuple::mscrl, basic_ntuple::n_fail, basic_ntuple::n_img, basic_ntuple::n_pix, basic_ntuple::n_trg, basic_ntuple::n_tsl0, basic_ntuple::primary, basic_ntuple::rcm, basic_ntuple::run, basic_ntuple::sig_e, basic_ntuple::sig_mscrl, basic_ntuple::sig_mscrl, basic_ntuple::sig_theta, basic_ntuple::sig_xmax, basic_ntuple::theta, basic_ntuple::tslope, basic_ntuple::tsphere, basic_ntuple::weight, basic_ntuple::xc, basic_ntuple::xfirst_true, basic_ntuple::xmax_true, basic_ntuple::yc, and basic_ntuple::yc_true.


Referenced by main().

7.4 best of.cc File Reference

Tool for extracting best values from listings of 'rh3' sensitivity evaluations.

```
#include "initial.h"
#include "straux.h"
#include "fileopen.h"
#include <vector>
#include <map>
#include <iostream>
#include <cstdio>
#include <cstring>
```

Include dependency graph for best_of.cc:



Data Structures

· struct best value

Enumerations

```
enum SpecType {
 SPEC NONE = -1, SPEC GAMMA = 0, SPEC ELECTRON = 1, SPEC PROTON = 101,
 SPEC_HE = 402, SPEC_CNO = 1407, SPEC_SI = 2814, SPEC_IRON = 5626,
 SPEC_NONE = -1, SPEC_GAMMA = 0, SPEC_ELECTRON = 1, SPEC_PROTON = 101,
 SPEC_HE = 402, SPEC_CNO = 1407, SPEC_SI = 2814, SPEC_IRON = 5626,
 SPEC_GAMMA = 0, SPEC_ELECTRON = 1, SPEC_PROTON = 101, SPEC_HE = 402,
 SPEC GAMMA = 0, SPEC ELECTRON = 1, SPEC PROTON = 101, SPEC HE = 402,
 SPEC NONE = -1, SPEC GAMMA = 0, SPEC ELECTRON = 1, SPEC PROTON = 101,
 SPEC_HE = 402, SPEC_CNO = 1407, SPEC_SI = 2814, SPEC_IRON = 5626,
 SPEC_NONE = -1, SPEC_GAMMA = 0, SPEC_ELECTRON = 1, SPEC_PROTON = 101,
 SPEC HE = 402, SPEC CNO = 1407, SPEC SI = 2814, SPEC IRON = 5626,
 SPEC_NONE = -1, SPEC_GAMMA = 0, SPEC_ELECTRON = 1, SPEC_PROTON = 101,
 SPEC_HE = 402, SPEC_CNO = 1407, SPEC_SI = 2814, SPEC_IRON = 5626 }
enum espec t {
 OLD_E_POWERLAW = 1, NEW_E_POWERLAW = 2, NEW_E_PL_LGN1 = 3, NEW_E_PL_LGN2 = 4,
 OLD_E_POWERLAW = 1, NEW_E_POWERLAW = 2, NEW_E_PL_LGN1 = 3, NEW_E_PL_LGN2 = 4,
 OLD_E_POWERLAW = 1, NEW_E_POWERLAW = 2, NEW_E_PL_LGN1 = 3, NEW_E_PL_LGN2 = 4,
 OLD E POWERLAW = 1, NEW E POWERLAW = 2, NEW E PL LGN1 = 3, NEW E PL LGN2 = 4,
 OLD E POWERLAW = 1, NEW E POWERLAW = 2, NEW E PL LGN1 = 3, NEW E PL LGN2 = 4}
enum BestChoice {
 BestDiff =1, BestIntegral =2, BestAngle =3, BestEres =4,
 BestRate =5, BestCombined =6 }
```

Functions

string particle_type (SpecType sp)

114 File Documentation

- double Crab_Unit (double E)
- static double cu (double x)
- double Crab_Unit_int (double E)
- double ergs (double E)
- static double **f50** (double x)
- static double fsp50 (double x)
- double Flux req50 south (double E)
- double Flux req50 E2erg south (double E)
- double Flux_req50_CU_south (double E)
- static double fn50 (double x)
- static double fnsp50 (double x)
- double Flux req50 north (double E)
- double Flux_req50_E2erg_north (double E)
- double Flux_req50_CU_north (double E)
- static double f5 (double x)
- static double fsp5 (double x)
- double Flux req5 south (double E)
- double Flux req5 E2erg south (double E)
- double Flux req5 CU south (double E)
- static double fn5 (double x)
- static double fnsp5 (double x)
- double Flux_req5_north (double E)
- double Flux_req5_E2erg_north (double E)
- double Flux req5 CU north (double E)
- static double f05 (double x)
- static double fsp05 (double x)
- double Flux req05 south (double E)
- double Flux req05 E2erg south (double E)
- double Flux req05 CU south (double E)
- static double fn05 (double x)
- static double fnsp05 (double x)
- double Flux req05 north (double E)
- double Flux_req05_E2erg_north (double E)
- double Flux_req05_CU_north (double E)
- static double fd50 (double x)
- static double fdes50 (double x)
- double Flux_goal50_south (double E)
- double Flux goal50 E2erg south (double E)
- double Flux goal50 CU south (double E)
- static double fnd50 (double x)
- static double fndes50 (double x)
- double Flux goal50 north (double E)
- double Flux_goal50_E2erg_north (double E)
- double Flux goal50 CU north (double E)
- double Angular resolution reg (double E)
- double Angular_resolution_goal (double E)
- static double eresb (double E)
- double Energy resolution req (double E)
- static double **eresdb** (double E)
- double Energy_resolution_goal (double E)
- double flux_int (SpecType sp, double E1, double E2)
- double lima17 (double on, double off, double alpha)
- bool matching required diffsens (int calc pput, bool with flux, double E, double diff sens)
- bool matching_required_performance (int calc_pput, bool with_flux, double E, double diff_sens, double angres, double eres)
- bool matching required angres (double E, double angres)
- bool matching_required_eres (double E, double eres)
- int **main** (int argc, char **argv)

Variables

- static double sce = 1.6022
- static double sca = 1e-4
- static double sc = sce*sca
- espec_t espec_type = OLD_E_POWERLAW

7.4.1 Detailed Description


Tool for extracting best values from listings of 'rh3' sensitivity evaluations. Three versions of the 'rh3' output format are supported. All of the input (from standard input) should be in the same format type.

7.5 camera_image.c File Reference

Plot a camera image from H.E.S.S.

```
#include "initial.h"
#include "io_basic.h"
#include "mc_tel.h"
#include "history.h"
#include "io_hess.h"
#include "fileopen.h"
#include "rec_tools.h"
#include "reconstruct.h"
#include "camera_image.h"
```

Include dependency graph for camera_image.c:



Macros

- #define H MAX NB1 8
- #define **H_MAX_NB2** 24

Functions

- static int guessed_pixel_shape_type (CameraSettings *camset, int itel)
- static double dist2 (double x, double y)
- static void print_pix_col (double n_o_r, FILE *psfile, double gamma_coeff)

Print a false-colour RGB value for a pixel intensity.

void hesscam_ps_plot (const char *image_fname, AllHessData *hsdata, int itel, int type, int amp_tm, double clip_amp)

Write PostScript of camera sum image or sample image to a dedicated file.

• static int find neighbours (CameraSettings *camset, int itel)

Find the list of neighbours for each pixel.

116 File Documentation

Variables

```
static char ps_head1 []
static char ps_head2 []
static char ps_head3 []
static char ps_begin_page1 []
static char ps_begin_page2 []
static char ps_end_page []
static char ps_trailer []
static char alt_az_arrow []
static int ps_num_page = 0
static int neighbours1 [H_MAX_TEL][H_MAX_PIX][H_MAX_NB1]
static int nnb1 [H_MAX_TEL][H_MAX_PIX]
static int has_nblist [H_MAX_TEL]
```

7.5.1 Detailed Description

Plot a camera image from H.E.S.S. /CTA data.

static int px_shape_type [H_MAX_TEL]

This code is derived from sim_conv2hess.c but now getting the relevant data from the data structure filled after reading the eventio based data, rather than from the internal data structures of sim_hessarray. As a consequence not all information available in the sim_hessarray generated plots is available in the plots generated here. Also some flexibility is lost, concerning for example the pixel shape which is not included in the data.

Author

Konrad Bernloehr

Date

```
CVS $Date: 2015/01/20 14:50:36 $

Version
```

```
CVS $Revision: 1.31 $
```

7.5.2 Function Documentation

7.5.2.1 static int find_neighbours (CameraSettings * camset, int itel) [static]

Find the list of neighbours for each pixel.

References hess_camera_settings_struct::area, hess_camera_settings_struct::num_pixels, hess_camera_settings_struct::size, hess_camera_settings_struct::tel_id, hess_camera_settings_struct::xpix, and hess_camera_settings_struct::ypix.

7.5.2.2 void hesscam_ps_plot (const char * image_fname, AllHessData * hsdata, int itel, int type, int amp_tm, double clip_amp)

Write PostScript of camera sum image or sample image to a dedicated file.

Also controlled via environment variables GAMMA_COEFF, GRAY_IMAGE, IMAGE_RANGE, IMAGE_OFFSET, PLOT WITH PIXEL ID.

Parameters

image_fname	The name of the postscript image file. Opened for appending new images.
hsdata	Pointer to the structure containing all data.
itel	The telescope index number.
type	Event type (<0: MC events, >=0: various type of calib data).
amp_tm	0: Use normal integrated amplitude. 1: Use integration around global peak position from
	pulse shape analysis. May include all pixels or only selected. 2: Use integration around local
	peak position from pulse shape analysis. Return 0 for pixels without a fairly significant peak.
clip_amp,:	if >0, any calibrated amplitude is clipped not to exceed this value [mean p.e.].

References hess_tel_event_adc_struct::adc_sum, hess_shower_parameter::Alt, hess_mc_shower_struct::altitude, hess tracking event data struct::altitude raw, hess tel image struct::amplitude, angles to offset(), shower parameter::Az, hess_mc_shower_struct::azimuth, hess tracking event data struct::azimuth raw, calibrate pixel amplitude(), hess camera settings struct::cam rot, hess event data struct::central, hess tel event_adc_struct::data_red_mode, hess_mc_shower_struct::energy, fileclose(), fileopen(), hess_camera_settings-_struct::flen, hess_central_event_data_struct::glob_count, H_MAX_TEL, HI_GAIN, hess_tel_event_data_struct-::image_pixels, hess_tel_event_data_struct::img, hess_tel_event_adc_struct::known, hess_pixel_calibrated_struct ::known, hess tel image struct::known, hess_tel_image_struct::l, LO_GAIN, hess_tel_event_data_struct::loc_count, hess_tel_event_data_struct::num_image_sets, hess_tel_monitor_struct::num_ped_slices, hess_camera_settings_struct::num_pixels, hess_tel_event_adc_struct::num_samples, hess_tel_monitor_struct::pedestal, hess_tel_image_struct::phi, hess_tel_event_data_struct::pixcal, hess_pixel_list::pixel_list, hess_pixel_list::pixels, hess_pixel_list::pixels, hess_pixel_list::pixels, hess_pixel_list::pixels, hess_pixel_list::pixels, hess_pixel_list::pixels, hess_pixel_list::pixels, hess_pixel_list::pixels, hess_pixel_list::pixels, hess_pixels, hess _tel_image_struct::pixels, hess_mc_shower_struct::primary_id, print_pix_col(), hess_tel_event_data_struct::raw, hess_run_header_struct::run, hess_event_data_struct::shower, hess_camera_settings_struct::size, hess_camerasettings struct::tel id, hess run header struct::tel pos, hess event data struct::teldata, hess event data struct::trackdata, hess tel event data struct::trigger pixels, hess tel image struct::w, hess tel image struct::x, hess mc event struct::xcore, hess camera settings struct::xpix, hess tel image struct::y, hess mc event struct::ycore, hess_camera_settings_struct::ypix, and hess_tel_event_adc_struct::zero_sup_mode.

Referenced by main().

```
7.5.2.3 static void print_pix_col ( double n_o_r, FILE * psfile, double gamma_coeff ) [static]
```

Print a false-colour RGB value for a pixel intensity.

Referenced by hesscam_ps_plot().

7.5.3 Variable Documentation

```
7.5.3.1 char alt_az_arrow[] [static]
```

Initial value:

```
"n 18000 26000 m '
"0 100 rl 200 -100 rl -200 -100 rl 0 100 rl -1000 0 rl "
cp gs 20 slw black s gr\n'
"txt5 18700 26100 mtxt (Az) tblack\n"
"n 17000 25000 m "
"100 0 rl -100 -200 rl -100 200 rl 100 0 rl 0 1000 rl "
cp gs 20 slw black s gr\n"
"txt5 17000 24600 mtxt (Alt) tblack\n"
"gs 17800 25500 tr %f rot -17800 -25500 tr\n"
   n 17800 25500 m
  "0 100 rl 200 -100 rl -200 -100 rl 0 100 rl -300 0 rl "
  "cp gs 10 slw black s gr\n"
 "txt2 17950 25350 mtxt (y) tblack\n"
"n 17500 25200 m"
 "100 0 rl -100 -200 rl -100 200 rl 100 0 rl 0 300 rl "
  "cp gs 10 slw black s gr\n"
  "txt2 17700 25200 mtxt (x) tblack\n"
```

118 File Documentation

```
7.5.3.2 char ps_begin_page1[] [static]
Initial value:
"%%Page: "
7.5.3.3 char ps_begin_page2[] [static]
Initial value:
"save\n"
"10 setmiterlimit\n"
"n -1000 31000 m -1000 -1000 1 22000 -1000 1 22000 31000 1 cp clip\n"
"0.02835 0.02835 sc\n"
"gs\n"
"7.500 slw\n"
"black\n"
7.5.3.4 char ps_end_page[] [static]
Initial value:
"gr\n"
"showpage\n"
7.5.3.5 char ps_head1[] [static]
Initial value:
"%!PS-Adobe-2.0\n"
"%%Title: H.E.S.S. Telescope Simulation\n"
"%%Creator:"
7.5.3.6 char ps_trailer[] [static]
Initial value:
=
"rs\n"
```


7.6 check_trgmask.c File Reference

Check consistency of 'trgmask' files produced with gen_trgmask for the CTA prod-2 data sets produced in 2013.

```
#include "initial.h"
#include "io_basic.h"
#include "fileopen.h"
#include "io_trgmask.h"
```

7.7 current.c File Reference

Include dependency graph for check_trgmask.c:



Functions

• int **main** (int argc, char **argv)

7.6.1 Detailed Description

Check consistency of 'trgmask' files produced with gen_trgmask for the CTA prod-2 data sets produced in 2013.

```
Syntax: bin/check_trgmask trgmask-file
```


@author Konrad Bernloehr

7.7 current.c File Reference

Code to insert current time string into warnings.

```
#include "initial.h"
#include "current.h"
```

Include dependency graph for current.c:



Macros

• #define __Current_Module__ 1

Functions

```
• static long time_correction (time_t now)
```

• time_t current_time ()

Get the current time in seconds since 1970.0 GMT.

• time t current localtime ()

Like current_time() but should return time in the local time zone.

void set_current_offset (long off)

Set current time offset.

· void set local offset (long off)

Set offset of local time zone.

void reset_local_offset ()

Reset any previous local time offset.

• char * time_string ()

Return a pointer to a formatted time-and-date string.

• time_t mkgmtime (struct tm *tms)

Inverse to gmtime() library function.

Variables

- static long tcor_parm [3]
- static long local_offset = DEFAULT_LOCAL_OFFSET
- static int local_set =0

7.7.1 Detailed Description

Code to insert current time string into warnings. This code is meant for inserting time strings into warnings passed through the code of warning.c. It is not currently used in my code and is not yet multi-threading safe. It is here mainly for improved backward-compatibility with config.c.

Author

Konrad Bernloehr

Date

1995, 2000, 2007

Date:

2010/07/20 13:37:45

Version

Revision:

1.7

7.7 current.c File Reference 121

7.7.2 Function Documentation

7.7.2.1 time_t current_localtime (void)

Like current time() but should return time in the local time zone.

The offset of the time zone to GMT must be set by set_local_offset() or it is derived from the machine's internal time zone setup.

References current time(), and mkgmtime().

Referenced by time_string().

7.7.2.2 time_t current_time (void)

Get the current time in seconds since 1970.0 GMT.

The resulting time includes the last time correction with respect to the server. Therefore, as long as the clock on the local computer is not much slower or faster than the clock on the I/O server, it is the current Greenwich Mean Time on the I/O server.

Returns

Time in seconds since 0h UT on January 1, 1970.

Referenced by current_localtime().

7.7.2.3 time_t mkgmtime (struct tm * tms)

Inverse to gmtime() library function.

Inverse to gmtime() library function without correction for timezone and daylight saving time.

Parameters

tms Pointer to time structure as filled by gmtime().

Returns

Time in seconds since 1970.0

Referenced by current_localtime().

7.7.2.4 void reset_local_offset (void)

Reset any previous local time offset.

Reset any previously set local time offset. The next call to current_localtime() will therefore set the offset to present system value.

Note: in a multi-threaded program this function should be called only at program startup.

Returns

(none)

7.7.2.5 void set_current_offset (long off)

Set current time offset.

Set the offset between the time on the time server and the local time (in seconds in the sense 'remote-local').

Note: in a multi-threaded program this function should be called only at program startup.

Parameters

off	Time offset in seconds

Returns

(none)

7.7.2.6 void set_local_offset (long off)

Set offset of local time zone.

Set the offset between the local time zone and GMT (in seconds in the sense 'local zone - GMT').

Note: in a multi-threaded program this function should be called only at program startup.

Parameters

off	Time offset in seconds
-----	------------------------

Returns

(none)

7.7.2.7 char* time_string (void)

Return a pointer to a formatted time-and-date string.

This string is reused (changed) on the next call.

Returns


Time/date character string pointer.

References current_localtime().

7.8 current.h File Reference

Header file for optional current time add-on to warning.c.

This graph shows which files directly or indirectly include this file:



7.8 current.h File Reference 123

Macros

#define DEFAULT_LOCAL_OFFSET 3600

Functions

```
• time_t current_time (void)
```

Get the current time in seconds since 1970.0 GMT.

time_t current_localtime (void)

Like current_time() but should return time in the local time zone.

void set_current_offset (long _toffset)

Set current time offset.

void set_local_offset (long _local_offset)

Set offset of local time zone.

void reset_local_offset (void)

Reset any previous local time offset.

• char * time_string (void)

Return a pointer to a formatted time-and-date string.

• time_t mkgmtime (struct tm *tms)

Inverse to gmtime() library function.

Variables

time_t last_data_time

7.8.1 Detailed Description

Header file for optional current time add-on to warning.c.

Author

Konrad Bernloehr

Date

1993 (original version)

Date:

2010/07/20 13:37:45

Revision:

1.4

7.8.2 Function Documentation

7.8.2.1 time_t current_localtime (void)

Like current_time() but should return time in the local time zone.

The offset of the time zone to GMT must be set by set_local_offset() or it is derived from the machine's internal time zone setup.

References current_time(), and mkgmtime().

Referenced by time_string().

7.8.2.2 time_t current_time (void)

Get the current time in seconds since 1970.0 GMT.

The resulting time includes the last time correction with respect to the server. Therefore, as long as the clock on the local computer is not much slower or faster than the clock on the I/O server, it is the current Greenwich Mean Time on the I/O server.

Returns

Time in seconds since 0h UT on January 1, 1970.

Referenced by current localtime().

7.8.2.3 time_t mkgmtime (struct tm * tms)

Inverse to gmtime() library function.

Inverse to gmtime() library function without correction for timezone and daylight saving time.

Parameters

tms	Pointer to time structure as filled by gmtime().
-----	--

Returns

Time in seconds since 1970.0

Referenced by current localtime().

7.8.2.4 void reset_local_offset (void)

Reset any previous local time offset.

Reset any previously set local time offset. The next call to current_localtime() will therefore set the offset to present system value.

Note: in a multi-threaded program this function should be called only at program startup.

Returns

(none)

7.8.2.5 void set_current_offset (long off)

Set current time offset.

Set the offset between the time on the time server and the local time (in seconds in the sense 'remote-local').

Note: in a multi-threaded program this function should be called only at program startup.

Parameters

off	Time offset in seconds

Returns

(none)

7.9 cvt2.c File Reference 125

7.8.2.6 void set_local_offset (long off)

Set offset of local time zone.

Set the offset between the local time zone and GMT (in seconds in the sense 'local zone - GMT').

Note: in a multi-threaded program this function should be called only at program startup.

Parameters

```
off Time offset in seconds
```

Returns

(none)

7.8.2.7 char* time_string (void)

Return a pointer to a formatted time-and-date string.

This string is reused (changed) on the next call.

Returns

Time/date character string pointer.


References current_localtime().

7.9 cvt2.c File Reference

Utility program for converting histograms to HBOOK format.

```
#include "initial.h"
#include "histogram.h"
#include "io_basic.h"
#include "tohbook.h"
#include "io_histogram.h"
#include "fileopen.h"
```

Include dependency graph for cvt2.c:



Functions

int main (int argc, char **argv)
 Main program.

7.9.1 Detailed Description

Utility program for converting histograms to HBOOK format.

```
Syntax: hdata2hbook [ input_file [ output_file ] ]
    or: hdata2hbook -a input_files ... -o output_file
```

The program was originally called cvt2. The default input file name is 'testpattern.hdata', the default output file name is 'testpattern.hbook' or the input file name with extension '.hbook' (instead of '.hdata'). The histograms may be within multiple I/O blocks of the input file. Only non-empty histograms are written to output.

With the '-a' option, all identical histograms in the input files will be added up before writing them to output.

Author

Konrad Bernloehr

Date

```
CVS $Date: 2014/02/20 10:53:06 $
```

Version


```
CVS $Revision: 1.23 $
```

7.10 cvt3.cc File Reference

Conversion of eventio histograms to ROOT format.

```
#include "initial.h"
#include "histogram.h"
#include "io_basic.h"
#include "io_histogram.h"
#include "warning.h"
#include "fileopen.h"
#include "straux.h"
#include "toroot.hh"
#include <vector>
```

Include dependency graph for cvt3.cc:



7.11 dhsort.c File Reference 127

Functions

- int read_file (IO_BUFFER *iobuf, const char *fname, int add_flag, int list_flag)
- int main (int argc, char **argv)

7.10.1 Detailed Description

Conversion of eventio histograms to ROOT format.

```
Syntax: hdata2root [ input_file [ output_file ] ]
    or: hdata2root -a input_files ... -o output_file
```

The program was originally called cvt3. The default input file name is 'testpattern.hdata', the default output file name is 'testpattern.root' or the input file name with extension '.root' (instead of '.hdata'). The histograms may be within multiple I/O blocks of the input file. Only non-empty histograms are written to output. Take care not to replace any ROOT data format you wanted to keep.

With the '-a' option, all identical histograms in the input files will be added up before writing them to output.

Author

Konrad Bernloehr

Date

```
CVS $Date: 2011/10/31 17:32:07 $
```

Version


```
CVS $Revision: 1.18 $
```

7.11 dhsort.c File Reference

dhsort - double type number heapsort

```
#include "initial.h"
#include "dhsort.h"
```

Include dependency graph for dhsort.c:



Functions

void dhsort (double *dnum, int nel)

Perform a heap sort on a double array starting at dnum.

7.11.1 Detailed Description

dhsort - double type number heapsort

```
@author Konrad Bernloehr
@date $Date: 2010/07/20 13:37:45 $
@version $Revision: 1.6 $
```

Based on algorithms by Jon Bentley [Communications of the ACM v 28~n~3~p~245~(Mar~85) and v 28~n~5~p~456~(May~85)], and the sort interface routines by Allen I. Holub [Dr. Dobb's Journal #102 (Apr 85)].

Notes...

This routine sorts N doubles in worst-case time proportional to N*log(N). The heapsort was discovered by J. W. J. Williams [Communications of the ACM v 7 p 347-348 (1964)] and is discussed by D. E. Knuth [The Art of Computer Programming, Volume 3: Sorting and Searching, Addison-Wesley, Reading, Mass., 1973, section 5.2.3].

This algorithm depends on a portion of an array having the "heap" property. The array X has the property heap[L,U] if:

```
for all L, i, and U such that 2L \le i \le U we have X[i \text{ div } 2] \le X[i]
```

7.11.2 Function Documentation

7.11.2.1 void dhsort (double * dnum, int nel)


Perform a heap sort on a double array starting at dnum.

7.12 eventio_registry.c File Reference

Register and enquire about well-known I/O block types.

```
#include "initial.h"
#include "eventio_registry.h"
#include "fileopen.h"
```

Include dependency graph for eventio_registry.c:



Data Structures

struct ev_reg_chain

Use a double-linked list for the registry.

Functions

```
- struct ev_reg_entry * new_reg_entry (unsigned long t, const char *n, const char *d)
```

Allocate a new entry for the registry.

int read_eventio_registry (const char *fname)

Read the type names and descriptions into the registry.

static void read_default_registry (void)

By default the registry contents will be searched in a few places.

struct ev_reg_entry * find_ev_reg_std (unsigned long t)

Find an entry for a given type number in the registry.

• void set_ev_reg_std ()

Set the default registry search function.

Variables

static struct ev_reg_chain * ev_reg_start = NULL

7.12.1 Detailed Description

Register and enquire about well-known I/O block types.

Author

Konrad Bernloehr

Date

2014

CVS

Date:

2014/06/03 16:19:44

Version

CVS

Revision:

1.3

7.12.2 Function Documentation

```
7.12.2.1 struct ev_reg_entry* find_ev_reg_std ( unsigned long t )
```

Find an entry for a given type number in the registry.

This is the standard implementation being used by default where available.

References ev_reg_chain::entry, and read_default_registry().

Referenced by set_ev_reg_std().

7.12.2.2 int read_eventio_registry (const char * fname)

Read the type names and descriptions into the registry.

Note: this will only be done once.

References ev_reg_chain::entry, fileclose(), fileopen(), and new_reg_entry().

Referenced by read_default_registry().

```
7.12.2.3 void set_ev_reg_std (void)
```

Set the default registry search function.

At least with GCC we can do this without explicitly calling it.


References find_ev_reg_std().

7.13 eventio_registry.h File Reference


Register and enquire about well-known I/O block types.

```
#include "initial.h"
#include "io_basic.h"
```

Include dependency graph for eventio_registry.h:



This graph shows which files directly or indirectly include this file:



Functions

```
    int read_eventio_registry (const char *fname)
        Read the type names and descriptions into the registry.
    struct ev_reg_entry * find_ev_reg_std (unsigned long t)
        Find an entry for a given type number in the registry.
    void set_ev_reg_std (void)
        Set the default registry search function.
```

7.13.1 Detailed Description

Register and enquire about well-known I/O block types.

Author

Konrad Bernloehr

Date

2014 CVS

Date:

2014/06/01 11:33:04

Version

CVS

Revision:

1.2

7.13.2 Function Documentation

```
7.13.2.1 struct ev_reg_entry* find_ev_reg_std ( unsigned long t )
```

Find an entry for a given type number in the registry.

This is the standard implementation being used by default where available.

References ev_reg_chain::entry, and read_default_registry().

Referenced by set_ev_reg_std().

```
7.13.2.2 int read_eventio_registry ( const char * fname )
```

Read the type names and descriptions into the registry.

Note: this will only be done once.

References ev_reg_chain::entry, fileclose(), fileopen(), and new_reg_entry().

Referenced by read_default_registry().

```
7.13.2.3 void set_ev_reg_std (void)
```

Set the default registry search function.

At least with GCC we can do this without explicitly calling it.


References find ev reg std().

7.14 extract_hess.c File Reference

Extract part of the H.E.S.S.

```
#include "initial.h"
#include "io_basic.h"
#include "mc_tel.h"
#include "history.h"
#include "io_hess.h"
#include "histogram.h"
#include "io_histogram.h"
#include "fileopen.h"
#include <signal.h>
```

Include dependency graph for extract_hess.c:



Functions

- static void syntax (char *program)
 - Show program syntax.
- int main (int argc, char **argv)

Main program.

Variables

· static int interrupted

7.14.1 Detailed Description

Extract part of the H.E.S.S. data from sim_hessarray.

7.15 fcat.c File Reference

Author

Konrad Bernloehr

Date

```
CVS $Date: 2014/10/28 14:23:47 $
```

Version


```
CVS $Revision: 1.7 $
```

7.15 fcat.c File Reference

Trivial test and utility program for the fileopen/fileclose functions.

```
#include <stdlib.h>
#include <stdio.h>
#include <errno.h>
#include "fileopen.h"
```

Include dependency graph for fcat.c:



Macros

• #define **BSIZE** 8192

Functions

• int main (int argc, char **argv)


7.15.1 Detailed Description

Trivial test and utility program for the fileopen/fileclose functions.

7.16 fileopen.c File Reference

Allow searching of files in declared include paths (fopen replacement).

```
#include "initial.h"
#include "straux.h"
#include "fileopen.h"
#include <errno.h>
#include <sys/types.h>
#include <sys/stat.h>
Include dependency graph for fileopen.c:
```



Data Structures

· struct incpath

An element in a linked list of include paths.

Functions

- static FILE * popenx (const char *fname, const char *mode)
- static FILE * fopenx (const char *fname, const char *mode)
- void set_permissive_pipes (int p)

Enable or disable the permissive execution of pipes.

• void enable_permissive_pipes ()

Enable the permissive execution of pipes.

· void disable_permissive_pipes ()

Disable the permissive execution of pipes.

static void freepath ()

Free a whole list of include path elements.

• static void freeexepath ()

Free a whole list of execution path elements.

• void initpath (const char *default_path)

Init the path list, with default_path as the only entry.

- void initexepath (const char *default_exe_path)
- void listpath (char *buffer, size_t bufsize)

Show the list of include paths.

void addpath (const char *name)

Add a path to the list of include paths, if not already there.

• void addexepath (const char *name)

Add a path to the list of execution paths, if not already there.

• static FILE * exe_popen (const char *fname, const char *mode)

Helper function for opening a pipe from or to a given program.

• static FILE * cmp_popen (const char *fname, const char *mode, int compression)

Helper function for opening a compressed file through a fifo.

• static FILE * uri_popen (const char *fname, const char *mode, int compression)

Helper function for opening a file with a URI (http://etc.).

• static FILE * ssh_popen (const char *fname, const char *mode, int compression)

Helper function for opening a file on a remote SSH server.

• FILE * fileopen (const char *fname, const char *mode)

Search for a file in the include path list and open it if possible.

• int fileclose (FILE *f)

Close a file or fifo but not if it is one of the standard streams.

Variables

static int verbose = 0

Use to decide if open/close success/failure is reported.

static struct incpath * root_path = NULL

The starting element of include paths.

static struct incpath * root exe path = NULL

The starting element for execution paths.

• static int permissive pipes = 0

Allow any execution pipe command if this variable is non-zero.

7.16.1 Detailed Description

Allow searching of files in declared include paths (fopen replacement). The functions provided in this file provide an enhanced replacement fileopen() for the C standard library's fopen() function. The enhancements are in several areas:

- Where possible files are opened such that more than 2 gigabytes of data can be accessed on 32-bit systems when suitably compiled. This also works with software where a '-D_FILE_OFFSET_BITS=64' at compile-time cannot be used (of which ROOT is an infamous example).
- For reading files, a list of paths can be configured before the the first fileopen() call and all files without absolute paths will be searched in these paths. Writing always strictly follows the given file name and will not search in the path list.
- Files compressed with gzip or bzip2 can be handled on the fly. Files with corresponding file name extensions (.gz and .bz2) will be automatically decompressed when reading or compressed when writing (in a pipe, i.e. without producing temporary copies).
- In the same way, files compressed with lzop (for extension .lzo), lzma (for extension .lzma) as well as xz (for extension @ .xz) and lz4 (for extension .lz4) are handled on the fly. No check is made if these programs are installed.
- URIs (uniform resource identifiers) starting with https:, or ftp: will also be opened in a pipe, with optional decompression, depending on the ending of the URI name. You can therefore easily process files located on a web or ftp server. Access is limited to reading.
- Files on any SSH server where you can login without a password can be read as 'ssh://user:filepath' where filepath can be an absolute path (starting with '/') or one relative to the users home directory.
- Input and output can also be from/to a user-defined program. Restrictions apply there which prevent execution of any program by default. Either a list of accepted execution paths has to be set up beforehand with initexepath()/addexepath() or permissive mode can be enabled, allowing execution of any given program.

Author

Konrad Bernloehr

```
Date
```

```
Nov. 2000
```

```
CVS $Date: 2015/05/05 11:50:06 $
```

Version

```
CVS $Revision: 1.19 $
```

7.16.2 Function Documentation

```
7.16.2.1 void addexepath ( const char * name )
```

Add a path to the list of execution paths, if not already there.

The path name is always copied to a newly allocated memory location. This path name can actually be a colon-separated list, as for initexepath().

References addpath(), root_exe_path, and root_path.

```
7.16.2.2 void addpath ( const char * name )
```

Add a path to the list of include paths, if not already there.

The path name is always copied to a newly allocated memory location. This path name can actually be a colon-separated list, as for initpath(). Also environment variables (indicated by starting with '\$', e.g. "\$HOME") are accepted (and may expand into colon-separated list) but no mixed expansion (like "\$HOME/bin").

References getword(), incpath::next, incpath::path, root_path, and verbose.

Referenced by addexepath(), and initpath().

```
7.16.2.3 static FILE* cmp_popen ( const char * fname, const char * mode, int compression ) [static]
```

Helper function for opening a compressed file through a fifo.

References verbose.

Referenced by fileopen().

```
7.16.2.4 void disable_permissive_pipes (void)
```

Disable the permissive execution of pipes.

Referenced by set permissive pipes().

```
7.16.2.5 void enable_permissive_pipes (void)
```

Enable the permissive execution of pipes.

Referenced by set permissive pipes().

```
7.16.2.6 static FILE* exe_popen ( const char * fname, const char * mode ) [static]
```

Helper function for opening a pipe from or to a given program.

References incpath::next, incpath::path, and verbose.

Referenced by fileopen().

```
7.16.2.7 int fileclose (FILE * f)
```

Close a file or fifo but not if it is one of the standard streams.

References verbose.

Referenced by check_autoload_trgmask(), hesscam_ps_plot(), main(), read_eventio_registry(), trgmask_scan_log(), write_all_histograms(), write_tel_compact_photons(), and write_tel_photons().

```
7.16.2.8 FILE* fileopen ( const char * fname, const char * mode )
```

Search for a file in the include path list and open it if possible.

References cmp_popen(), exe_popen(), initpath(), incpath::next, incpath::path, root_path, ssh_popen(), uri_popen(), and verbose.

Referenced by check_autoload_trgmask(), hesscam_ps_plot(), init_atmprof(), main(), read_eventio_registry(), trgmask_scan_log(), write_all_histograms(), write_tel_compact_photons(), and write_tel_photons().

```
7.16.2.9 static void freeexepath( ) [static]
```

Free a whole list of execution path elements.

References incpath::next, and incpath::path.

```
7.16.2.10 static void freepath( ) [static]
```

Free a whole list of include path elements.

References incpath::next, and incpath::path.

Referenced by initpath().

```
7.16.2.11 void initpath ( const char * default_path )
```

Init the path list, with default path as the only entry.

References addpath(), freepath(), getword(), and verbose.

Referenced by fileopen().

```
7.16.2.12 void listpath ( char * buffer, size_t bufsize )
```

Show the list of include paths.

References incpath::next, and incpath::path.

```
7.16.2.13 void set_permissive_pipes ( int p )
```

Enable or disable the permissive execution of pipes.

References disable_permissive_pipes(), and enable_permissive_pipes().

```
7.16.2.14 static FILE * uri_popen ( const char * fname, const char * mode, int compression ) [static]
```

Helper function for opening a file with a URI (http://etc.).

References verbose.

Referenced by fileopen().

7.16.3 Variable Documentation

7.16.3.1 int permissive_pipes = 0 [static]

Allow any execution pipe command if this variable is non-zero.

7.16.3.2 struct incpath* root_exe_path = NULL [static]

The starting element for execution paths.

Referenced by addexepath().

7.16.3.3 struct incpath* root_path = NULL [static]

The starting element of include paths.

Referenced by addexepath(), addpath(), and fileopen().

7.17 fileopen.h File Reference

Function prototypes for fileopen.c.

This graph shows which files directly or indirectly include this file:



Functions

void initpath (const char *default path)

Init the path list, with default_path as the only entry.

- void initexepath (const char *default_path)
- void listpath (char *buffer, size_t bufsize)

Show the list of include paths.

void addpath (const char *name)

Add a path to the list of include paths, if not already there.

void addexepath (const char *name)

Add a path to the list of execution paths, if not already there.

• FILE * fileopen (const char *fname, const char *mode)

Search for a file in the include path list and open it if possible.

int fileclose (FILE *f)

Close a file or fifo but not if it is one of the standard streams.

void set_permissive_pipes (int p)

Enable or disable the permissive execution of pipes.

void enable_permissive_pipes (void)

Enable the permissive execution of pipes.

• void disable_permissive_pipes (void)

Disable the permissive execution of pipes.

7.17.1 Detailed Description

Function prototypes for fileopen.c.

Author

Konrad Bernloehr

Date

```
CVS $Date: 2014/06/23 09:34:45 $
```

Version

```
CVS $Revision: 1.7 $
```

7.17.2 Function Documentation

```
7.17.2.1 void addexepath ( const char * name )
```

Add a path to the list of execution paths, if not already there.

The path name is always copied to a newly allocated memory location. This path name can actually be a colon-separated list, as for initexepath().

References addpath(), root exe path, and root path.

```
7.17.2.2 void addpath ( const char * name )
```

Add a path to the list of include paths, if not already there.

The path name is always copied to a newly allocated memory location. This path name can actually be a colon-separated list, as for initpath(). Also environment variables (indicated by starting with '\$', e.g. "\$HOME") are accepted (and may expand into colon-separated list) but no mixed expansion (like "\$HOME/bin").

References getword(), incpath::next, incpath::path, root_path, and verbose.

Referenced by addexepath(), and initpath().

```
7.17.2.3 void disable_permissive_pipes (void)
```

Disable the permissive execution of pipes.

Referenced by set_permissive_pipes().

```
7.17.2.4 void enable_permissive_pipes ( void )
```

Enable the permissive execution of pipes.

Referenced by set_permissive_pipes().

```
7.17.2.5 int fileclose (FILE * f)
```

Close a file or fifo but not if it is one of the standard streams.

References verbose.

Referenced by check_autoload_trgmask(), hesscam_ps_plot(), main(), read_eventio_registry(), trgmask_scan_log(), write_all_histograms(), write_tel_compact_photons(), and write_tel_photons().

```
7.17.2.6 FILE* fileopen ( const char * fname, const char * mode )
```

Search for a file in the include path list and open it if possible.

References cmp_popen(), exe_popen(), initpath(), incpath::next, incpath::path, root_path, ssh_popen(), uri_popen(), and verbose.

Referenced by check_autoload_trgmask(), hesscam_ps_plot(), init_atmprof(), main(), read_eventio_registry(), trgmask scan log(), write all histograms(), write tel compact photons(), and write tel photons().

```
7.17.2.7 void initpath ( const char * default_path )
```

Init the path list, with default_path as the only entry.

References addpath(), freepath(), getword(), and verbose.

Referenced by fileopen().

```
7.17.2.8 void listpath ( char * buffer, size_t bufsize )
```

Show the list of include paths.

References incpath::next, and incpath::path.

```
7.17.2.9 void set_permissive_pipes ( int p )
```

Enable or disable the permissive execution of pipes.


References disable_permissive_pipes(), and enable_permissive_pipes().

7.18 gen_lookup.c File Reference

Generate image shape and energy lookups for user analysis in read_hess.

```
#include "initial.h"
#include "io_basic.h"
#include "histogram.h"
#include "io_histogram.h"
#include "fileopen.h"
```

Include dependency graph for gen_lookup.c:



Functions

- void fill_gaps ()
 - Fill gaps in those histograms used for generating the lookups.
- void gen_image_lookups ()

Generate the lookups for image shape parameters and energy.

- void fill_ebias_correction (void)
- void syntax (char *prgm)
- int main (int argc, char **argv)

Variables

- HISTOGRAM * h18000
- HISTOGRAM * h18001
- HISTOGRAM * h18011
- HISTOGRAM * h18012
- HISTOGRAM * h18021
- HISTOGRAM * h18022
- HISTOGRAM * h18051
- HISTOGRAM * **h18052**
- HISTOGRAM * h18100
 HISTOGRAM * h18101
- HISTOGRAM * h18111
- HISTOGRAM * h18112
- · IIIOTOGITAW * IIIOTIZ
- HISTOGRAM * h18121
 HISTOGRAM * h18122
- HIGT CODAM HIGHE
- HISTOGRAM * **h18151**
- HISTOGRAM * h18152
- HISTOGRAM * h18113
 HISTOGRAM * h18114
- HISTOGRAM * h18123
- HISTOGRAM * h18124

```
    HISTOGRAM * h18140

    HISTOGRAM * h18141

    HISTOGRAM * h18153

    HISTOGRAM * h18154

    HISTOGRAM * h18005

    HISTOGRAM * h18006

    HISTOGRAM * h18071

    HISTOGRAM * h18072

    HISTOGRAM * h18081

    HISTOGRAM * h18082

    HISTOGRAM * h18105

    HISTOGRAM * h18106

    HISTOGRAM * h18171

    HISTOGRAM * h18172

    HISTOGRAM * h18181

    HISTOGRAM * h18182

    HISTOGRAM * h18173

    HISTOGRAM * h18174

    HISTOGRAM * h18183

    HISTOGRAM * h18184

    HISTOGRAM * h18200

    HISTOGRAM * h18201

    HISTOGRAM * h18211

    HISTOGRAM * h18212

    HISTOGRAM * h18301

    HISTOGRAM * h18311

    HISTOGRAM * h18321

    HISTOGRAM * h18322
```

7.18.1 Detailed Description

Generate image shape and energy lookups for user analysis in read_hess. Read_hess must be run with user analysis once and the generated histogram file is used by this program to generate the lookups. The lookup file is used in the next round of read_hess user analysis, if found under the desired name. Look at the last lines of output from read_hess (or at the beginning, right after the history) to see how the lookup file should be called (depends on tail cut parameters, and so on).

```
Date
```

```
CVS $Revision: 1.21 $

Version

CVS $Date: 2012/05/11 13:18:48 $
```

7.18.2 Function Documentation

```
7.18.2.1 void fill_gaps ( )
```

Fill gaps in those histograms used for generating the lookups.

Depending on the physical quantities we have different strategies for interpolation/extrapolation/smoothing.


References Histogram_Extension::ddata, histogram::extension, fill_histogram(), Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, Histogram_Parameters::real, and Histogram_Parameters::upper_limit.

7.19 gen_trgmask.c File Reference

A utility program for fixing problems with simulation data which does not have the correct bit pattern of telescope triggers but the correct pattern can be extracted from the log files.

```
#include "initial.h"
#include "io_basic.h"
#include "fileopen.h"
#include "io_trgmask.h"
```

Include dependency graph for gen_trgmask.c:



Functions

- void syntax (char *prgname)
- int main (int argc, char **argv)

7.19.1 Detailed Description

A utility program for fixing problems with simulation data which does not have the correct bit pattern of telescope triggers but the correct pattern can be extracted from the log files.

```
Syntax: bin/gen_trgmask log-file [ trgmask-file ] or: bin/gen_trgmask -1 trgmask-file

The first variant will create a file with a single data block for the trigger mask patterns recovered from the log file.

The default file name is derived with extension .trgmask.gz

Note that only data for one run per file is supported.

The second variant will list the contents of such a file.
```


@author Konrad Bernloehr

7.20 hconfig.c File Reference

Configuration control and procedure call interface.

```
#include "initial.h"
#include "io_basic.h"
#include <ctype.h>
#include "warning.h"
#include <errno.h>
#include "hconfig.h"
#include "history.h"
```

Include dependency graph for hconfig.c:



Data Structures

• struct ConfigBlockStruct

Configuration is organized in sections.

- struct config_specific_data
- · struct Binary_Interface_Chain

Macros

- #define get_config_specific() (&config_defaults)
- #define TMP_FORMAT "cfg%d.tmp"

Typedefs

• typedef struct ConfigBlockStruct CONFIG_BLOCK

Functions

- static int do_config (CONFIG_ITEM *item, CONST char *line)

 Internal configuration function.
- static void config_syntax_error (const char *name, const char *text)
- static void config_info (const char *name, const char *text)
- static int set_config_values (CONFIG_ITEM *item, int first, int last, char *text)

Set configuration values (internal usage only).

static void display_config_current (CONFIG_ITEM *item)

Display current values of a single configuration item (internal usage only).

• static void display_config_item (CONFIG_ITEM *item)

Display a single configuration item (internal usage only).

- static int do_reset_func (const char *text)
- static int **signed_config_val** (const char *name, const char *text, const char *lbound, const char *ubound, int strict, long *ival)
- static int **unsigned_config_val** (const char *name, const char *text, const char *lbound, const char *ubound, int strict, unsigned long *uval)
- static int **hex_config_val** (const char *name, const char *text, const char *lbound, const char *ubound, int strict, unsigned long *uval)

- static int **real_config_val** (const char *name, const char *text, const char *lbound, const char *ubound, int strict, double *rval)
- static int f_show_config (const char *name, CONFIG_VALUES *val)

Display the current configuration status (internal usage only).

- static int f lock config (const char *name, CONFIG VALUES *val)
- static int f unlock config (const char *name, CONFIG VALUES *val)
- static int f_limit_config (const char *name, CONFIG_VALUES *val)
- static int f_status_config (const char *name, CONFIG_VALUES *val)
- static int f list config (const char *name, CONFIG VALUES *val)
- static int f_get_config (const char *name, CONFIG_VALUES *val)
- static int **f_echo** (const char *name, CONFIG_VALUES *val)
- static int f_warning (const char *name, CONFIG_VALUES *val)
- static int f_error (const char *name, CONFIG_VALUES *val)
- static int save config values (CONFIG ITEM *item, int first, int last)
- static int restore config values (CONFIG ITEM *item, int first, int last)
- int build config (CONFIG ITEM *items, const char *section)

Build up the configuration by adding another section of configuration definitions.

int init_config (char *(*fptr)(void))

Initialize the configuration after all build_config() calls.

void unhook internal ()

Disable access to internal functions via configuration.

void rehook internal ()

Enable access again to internal functions via configuration.

int reload_config (char *(*fptr)(void))

Reload some configuration using the file name/preprocessor as set up for init config() or with different file etc.

CONFIG ITEM * find config item (const char *name)

Find a configuration item by its name (mainly for internal usage).

- int verify_config_section (char *section)
- int set_config_history (PFITI fptr)

Set a function for recording the history of the configuration settings.

int reconfig (char *text)

Modify the configuration after init config() has been called.

- static int lock unlock status (const char *name, int lock)
- int is_signed_number (const char *text)
- int is_unsigned_number (const char *text)
- int is_hex_number (const char *text)
- int is_bin_number (const char *text)
- unsigned long decode_bin_number (const char *text)
- int is_real_number (const char *text)
- void set_config_filename (const char *fname)

Set the name of the configuration file to be read by the function read_config_lines().

char * get config filename ()

Return the current value of the configuration file name.

void set_config_preprocessor (char *preproc)

Set the command name and options of a preprocessor for configuration files to be read by function read_config_-lines().

• char * get config preprocessor ()

Return the current value of the configuration preprocessor.

void set_config_stack (char **stack)

Set a list of configuration lines to be processed before any lines from a file are read by read_config_lines().

char * read_config_lines ()

Read configuration data from a file and return it line by line to the calling function (one line per call).

• int read_config_status ()

Return the status of reading a configuration file with read_config_lines() in a preceding call to init_config().

int define_config_binary_interface (int item_type, size_t elem_size, void *(*new_func)(int nelem, int item_type), int(*delete_func)(void *ptr, int nelem, int item_type), int(*read_func)(void *bin_item, IO_BUFFER *iobuf, int item_type), int(*write_func)(void *bin_item, IO_BUFFER *iobuf, int item_type), int(*readtext_func)(void *bin_item, char *text, int item_type), int(*list_func)(void *bin_item, int item_type), int(*copy_func)(void *bin_item_to, void *bin_item_from, int io_type))

Define a binary interface for an I/O type.

struct

```
Config_Binary_Item_Interface * find_config_binary_interface (int item_type)
```

Find the matching binary interface for given item type.

Variables

static CONFIG_ITEM default_config []

Internal functions of the hoonfig package.

- · static CONFIG BLOCK first config block
- static int internal unhooked = 0
- static PFITI history_function
- · int config level
- static struct config_specific_data config_defaults
- · static struct

Binary_Interface_Chain * bin_chain_root

- static char cfg_fname [1024]
- static char preprocessor [4096] = ""
- static char ** cfg_stack
- · static int read_status

7.20.1 Detailed Description

Configuration control and procedure call interface.

Author

Konrad Bernloehr

Date

Date:

2015/06/25 13:01:17

Version

Revision:

1.19

This is the module controlling all configuration except that a function has to be supplied that collects input line for line. Most functions in this file are for internal use only and are given a 'static' modifier. The only functions to be called by the user are

```
build_config()
       init config()
       reconfig().
In order to set up the configuration, one or several calls to
build_config() should be done, each with a list of 'configuration
items' ('CONFIG_ITEM *items') terminated by a NULL_CONFIG_ITEM
as an end marker. The list must be of 'static' or global/'extern'
type and none of its entries must be modified by the user in any
way, once they have been passed to build_config.
Such a list might look like the following example:
       static CONFIG_ITEM cfg_list[] =
          { "ANY_Numbers", "Int", 30, iarray },
          { "ANY_Function", "function", -1, NULL, some_function }, 
{ "REAL_Number", "R", 10, dblarray, NULL, "0-9: 99.9",
              "10", "100", CFG_REQUIRE_ALL_DATA | CFG_REJECT_MODIFICATION },
          { "DYnAllocArray", "i", 100, NULL, NULL },
          { NULL_CONFIG_ITEM }
The components of each item are:
       1) The name, consisting of letters, digits, and ^\prime\_^\prime .
          In external data the items are referenced by their name
          which may be abbreviated and is case-insensitive. However,
          the name used for the definition is case-sensitive in the
          current implementation. The first lowercase letter indicates
          the minimum length of accepted abbrevations. In the example
          above "ANY_Numbers" may be abbreviated as "any_n", "any_nu",
          and so on, "DYnAllocArray" as "dy", "dyn", and so on.
          It is the user's responsibility the avoid conflicts of the
          accepted abbreviations of any two items.
       2) The type which may be an abbreviation of one of the following:
             "Character", "Short", "Integer", "Long" (signed integer types),
             "UCharacter", "UShort", "UInteger, "ULong" (unsigned types)
"FLoat", "Real", "Double" (floating point, "Real" == "Double"),
             "Text" (simple text, character string),
             "FUnction" (a function reference, not a data reference).
       3) The number of data element. Must be -1 for "FUnction" type.
          The terminating ' \setminus 0' in characters strings should be included.
       4) A data pointer of any type. Must be NULL for "FUnction type.
          If the data should be dynamically allocated by the configuration
          software it should be a pointer to the pointer that should
          be set. Allocated data is initialized with '0's.
       5) A function pointer. Must not be NULL except for "FUnction" type
          and is optional (may be NULL) for data type entries.
          For the "Function" type, the data (normally a character string)
          is passed as the only argument. For data type entries,
          the associated functions are called with an extended
          calling syntax.
       6) A pointer to a character string with the default initialization
          values or NULL.
       7) A pointer to a character string with a lower bound value or \mathtt{NULL}.
       8) A pointer to a character string with an upper bound value or NULL.
       9) An integer where any of the following flags may be combined
          CFG_REQUIRE_DATA
             CFG_REQUIRE_ALL_DATA
             CFG_REJECT_MODIFICATION
      10) Reserved. In multi_threaded mode, use
             CFG_MUTEX(&some_pthread_mutex)
          if the associated function is not fully reentrant or
          if a set of functions should only be called one at a time.
      11) Reserved. Do not modify. Is 1 if reconfigured.
```

Components not specified are automatically initialized to NULL or 0.

The reason why build_config may be called several times (with different configuration items each time) is that this way the configuration items for each more or less independent part of a program may be defined separately and

there is no need for global data sharing. You only need to call a 'configuration definition function' for each part which has its items defined and only calls build_config().

Once the whole configuration items from all parts have been passed to build_config(), a single call to init_config() is required to make the configuration effective. init_config() first sets those initial values declared in the items (if any) and then tries to get external data line by line from a function passed to init_config(), unless a NULL pointer is passed instead of a function pointer. This user-defined function (declared 'char *user_function(void);') should return the address of the first character of each line read from a configuration file, the command line, or anywhere else, until the end of input which the function must indicate by returning a NULL pointer. Input lines can be of any length up to 10240 bytes and may include a linefeed character as read by fgets(). Note that there used to be a problem with semicolons in comments, which should be fixed now - but beware of possible side-effects.

Later, configuration data can be changed by calling reconfig() with a line of input passed as argument. Configuration data marked as 'not to be modified' will not be changed. If a configuration item is of 'function' type that function will be called with the remaining line (after extracting the item name and processing special characters) passed as argument.

7.20.2 Function Documentation

7.20.2.1 int build_config (CONFIG ITEM * items, const char * section)

Build up the configuration by adding another section of configuration definitions.

Parameters

items	Vector of configuration items, which is terminated by a NULL_CONFIG_ITEM
section	Name of this configuration section.

Returns

0 (O.k.), -1 (memory allocation failed), -2 (other error)

7.20.2.2 CONFIG_ITEM* find_config_item (const char * name)

Find a configuration item by its name (mainly for internal usage).

Parameters

name	Item name or block:name

Returns

Pointer to (first) configuration item found or NULL.

References abbrev(), and ConfigltemStruct::name.

Referenced by f_show_config(), and reconfig().

7.20.2.3 char* get_config_filename (void)

Return the current value of the configuration file name.

Parameters

–	(none)

Returns

pointer to static file name string

7.20.2.4 char* get_config_preprocessor (void)

Return the current value of the configuration preprocessor.

Parameters

–	(none)
---	--------

Returns

pointer to static command string

7.20.2.5 int init_config (char *(*)(void) fptr)

Initialize the configuration after all build_config() calls.

Initialize the configuration after all sections have been supplied via build_config(). A function may be specified for reading external configuration data after the internal specifications have been processed. This function may be called only once.

Parameters

fptr	Pointer to function that returns a string pointer as long as external configuration data is avail-
	able, and NULL when no more data is available. fptr may be NULL if no such function should
	be called.

Returns

0 (O.k.), -1 (called a second time or invalid configuration data)

References abbrev(), ConfigItemStruct::data, ConfigValues::data_changed, ConfigValues::data_saved, do_config(), ConfigValues::elem_size, Config_Binary_Item_Interface::elem_size, ConfigIntern::elem_size, ConfigValues::elem_size, ConfigValues::elem_size, ConfigItemStruct::flags, ConfigItemStruct::initial, ConfigItemStruct::internal, Config_Binary_Item_Interface::io_item_type, ConfigValues::itype, ConfigIntern::itype, ConfigItemStruct::lbound, ConfigValues::list_mod, ConfigValues::max_mod, ConfigValues::mod_flag, ConfigValues::name, ConfigItemStruct::name, Config_Binary_Item_Interface::new_func, reconfig(), ConfigValues::section, ConfigItemStruct::size, ConfigItemStruct::type, ConfigItemStruct::ubound, and ConfigIntern::values.

7.20.2.6 char* read_config_lines (void)

Read configuration data from a file and return it line by line to the calling function (one line per call).

A NULL pointer is returned on end-of-file. This function is intended to be used as the usual 'fptr' argument for init_config().

Parameters

–	(none)

Returns

Pointer to character string or NULL.

7.20.2.7 int read_config_status (void)

Return the status of reading a configuration file with read_config_lines() in a preceding call to init_config().

Parameters

–	(none)
---	--------

Returns

0 (o.k.), -1 (no config file set), -2 (config file open failed), -3 (preprocessing failed), -4 (read error).

7.20.2.8 int reconfig (char * text)

Modify the configuration after init_config() has been called.

Parameters

text	String consisting of configuration keyword (separated by a blank or '=' from the rest) and the
	corresponding data.

Returns

0 (O.k.), -1 (invalid or undefined configuration keyword or error in the data)

References do_config(), find_config_item(), getword(), ConfigItemStruct::internal, ConfigIntern::locked, and ConfigItemStruct::name.

Referenced by init_config(), and reload_config().

7.20.2.9 int reload_config (char *(*)(void) fptr)

Reload some configuration using the file name/preprocessor as set up for init_config() or with different file etc.

Parameters

fptr	Pointer to function that returns a string pointer as long as external configuration data is avail-
	able, and NULL when no more data is available.

Returns

0 (O.k.), -1 (invalid configuration data)

References reconfig().

7.20.2.10 void set_config_filename (const char * fname)

Set the name of the configuration file to be read by the function read_config_lines().

Parameters

fname	Name of file to be used.
-------	--------------------------

Returns

(none)

7.20.2.11 int set_config_history (PFITI fptr)

Set a function for recording the history of the configuration settings.

Parameters

fptr	- Pointer to function of type 'int fptr(char *text,int flag)' where 'text' is the configuration line
	and flag is 0 for configuration file processing and 1 for latre reconfiguration.

Returns

0

7.20.2.12 void set_config_preprocessor (char * preproc)

Set the command name and options of a preprocessor for configuration files to be read by function read_config_lines().

The input and output file names will be appended to the command string set by this function.

Parameters

```
preproc Command string
```

Returns

(none)

7.20.2.13 void set_config_stack (char ** stack)

Set a list of configuration lines to be processed before any lines from a file are read by read_config_lines().

Parameters

```
stack Pointer to NULL terminated vector of strings.
```

Returns

(none)

7.20.3 Variable Documentation

7.20.3.1 struct config_specific_data config_defaults [static]

Initial value:

```
=
{
    "_internal_"
}
```

7.20.3.2 CONFIG_ITEM default_config[] [static]

Initial value:

```
CFG_MUTEX(mlock_hconfig) },
{ "LIMITS", "FUN", -1, NULL, f_limit_config, NULL, NULL, NULL, 0, NULL, CFG_MUTEX(mlock_hconfig) },
{ "STATUS", "FUN", -1, NULL, f_status_config, NULL, NULL, NULL, 0, NULL,
   CFG_MUTEX(mlock_hconfig) },
'LIST", "FUN", -1, NULL, f_list_config, NULL, NULL, NULL, 0, NULL,
{ "LIST",
   CFG_MUTEX(mlock_hconfig) },
             "FUN", -1, NULL, f_get_config, NULL, NULL, NULL, 0, NULL,
   CFG_MUTEX(mlock_hconfig) },
{ "ECHO", "FUN", -1, NULL, f_echo,
    CFG_MUTEX(mlock_hconfig) },
                                                NULL, NULL, NULL, 0, NULL,
{ "WARNING", "FUN", -1, NULL, f_warning,
                                                 NULL, NULL, NULL, O, NULL,
   CFG_MUTEX(mlock_hconfig) },
{ "ERROR", "FUN", -1, NULL, f_error,
                                                NULL, NULL, NULL, O, NULL,
   CFG_MUTEX(mlock_hconfig) },
{ NULL_CONFIG_ITEM }
```

Internal functions of the hconfig package.

7.20.3.3 CONFIG_BLOCK first_config_block [static]


Initial value:

```
= 
{ "_internal_", default_config, (CONFIG_BLOCK *) NULL, 0 }
```


7.21 hconfig.h File Reference

Declare hconfig structures and functions.

```
#include "initial.h"
#include "io_basic.h"
Include dependency graph for hconfig.h:
```



This graph shows which files directly or indirectly include this file:



Data Structures

· union ConfigDataPointer

This union of pointers allows convenient access of various types of data.

• union ConfigBoundary

Configuration value may have optional lower and/or upper bounds.

struct ConfigValues

Configuration values and supporting data passed to user functions.

• struct Config_Binary_Item_Interface

Interface definitions for binary-only items.

• struct ConfigIntern

Configuration elements used only internally.

struct ConfigItemStruct

Configuration as used in definitions of configuration blocks.

Macros

- #define NO_INITIAL_MACROS 1
- #define _XSTR_(s) _STR_(s)

Expand a macro first and then enclose in string.

• #define _STR_(s) #s

Enclose in string without macro expansion.

- #define CONST const
- #define IO TYPE HCONFIG ENVELOPE 900
- #define IO_TYPE_HCONFIG_NAME 901
- #define IO_TYPE_HCONFIG_TEXT 902
- #define IO_TYPE_HCONFIG_INDEX 903
- #define IO_TYPE_HCONFIG_NUMBERS 904
- #define CFG_REQUIRE_DATA 1
- #define CFG_REQUIRE_ALL_DATA 2
- #define CFG_REJECT_MODIFICATION 4
- #define CFG_HARD_BOUND 8
- #define CFG STRICT BOUND 16
- #define CFG_INITIALIZED 32
- #define CFG ALL INITIALIZED 64
- #define CFG_NOT_INITIAL 128

- #define NULL_CONFIG_ITEM (char *) NULL, (char *) NULL, 0, NULL, NULL
- #define CFG_MUTEX(mutex) (NULL)

Mutexes are only inserted when pthreads are used.

Typedefs

- typedef void *(* PFVP)(char *, char *, int)
- typedef int(* PFISI)(char *, int)
- typedef int(* PFITI)(const char *, int)
- typedef int(* PFISS)(char *, char *)
- typedef struct ConfigValues CONFIG_VALUES
- typedef int(* PFIX)(const char *name, CONFIG_VALUES *val)
- typedef struct ConfigItemStruct CONFIG_ITEM

Functions

• int build_config (CONFIG_ITEM *items, const char *section)

Build up the configuration by adding another section of configuration definitions.

int init config (char *(*fptr)(void))

Initialize the configuration after all build_config() calls.

· void unhook_internal (void)

Disable access to internal functions via configuration.

void rehook_internal (void)

Enable access again to internal functions via configuration.

int reload_config (char *(*fptr)(void))

Reload some configuration using the file name/preprocessor as set up for init_config() or with different file etc.

- void * config_alloc_data (char *name, char *type, int size)
- int reconfig (char *text)

Modify the configuration after init_config() has been called.

- int verify_config_section (char *section)
- int set_config_history (PFITI fptr)

Set a function for recording the history of the configuration settings.

• void set_config_filename (const char *fname)

Set the name of the configuration file to be read by the function read_config_lines().

char * get_config_filename (void)

Return the current value of the configuration file name.

void set_config_preprocessor (char *preproc)

Set the command name and options of a preprocessor for configuration files to be read by function read_config_-lines().

char * get_config_preprocessor (void)

Return the current value of the configuration preprocessor.

void set_config_stack (char **stack)

Set a list of configuration lines to be processed before any lines from a file are read by read_config_lines().

• char * read_config_lines (void)

Read configuration data from a file and return it line by line to the calling function (one line per call).

int read_config_status (void)

Return the status of reading a configuration file with read_config_lines() in a preceding call to init_config().

CONFIG ITEM * find config item (const char *name)

Find a configuration item by its name (mainly for internal usage).

int define_config_binary_interface (int item_type, size_t elem_size, void *(*new_func)(int nelem, int item_type), int(*delete_func)(void *ptr, int nelem, int item_type), int(*read_func)(void *bin_item, IO_BUFFER *iobuf, int item_type), int(*write_func)(void *bin_item, IO_BUFFER *iobuf, int item_type), int(*readtext_func)(void *bin_item, char *text, int item_type), int(*list_func)(void *bin_item, int item_type), int(*copy_func)(void *bin_item_to, void *bin_item_from, int io_type))

Define a binary interface for an I/O type.

· struct

Config_Binary_Item_Interface * find_config_binary_interface (int item_type)

Find the matching binary interface for given item type.

- int reconfig_binary (char *buffer, size_t buflen)
- int config binary read text (IO BUFFER *iobuf, char *name, int maxlen)

Get a hconfig name or text item from an I/O buffer.

- int is_signed_number (const char *text)
- int is_unsigned_number (const char *text)
- int is hex number (const char *text)
- int is_bin_number (const char *text)
- int is real number (const char *text)
- unsigned long decode bin number (const char *text)
- int abbrev (CONST char *s, CONST char *t)

Compare strings s and t.

• int getword (CONST char *s, int *spos, char *word, int maxlen, char blank, char endchar)

Copies a blank or '\0' or < endchar > delimeted word from position *spos of the string s to the string word and increment *spos to the position of the first non-blank character after the word.

• int config_binary_read_index (IO_BUFFER *iobuf, int *nidx, int *idx_low, int *idx_high, int max_idx)

Get a list of index ranges for binary hconfig data following.

• int config_binary_write_name (IO_BUFFER *iobuf, char *name)

Write the name of a hconfig item for which binary data should follow.

• int config_binary_write_text (IO_BUFFER *iobuf, char *text)

Write 'binary' hconfig data as text (for 'string' or 'function' types).

• int config_binary_text_length (IO_BUFFER *iobuf)

If the next item is of the text type, get the length of the text.

• int config_binary_read_name (IO_BUFFER *iobuf, char *name, int maxlen)

Is the same as config_binary_read_text().

• int config_binary_write_index (IO_BUFFER *iobuf, int nidx, int *idx_low, int *idx_high)

Put a list of index ranges for binary hconfig data following.

• int config_binary_envelope_begin (IO_BUFFER *iobuf, IO_ITEM_HEADER *item_header)

Begin with the envelope for a binary configuration item.

• int config_binary_envelope_end (IO_BUFFER *iobuf, IO_ITEM_HEADER *item_header)

Close the envelope for a binary configuration item.

• int config_binary_inquire_numbers (IO_BUFFER *iobuf, int *ntype, int *nsize, int32_t *num, int *nopt)

Tell me what kind of binary numbers follow in the next I/O item.

• int config_binary_read_numbers (IO_BUFFER *iobuf, void *data, size_t max_size)

Get the binary numbers from the next I/O item.

• int config_binary_convert_data (void *out, int out_type, int out_size, void *in, int in_type, int in_size)

Concert binary numbers of one type to numbers of another type.

7.21.1 Detailed Description

Declare hoonfig structures and functions.

Author

Konrad Bernloehr

Date

CVS

Date:

2014/02/20 11:40:42

Version

CVS

Revision:

1.7

7.21.2 Macro Definition Documentation

```
7.21.2.1 #define _STR_( s ) #s
```

Enclose in string without macro expansion.

7.21.2.2 #define CFG_MUTEX(mutex) (NULL)

Mutexes are only inserted when pthreads are used.

In the multi-threaded variant: the address of the given mutex. In the single-threaded variant: a null pointer.

7.21.3 Function Documentation

```
7.21.3.1 int abbrev ( CONST char * s, CONST char * t )
```

Compare strings s and t.

s may be an abbreviation of t. Upper/lower case in s is ignored. s has to be at least as long as the leading upper case, digit, and '_' part of t.

Parameters

s	The string to be checked.
t	The test string with minimum part in upper case.

Returns

1 if s is an abbreviation of t, 0 if not.

Referenced by do_config(), find_config_item(), and init_config().

7.21.3.2 int build_config (CONFIG_ITEM * items, const char * section)

Build up the configuration by adding another section of configuration definitions.

Parameters

items	Vector of configuration items, which is terminated by a NULL_CONFIG_ITEM
section	Name of this configuration section.

Returns

0 (O.k.), -1 (memory allocation failed), -2 (other error)

7.21.3.3 int config_binary_convert_data (void * out, int out_type, int out_size, void * in, int in_type, int in_size)

Concert binary numbers of one type to numbers of another type.

Supported types are signed integers of various lengths, unsigned integers of various lengths, float and double. The signed and unsigned integers can be 1, 2, 4 or perhaps 8 bytes long. Float should be 4 bytes long, double 8 bytes.

7.21.3.4 int config_binary_read_text (IO_BUFFER * iobuf, char * name, int maxlen)

Get a hoonfig name or text item from an I/O buffer.

Both the IO_TYPE_HCONFIG_NAME and IO_TYPE_HCONFIG_TEXT eventio item types are simple text strings enclosed in an I/O item. Because either of them can appear at the beginning of binary configuration data (with different interpretations) they are distinguished by different item type numbers. Otherwise they are the same.

Referenced by config binary read name().

7.21.3.5 int config_binary_text_length (IO_BUFFER * iobuf)

If the next item is of the text type, get the length of the text.

This allows finding out the length of the text first, allocating enough memory to read it and then start reading the text.

Returns

The length of the string not including the trailing '\0' which has to be appended.

7.21.3.6 int config_binary_write_name ($IO_BUFFER * iobuf$, char * name)

Write the name of a hoonfig item for which binary data should follow.

Calls config_binary_write_as_text().

7.21.3.7 int config_binary_write_text ($IO_BUFFER * iobuf$, char * text)

Write 'binary' hconfig data as text (for 'string' or 'function' types).

Calls config_binary_write_as_text().

7.21.3.8 CONFIG_ITEM* find_config_item (const char * name)

Find a configuration item by its name (mainly for internal usage).

Parameters

name	Item name or block:name
------	-------------------------

Returns

Pointer to (first) configuration item found or NULL.

References abbrev(), and ConfigltemStruct::name.

Referenced by f_show_config(), and reconfig().

7.21.3.9 char* get_config_filename (void)

Return the current value of the configuration file name.

Parameters

–	(none)
,	

Returns

pointer to static file name string

7.21.3.10 char* get_config_preprocessor (void)

Return the current value of the configuration preprocessor.

Parameters

–	(none)

Returns

pointer to static command string

7.21.3.11 int getword (CONST char * s, int * spos, char * word, int maxlen, char blank, char endchar)

Copies a blank or '\0' or < endchar > delimeted word from position *spos of the string s to the string word and increment *spos to the position of the first non-blank character after the word.

The word must have a length less than or equal to maxlen.

Parameters

S	string with any number of words.
spos	position in the string where we start and end.
word	the extracted word.
maxlen	the maximum allowed length of word.
blank	has the same effect as '', i.e. end-of-word.
endchar	his terminates the whole string (as '\0').

Returns

-2 : Invalid string or NULL -1 : The word was longer than maxlen (without the terminating $\0$); 0 : There were no more words in the string s. 1 : ok, we have a word and there are still more of them in the string s 2 : ok, but this was the last word

Referenced by addpath(), do_config(), initpath(), main(), prog_path(), reconfig(), and user_set_tel_type_param_by_str().

7.21.3.12 int init_config (char *(*)(void) fptr)

Initialize the configuration after all build_config() calls.

Initialize the configuration after all sections have been supplied via build_config(). A function may be specified for reading external configuration data after the internal specifications have been processed. This function may be called only once.

Parameters

fptr	Pointer to function that returns a string pointer as long as external configuration data is avail-
	able, and NULL when no more data is available. fptr may be NULL if no such function should
	be called.

Returns

0 (O.k.), -1 (called a second time or invalid configuration data)

References abbrev(), ConfigItemStruct::data, ConfigValues::data_changed, ConfigValues::data_saved, do_config(), ConfigValues::elem_size, Config_Binary_Item_Interface::elem_size, ConfigIntern::elem_size, ConfigValues::elem_size, ConfigValues::elem_size, ConfigItemStruct::flags, ConfigItemStruct::initial, ConfigItemStruct::internal, Config_Binary_Item_Interface::io_item_type, ConfigValues::itype, ConfigIntern::itype, ConfigItemStruct::lbound, ConfigValues::list_mod, ConfigValues::max_mod, ConfigValues::mod_flag, ConfigValues::name, ConfigItemStruct::name, Config_Binary_Item_Interface::new_func, reconfig(), ConfigValues::section, ConfigItemStruct::size, ConfigItemStruct::type, ConfigItemStruct::ubound, and ConfigIntern::values.

7.21.3.13 char* read_config_lines (void)

Read configuration data from a file and return it line by line to the calling function (one line per call).

A NULL pointer is returned on end-of-file. This function is intended to be used as the usual 'fptr' argument for init_config().

Parameters

–	(none)

Returns

Pointer to character string or NULL.

7.21.3.14 int read_config_status (void)

Return the status of reading a configuration file with read_config_lines() in a preceding call to init_config().

Parameters

– (none)

Returns

0 (o.k.), -1 (no config file set), -2 (config file open failed), -3 (preprocessing failed), -4 (read error).

7.21.3.15 int reconfig (char * text)

Modify the configuration after init_config() has been called.

Parameters

text	String consisting of configuration keyword (separated by a blank or '=' from the rest) and the
	corresponding data.

Returns

0 (O.k.), -1 (invalid or undefined configuration keyword or error in the data)

References do_config(), find_config_item(), getword(), ConfigItemStruct::internal, ConfigIntern::locked, and ConfigItemStruct::name.

Referenced by init_config(), and reload_config().

7.21.3.16 int reload_config (char *(*)(void) fptr)

Reload some configuration using the file name/preprocessor as set up for init_config() or with different file etc.

Parameters

fptr	Pointer to function that returns a string pointer as long as external configuration data is avail-
	able, and NULL when no more data is available.

Returns

0 (O.k.), -1 (invalid configuration data)

References reconfig().

7.21.3.17 void set_config_filename (const char * fname)

Set the name of the configuration file to be read by the function read_config_lines().

Parameters

fname Name of file to be used.	fname
--------------------------------	-------

Returns

(none)

7.21.3.18 int set_config_history (PFITI fptr)

Set a function for recording the history of the configuration settings.

Parameters

fptr	- Pointer to function of type 'int fptr(char *text,int flag)' where 'text' is the configuration line
	and flag is 0 for configuration file processing and 1 for latre reconfiguration.

Returns

0

7.21.3.19 void set_config_preprocessor (char * preproc)

Set the command name and options of a preprocessor for configuration files to be read by function read_config_lines().

The input and output file names will be appended to the command string set by this function.

Parameters

preproc	Command string

Returns

(none)

7.21.3.20 void set_config_stack (char ** stack)

Set a list of configuration lines to be processed before any lines from a file are read by read_config_lines().

Parameters

stack	Pointer to NULL terminated vector of strings.
-------	---

Returns

(none)

7.22 hessio_doc.h File Reference

Add an introduction to doxygen-generated documentation.

7.22.1 Detailed Description


Add an introduction to doxygen-generated documentation. This file is not included during compilation.

7.23 histogram.c File Reference

Manage, fill, and display one- and two-dimensional histograms.

```
#include "initial.h"
#include "histogram.h"
#include "warning.h"
```

Include dependency graph for histogram.c:



Macros

- #define HLOCK
- #define _HUNLOCK_
- #define WAIT_IF_BUSY_(histo)
- #define CLEAR BUSY (histo)
- #define HistOutput(a)

Functions

static void initialize histogram (HISTOGRAM *histo)

For internal purpose only.

static HISTOGRAM * aux_alloc_histogram (int ncounts, const char *type)

For internal purpose only.

static void free_histo_contents (HISTOGRAM *histo)

Free the contents (data pointers) of a histogram to be released or removed.

static void display_2d_histogram (HISTOGRAM *histo)

Display contents of a 2D histogram.

- void histogram lock (HISTOGRAM *histo)
- void histogram_unlock (HISTOGRAM *histo)
- HISTOGRAM * get_first_histogram ()

Get a pointer to the first histogram.

void sort_histograms ()

Sort histograms in linked list by idents.

void set first histogram (HISTOGRAM *new first histogram)

Set a new histogram as the first element (context switching).

HISTOGRAM * get_histogram_by_ident (long ident)

Get a histogram with the given ID.

void list histograms (long ident)

List all available histograms using the 'Output()' function.

 HISTOGRAM * book_histogram (long id, const char *title, const char *type, int dimension, double *low, double *high, int *nbins)

General histogram booking function, assigning ID and title.

 HISTOGRAM * book_1d_histogram (long id, const char *title, const char *type, double low, double high, int nbins)

Simplified histogram booking function for one-dimensional histograms, assigning ID and title.

- HISTOGRAM * book_int_histogram (long id, const char *title, int dimension, long *low, long *high, int *nbins)

 Book and integer-type histogram (content incremented by one per entry).
- HISTOGRAM * allocate_histogram (const char *type, int dimension, double *low, double *high, int *nbins)
- HISTOGRAM * alloc_int_histogram (long low, long high, int nbins)

Allocate memory for a 1-D 'int' histogram and initialize it.

Allocate any histogram without ID and title.

• HISTOGRAM * alloc_real_histogram (double low, double high, int nbins)

Allocate memory for a 1-D 'real' histogram and initialize it.

HISTOGRAM * alloc_2d_int_histogram (long xlow, long xhigh, int nxbins, long ylow, long yhigh, int nybins)

Allocate memory for a 2-D 'int' histogram and initialize it.

HISTOGRAM * alloc_2d_real_histogram (double xlow, double xhigh, int nxbins, double ylow, double yhigh, int nybins)

Allocate memory for a 2-D 'int' histogram and initialize it.

void describe histogram (HISTOGRAM *histo, const char *title, long ident)

Add a describing title to a histogram previously allocated.

void clear_histogram (HISTOGRAM *histo)

Initialize an existing histogram.

void free_histogram (HISTOGRAM *histo)

Free a histogram completely (both data and control structure).

void free_all_histograms ()

Deletes all histograms which are included in the linked list of histograms.

void unlink histogram (HISTOGRAM *histo)

Remove a histogram from the list without destroying it.

• int fill_int_histogram (HISTOGRAM *histo, long value)

Increment a bin of a 1-D 'int' histogram by one.

• int fill_real_histogram (HISTOGRAM *histo, double value)

Increment a bin of a 1-D 'real' histogram by one.

• int fill_weighted_histogram (HISTOGRAM *histo, double value, double weight)

Add an entry to a weighted 1-D histogram.

int fill_2d_int_histogram (HISTOGRAM *histo, long xvalue, long yvalue)

Increment a bin of a 2-D 'int' histogram by one.

• int fill_2d_real_histogram (HISTOGRAM *histo, double xvalue, double yvalue)

Increment a bin of a 2-D 'real' histogram by one.

• int fill_2d_weighted_histogram (HISTOGRAM *histo, double xvalue, double yvalue, double weight)

Add an entry to a weighted 2-D histogram.

int fill_histogram (HISTOGRAM *histo, double xvalue, double yvalue, double weight)

Fill any type of 1-D or 2-D histogram known by its pointer.

• int fill_histogram_by_ident (long id, double xvalue, double yvalue, double weight)

Fill any type of 1-D or 2-D histogram known by its ID number.

• int histogram_matching (HISTOGRAM *histo1, HISTOGRAM *histo2)

Check if two histograms have exactly matching definitions (same type, dimension, size, ranges).

HISTOGRAM * add_histogram (HISTOGRAM *histo1, HISTOGRAM *histo2)

Add a second histogram to a first one.

• int stat histogram (HISTOGRAM *histo, struct histstat *stbuf)

Statistical analysis of a histogram.

• double locate histogram fraction (HISTOGRAM *histo, double fraction)

Locate point of arbitrary fraction of entries (quantile).

• int fast_stat_histogram (HISTOGRAM *histo, struct histstat *stbuf)

Fast and basic histogram statistics.

void print_histogram (HISTOGRAM *histo)

Print contents of a histogram on the terminal.

void display_histogram (HISTOGRAM *histo)

Display contents of a histogram on the terminal.

• void display_all_histograms ()

Display all histograms in list of histograms.

int histogram_to_lookup (HISTOGRAM *histo, HISTOGRAM *lookup)

Convert a histogram to a lookup table by integrating the histogram.

long lookup_int (HISTOGRAM *lookup, long value, long factor)

Look up a table created from an integer histogram.

double lookup_real (HISTOGRAM *lookup, double value, double factor)

Look up a table created from an 'real' histogram.

• int histogram_hashing (int tabsize)

Turn hashing of histograms (using their ident as key) on or off.

Variables

```
    static HISTOGRAM * first_histogram = (HISTOGRAM *) NULL
    static HISTOGRAM * last_histogram = (HISTOGRAM *) NULL
    FILE * histogram_file
    static HISTOGRAM ** hash_table
    static long hash_size = 0
    static CONST_QUAL short primetab []
    static CONST_QUAL int zero = 0
```

7.23.1 Detailed Description

Manage, fill, and display one- and two-dimensional histograms. Eventio routines for these types of histograms are available in io_histogram.c. Conversion to HBOOK format is available through the hdata2hbook (was cvt2) program. Conversion to ROOT format is available through the hdata2root (was cvt3) program.

Note: multi-threading safety of functions provided in this file has not been tested extensively. Threads must not delete histograms shared with other threads when referenced by pointers.

Author

Konrad Bernloehr

Date

1991 - 2010 CVS

Date:

2014/02/20 10:53:06

Version

CVS

Revision:

1.21

7.23.2 Macro Definition Documentation

```
7.23.2.1 #define HistOutput( a)
```

Value:

```
do { if ( histogram_file == (FILE *) NULL ) \
    Output(a); \
    else \
        fputs(a, histogram_file); } while(zero)
```

7.23.3 Function Documentation

```
7.23.3.1 HISTOGRAM* add_histogram ( HISTOGRAM * histo1, HISTOGRAM * histo2 )
```

Add a second histogram to a first one.

The histograms must exactly match in their definitions. The first histogram will be modified, the second is unchanged.

Parameters

histo1	pointer to first histogram
histo2	pointer to second histogram

Returns

NULL pointer indicates failure.

References Histogram_Extension::content_all, Histogram_Extension::content_inside, Histogram_Extension::content_outside, histogram::counts, Histogram_Extension::ddata, histogram::extension, Histogram_Extension::fdata, histogram_matching(), histogram::ident, Histogram_Parameters::integer, histogram::nbins, histogram::overflow, histogram::overflow_2d, Histogram_Parameters::real, Histogram_Parameters::sum, Histogram_Parameters::tsum, histogram::type, histogram::underflow, and histogram::underflow_2d.

Referenced by read histograms x().

7.23.3.2 HISTOGRAM* alloc_2d_int_histogram (long xlow, long xhigh, int nxbins, long ylow, long yhigh, int nybins)

Allocate memory for a 2-D 'int' histogram and initialize it.

Resulting histogram has integer range limits and integer contents (incremented by one per entry).

Parameters

xlow	lower limit of values in X to be covered by histogram
xhigh	upper limit
nxbins	the number of bins to be allocated in X
ylow	lower limit of values in Y to be covered by histogram
yhigh	upper limit
nybins	the number of bins to be allocated in Y

Returns

pointer to allocated histogram or NULL

References aux_alloc_histogram(), initialize_histogram(), Histogram_Parameters::integer, Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, Histogram_Parameters::upper_limit, and Histogram_Parameters::width.

Referenced by allocate_histogram(), book_int_histogram(), and read_histograms_x().

7.23.3.3 **HISTOGRAM*** alloc_2d_real_histogram (double *xlow*, double *xhigh*, int *nxbins*, double *ylow*, double *yhigh*, int *nybins*)

Allocate memory for a 2-D 'int' histogram and initialize it.

Resulting histogram has floating point range limits and integer contents (incremented by one per entry).

Parameters

xlow	lower limit of values in X to be covered by histogram
xhigh	upper limit
nxbins	the number of bins to be allocated in X
ylow	lower limit of values in Y to be covered by histogram

yhigh	upper limit
nybins	the number of bins to be allocated in Y

Returns

pointer to allocated histogram or NULL

References allocate_histogram().

Referenced by read_histograms_x().

7.23.3.4 HISTOGRAM* alloc_int_histogram (long low, long high, int nbins)

Allocate memory for a 1-D 'int' histogram and initialize it.

Resulting histogram has integer range limits and integer contents (incremented by one per entry).

Parameters

low	lower limit of values to be covered by histogram
high	upper limit
nbins	the number of bins to be allocated

Returns

pointer to allocated histogram or NULL

References aux_alloc_histogram(), initialize_histogram(), Histogram_Parameters::integer, Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, Histogram_Parameters::upper_limit, and Histogram_Parameters::width.

Referenced by allocate_histogram(), book_int_histogram(), and read_histograms_x().

7.23.3.5 HISTOGRAM* alloc_real_histogram (double low, double high, int nbins)

Allocate memory for a 1-D 'real' histogram and initialize it.

Resulting histogram has floating point range limits and integer contents (incremented by one per entry).

Parameters

low	lower limit of values to be covered by histogram
high	upper limit
nbins	the number of bins to be allocated

Returns

pointer to allocated histogram or NULL

References allocate_histogram().

Referenced by read_histograms_x().

7.23.3.6 HISTOGRAM* allocate_histogram (const char * type, int dimension, double * low, double * high, int * nbins)

Allocate any histogram without ID and title.

Allocate a histogram of 1 or 2 dimensions, 'I', 'R', 'F' or 'D' type, without assigning an ID number and title string to it. To avoid the (long) <-> (double) typecasts, the direct calls to alloc_int_histogram() and alloc_2d_int_histogram() are recommended for integer-limits histograms (type 'I').

Parameters

type	"I" (int, no weights), "R" (real, no weights), "F" (float, with weights), "D" (double, w.w.)
dimension	1 or 2 for 1-D or 2-D histogram
low	Pointer to lower limits (x or x,y for 1-D or 2-D)
high	Pointer to upper limits
nbins	Pointer to no. of bins per dimension (nx or nx, ny)

Returns

Pointer to new histogram or NULL

References alloc_2d_int_histogram(), alloc_int_histogram(), aux_alloc_histogram(), initialize_histogram(), Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins, histogram::nbins, histogram_Parameters::real, and Histogram_Parameters::upper_limit.

Referenced by alloc_2d_real_histogram(), alloc_real_histogram(), book_1d_histogram(), book_histogram(), and read_histograms_x().

7.23.3.7 HISTOGRAM* book_1d_histogram (long id, const char * title, const char * type, double low, double high, int nbins)

Simplified histogram booking function for one-dimensional histograms, assigning ID and title.

Book a histogram of one dimension, 'I', 'R', 'F', or 'D' type. The histogram is allocated (if possible) and the supplied ID number and title string are assigned.

Parameters

id	ID number
title	Histogram title string
type	"I" (int, no weights), "R" (real, no weights), "F" (float, with weights), "D" (double, w.w.)
low	Lower limit (x)
high	Upper limit (x)
nbins	No. of bins (nx)

Returns

Pointer to new histogram or NULL

References allocate_histogram(), and describe_histogram().

Referenced by mc event fill(), and user init().

7.23.3.8 HISTOGRAM* book_histogram (long id, const char * title, const char * type, int dimension, double * low, double * high, int * nbins)

General histogram booking function, assigning ID and title.

Book a histogram of 1 or 2 dimensions, 'I', 'R', 'F', or 'D' type. The histogram is allocated (if possible) and the supplied ID number and title string are assigned.

Parameters

id	ID number
title	Histogram title string

type	"I" (int, no weights), "R" (real, no weights), "F" (float, with weights), "D" (double, w.w.)
dimension	1 or 2 for 1-D or 2-D histogram
low	Pointer to lower limits (x or x,y for 1-D or 2-D)
high	Pointer to upper limits
nbins	Pointer to no. of bins per dimension (nx or nx, ny)

Returns

Pointer to new histogram or NULL

References allocate_histogram(), and describe_histogram().

Referenced by main(), mc_event_fill(), and user_init().

7.23.3.9 HISTOGRAM* book_int_histogram (long id, const char * title, int dimension, long * low, long * high, int * nbins)

Book and integer-type histogram (content incremented by one per entry).

Like book_histogram() but for 'I' type histograms only (1-D or 2-D)

Parameters

id	ID number
title	Histogram title string
dimension	1 or 2 for 1-D or 2-D histogram
low	Pointer to lower limits (x or x,y for 1-D or 2-D)
high	Pointer to upper limits
nbins	Pointer to no. of bins per dimension (nx or nx, ny)

Returns

Pointer to new histogram or NULL

References alloc_2d_int_histogram(), alloc_int_histogram(), and describe_histogram().

7.23.3.10 void clear_histogram (HISTOGRAM * histo)

Initialize an existing histogram.

Parameters

histo	– pointer to histogram

Returns

(none)

References Histogram_Extension::content_all, Histogram_Extension::content_inside, Histogram_Extension::content_outside, histogram::counts, Histogram_Extension::ddata, histogram::extension, Histogram_Extension::fdata, Histogram_Parameters::integer, histogram::nbins, histogram::nbins_2d, histogram::overflow, histogram::overflow_2d, Histogram_Parameters::real, Histogram_Parameters::sum, histogram::tentries, Histogram_Parameters::tsum, histogram::type, histogram::underflow, and histogram::underflow_2d.

Referenced by gen_image_lookups(), histogram_to_lookup(), initialize_histogram(), and write_dst_histos().

7.23.3.11 void describe_histogram (HISTOGRAM * histo, const char * title, long ident)

Add a describing title to a histogram previously allocated.

Parameters

	histo	Histogram to which the title should be added
ſ	title	The title string. This is ignored if the histogram already has a title.
ſ	ident	Identification number, must be unique (or 0) if any I/O is intended, because read_histogram()
		deletes a pre-existing histogram with the same ID.

Returns

none

References get_histogram_by_ident(), histogram::ident, and histogram::title.

Referenced by book_1d_histogram(), book_histogram(), book_int_histogram(), and read_histograms_x().

7.23.3.12 static void display_2d_histogram (HISTOGRAM * histo) [static]

Display contents of a 2D histogram.

Called by display_histogram().

The histogram has already been checked by display_histogram() and its title has been printed.

Parameters

histo	- Pointer to histogram

Returns

(none)

References histogram::counts, Histogram_Extension::ddata, histogram::entries, histogram::extension, Histogram_Extension::fdata, Histogram_Parameters::integer, Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, histogram::overflow, histogram::overflow_2d, Histogram_Parameters::real, histogram::type, histogram::underflow, histogram::underflow_2d, and Histogram_Parameters::upper_limit.

Referenced by display_histogram().

7.23.3.13 void display_all_histograms (void)

Display all histograms in list of histograms.

Arguments: none
Return value: none

References display_histogram(), and histogram::next.

Referenced by main().

7.23.3.14 void display_histogram (HISTOGRAM*histo)

Display contents of a histogram on the terminal.

This is a simple 'HPRINT' type display on one screen.

Parameters

histo	Pointer to histogram

Returns

(none)

References histogram::counts, display_2d_histogram(), histogram::entries, histogram::extension, histogram::ident, Histogram_Parameters::integer, Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, histogram::overflow, Histogram_Parameters::real, histogram::tentries, histogram::title, histogram::type, histogram::underflow, and Histogram Parameters::upper limit.

Referenced by display_all_histograms(), and main().

7.23.3.15 int fast_stat_histogram (HISTOGRAM * histo, struct histstat * stbuf)

Fast and basic histogram statistics.

Compute mean and truncated mean for histogram. For this kind of histogram analysis actually no histogram is required. A 'moments' structure would be sufficient.

Parameters

histo	pointer to histogram (1-D)
stbuf	pointer to histogram statistics structure

Returns

Nonzero result indicates failure

References histogram::entries, histogram::extension, Histogram_Parameters::integer, histogram::nbins_2d, Histogram_Parameters::real, Histogram_Parameters::sum, histogram::tentries, Histogram_Parameters::tsum, and histogram::type.

7.23.3.16 int fill_2d_int_histogram (HISTOGRAM * histo, long xvalue, long yvalue)

Increment a bin of a 2-D 'int' histogram by one.

Increment a bin of a 2-D histogram by one. Either a count for one of the bins in the histogram range is incremented or an underflow or overflow count. For the calculation of the mean value and truncated mean value sums of values and number of histogram entries are updated as well.

Arguments: histo – pointer to histogram xvalue, yvalue – X and Y positions where an entry is to be to the histogram (they may be outside the given ranges)

Return value: 0 (o.k.), -1 (no histogram that can be filled)

References histogram::counts, histogram::entries, fill_2d_real_histogram(), fill_int_histogram(), Histogram_Parameters::integer, Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, histogram::overflow, histogram::overflow_2d, Histogram_Parameters::sum, histogram::tentries, Histogram_Parameters::sum, histogram::tentries, Histogram_Parameters::upper_limit, and Histogram_Parameters::width.

Referenced by fill_histogram().

7.23.3.17 int fill_2d_real_histogram (HISTOGRAM * histo, double xvalue, double yvalue)

Increment a bin of a 2-D 'real' histogram by one.

Increment a bin of a 2-D histogram by one. Either a count for one of the bins in the histogram range is incremented or an underflow or overflow count. For the calculation of the mean value and truncated mean value sums of values and number of histogram entries are updated as well.

Parameters

histo	Pointer to histogram
xvalue	X position where an entry is to be to the histogram (may be outside the given ranges)
yvalue	Y position where an entry is to be to the histogram (may be outside the given ranges)

Returns

0 (o.k.), -1 (no histogram that can be filled)

References histogram::counts, histogram::entries, fill_2d_weighted_histogram(), fill_real_histogram(), Histogram_Parameters::inverse_binwidth, Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, histogram::overflow, histogram::overflow_2d, Histogram_Parameters::real, Histogram_Parameters::sum, histogram::tentries, Histogram_Parameters::tsum, histogram::type, histogram::underflow, histogram::underflow_2d, and Histogram_Parameters::upper_limit.

Referenced by fill_2d_int_histogram(), and fill_histogram().

7.23.3.18 int fill 2d weighted histogram (HISTOGRAM * histo, double xvalue, double yvalue, double weight)

Add an entry to a weighted 2-D histogram.

Increment a bin of a 2-D histogram by a given weight rather than by 1. This requires a suitable histogram type 'F' or 'D'.

Parameters

histo	Pointer to histogram.
xvalue	X posistion where an entry is to be added.
yvalue	Y posistion where an entry is to be added.
weight	The weight of that entry.

Returns

0 (o.k.), -1 (no histogram that can be filled with weights)

References Histogram_Extension::content_all, Histogram_Extension::content_inside, Histogram_Extension::content_outside, histogram::entries, histogram::extension, Histogram_Extension::fdata, fill_weighted_histogram(), histogram::ident, Histogram_Parameters::inverse_binwidth, Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, histogram::overflow, histogram::overflow_2d, Histogram_Parameters::real, Histogram_Parameters::sum, histogram::tentries, Histogram_Parameters::tsum, histogram::underflow, histogram::underflow 2d, and Histogram Parameters::upper limit.

Referenced by fill_2d_real_histogram(), and fill_histogram().

7.23.3.19 int fill_histogram (HISTOGRAM * histo, double xvalue, double yvalue, double weight)

Fill any type of 1-D or 2-D histogram known by its pointer.

Generic histogram fill function that can be used for type 'I', 'R', 'F', and 'D' histograms, although it is not recommended for type 'I' histograms, due to type conversions.

Parameters

histo	Pointer to histogram.
xvalue	X posistion where an entry is to be added.

yvalue	Y posistion (ignored for 1-D histograms)
weight	The weight of that entry (must be 1.0 for 'I' and 'R' type histograms).

Returns

0 (o.k.), -1 (no histogram that can be filled)

References fill_2d_int_histogram(), fill_2d_real_histogram(), fill_2d_weighted_histogram(), fill_int_histogram(), fill_real_histogram(), fill_weighted_histogram(), fill_weighted_histogram(), fill_stogram:ident, histogram:ident, histogram(), fill_ident, histo

Referenced by fill_gaps(), fill_histogram_by_ident(), gen_image_lookups(), main(), mc_event_fill(), and user_init().

7.23.3.20 int fill_histogram_by_ident (long id, double xvalue, double yvalue, double weight)

Fill any type of 1-D or 2-D histogram known by its ID number.

Generic histogram fill function that can be used for type 'I', 'R', 'F', and 'D' histograms, although it is not recommended for type 'I' histograms, due to type conversions.

Parameters

id	Identifier number of the histogram.
xvalue	X posistion where an entry is to be added.
yvalue	Y posistion (ignored for 1-D histograms)
weight	The weight of that entry (must be 1.0 for 'I' and 'R' type histograms).

Returns

0 (o.k.), -1 (no histogram that can be filled)

References fill histogram(), and get histogram by ident().

Referenced by main(), user_event_fill(), and user_mc_event_fill().

7.23.3.21 int fill_int_histogram (HISTOGRAM * histo, long value)

Increment a bin of a 1-D 'int' histogram by one.

Either a count for one of the bins in the histogram range is incremented or an underflow or overflow count. For the calculation of the mean value and truncated mean value sums of values and number of histogram entries are updated as well.

Parameters

histo	Pointer to histogram
value	Position where an entry is to be added (may be outside the given range)

Returns

0 (o.k.), -1 (no histogram that can be filled)

References histogram::counts, histogram::entries, fill_real_histogram(), Histogram_Parameters::integer, Histogram_Parameters::lower_limit, histogram::nbins, histogram::overflow, Histogram_Parameters::sum, histogram::tentries, Histogram_Parameters::sum, histogram::tentries, histogram_Parameters::upper_limit, and Histogram Parameters::width.

Referenced by fill_2d_int_histogram(), and fill_histogram().

7.23.3.22 int fill_real_histogram (HISTOGRAM * histo, double value)

Increment a bin of a 1-D 'real' histogram by one.

Either a count for one of the bins in the histogram range is incremented or an underflow or overflow count. For the calculation of the mean value and truncated mean value sums of values and number of histogram entries are updated as well.

Parameters

histo	Pointer to histogram
value	Position where an entry is to be added (may be outside the given range)

Returns

0 (o.k.), -1 (no histogram that can be filled)

References histogram::counts, histogram::entries, fill_weighted_histogram(), Histogram_Parameters::inverse_binwidth, Histogram_Parameters::lower_limit, histogram::nbins, histogram::overflow, Histogram_Parameters::real, Histogram_Parameters::sum, histogram::tentries, Histogram_Parameters::tsum, histogram::type, histogram::underflow, and Histogram_Parameters::upper_limit.

Referenced by fill_2d_real_histogram(), fill_histogram(), and fill_int_histogram().

7.23.3.23 int fill_weighted_histogram (HISTOGRAM * histo, double value, double weight)

Add an entry to a weighted 1-D histogram.

Increment a bin of a histogram by a given weight rather than by 1. This requires a suitable histogram type 'F' or 'D'.

Parameters

histo	Pointer to histogram.
value	Position where an entry is to be added.
weight	The weight of that entry.

Returns

0 (o.k.), -1 (no histogram that can be filled with weights)

References Histogram_Extension::content_all, Histogram_Extension::content_inside, Histogram_Extension::content_outside, Histogram_Extension::ddata, histogram::extension, Histogram::extension, Histogram_Extension::fdata, histogram::ident, Histogram_Parameters::inverse_binwidth, Histogram_Parameters::lower_limit, histogram::nbins, histogram::overflow, Histogram_Parameters::real, Histogram_Parameters::sum, histogram::tentries, Histogram Parameters::tsum, histogram::type, histogram::underflow, and Histogram Parameters::upper limit.

Referenced by fill_2d_weighted_histogram(), fill_histogram(), and fill_real_histogram().

7.23.3.24 void free_all_histograms (void)

Deletes all histograms which are included in the linked list of histograms.

Returns

(none)

References free_histogram(), and histogram::next.

7.23.3.25 static void free histo_contents (HISTOGRAM * histo) [static]

Free the contents (data pointers) of a histogram to be released or removed.

Parameters

Pointer	to histogram that should be 'cleaned'.
---------	--

Returns

(none)

References histogram::counts, Histogram_Extension::ddata, histogram::extension, Histogram_Extension::fdata, and histogram::title.

Referenced by free histogram().

7.23.3.26 void free_histogram (HISTOGRAM * histo)

Free a histogram completely (both data and control structure).

Deallocates memory previously allocated to a histogram. If release_histogram was applied to that histogram before, it cannot be reallocated.

Parameters

histo	- pointer to previously allocated histogram
111310	- pointer to previously anocated histogram
i e	' '

Returns

(none)

References free_histo_contents(), and unlink_histogram().

Referenced by free_all_histograms(), main(), read_histograms_x(), and user_init().

7.23.3.27 HISTOGRAM* get_first_histogram (void)

Get a pointer to the first histogram.

Get a pointer to the first histogram in the linked list of available histograms without making the corresponding variable global.

Returns

Pointer to the first histogram in the linked list.

Referenced by convert_histograms_to_root(), main(), write_all_histograms(), and write_histograms().

7.23.3.28 HISTOGRAM* get_histogram_by_ident (long ident)

Get a histogram with the given ID.

Get the first histogram with a given ident (different from 0) or return NULL pointer if none exists.

Parameters

ident	The histogram ident to be searched for.

Returns

Histogram pointer or NULL

References histogram::ident, and histogram::next.

Referenced by describe_histogram(), fill_histogram_by_ident(), histogram_to_root(), img_norm(), main(), read_histograms_x(), user_init(), and write_dst_histos().

7.23.3.29 int histogram_hashing (int tabsize)

Turn hashing of histograms (using their ident as key) on or off.

Parameters

tabsize	Minimum number of elements in hashing table or 0 if hash table should be released (max:	1
	15000).	

Returns

0 (o.k.), -1 (error)

References histogram::ident, and histogram::next.

Referenced by mc_event_fill(), and user_init().

7.23.3.30 int histogram_matching (HISTOGRAM * histo1, HISTOGRAM * histo2)

Check if two histograms have exactly matching definitions (same type, dimension, size, ranges).

Parameters

histo1	pointer to first histogram
histo2	pointer to second histogram

Returns

0 (not matching) or 1 (matching)

References histogram::counts, histogram::extension, Histogram_Parameters::integer, Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, Histogram_Parameters::real, histogram::type, and Histogram_Parameters::upper_limit.

Referenced by add_histogram().

7.23.3.31 int histogram_to_lookup (HISTOGRAM * histo, HISTOGRAM * lookup)

Convert a histogram to a lookup table by integrating the histogram.

Parameters

histo	input histogram
lookup	output lookup table

Returns

0 if ok or -1 for failure

References clear_histogram(), histogram::counts, histogram::entries, histogram::nbins, histogram::nbins_2d, histogram::overflow, histogram::tentries, histogram::type, and histogram::underflow.

7.23.3.32 void list_histograms (long ident)

List all available histograms using the 'Output()' function.

Parameters

ident	- histogram ident to search or 0

Returns

(none)

References histogram::entries, histogram::ident, histogram::nbins, histogram::nbins_2d, histogram::next, histogram::tentries, histogram::title, and histogram::type.

7.23.3.33 double locate_histogram_fraction (HISTOGRAM * histo, double fraction)

Locate point of arbitrary fraction of entries (quantile).

Locate the place in a 1-D histogram where a given fraction of the entries is to the 'left' of this place ('l' and 'R' type only).

Parameters

histo	Pointer to histogram
fraction	Fraction of entries to the left.

Returns

x-coordinate of given fraction or 0. for error.

References histogram::counts, Histogram_Parameters::integer, Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, histogram::overflow, Histogram_Parameters::real, histogram::type, histogram::underflow, and Histogram Parameters::upper limit.

Referenced by stat_histogram().

7.23.3.34 long lookup_int (HISTOGRAM * lookup, long value, long factor)

Look up a table created from an integer histogram.

Parameters

lookup	the lookup table
value	the value at which to look up
factor	the scaling factor of the lookup result or 0

Returns

If 'value' is inside the range of the lookup table (that is the range of the histogram from which the lookup table was created), a value between 0 and 'factor' (or the number of entries in the range, if factor==0) is returned.

References histogram::counts, Histogram_Parameters::integer, Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, histogram::tentries, histogram::type, Histogram_Parameters::upper_limit, and Histogram_Parameters::width.

7.23.3.35 double lookup_real (HISTOGRAM * lookup, double value, double factor)

Look up a table created from an 'real' histogram.

Parameters

lookup	the lookup table
value	the value at which to look up
factor	the scaling factor of the lookup result or 0

Returns

If 'value' is inside the range of the lookup table (that is the range of the histogram from which the lookup table was created), a value between 0 and 'factor' (or the number of entries in the range, if factor==0) is returned.

References histogram::counts, Histogram_Parameters::inverse_binwidth, Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, Histogram_Parameters::real, histogram::tentries, histogram::type, and Histogram_Parameters::upper_limit.

7.23.3.36 void print_histogram (HISTOGRAM * histo)

Print contents of a histogram on the terminal.

Showing the actual content of each bin.

Parameters

histo	Pointer to histogram
-------	----------------------

Returns

(none)

References histogram::counts, Histogram_Extension::ddata, histogram::entries, histogram::extension, Histogram_Extension::fdata, histogram::ident, Histogram_Parameters::integer, Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, histogram::overflow, Histogram_Parameters::real, histogram::tentries, histogram::title, histogram::underflow, and Histogram_Parameters::upper_limit.

Referenced by main().

7.23.3.37 void set_first_histogram (HISTOGRAM * new_first_histogram)

Set a new histogram as the first element (context switching).

To allow 'context switching' of histograms the first element of the linked list of histograms can be changed by this function. Before that, the old value should be obtained with get_first_histogram() and saved. Note: For context switching it is not necessary to specify the actually first member of a linked list but any member of a list can be specifed to activate that list.

Parameters

new_first	A histogram in the new list (may be NULL pointer).
histogram	

Returns

none

References histogram::next, and histogram::previous.

7.23.3.38 void sort_histograms (void)

Sort histograms in linked list by idents.

Returns

(none)

References histogram::next, and histogram::previous.

Referenced by main().

7.23.3.39 int stat_histogram (HISTOGRAM * histo, struct histstat * stbuf)

Statistical analysis of a histogram.

The median calculation is implemented for 1-D 'I' and 'R' types histograms only.

Parameters

histo	pointer to histogram
stbuf	pointer to histogram statistics structure

Returns

Nonzero result indicates failure

References Histogram_Extension::content_all, Histogram_Extension::content_inside, histogram::counts, Histogram_Extension::data, histogram::entries, histogram::extension, Histogram_Extension::fdata, Histogram_Parameters::integer, locate_histogram_fraction(), Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, Histogram_Parameters::real, Histogram_Parameters::sum, histogram::tentries, Histogram_Parameters::tsum, histogram::type, and Histogram_Parameters::upper_limit.

```
7.23.3.40 void unlink_histogram ( HISTOGRAM * histo )
```

Remove a histogram from the list without destroying it.

Remove a histogram from the linked list of histograms. That histogram will therefore not be found by any subsequent call to 'free_all_histograms()', display_all_histograms()', and 'get_histogram_by_ident()'.

Parameters

histo	Pointer to histogram.
	- Sinter to motogram

Returns

(none)

References histogram::ident, histogram::next, and histogram::previous.

Referenced by free_histogram().

7.23.4 Variable Documentation

```
7.23.4.1 CONST_QUAL short primetab[] [static]
```

Initial value:


```
= { 131, 233, 353, 541, 751, 1051, 1367, 1511, 1723, 1931, 2393, 3163, 3907, 5261, 6143, 7187, 8623, 9749, 11321, 15031 }
```

7.24 histogram.h File Reference

Declarations for handling one- and two-dimensional histograms.

#include "initial.h"

Include dependency graph for histogram.h:



This graph shows which files directly or indirectly include this file:



Data Structures

• union Histogram_Parameters

Parameters defining the usable range of coordinates.

• struct Histogram_Extension

A histogram extension only allocated for weighted histograms.

· struct histogram

A complete 1-D or 2-D histogram with control and data elements.

· struct histstat

Statistics element for histogram analysis.

struct momstat

First, second, and higher moments of a 1-D histogram.

· struct moments

Numbers to be summed up to obtain the moments.

Macros

- #define MAX_HISTCOUNT 4294967295UL /* or ULONG_MAX from < limits.h > */

Typedefs

• typedef double HISTVALUE_REAL

May be 'float' for ANSI C compiler.

• typedef long HISTVALUE_INT

Short int is not recommended.

typedef unsigned long HISTCOUNT

The histogram counts may be unsigned short or unsigned long.

typedef double HISTSUM REAL

To avoid loss of precision for adding many numbers, sums are of double type if 'real' type HISTVALUEs are used.

- typedef long HISTSUM_INT
- typedef double **HISTSTATVALUE**
- typedef struct histogram HISTOGRAM
- typedef struct moments MOMENTS

Functions

- void histogram_lock (HISTOGRAM *histo)
- void histogram_unlock (HISTOGRAM *histo)
- HISTOGRAM * get_first_histogram (void)

Get a pointer to the first histogram.

• void set_first_histogram (HISTOGRAM *new_first_histogram)

Set a new histogram as the first element (context switching).

HISTOGRAM * get_histogram_by_ident (long ident)

Get a histogram with the given ID.

void list_histograms (long ident)

List all available histograms using the 'Output()' function.

 HISTOGRAM * book_histogram (long id, const char *title, const char *type, int dimension, double *low, double *high, int *nbins)

General histogram booking function, assigning ID and title.

- HISTOGRAM * book_int_histogram (long id, const char *title, int dimension, long *low, long *high, int *nbins)

 Book and integer-type histogram (content incremented by one per entry).
- HISTOGRAM * book_1d_histogram (long id, const char *title, const char *type, double low, double high, int nbins)

Simplified histogram booking function for one-dimensional histograms, assigning ID and title.

• HISTOGRAM * allocate_histogram (const char *type, int dimension, double *low, double *high, int *nbins)

**Allocate any histogram without ID and title.

• HISTOGRAM * alloc_int_histogram (long low, long high, int nbins)

Allocate memory for a 1-D 'int' histogram and initialize it.

HISTOGRAM * alloc_real_histogram (double low, double high, int nbins)

Allocate memory for a 1-D 'real' histogram and initialize it.

HISTOGRAM * alloc_2d_int_histogram (long xlow, long xhigh, int nxbins, long ylow, long yhigh, int nybins)

Allocate memory for a 2-D 'int' histogram and initialize it.

HISTOGRAM * alloc_2d_real_histogram (double xlow, double xhigh, int nxbins, double ylow, double yhigh, int nybins)

Allocate memory for a 2-D 'int' histogram and initialize it.

void describe_histogram (HISTOGRAM *histo, const char *title, long ident)

Add a describing title to a histogram previously allocated.

void clear_histogram (HISTOGRAM *histo)

Initialize an existing histogram.

void free histogram (HISTOGRAM *histo)

Free a histogram completely (both data and control structure).

• void free_all_histograms (void)

Deletes all histograms which are included in the linked list of histograms.

void unlink_histogram (HISTOGRAM *histo)

Remove a histogram from the list without destroying it.

int fill_int_histogram (HISTOGRAM *histo, long value)

Increment a bin of a 1-D 'int' histogram by one.

• int fill_real_histogram (HISTOGRAM *histo, double value)

Increment a bin of a 1-D 'real' histogram by one.

• int fill_weighted_histogram (HISTOGRAM *histo, double value, double weight)

Add an entry to a weighted 1-D histogram.

int fill_2d_int_histogram (HISTOGRAM *histo, long xvalue, long yvalue)

Increment a bin of a 2-D 'int' histogram by one.

• int fill 2d real histogram (HISTOGRAM *histo, double xvalue, double yvalue)

Increment a bin of a 2-D 'real' histogram by one.

int fill_2d_weighted_histogram (HISTOGRAM *histo, double xvalue, double yvalue, double weight)

Add an entry to a weighted 2-D histogram.

• int fill histogram (HISTOGRAM *histo, double xvalue, double yvalue, double weight)

Fill any type of 1-D or 2-D histogram known by its pointer.

int fill_histogram_by_ident (long id, double xvalue, double yvalue, double weight)

Fill any type of 1-D or 2-D histogram known by its ID number.

int stat_histogram (HISTOGRAM *histo, struct histstat *stbuf)

Statistical analysis of a histogram.

• double locate histogram fraction (HISTOGRAM *histo, double fraction)

Locate point of arbitrary fraction of entries (quantile).

• int fast_stat_histogram (HISTOGRAM *histo, struct histstat *stbuf)

Fast and basic histogram statistics.

int histogram matching (HISTOGRAM *histo1, HISTOGRAM *histo2)

Check if two histograms have exactly matching definitions (same type, dimension, size, ranges).

HISTOGRAM * add histogram (HISTOGRAM *histo1, HISTOGRAM *histo2)

Add a second histogram to a first one.

void print histogram (HISTOGRAM *histo)

Print contents of a histogram on the terminal.

void display_histogram (HISTOGRAM *histo)

Display contents of a histogram on the terminal.

void display_all_histograms (void)

Display all histograms in list of histograms.

int histogram_to_lookup (HISTOGRAM *histo, HISTOGRAM *lookup)

Convert a histogram to a lookup table by integrating the histogram.

long lookup int (HISTOGRAM *lookup, long value, long factor)

Look up a table created from an integer histogram.

double lookup_real (HISTOGRAM *lookup, double value, double factor)

Look up a table created from an 'real' histogram.

int histogram hashing (int tabsize)

Turn hashing of histograms (using their ident as key) on or off.

void sort_histograms (void)

Sort histograms in linked list by idents.

- void release_histogram (HISTOGRAM *histo)
- MOMENTS * alloc_moments (double low, double high)

Allocate a structure for sums of powers of data.

void clear moments (MOMENTS *mom)

Initialize an existing moments structure (except for its range limits).

void free_moments (MOMENTS *mom)

Deallocates memory previously allocated to a moments structure.

void fill moments (MOMENTS *mom, double value)

Add up those things needed to compute mean, standard deviation, skewness, and kurtosis (both for all data and separately for data in a range defined in alloc moments().

void fill_mean (MOMENTS *mom, double value)

Add up those things needed to compute – mean, (both for all data and separately for data in a range defined in alloc moments().

void fill mean and sigma (MOMENTS *mom, double value)

Add up those things needed to compute – mean, – standard deviation, (both for all data and separately for data in a range defined in alloc_moments().

void fill real moments (MOMENTS *mom, double value, double weight)

Add up those things needed to compute – mean, – standard deviation, – skewness, and – kurtosis (both for all data and separately for data in a range defined in alloc_moments().

· void fill real mean (MOMENTS *mom, double value, double weight)

Add up those things needed to compute – mean, (both for all data and separately for data in a range defined in alloc_moments().

• void fill real mean and sigma (MOMENTS *mom, double value, double weight)

Add up those things needed to compute – mean, – standard deviation, (both for all data and separately for data in a range defined in alloc_moments().

int stat_moments (MOMENTS *mom, struct momstat *stmom)

Calculate moments (mean, rms, skewness, kurtosis) from the sums of powers of data values.

7.24.1 Detailed Description

Declarations for handling one- and two-dimensional histograms. The functions to work with these histograms is found in histogram.c . Eventio routines are available in io_histogram.c and conversion to HBOOK format is available through the 'cvt2' program. Handling of moments of a 1-D distribution is implemented in moments.c .

Author

Konrad Bernloehr

Date

1991 - 2010 CVS

Date:

2013/10/21 12:53:31

Version

CVS

Revision:

1.12

7.24.2 Typedef Documentation

7.24.2.1 typedef unsigned long HISTCOUNT

The histogram counts may be unsigned short or unsigned long.

With a unsigned short the overflow of a bin might easily happen.

7.24.2.2 typedef double HISTVALUE_REAL

May be 'float' for ANSI C compiler.

HISTVALUE may be either an 'integer' type (recommended: long int) or a 'real' type (recommended: double). The method of calculating the array index corresponding to a given value is somewhat different for these two alternatives. Using a float for the 'real' type instead of a double would make no difference. However, a short int or an unsigned short int as 'integer' type requires more care for the calculation of the array index compared to a long or a unsigned long (frequent overflows unless a type cast of intermediate values to a long type is used).

7.24.3 Function Documentation

7.24.3.1 HISTOGRAM* add_histogram (HISTOGRAM * histo1, HISTOGRAM * histo2)

Add a second histogram to a first one.

The histograms must exactly match in their definitions. The first histogram will be modified, the second is unchanged.

Parameters

histo1	pointer to first histogram
histo2	pointer to second histogram

Returns

NULL pointer indicates failure.

References Histogram_Extension::content_all, Histogram_Extension::content_inside, Histogram_Extension::content_outside, histogram::counts, Histogram_Extension::ddata, histogram::extension, Histogram_Extension::fdata, histogram_matching(), histogram::ident, Histogram_Parameters::integer, histogram::nbins, histogram::nbins_2d, histogram::overflow, histogram::overflow_2d, Histogram_Parameters::real, Histogram_Parameters::sum, histogram::type, histogram::underflow, and histogram::underflow_2d.

Referenced by read_histograms_x().

7.24.3.2 HISTOGRAM* alloc_2d_int_histogram (long xlow, long xhigh, int nxbins, long ylow, long yhigh, int nybins)

Allocate memory for a 2-D 'int' histogram and initialize it.

Resulting histogram has integer range limits and integer contents (incremented by one per entry).

Parameters

xlow	lower limit of values in X to be covered by histogram
xhigh	upper limit
nxbins	the number of bins to be allocated in X
ylow	lower limit of values in Y to be covered by histogram
yhigh	upper limit

nybins	the number of bins to be allocated in Y
--------	---

Returns

pointer to allocated histogram or NULL

References aux_alloc_histogram(), initialize_histogram(), Histogram_Parameters::integer, Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, Histogram_Parameters::upper_limit, and Histogram_Parameters::width.

Referenced by allocate_histogram(), book_int_histogram(), and read_histograms_x().

7.24.3.3 HISTOGRAM* alloc_2d_real_histogram (double *xlow*, double *xhigh*, int *nxbins*, double *ylow*, double *yhigh*, int *nybins*)

Allocate memory for a 2-D 'int' histogram and initialize it.

Resulting histogram has floating point range limits and integer contents (incremented by one per entry).

Parameters

xlow	lower limit of values in X to be covered by histogram
xhigh	upper limit
nxbins	the number of bins to be allocated in X
ylow	lower limit of values in Y to be covered by histogram
yhigh	upper limit
nybins	the number of bins to be allocated in Y

Returns

pointer to allocated histogram or NULL

References allocate_histogram().

Referenced by read_histograms_x().

7.24.3.4 HISTOGRAM* alloc_int_histogram (long low, long high, int nbins)

Allocate memory for a 1-D 'int' histogram and initialize it.

Resulting histogram has integer range limits and integer contents (incremented by one per entry).

Parameters

low	lower limit of values to be covered by histogram
high	upper limit
nbins	the number of bins to be allocated

Returns

pointer to allocated histogram or NULL

References aux_alloc_histogram(), initialize_histogram(), Histogram_Parameters::integer, Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, Histogram_Parameters::upper_limit, and Histogram_Parameters::width.

Referenced by allocate_histogram(), book_int_histogram(), and read_histograms_x().

7.24.3.5 MOMENTS* alloc_moments (HISTVALUE_REAL low, HISTVALUE_REAL high)

Allocate a structure for sums of powers of data.

Returns NULL if no structure could be allocated.

Parameters

low	Lower limit of range for truncation
high	Upper limit of range for truncation

Returns

Pointer to allocated structure or NULL.

References clear_moments().

Referenced by user_init().

7.24.3.6 HISTOGRAM* alloc_real_histogram (double low, double high, int nbins)

Allocate memory for a 1-D 'real' histogram and initialize it.

Resulting histogram has floating point range limits and integer contents (incremented by one per entry).

Parameters

low	lower limit of values to be covered by histogram
high	upper limit
nbins	the number of bins to be allocated

Returns

pointer to allocated histogram or NULL

References allocate_histogram().

Referenced by read_histograms_x().

7.24.3.7 HISTOGRAM* allocate_histogram (const char * type, int dimension, double * low, double * high, int * nbins)

Allocate any histogram without ID and title.

Allocate a histogram of 1 or 2 dimensions, 'I', 'R', 'F' or 'D' type, without assigning an ID number and title string to it. To avoid the (long) <-> (double) typecasts, the direct calls to alloc_int_histogram() and alloc_2d_int_histogram() are recommended for integer-limits histograms (type 'I').

Parameters

type	"I" (int, no weights), "R" (real, no weights), "F" (float, with weights), "D" (double, w.w.)
dimension	1 or 2 for 1-D or 2-D histogram
low	Pointer to lower limits (x or x,y for 1-D or 2-D)
high	Pointer to upper limits
nbins	Pointer to no. of bins per dimension (nx or nx, ny)

Returns

Pointer to new histogram or NULL

References alloc_2d_int_histogram(), alloc_int_histogram(), aux_alloc_histogram(), initialize_histogram(), Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins, histogram_Parameters::real, and Histogram_Parameters::upper_limit.

Referenced by alloc_2d_real_histogram(), alloc_real_histogram(), book_1d_histogram(), book_histogram(), and read_histograms_x().

7.24.3.8 HISTOGRAM* book_1d_histogram (long id, const char * title, const char * type, double low, double high, int nbins)

Simplified histogram booking function for one-dimensional histograms, assigning ID and title.

Book a histogram of one dimension, 'I', 'R', 'F', or 'D' type. The histogram is allocated (if possible) and the supplied ID number and title string are assigned.

Parameters

id	ID number
title	Histogram title string
type	"I" (int, no weights), "R" (real, no weights), "F" (float, with weights), "D" (double, w.w.)
low	Lower limit (x)
high	Upper limit (x)
nbins	No. of bins (nx)

Returns

Pointer to new histogram or NULL

References allocate_histogram(), and describe_histogram().

Referenced by mc_event_fill(), and user_init().

7.24.3.9 **HISTOGRAM*** book_histogram (long *id*, const char * *title*, const char * *type*, int *dimension*, double * *low*, double * *high*, int * *nbins*)

General histogram booking function, assigning ID and title.

Book a histogram of 1 or 2 dimensions, 'I', 'R', 'F', or 'D' type. The histogram is allocated (if possible) and the supplied ID number and title string are assigned.

Parameters

id	ID number
title	Histogram title string
type	"I" (int, no weights), "R" (real, no weights), "F" (float, with weights), "D" (double, w.w.)
dimension	1 or 2 for 1-D or 2-D histogram
low	Pointer to lower limits (x or x,y for 1-D or 2-D)
high	Pointer to upper limits
nbins	Pointer to no. of bins per dimension (nx or nx, ny)

Returns

Pointer to new histogram or NULL

References allocate histogram(), and describe histogram().

Referenced by main(), mc_event_fill(), and user_init().

7.24.3.10 HISTOGRAM* book_int_histogram (long id, const char * title, int dimension, long * low, long * high, int * nbins)

Book and integer-type histogram (content incremented by one per entry).

Like book_histogram() but for 'I' type histograms only (1-D or 2-D)

Parameters

id	ID number
title	Histogram title string
dimension	1 or 2 for 1-D or 2-D histogram
low	Pointer to lower limits (x or x,y for 1-D or 2-D)
high	Pointer to upper limits
nbins	Pointer to no. of bins per dimension (nx or nx, ny)

Returns

Pointer to new histogram or NULL

References alloc_2d_int_histogram(), alloc_int_histogram(), and describe_histogram().

7.24.3.11 void clear_histogram (HISTOGRAM * histo)

Initialize an existing histogram.

Parameters

histo	– pointer to histogram

Returns

(none)

References Histogram_Extension::content_all, Histogram_Extension::content_inside, Histogram_Extension::content_outside, histogram::counts, Histogram_Extension::ddata, histogram::entries, histogram::extension, Histogram_Extension::fdata, Histogram_Parameters::integer, histogram::nbins, histogram::nbins_2d, histogram::overflow, histogram::overflow_2d, Histogram_Parameters::real, Histogram_Parameters::sum, histogram::tentries, Histogram_Parameters::tsum, histogram::type, histogram::underflow, and histogram::underflow_2d.

Referenced by gen_image_lookups(), histogram_to_lookup(), initialize_histogram(), and write_dst_histos().

7.24.3.12 void clear_moments (MOMENTS * mom)

Initialize an existing moments structure (except for its range limits).

Parameters

mom	Pointer to moments structure
-----	------------------------------

Referenced by alloc_moments(), and user_event_fill().

7.24.3.13 void describe_histogram (HISTOGRAM * histo, const char * title, long ident)

Add a describing title to a histogram previously allocated.

Parameters

histo	Histogram to which the title should be added
title	The title string. This is ignored if the histogram already has a title.
ident	Identification number, must be unique (or 0) if any I/O is intended, because read_histogram()
	deletes a pre-existing histogram with the same ID.

Returns

none

References get_histogram_by_ident(), histogram::ident, and histogram::title.

Referenced by book 1d histogram(), book histogram(), book int histogram(), and read histograms x().

7.24.3.14 void display_all_histograms (void)

Display all histograms in list of histograms.

Arguments: none
Return value: none

References display_histogram(), and histogram::next.

Referenced by main().

7.24.3.15 void display_histogram (HISTOGRAM * histo)

Display contents of a histogram on the terminal.

This is a simple 'HPRINT' type display on one screen.

Parameters

_		
	histo	Pointer to histogram

Returns

(none)

References histogram::counts, display_2d_histogram(), histogram::entries, histogram::extension, histogram::ident, Histogram_Parameters::integer, Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, histogram::overflow, Histogram_Parameters::real, histogram::tentries, histogram::title, histogram::type, histogram::underflow, and Histogram_Parameters::upper_limit.

Referenced by display_all_histograms(), and main().

7.24.3.16 int fast_stat_histogram (HISTOGRAM * histo, struct histstat * stbuf)

Fast and basic histogram statistics.

Compute mean and truncated mean for histogram. For this kind of histogram analysis actually no histogram is required. A 'moments' structure would be sufficient.

Parameters

histo	pointer to histogram (1-D)
stbuf	pointer to histogram statistics structure

Returns

Nonzero result indicates failure

References histogram::entries, histogram::extension, Histogram_Parameters::integer, histogram::nbins_2d, Histogram_Parameters::real, Histogram_Parameters::sum, histogram::tentries, Histogram_Parameters::tsum, and histogram::type.

7.24.3.17 int fill_2d_int_histogram (HISTOGRAM * histo, long xvalue, long yvalue)

Increment a bin of a 2-D 'int' histogram by one.

Increment a bin of a 2-D histogram by one. Either a count for one of the bins in the histogram range is incremented or an underflow or overflow count. For the calculation of the mean value and truncated mean value sums of values and number of histogram entries are updated as well.

Arguments: histo – pointer to histogram xvalue, yvalue – X and Y positions where an entry is to be to the histogram (they may be outside the given ranges)

Return value: 0 (o.k.), -1 (no histogram that can be filled)

References histogram::counts, histogram::entries, fill_2d_real_histogram(), fill_int_histogram(), Histogram_Parameters::integer, Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, histogram::overflow, histogram::overflow_2d, Histogram_Parameters::sum, histogram::tentries, Histogram_Parameters::sum, histogram::tentries, Histogram_Parameters::upper_limit, and Histogram_Parameters::width.

Referenced by fill_histogram().

7.24.3.18 int fill_2d_real_histogram (HISTOGRAM * histo, double xvalue, double yvalue)

Increment a bin of a 2-D 'real' histogram by one.

Increment a bin of a 2-D histogram by one. Either a count for one of the bins in the histogram range is incremented or an underflow or overflow count. For the calculation of the mean value and truncated mean value sums of values and number of histogram entries are updated as well.

Parameters

histo	Pointer to histogram
xvalue	X position where an entry is to be to the histogram (may be outside the given ranges)
yvalue	Y position where an entry is to be to the histogram (may be outside the given ranges)

Returns

0 (o.k.), -1 (no histogram that can be filled)

References histogram::counts, histogram::entries, fill_2d_weighted_histogram(), fill_real_histogram(), Histogram-Parameters::inverse_binwidth, Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, histogram::overflow, histogram::overflow_2d, Histogram_Parameters::real, Histogram_Parameters::sum, histogram::tentries, Histogram_Parameters::tsum, histogram::type, histogram::underflow, histogram::underflow-2d, and Histogram Parameters::upper limit.

Referenced by fill_2d_int_histogram(), and fill_histogram().

7.24.3.19 int fill 2d weighted histogram (HISTOGRAM * histo, double xvalue, double yvalue, double weight)

Add an entry to a weighted 2-D histogram.

Increment a bin of a 2-D histogram by a given weight rather than by 1. This requires a suitable histogram type 'F' or 'D'.

Parameters

histo	Pointer to histogram.
xvalue	X posistion where an entry is to be added.

yvalue	Y posistion where an entry is to be added.
weight	The weight of that entry.

Returns

0 (o.k.), -1 (no histogram that can be filled with weights)

References Histogram_Extension::content_all, Histogram_Extension::content_inside, Histogram_Extension::content_outside, histogram::entries, histogram::extension, Histogram_Extension::fdata, fill_weighted_histogram(), histogram::ident, Histogram_Parameters::inverse_binwidth, Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, histogram::overflow, histogram::overflow_2d, Histogram_Parameters::real, Histogram_Parameters::sum, histogram::underflow, histogram::underflow 2d, and Histogram Parameters::upper limit.

Referenced by fill_2d_real_histogram(), and fill_histogram().

7.24.3.20 int fill_histogram (HISTOGRAM * histo, double xvalue, double yvalue, double weight)

Fill any type of 1-D or 2-D histogram known by its pointer.

Generic histogram fill function that can be used for type 'I', 'R', 'F', and 'D' histograms, although it is not recommended for type 'I' histograms, due to type conversions.

Parameters

histo	Pointer to histogram.
xvalue	X posistion where an entry is to be added.
yvalue	Y posistion (ignored for 1-D histograms)
weight	The weight of that entry (must be 1.0 for 'I' and 'R' type histograms).

Returns

0 (o.k.), -1 (no histogram that can be filled)

References fill_2d_int_histogram(), fill_2d_real_histogram(), fill_2d_weighted_histogram(), fill_int_histogram(), fill_real_histogram(), fill_weighted_histogram(), histogram::ident, histogram::nbins_2d, and histogram::type.

Referenced by fill_gaps(), fill_histogram_by_ident(), gen_image_lookups(), main(), mc_event_fill(), and user_init().

7.24.3.21 int fill_histogram_by_ident (long id, double xvalue, double yvalue, double weight)

Fill any type of 1-D or 2-D histogram known by its ID number.

Generic histogram fill function that can be used for type 'I', 'R', 'F', and 'D' histograms, although it is not recommended for type 'I' histograms, due to type conversions.

Parameters

id	Identifier number of the histogram.
xvalue	X posistion where an entry is to be added.
yvalue	Y posistion (ignored for 1-D histograms)
weight	The weight of that entry (must be 1.0 for 'I' and 'R' type histograms).

Returns

0 (o.k.), -1 (no histogram that can be filled)

References fill_histogram(), and get_histogram_by_ident().

Referenced by main(), user_event_fill(), and user_mc_event_fill().

7.24.3.22 int fill_int_histogram (HISTOGRAM * histo, long value)

Increment a bin of a 1-D 'int' histogram by one.

Either a count for one of the bins in the histogram range is incremented or an underflow or overflow count. For the calculation of the mean value and truncated mean value sums of values and number of histogram entries are updated as well.

Parameters

histo	Pointer to histogram
value	Position where an entry is to be added (may be outside the given range)

Returns

0 (o.k.), -1 (no histogram that can be filled)

References histogram::counts, histogram::entries, fill_real_histogram(), Histogram_Parameters::integer, Histogram_Parameters::lower_limit, histogram::nbins, histogram::overflow, Histogram_Parameters::sum, histogram::tentries, Histogram_Parameters::tsum, histogram::type, histogram::underflow, Histogram_Parameters::upper_limit, and Histogram_Parameters::width.

Referenced by fill_2d_int_histogram(), and fill_histogram().

7.24.3.23 void fill_mean (MOMENTS * mom, HISTVALUE_REAL value)

Add up those things needed to compute – mean, (both for all data and separately for data in a range defined in alloc moments().

Parameters

mom	Pointer to previously allocated MOMENTS structure.
value	One measurement value

7.24.3.24 void fill_mean_and_sigma (MOMENTS * mom, HISTVALUE REAL value)

Add up those things needed to compute – mean, – standard deviation, (both for all data and separately for data in a range defined in alloc moments().

Parameters

mom	Pointer to previously allocated MOMENTS structure.
value	One measurement value

7.24.3.25 void fill_moments (MOMENTS * mom, HISTVALUE_REAL value)

Add up those things needed to compute mean, standard deviation, skewness, and kurtosis (both for all data and separately for data in a range defined in alloc_moments().

Parameters

mom	Pointer to previously allocated MOMENTS structure.
value	One measurement value

Referenced by user_event_fill().

7.24.3.26 int fill_real_histogram (HISTOGRAM * histo, double value)

Increment a bin of a 1-D 'real' histogram by one.

Either a count for one of the bins in the histogram range is incremented or an underflow or overflow count. For the calculation of the mean value and truncated mean value sums of values and number of histogram entries are updated as well.

Parameters

histo	Pointer to histogram
value	Position where an entry is to be added (may be outside the given range)

Returns

0 (o.k.), -1 (no histogram that can be filled)

References histogram::counts, histogram::entries, fill_weighted_histogram(), Histogram_Parameters::inverse_binwidth, Histogram_Parameters::lower_limit, histogram::nbins, histogram::overflow, Histogram_Parameters::real, Histogram_Parameters::sum, histogram::tentries, Histogram_Parameters::tsum, histogram::type, histogram::underflow, and Histogram_Parameters::upper_limit.

Referenced by fill_2d_real_histogram(), fill_histogram(), and fill_int_histogram().

7.24.3.27 void fill_real_mean (MOMENTS * mom, HISTVALUE_REAL value, double weight)

Add up those things needed to compute – mean, (both for all data and separately for data in a range defined in alloc_moments().

Parameters

mom	Pointer to previously allocated MOMENTS structure.
value	One measurement value
weight	Weighting factor of this value

7.24.3.28 void fill_real_mean_and_sigma (MOMENTS * mom, HISTVALUE REAL value, double weight)

Add up those things needed to compute – mean, – standard deviation, (both for all data and separately for data in a range defined in alloc_moments().

Parameters

mom	Pointer to previously allocated MOMENTS structure.
value	One measurement value
weight	Weighting factor of this value

7.24.3.29 void fill_real_moments (MOMENTS * mom, HISTVALUE_REAL value, double weight)

Add up those things needed to compute – mean, – standard deviation, – skewness, and – kurtosis (both for all data and separately for data in a range defined in alloc_moments().

Parameters

mom	Pointer to previously allocated MOMENTS structure.
value	One measurement value
weight	Weighting factor of this value

7.24.3.30 int fill_weighted_histogram (HISTOGRAM * histo, double value, double weight)

Add an entry to a weighted 1-D histogram.

Increment a bin of a histogram by a given weight rather than by 1. This requires a suitable histogram type 'F' or 'D'.

Parameters

histo	Pointer to histogram.
value	Position where an entry is to be added.
weight	The weight of that entry.

Returns

0 (o.k.), -1 (no histogram that can be filled with weights)

References Histogram_Extension::content_all, Histogram_Extension::content_inside, Histogram_Extension::content_outside, Histogram_Extension::ddata, histogram::entries, histogram::extension, Histogram_Extension::fdata, histogram::ident, Histogram_Parameters::inverse_binwidth, Histogram_Parameters::lower_limit, histogram::nbins, histogram::overflow, Histogram_Parameters::real, Histogram_Parameters::sum, histogram::tentries, Histogram_Parameters::tsum, histogram::type, histogram::underflow, and Histogram_Parameters::upper_limit.

Referenced by fill_2d_weighted_histogram(), fill_histogram(), and fill_real_histogram().

7.24.3.31 void free_all_histograms (void)

Deletes all histograms which are included in the linked list of histograms.

Returns

(none)

References free_histogram(), and histogram::next.

7.24.3.32 void free_histogram (HISTOGRAM * histo)

Free a histogram completely (both data and control structure).

Deallocates memory previously allocated to a histogram. If release_histogram was applied to that histogram before, it cannot be reallocated.

Parameters

histo	- pointer to previously allocated histogram
	pointer to providuoly amounted motogram

Returns

(none)

References free_histo_contents(), and unlink_histogram().

Referenced by free_all_histograms(), main(), read_histograms_x(), and user_init().

7.24.3.33 void free_moments (MOMENTS * mom)

Deallocates memory previously allocated to a moments structure.

Parameters

mom	Pointer to previously allocated structure

7.24.3.34 HISTOGRAM* get_first_histogram (void)

Get a pointer to the first histogram.

Get a pointer to the first histogram in the linked list of available histograms without making the corresponding variable global.

Returns

Pointer to the first histogram in the linked list.

Referenced by convert histograms to root(), main(), write all histograms(), and write histograms().

7.24.3.35 HISTOGRAM* get_histogram_by_ident (long ident)

Get a histogram with the given ID.

Get the first histogram with a given ident (different from 0) or return NULL pointer if none exists.

Parameters

ident	- The histogram ident to be searched for.

Returns

Histogram pointer or NULL

References histogram::ident, and histogram::next.

Referenced by describe_histogram(), fill_histogram_by_ident(), histogram_to_root(), img_norm(), main(), read_histograms_x(), user_init(), and write_dst_histos().

7.24.3.36 int histogram_hashing (int tabsize)

Turn hashing of histograms (using their ident as key) on or off.

Parameters

tabsize	Minimum number of elements in hashing table or 0 if hash table should be released (max:
	15000).

Returns

0 (o.k.), -1 (error)

References histogram::ident, and histogram::next.

Referenced by mc_event_fill(), and user_init().

7.24.3.37 int histogram_matching (HISTOGRAM * histo1, HISTOGRAM * histo2)

Check if two histograms have exactly matching definitions (same type, dimension, size, ranges).

Parameters

histo1	pointer to first histogram
histo2	pointer to second histogram

Returns

0 (not matching) or 1 (matching)

References histogram::counts, histogram::extension, Histogram_Parameters::integer, Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, Histogram_Parameters::real, histogram::type, and Histogram_Parameters::upper_limit.

Referenced by add_histogram().

7.24.3.38 int histogram_to_lookup (HISTOGRAM * histo, HISTOGRAM * lookup)

Convert a histogram to a lookup table by integrating the histogram.

Parameters

histo	input histogram
lookup	output lookup table

Returns

0 if ok or -1 for failure

References clear_histogram(), histogram::counts, histogram::entries, histogram::nbins, histogram::nbins_2d, histogram::overflow, histogram::tentries, histogram::type, and histogram::underflow.

7.24.3.39 void list_histograms (long ident)

List all available histograms using the 'Output()' function.

Parameters

ident	– histogram ident to search or 0

Returns

(none)

References histogram::entries, histogram::ident, histogram::nbins, histogram::nbins_2d, histogram::tentries, histogram::title, and histogram::type.

7.24.3.40 double locate_histogram_fraction (HISTOGRAM * histo, double fraction)

Locate point of arbitrary fraction of entries (quantile).

Locate the place in a 1-D histogram where a given fraction of the entries is to the 'left' of this place ('l' and 'R' type only).

Parameters

histo	Pointer to histogram
fraction	Fraction of entries to the left.

Returns

x-coordinate of given fraction or 0. for error.

References histogram::counts, Histogram_Parameters::integer, Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, histogram::overflow, Histogram_Parameters::real, histogram::type, histogram::underflow, and Histogram_Parameters::upper_limit.

Referenced by stat_histogram().

7.24.3.41 long lookup_int (HISTOGRAM * lookup, long value, long factor)

Look up a table created from an integer histogram.

Parameters

Generated on Thu Jun 25 2015 15:03:22 for hessio by Doxygen

lookup	the lookup table
value	the value at which to look up
factor	the scaling factor of the lookup result or 0

Returns

If 'value' is inside the range of the lookup table (that is the range of the histogram from which the lookup table was created), a value between 0 and 'factor' (or the number of entries in the range, if factor==0) is returned.

References histogram::counts, Histogram_Parameters::integer, Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, histogram::tentries, histogram::type, Histogram_Parameters::upper_limit, and Histogram_Parameters::width.

7.24.3.42 double lookup_real (HISTOGRAM * lookup, double value, double factor)

Look up a table created from an 'real' histogram.

Parameters

lookup	the lookup table
value	the value at which to look up
factor	the scaling factor of the lookup result or 0

Returns

If 'value' is inside the range of the lookup table (that is the range of the histogram from which the lookup table was created), a value between 0 and 'factor' (or the number of entries in the range, if factor==0) is returned.

References histogram::counts, Histogram_Parameters::inverse_binwidth, Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, Histogram_Parameters::real, histogram::tentries, histogram::type, and Histogram_Parameters::upper_limit.

7.24.3.43 void print_histogram (HISTOGRAM * histo)

Print contents of a histogram on the terminal.

Showing the actual content of each bin.

Parameters

histo	Pointer to histogram

Returns

(none)

References histogram::counts, Histogram_Extension::ddata, histogram::entries, histogram::extension, Histogram_Extension::fdata, histogram::integer, Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, histogram::overflow, Histogram_Parameters::real, histogram::tentries, histogram::title, histogram::underflow, and Histogram_Parameters::upper_limit.

Referenced by main().

7.24.3.44 void set_first_histogram (HISTOGRAM * new_first_histogram)

Set a new histogram as the first element (context switching).

To allow 'context switching' of histograms the first element of the linked list of histograms can be changed by this function. Before that, the old value should be obtained with get_first_histogram() and saved. Note: For context

7.24 histogram.h File Reference 201

switching it is not necessary to specify the actually first member of a linked list but any member of a list can be specified to activate that list.

Parameters

new_first	A histogram in the new list (may be NULL pointer).
histogram	

Returns

none

References histogram::next, and histogram::previous.

7.24.3.45 void sort_histograms (void)

Sort histograms in linked list by idents.

Returns

(none)

References histogram::next, and histogram::previous.

Referenced by main().

7.24.3.46 int stat_histogram (HISTOGRAM * histo, struct histstat * stbuf)

Statistical analysis of a histogram.

The median calculation is implemented for 1-D 'I' and 'R' types histograms only.

Parameters

histo	pointer to histogram
Tiloto	pointer to mistogram
stbuf	pointer to histogram statistics structure

Returns

Nonzero result indicates failure

References Histogram_Extension::content_all, Histogram_Extension::content_inside, histogram::counts, Histogram_Extension::data, histogram::entries, histogram::extension, Histogram_Extension::fdata, Histogram_Parameters::integer, locate_histogram_fraction(), Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_-2d, Histogram_Parameters::real, Histogram_Parameters::sum, histogram::tentries, Histogram_Parameters::tsum, histogram::type, and Histogram_Parameters::upper_limit.

7.24.3.47 int stat_moments (MOMENTS * mom, struct momstat * stmom)

Calculate moments (mean, rms, skewness, kurtosis) from the sums of powers of data values.

Parameters

mom	'moments' structure with the sums of the powers of data values (only 1st power if only mean
	to be calculated, also 2nd power if r.m.s. to be calculated, and also 3rd and 4th if skewness
	and kurtosis wanted.

stmom	Pointer to structure for computed moments

Returns

0 (o.k.), -1 and -2 (invalid data)

Referenced by user_event_fill().

7.24.3.48 void unlink_histogram (HISTOGRAM * histo)

Remove a histogram from the list without destroying it.

Remove a histogram from the linked list of histograms. That histogram will therefore not be found by any subsequent call to 'free_all_histograms()', display_all_histograms()', and 'get_histogram_by_ident()'.

Parameters

histo	Pointer to histogram.

Returns

(none)

References histogram::ident, histogram::next, and histogram::previous.


Referenced by free_histogram().

7.25 history.h File Reference


Keep blocks of history in the data (like command line of programs operating on the data, ...)

#include "initial.h"

Include dependency graph for history.h:



This graph shows which files directly or indirectly include this file:



Functions

- int push command history (int argc, char **argv)
- int push_config_history (const char *line, int replace)
- int write_history (long id, IO_BUFFER *iobuf)
- int write config history (const char *htext, long htime, long id, IO BUFFER *iobuf)
- int list_history (IO_BUFFER *iobuf, FILE *file)

7.25.1 Detailed Description

Keep blocks of history in the data (like command line of programs operating on the data, ...)

Author

Konrad Bernloehr

Date

```
1997 to 2010
```

```
$Date: 2014/02/20 11:40:42 $
```


Version

```
$Revision: 1.5 $
```

7.26 initial.h File Reference

Indentification of the system and including some basic include file.

```
#include <string.h>
#include <stdio.h>
#include <math.h>
#include <time.h>
#include <stdlib.h>
#include <sys/types.h>
Include dependency graph for initial.h:
```



This graph shows which files directly or indirectly include this file:



7.26 initial.h File Reference 205

Macros

- #define IEEE FLOAT_FORMAT 1
- #define M_PI 3.14159265358979323846
- #define ARGLIST(a) a
- #define SEEK_CUR 1
- #define WRITE TEXT "w"
- #define WRITE BINARY "w"
- #define READ_TEXT "r"
- #define READ_BINARY "r"
- #define APPEND_TEXT "a"
- #define APPEND_BINARY "a"
- #define **Nint**(a) (((a)>=0.)?((long)(a+0.5)):((long)(a-0.5)))
- #define **Abs**(a) (((a)>=0)?(a):(-1*(a)))
- #define **Min**(a, b) ((a)<(b)?(a):(b))
- #define **Max**(a, b) ((a)>(b)?(a):(b))
- #define **min**(a, b) ((a)<(b)?(a):(b))
- #define **max**(a, b) ((a)>(b)?(a):(b))
- · #define REGISTER register
- #define CONST_QUAL

Typedefs

- · typedef char int8_t
- · typedef unsigned char uint8_t
- typedef short int16_t
- · typedef unsigned short uint16_t
- · typedef int int32_t
- · typedef unsigned int uint32_t
- · typedef long intmax_t
- · typedef unsigned long uintmax_t

7.26.1 Detailed Description

Indentification of the system and including some basic include file.

```
@author Konrad Bernloehr
@date 1991 to 2010
@date @verbatim $Date: 2012/11/13 16:28:15 $
```

Version

```
$Revision: 1.14 $
```

This file identifies a range of supported operating systems and processor types. As a result, some preprocessor definitions are made. A basic set of system include files (which may vary from one system to another) are included. In addition, compatibility between different systems is improved, for example between K&R compiler systems and ANSI C compilers of various flavours.


```
OS_DARWIN (Mac OS X).
   Note: ULTRIX may be on VAX or MIPS, LINUX on Intel or Alpha,
    OS_LYNX on 68K or PowerPC.
You might first reset all identifiers here.
Then set one or more identifiers according to the system.
Identification of the CPU architecture:
Supported CPU identifiers are
  CPU_I86
  CPU_X86_64
  CPU_VAX
  CPU_MIPS
   CPU_ALPHA
  CPU 68K
  CPU_RS6000
   CPU_PowerPC
  CPU_HPPA
```

7.27 io_hess.c File Reference

Writing and reading of H.E.S.S.

```
#include "initial.h"
#include "io_basic.h"
#include "mc_tel.h"
#include "io_hess.h"
#include <assert.h>
#include <sys/time.h>
```

Include dependency graph for io_hess.c:



Functions

• void check_hessio_max (int ncheck, int max_tel, int max_pix, int max_sectors, int max_drawers, int max_pixsectors, int max_slices, int max_hotpix, int max_profile, int max_d_temp, int max_c_temp, int max_gains)

Support for checking if user functions are compiled with the same limits as the library.

- void show_hessio_max ()
- static void put_time_blob (HTime *t, IO_BUFFER *iobuf)

Put the time (seconds since 1970.0, nanoseconds) into an eventio block already started.

static void get_time_blob (HTime *t, IO_BUFFER *iobuf)

Get the time (seconds since 1970.0, nanoseconds) from an eventio block already started.

· void set tel idx ref (int iref)

Switch between multiple telescope lookup tables.

void set_tel_idx (int ntel, int *idx)

Setup of telescope index lookup table.

• int find_tel_idx (int tel_id)

Lookup from telescope ID to offset number (index) in structures.

int write hess runheader (IO BUFFER *iobuf, RunHeader *rh)

Write the run header in eventio format.

int read hess runheader (IO BUFFER *iobuf, RunHeader *rh)

Read the run header in eventio format.

int print_hess_runheader (IO_BUFFER *iobuf)

Read the run header in eventio format.

int write_hess_mcrunheader (IO_BUFFER *iobuf, MCRunHeader *mcrh)

Write the Monte Carlo run header in eventio format.

• int read_hess_mcrunheader (IO_BUFFER *iobuf, MCRunHeader *mcrh)

Read the Monte Carlo run header in eventio format.

int print_hess_mcrunheader (IO_BUFFER *iobuf)

Print the Monte Carlo run header data.

• int write hess camsettings (IO BUFFER *iobuf, CameraSettings *cs)

Write the camera definition (pixel positions) in eventio format.

• int read hess camsettings (IO BUFFER *iobuf, CameraSettings *cs)

Read the camera definition (pixel positions) in eventio format.

int print hess camsettings (IO BUFFER *iobuf)

Print the camera definition (pixel positions) in eventio format.

int write_hess_camorgan (IO_BUFFER *iobuf, CameraOrganisation *co)

Write the logical organisation of camera electronics in eventio format.

int read_hess_camorgan (IO_BUFFER *iobuf, CameraOrganisation *co)

Read the logical organisation of camera electronics in eventio format.

• int print hess camorgan (IO BUFFER *iobuf)

Read the logical organisation of camera electronics in eventio format.

int write_hess_pixelset (IO_BUFFER *iobuf, PixelSetting *ps)

Write the settings of pixel parameters (HV, thresholds, ...) in eventio format.

int read hess pixelset (IO BUFFER *iobuf, PixelSetting *ps)

Read the settings of pixel parameters (HV, thresholds, ...) in eventio format.

int print_hess_pixelset (IO_BUFFER *iobuf)

Show the settings of pixel parameters (HV, thresholds, ...) in eventio format.

int write_hess_pixeldis (IO_BUFFER *iobuf, PixelDisabled *pd)

Write which pixels are disabled in HV and/or trigger in eventio format.

int read_hess_pixeldis (IO_BUFFER *iobuf, PixelDisabled *pd)

Read which pixels are disabled in HV and/or trigger in eventio format.

• int write_hess_camsoftset (IO_BUFFER *iobuf, CameraSoftSet *cs)

Write camera software parameters relevant for data recording in eventio format.

int read_hess_camsoftset (IO_BUFFER *iobuf, CameraSoftSet *cs)

Read camera software parameters relevant for data recording in eventio format.

• int write hess trackset (IO BUFFER *iobuf, TrackingSetup *ts)

Write the settings for tracking of a telescope in eventio format.

int read_hess_trackset (IO_BUFFER *iobuf, TrackingSetup *ts)

Read the settings for tracking of a telescope in eventio format.

• int write_hess_pointingcor (IO_BUFFER *iobuf, PointingCorrection *pc)

Write the parameters of a telescope's pointing correction in eventio format.

int read_hess_pointingcor (IO_BUFFER *iobuf, PointingCorrection *pc)

Read the parameters of a telescope's pointing correction in eventio format.

• int write_hess_centralevent (IO_BUFFER *iobuf, CentralEvent *ce)

Write the trigger data of the central trigger in eventio format.

• int read_hess_centralevent (IO_BUFFER *iobuf, CentralEvent *ce)

Read the trigger data of the central trigger in eventio format.

• int print hess centralevent (IO BUFFER *iobuf)

Print the trigger data of the central trigger in eventio format.

int write_hess_trackevent (IO_BUFFER *iobuf, TrackEvent *tke)

Write a tracking position in eventio format.

int read_hess_trackevent (IO_BUFFER *iobuf, TrackEvent *tke)

Read a tracking position in eventio format.

int print_hess_trackevent (IO_BUFFER *iobuf)

Print the tracking data in eventio format.

• int write hess televt head (IO BUFFER *iobuf, TelEvent *te)

Write the event header for data from one camera in eventio format.

int read_hess_televt_head (IO_BUFFER *iobuf, TelEvent *te)

Read the event header for data from one camera in eventio format.

int print hess televt head (IO BUFFER *iobuf)

Print the event header for data from one camera in eventio format.

- void put_adcsum_as_uint16 (uint32_t *adc_sum, int n, IO_BUFFER *iobuf)
- void get adcsum as uint16 (uint32 t *adc sum, int n, IO BUFFER *iobuf)
- void put adcsum_differential (uint32 t *adc sum, int n, IO BUFFER *iobuf)
- void get_adcsum_differential (uint32_t *adc_sum, int n, IO_BUFFER *iobuf)
- void put_adcsample_differential (uint16_t *adc_sample, int n, IO_BUFFER *iobuf)
- void get_adcsample_differential (uint16_t *adc_sample, int n, IO_BUFFER *iobuf)
- int write_hess_teladc_sums (IO_BUFFER *iobuf, AdcData *raw)

Write ADC sum data for one camera in eventio format.

• int read_hess_teladc_sums (IO_BUFFER *iobuf, AdcData *raw)

Write ADC sum data for one camera in eventio format.

• int print_hess_teladc_sums (IO_BUFFER *iobuf)

Print summed ADC data in eventio format.

int write hess teladc samples (IO BUFFER *iobuf, AdcData *raw)

Write sampled ADC data in eventio format.

• int read hess telado samples (IO BUFFER *iobuf, AdoData *raw, int what)

Read sampled ADC data in eventio format.

int print_hess_teladc_samples (IO_BUFFER *iobuf)

Print sampled ADC data in eventio format.

- static void adc_reset (AdcData *raw)
- static void build_list_for_hess_pixtime (PixelTiming *pixtm)

A helper function finding the shorter of two possible formats for the list of pixels with any timing information.

• int write_hess_pixtime (IO_BUFFER *iobuf, PixelTiming *pixtm)

Write pixel timing parameters for selected pixels.

• int read_hess_pixtime (IO_BUFFER *iobuf, PixelTiming *pixtm)

Read pixel timing parameters for selected pixels.

int print_hess_pixtime (IO_BUFFER *iobuf)

Print sampled ADC data in eventio format.

int write hess pixcalib (IO BUFFER *iobuf, PixelCalibrated *pixcal)

Write pixel intensities calibrated to (mean?) p.e.

• int read hess pixcalib (IO BUFFER *iobuf, PixelCalibrated *pixcal)

Read pixel intensities calibrated to (mean?) p.e.

int print_hess_pixcalib (IO_BUFFER *iobuf)

Print pixel intensities calibrated to (mean?) p.e.

int write_hess_telimage (IO_BUFFER *iobuf, ImgData *img, int what)

Write image parameters for one telescope in eventio format.

int read_hess_telimage (IO_BUFFER *iobuf, ImgData *img)

Read image parameters for one telescope in eventio format.

• int print hess telimage (IO BUFFER *iobuf)

Print image parameters for one telescope in eventio format.

int write_hess_televent (IO_BUFFER *iobuf, TelEvent *te, int what)

Write data for one telescope camera in eventio format.

• int read hess televent (IO BUFFER *iobuf, TelEvent *te, int what)

Read data for one telescope camera in eventio format.

int print hess televent (IO BUFFER *iobuf)

Print data for one telescope camera in eventio format.

int write hess shower (IO BUFFER *iobuf, ShowerParameters *sp)

Write reconstructed shower parameters in eventio format.

int read_hess_shower (IO_BUFFER *iobuf, ShowerParameters *sp)

Read reconstructed shower parameters in eventio format.

• int print hess shower (IO BUFFER *iobuf)

Print reconstructed shower parameters in eventio format.

int write_hess_event (IO_BUFFER *iobuf, FullEvent *ev, int what)

Write the full array data of one event in eventio format.

• int read hess event (IO BUFFER *iobuf, FullEvent *ev, int what)

Read the full array data of one event in eventio format.

int print_hess_event (IO_BUFFER *iobuf)

Print the full array data of one event in eventio format.

• int write hess calib event (IO BUFFER *iobuf, FullEvent *ev, int what, int type)

Write a calibration event (pedestal, laser, led, ...) as an encapsulated raw data event.

• int read_hess_calib_event (IO_BUFFER *iobuf, FullEvent *ev, int what, int *ptype)

Read a calibration event (pedestal, laser, led, ...) as an encapsulated raw data event.

int print_hess_calib_event (IO_BUFFER *iobuf)

Print a calibration event (pedestal, laser, led, ...) as an encapsulated raw data event.

• int write_hess_mc_shower (IO_BUFFER *iobuf, MCShower *mcs)

Write MC data for one simulated shower in eventio format.

• int read_hess_mc_shower (IO_BUFFER *iobuf, MCShower *mcs)

Read MC data for one simulated shower in eventio format.

int print_hess_mc_shower (IO_BUFFER *iobuf)

Print MC data for one simulated shower in eventio format.

int write_hess_mc_event (IO_BUFFER *iobuf, MCEvent *mce)

Write MC data for one use of a simulated shower in eventio format.

int read_hess_mc_event (IO_BUFFER *iobuf, MCEvent *mce)

Read MC data for one use of a simulated shower in eventio format.

int print hess mc event (IO BUFFER *iobuf)

Print MC data for one use of a simulated shower in eventio format.

• int write hess mc pe sum (IO BUFFER *iobuf, MCpeSum *mcpes)

Write the numbers of photo-electrons detected from Cherenkov light in eventio format.

int read_hess_mc_pe_sum (IO_BUFFER *iobuf, MCpeSum *mcpes)

Read the numbers of photo-electrons detected from Cherenkov light in eventio format.

• int print hess mc pe sum (IO BUFFER *iobuf)

Print the numbers of photo-electrons detected from Cherenkov light in eventio format.

- void reset_htime (HTime *t)
- void fill_htime_now (HTime *now)

Fill the current time into a HTime structure.

void copy_htime (HTime *t2, HTime *t1)

Copy a time from one HTime structure into another one.

• int write_hess_tel_monitor (IO_BUFFER *iobuf, TelMoniData *mon, int what)

Write telescope camera monitoring information in eventio format.

int read_hess_tel_monitor (IO_BUFFER *iobuf, TelMoniData *mon)

Read telescope camera monitoring information in eventio format.

int print hess tel monitor (IO BUFFER *iobuf)

Print telescope camera monitoring information in eventio format.

int write hess laser calib (IO BUFFER *iobuf, LasCalData *lcd)

Write a set of laser calibration data in eventio format.

• int read_hess_laser_calib (IO_BUFFER *iobuf, LasCalData *lcd)

Read a set of laser calibration data in eventio format.

• int print_hess_laser_calib (IO_BUFFER *iobuf)

Print a set of laser calibration data in eventio format.

int write hess run stat (IO BUFFER *iobuf, RunStat *rs)

Write run statistics in eventio format.

• int read_hess_run_stat (IO_BUFFER *iobuf, RunStat *rs)

Read run statistics in eventio format.

int print hess run stat (IO BUFFER *iobuf)

Print run statistics in eventio format.

• int write_hess_mc_run_stat (IO_BUFFER *iobuf, MCRunStat *mcrs)

Write Monte Carlo run statistics in eventio format.

int read_hess_mc_run_stat (IO_BUFFER *iobuf, MCRunStat *mcrs)

Read Monte Carlo run statistics in eventio format.

• int print_hess_mc_run_stat (IO_BUFFER *iobuf)

Print Monte Carlo run statistics in eventio format.

int read_hess_mc_phot (IO_BUFFER *iobuf, MCEvent *mce)

Read Monte Carlo photons and photo-electrons.

int print_hess_mc_phot (IO_BUFFER *iobuf)

Print Monte Carlo photons and photo-electrons.

int write_hess_pixel_list (IO_BUFFER *iobuf, PixelList *pl, int telescope)

Write lists of pixels (triggered, selected in image analysis, ...)

• int read_hess_pixel_list (IO_BUFFER *iobuf, PixelList *pl, int *telescope)

Read lists of pixels (triggered, selected in image analysis, ...)

int print hess pixel list (IO BUFFER *iobuf)

Print lists of pixels (triggered, selected in image analysis, ...)

Variables

- static int g_tel_idx [3][H_MAX_TEL+1]
- static int g_tel_idx_init [3]
- static int g_tel_idx_ref

7.27.1 Detailed Description

Writing and reading of H.E.S.S. /CTA data (or other simulation data produced by sim_telarray/sim_hessarray) in eventio format.

This file provides functions for writing and reading of H.E.S.S./CTA related data blocks or similar data for other telescope arrays. This software will attempt to be backward-compatible, i.e. to be able to read older data in slightly different formats - but we cannot guarantee that it really works. There is no attempt to write data in older formats. As always: use at your own risc.

Author

Konrad Bernlöhr

Date

```
July 2000 (initial version)
```

```
CVS $Date: 2015/03/13 18:53:34 $
```

Version

```
CVS $Revision: 1.87 $
```

7.27.2 Function Documentation

7.27.2.1 void check_hessio_max (int ncheck, int max_tel, int max_pix, int max_sectors, int max_drawers, int max_pixsectors, int max_slices, int max_hotpix, int max_profile, int max_d_temp, int max_c_temp, int max_gains)

Support for checking if user functions are compiled with the same limits as the library.

References H_MAX_GAINS, H_MAX_HOTPIX, H_MAX_PROFILE, H_MAX_SLICES, and H_MAX_TEL.

7.27.2.2 int find_tel_idx (int tel_id)

Lookup from telescope ID to offset number (index) in structures.

The lookup table must have been filled before with set_tel_idx(). When dealing with multiple lookups, use set_tel_idx_ref() first to select the lookup table to be used.

Parameters

tel_id A telescope ID for which we want the index count.

Returns

>= 0 (index in the original list passed to set_tel_idx), -1 (not found in index, -2 (index not initialized).

Referenced by main(), print_hess_event(), read_hess_event(), and which_telescope_type().

7.27.2.3 int print_hess_pixcalib (IO_BUFFER * iobuf)

Print pixel intensities calibrated to (mean?) p.e.

units.

Referenced by print_hess_televent().

7.27.2.4 int read_hess_pixcalib (IO_BUFFER * iobuf, PixelCalibrated * pixcal)

Read pixel intensities calibrated to (mean?) p.e.

units.

References hess_pixel_calibrated_struct::int_method, hess_pixel_calibrated_struct::known, hess_pixel_calibrated_struct::list_known, hess_pixel_calibrated_struct::list_size, hess_pixel_calibrated_struct::num_pixels, hess_pixel_calibrated_struct::pixel_pe, hess_pixel_calibrated_struct::significant, and hess_pixel_calibrated_struct::tel_id.

Referenced by read_hess_televent().

7.27.2.5 void set_tel_idx (int ntel, int *idx)

Setup of telescope index lookup table.

Must be filled before first use of find_tel_idx() - which is automatically done when reading a run header data block. When dealing with multiple lookups, use set_tel_idx_ref() first to select the one to fill.

Parameters

ntel	The number of telescope following.
idx	The list of telescope IDs mapped to indices 0, 1,

Referenced by read_hess_runheader(), and write_hess_runheader().

7.27.2.6 void set_tel_idx_ref (int iref)

Switch between multiple telescope lookup tables.

Use this function when dealing simultaneously with multiple data streams for different array configurations. Both the set tel idx and the find tel idx will then work wit the selected choice of lookup table.

Parameters

iref	Which lookup table to use from now on (0<=iref<=2). Not switching lookup if iref is out of
	range.

Referenced by merge data from io block().

7.27.2.7 int write_hess_event (IO_BUFFER * iobuf, FullEvent * ev, int what)

Write the full array data of one event in eventio format.

This can include raw data, tracking data, and central trigger data as gathered from the individual computers, as well as reconstructed parameters (image parameters, shower parameters).

References hess_event_data_struct::central, hess_tracking_event_data_struct::cor_known, hess_central_event_data_struct::glob_count, hess_central_event_data_struct::gps_time, hess_tel_event_data_struct::loc_count, hess_event_data_struct::num_tel, hess_central_event_data_struct::num_teldata, hess_central_event_data_struct::num_teltrg, hess_tracking_event_data_struct::raw_known, RAWDAT-A_FLAG, hess_event_data_struct::shower, hess_tel_event_data_struct::tel_id, hess_event_data_struct::teldata, hess_central_event_data_struct::teldata_list, hess_central_event_data_struct::teltrg_list, hess_central_event_data_struct::teltrg_type_mask, hess_event_data_struct::trackdata, write hess centralevent(), write hess shower(), write hess televent(), and write hess trackevent().

Referenced by main(), and write_hess_calib_event().

7.27.2.8 int write_hess_laser_calib (IO_BUFFER * iobuf, LasCalData * lcd)

Write a set of laser calibration data in eventio format.

This may well change in a future revision (when more details are known how the real laser calibration should work).

References hess_laser_calib_data_struct::calib, hess_laser_calib_data_struct::lascal_id, hess_laser_calib_data_struct::max_int_frac, hess_laser_calib_data_struct::max_pixtm_frac, hess_laser_calib_data_struct::num_gains, hess_laser_calib_data_struct::num_pixels, and hess_laser_calib_data_struct::tel_id.

Referenced by merge data from io block().

7.27.2.9 int write_hess_mc_event (IO_BUFFER * iobuf, MCEvent * mce)

Write MC data for one use of a simulated shower in eventio format.

This includes the core position shift with respect to the telescope array and the cross reference to the simulated shower.

References hess_mc_event_struct::aweight, hess_mc_event_struct::event, hess_mc_event_struct::shower_num, hess_mc_event_struct::ycore, and hess_mc_event_struct::ycore.

Referenced by main().

7.27.2.10 int write_hess_mc_pe_sum (IO_BUFFER * iobuf, MCpeSum * mcpes)

Write the numbers of photo-electrons detected from Cherenkov light in eventio format.

These are the 'true' numbers registered, not including photo-electrons from nightsky background.

References hess_mc_pe_sum_struct::event, hess_mc_pe_sum_struct::num_pe, hess_mc_pe_sum_struct::num_pixels, hess_mc_pe_sum_struct::photons, hess_mc_pe_sum_struct::photons-atm, hess_mc_pe_sum_struct::photons_atm_3_6, hess_mc_pe_sum_struct::photons_atm_400, hess_mc_pe_sum_struct::photons_atm_400, hess_mc_pe_sum_struct::photons_atm_400, hess_mc_pe_sum_struct::photons_atm_400, hess_mc_pe_sum_struct::pix_pe, and hess_mc_pe_sum_struct::shower_num.

Referenced by main().

7.27.2.11 int write_hess_mc_shower (IO_BUFFER * iobuf, MCShower * mcs)

Write MC data for one simulated shower in eventio format.

This includes data from the shower simulation itself, independent of how many times a shower is used and where the core position is shifted to with respect to the telescope array.

References hess_mc_shower_struct::altitude, hess_mc_shower_struct::azimuth, hess_mc_shower_struct::cmax, hess_mc_shower_profile_struct::content, hess_mc_shower_struct::depth_start, hess_mc_shower_struct::emax, hess_mc_shower_profile_struct::end, hess_mc_shower_struct::energy, hess_mc_shower_struct::h_first_int, hess_mc_shower_struct::hmax, hess_mc_shower_profile_struct::id, shower_extra_parameters::is_set, hess_mc_shower_struct::num_profiles, hess_mc_shower_profile_struct::num_steps, hess_mc_shower_struct::primary_id, hess_mc_shower_profile_struct::start, and hess_mc_shower_struct::xmax.

Referenced by main().

7.27.2.12 int write_hess_pixcalib (IO_BUFFER * iobuf, PixelCalibrated * pixcal)

Write pixel intensities calibrated to (mean?) p.e.

units.

References hess_pixel_calibrated_struct::int_method, hess_pixel_calibrated_struct::known, hess_pixel_calibrated_struct::list_known, hess_pixel_calibrated_struct::list_size, hess_pixel_calibrated_struct::num_pixels, hess_pixel_calibrated_struct::pixel_pe, hess_pixel_calibrated_struct::significant, and hess pixel calibrated struct::tel id.

Referenced by write hess televent().

7.27.2.13 int write_hess_run_stat (IO_BUFFER * iobuf, RunStat * rs)

Write run statistics in eventio format.

This is pretty much dummy at this moment. Once we get closer to the real experiment, this data will certainly increase by a considerable amount.

References hess_run_end_statistics_struct::num_central_trig, hess_run_end_statistics_struct::num_events, hess_run_end_statistics_struct::num_local_sys_trig, hess_run_end_statistics_struct::num_local_trig, hess_run_end_statistics_struct::num_tel, hess_run_end_statistics_struct::run_num, and hess_run_end_statistics_struct::tel_ids.

7.27.2.14 int write_hess_shower (IO_BUFFER * iobuf, ShowerParameters * sp)

Write reconstructed shower parameters in eventio format.

Note that the actual amount of data stored depends on what is actually available (as indicated in the 'result_bits').

References hess_shower_parameter::Alt, hess_shower_parameter::Az, hess_shower_parameter::energy, hess_shower_parameter::err_core1, hess_shower_parameter::err_core2, hess_shower_parameter::err_core3, hess_shower_parameter::err_dir1, hess_shower_parameter::err_dir2, hess_shower_parameter::err_dir3, hess_shower_parameter::mg_list, hess_shower_parameter::mg_pattern, hess_shower_parameter::mscl, hess_shower_parameter::num_img, hess_shower_parameter::num_read, hess_shower_parameter::num_trg, hess_shower_parameter::result_bits, hess_shower_parameter::xc, hess_shower_parameter::xmax, and hess_shower_parameter::yc.

Referenced by write hess event().

7.27.2.15 int write_hess_tel_monitor (IO_BUFFER * iobuf, TelMoniData * mon, int what)

Write telescope camera monitoring information in eventio format.

What actually is written depends on the 'what' parameter. The general idea is to write only those things which have changed. Only when a target farm CPU becomes the target of the data stream, the full set of monitoring data is written.

References hess_tel_monitor_struct::camera_temp, hess_tel_monitor_struct::coinc_count, copy_htime(), hess_tel_monitor_struct::current, hess_tel_monitor_struct::daq_conf, hess_tel_monitor_struct::data_rate, hess_tel_monitor_struct::data_rate, hess_tel_monitor_struct::de_rate_time, hess_tel_monitor_struct::drawer_temp, hess_tel_monitor_struct::event_count, hess_tel_monitor_struct::event_rate, fill_htime_now(), hess_tel_monitor_struct::hv_dac, hess_tel_monitor_struct::hv_i-mon, hess_tel_monitor_struct::hv_set, hess_tel_monitor_struct::hv_stat, hess_tel_monitor_struct::hv_temp_time, hess_tel_monitor_struct::hv_v_mon, hess_tel_monitor_struct::known, hess_tel_monitor_struct::mean_significant, hess_tel_monitor_struct::moni_time, hess_tel_monitor_struct::monitor_id, hess_tel_monitor_struct::new_parts, hess_tel_monitor_struct::noise, hess_tel_monitor_struct::num_camera_temp, hess_tel_monitor_struct::num_drawers, hess_tel_monitor_struct::num_ped_slices, hess_tel_monitor_struct::num_ped_slices, hess_tel_monitor_struct::num_ped_slices, hess_tel_monitor_struct::num_sectors, hess_tel_monitor_struct::ped_noise_time, hess_tel_monitor_struct::set_monitor_struct::set_monitor_struct::set_monitor_struct::set_monitor_struct::set_monitor_struct::set_monitor_struct::set_monitor_struct::set_monitor_struct::set_monitor_struct::set_monitor_struct::set_monitor_struct::set_monitor_struct::set_monitor_struct::trig set, hess_tel_monitor_struct::trig time, and hess_tel_monitor_struct::trigger_rate.

Referenced by merge_data_from_io_block().

7.27.2.16 int write_hess_teladc_samples (IO_BUFFER * iobuf, AdcData * raw)

Write sampled ADC data in eventio format.

In contrast to sum data, no data reduction is applied so far. It is assumed that sampled data would be taken only for hardware tests, where the full information has to be maintained. If large amounts of sampled data are taken, a suitable data reduction method should be inserted here.

References hess_tel_event_adc_struct::adc_sample, H_MAX_GAINS, hess_tel_event_adc_struct::known, hess_tel_event_adc_struct::num_gains, hess_tel_event_adc_struct::num_pixels, hess_tel_event_adc_struct::num_samples, hess_tel_event_adc_struct::significant, hess_tel_event_adc_struct::tel_id, and hess_tel_event_adc_struct::zero sup mode.

Referenced by write_hess_televent().

7.27.2.17 int write_hess_teladc_sums (IO_BUFFER * iobuf, AdcData * raw)

Write ADC sum data for one camera in eventio format.

The data can be optionally reduced (like writing only high-gain channels for pixels with low signals etc.) and zero-suppressed (not writing anything for pixels with very low signals).

References hess_tel_event_adc_struct::adc_list, hess_tel_event_adc_struct::adc_sum, hess_tel_event_adc_struct::data_red_mode, H_MAX_GAINS, HI_GAIN, hess_tel_event_adc_struct::known, hess_tel_event_adc_struct::list_known, hess_tel_event_adc_struct::list_size, LO_GAIN, hess_tel_event_adc_struct::num_gains, hess_tel_event_adc_struct::num_pixels, hess_tel_event_adc_struct::offset_hg8, hess_tel_event_adc_struct::scale_hg8, hess_tel_event_adc_struct::significant, hess_tel_event_adc_struct::tel_id, hess_tel_event_adc_struct::threshold, and hess_tel_event_adc_struct::zero_sup_mode.

Referenced by write hess televent().

7.27.2.18 int write_hess_televent (IO_BUFFER * iobuf, TelEvent * te, int what)

Write data for one telescope camera in eventio format.

Depending on the 'what' parameter, either sampled or summed pixel values are expected to be in the 'te' structure. Writing of image paramaters is another option.


References hess_tel_event_adc_struct::adc_known, hess_tel_event_adc_struct::adc_sum, hess_tel_event_data_struct::glob_count, H_MAX_SLICES, hess_tel_event_data_struct::image_pixels, hess_tel_event_data_struct::img, hess_tel_event_adc_struct::known, hess_pixel_timing_struct::known, hess_pixel_calibrated_struct::known, hess_tel_image_struct::known, hess_tel_event_adc_struct::num_gains, hess_tel_event_data_struct::num_image_sets, hess_tel_event_adc_struct::num_pixels, hess_tel_event_adc_struct::num_samples, hess_tel_event_data_struct::pixcal, hess_pixel_list::pixels, hess_tel_event_data_struct::pixtm, hess_tel_event_data_struct::raw, RAWDATA_FLAG, hess_tel_event_data_struct::readout_mode, hess_tel_event_adc_struct::significant, hess_tel_event_data_struct::tel_id, hess_pixel_timing_struct::timval, hess_tel_event_data_struct::trigger_pixels, write_hess_pixcalib(), write_hess_pixel_list(), write_hess_pixelimage(), and hess_tel_event_adc_struct::zero_sup_mode.

Referenced by write_hess_event().

7.28 io hess.h File Reference

Definition and structures for H.E.S.S.

#include "mc_tel.h"
Include dependency graph for io_hess.h:



This graph shows which files directly or indirectly include this file:



Data Structures

· struct hess run header struct

Run header common to measured and simulated data.

struct hess_mc_run_header_struct

MC run header.

struct hess_camera_settings_struct

Definition of camera optics settings.

• struct hess_camera_organisation_struct

Logical organisation of camera electronics channels.

• struct hess_pixel_setting_struct

Settings of pixel HV and thresholds.

• struct hess_pixel_disabled_struct

Pixels disabled in HV and/or trigger.

struct hess_camera_software_setting_struct

Software settings used in camera process.

· struct hess_tracking_setup_struct

Definition of tracking parameters.

struct hess_pointing_correction_struct

Pointing correction parameters.

struct hess_time_struct

Breakdown of time into seconds since 1970.0 and nanoseconds.

• struct hess_tel_event_adc_struct

ADC data (either sampled or sum mode)

- struct hess_pixel_timing_struct
- struct hess_pixel_calibrated_struct
- struct hess_pixel_list

Lists of pixels (triggered, selected, etc.)

struct hess_tel_image_struct

Image parameters.

struct hess_tel_event_data_struct

Event raw and image data from one telescope.

• struct hess_central_event_data_struct

Central trigger event data.

• struct hess_tracking_event_data_struct

Tracking data interpolated for one event and one telescope.

• struct hess_shower_parameter

Reconstructed shower parameters.

struct hess_event_data_struct

All data for one event.

struct hess_mc_shower_profile_struct

Monte Carlo shower profile (sort of histogram).

• struct hess_mc_shower_struct

Shower specific data.

• struct hess_mc_pe_sum_struct

Sums of photo-electrons in MC (total and per pixel).

struct hess_mc_photons

Photons from Monte Carlo.

struct hess_mc_pe_list

Photo-electrons from Monte Carlo individually.

struct hess_mc_event_struct

Monte Carlo event-specific data.

• struct hess_tel_monitor_struct

Monitoring data.

• struct hess_laser_calib_data_struct

Laser calibration data.

· struct hess_run_end_statistics_struct

End-of-run statistics.

• struct hess_run_end_mc_statistics_struct

MC end-of-run statistics.

· struct hess all data struct

Container for all H.E.S.S.

Macros

- #define IO HESS VERSION 2
- #define HI GAIN 0

Which index refers to which type of channel:

#define LO_GAIN 1

Index to low-gain channels in adc_sum, adc_sample, pedestal, ...

• #define LARGE_TELESCOPE 1

Maximum sizes for various arrays:

- #define SMARTPIXEL 1
- #define H MAX TEL 16

Maximum number of telescopes handled.

- #define H_MAX_TRG_PER_SECTOR 1
- #define **H_MAX_PIX** 4095
- #define H MAX SECTORS (H MAX PIX*H MAX TRG PER SECTOR)
- #define H_MAX_DRAWERS H_MAX_PIX
- #define H_MAX_GAINS 2

Maximum number of different gains per PM.

- #define **H_MAX_PIXSECTORS** 4
- #define H_MAX_SLICES 128

Maximum number of time slices handled.

• #define H_MAX_HOTPIX 5

The max.

• #define H_MAX_PROFILE 10

The max.

- #define H_MAX_D_TEMP 8
- #define H_MAX_C_TEMP 10
- #define H MAX FSHAPE 1000

Max.

• #define H_CHECK_MAX()

Macro expanding into a function call checking if user function.

#define RAWDATA_FLAG 0x01

Flags used for saving and restoring event data:

- #define RAWSUM FLAG 0x02
- #define TRACKRAW FLAG 0x04
- #define TRACKCOR_FLAG 0x08
- #define TRACKDATA_FLAG (TRACKRAW_FLAG|TRACKCOR_FLAG)
- #define IMG_BASE_FLAG 0x10
- #define IMG ERR FLAG 0x20
- #define IMG 34M FLAG 0x40
- #define IMG HOT FLAG 0x80
- #define IMG PIXTM FLAG 0x100
- #define IMAGE_FLAG (IMG_BASE_FLAG|IMG_ERR_FLAG|IMG_34M_FLAG|IMG_HOT_FLAG|IMG_PIX-TM FLAG)
- #define TIME_FLAG 0x200
- #define SHOWER FLAG 0x400
- #define CALSUM FLAG 0x800
- #define IO TYPE HESS BASE 2000

Never change the following numbers after MC data is created:

- #define IO TYPE HESS RUNHEADER (IO TYPE HESS BASE+0)
- #define IO_TYPE_HESS_MCRUNHEADER (IO_TYPE_HESS_BASE+1)
- #define IO_TYPE_HESS_CAMSETTINGS (IO_TYPE_HESS_BASE+2)
- #define IO_TYPE_HESS_CAMORGAN (IO_TYPE_HESS_BASE+3)
- #define IO_TYPE_HESS_PIXELSET (IO_TYPE_HESS_BASE+4)
- #define IO TYPE HESS PIXELDISABLE (IO TYPE HESS BASE+5)
- #define IO TYPE HESS CAMSOFTSET (IO TYPE HESS BASE+6)
- #define IO_TYPE_HESS_POINTINGCOR (IO_TYPE_HESS_BASE+7)
- #define IO_TYPE_HESS_TRACKSET (IO_TYPE_HESS_BASE+8)
- #define IO_TYPE_HESS_CENTEVENT (IO_TYPE_HESS_BASE+9)
- #define IO TYPE HESS TRACKEVENT (IO TYPE HESS BASE+100)
- #define IO TYPE HESS TELEVENT (IO TYPE HESS BASE+200)
- #define IO TYPE HESS EVENT (IO TYPE HESS BASE+10)
- #define IO_TYPE_HESS_TELEVTHEAD (IO_TYPE_HESS_BASE+11)
- #define IO_TYPE_HESS_TELADCSUM (IO_TYPE_HESS_BASE+12)
- #define IO_TYPE_HESS_TELADCSAMP (IO_TYPE_HESS_BASE+13)
- #define IO_TYPE_HESS_TELIMAGE (IO_TYPE_HESS_BASE+14)
- #define IO_TYPE_HESS_SHOWER (IO_TYPE_HESS_BASE+15)
- #define IO_TYPE_HESS_PIXELTIMING (IO_TYPE_HESS_BASE+16)
- #define IO_TYPE_HESS_PIXELCALIB (IO_TYPE_HESS_BASE+17)
- #define IO TYPE HESS MC SHOWER (IO TYPE HESS BASE+20)
- #define IO_TYPE_HESS_MC_EVENT (IO_TYPE_HESS_BASE+21)
- #define IO TYPE HESS TEL MONI (IO TYPE HESS BASE+22)
- #define IO_TYPE_HESS_LASCAL (IO_TYPE_HESS_BASE+23)
- #define IO_TYPE_HESS_RUNSTAT (IO_TYPE_HESS_BASE+24)
- #define IO_TYPE_HESS_MC_RUNSTAT (IO_TYPE_HESS_BASE+25)
 #define IO_TYPE_HESS_MC_PE_SUM (IO_TYPE_HESS_BASE+26)
- #define IO_TYPE_HESS_PIXELLIST (IO_TYPE_HESS_BASE+27)
- #define IO TYPE HESS CALIBEVENT (IO TYPE HESS BASE+28)
- #define HAS_CORSIKA_INTERACTION_DETAIL 1
- #define H_MAX_PIX_TIMES 7

In addition to ADC we may (optionally) also have timing data.

#define PIX TIME PEAKPOS TYPE 1

Position of peak in time (slices since readout).

• #define PIX_TIME_STARTPOS_REL_TYPE 2

Position of first rise above fraction of peak ampl.

#define PIX_TIME_STARTPOS_ABS_TYPE 3

Position of first rise above absolute threshold.

• #define PIX_TIME_WIDTH_REL_TYPE 4

Width of pulse over fraction of peak ampl.

#define PIX_TIME_WIDTH_ABS_TYPE 5

Width of pulse over absolute threshold (time over threshold).

Typedefs

· typedef struct

hess_run_header_struct RunHeader

typedef struct

hess_mc_run_header_struct MCRunHeader

· typedef struct

hess_camera_settings_struct CameraSettings

typedef struct

hess_camera_organisation_struct CameraOrganisation

typedef struct

hess_pixel_setting_struct PixelSetting

· typedef struct

hess_pixel_disabled_struct PixelDisabled

typedef struct

hess_camera_software_setting_struct CameraSoftSet

typedef struct

hess_tracking_setup_struct TrackingSetup

· typedef struct

hess_pointing_correction_struct PointingCorrection

- typedef struct hess_time_struct HTime
- · typedef struct

hess tel event adc struct AdcData

· typedef struct

hess_pixel_timing_struct PixelTiming

· typedef struct

hess_pixel_calibrated_struct PixelCalibrated

- typedef struct hess_pixel_list PixelList
- · typedef struct

hess_tel_image_struct ImgData

· typedef struct

hess_tel_event_data_struct TelEvent

· typedef struct

hess_central_event_data_struct CentralEvent

· typedef struct

hess_tracking_event_data_struct TrackEvent

· typedef struct

hess_shower_parameter ShowerParameters

· typedef struct

hess_event_data_struct FullEvent

typedef struct

 $hess_mc_shower_profile_struct~\textbf{ShowerProfile}$

· typedef struct

hess_mc_shower_struct MCShower

· typedef struct

hess_mc_pe_sum_struct MCpeSum

typedef struct hess_mc_event_struct MCEvent

```
    typedef struct
hess_tel_monitor_struct TelMoniData
```

 typedef struct hess_laser_calib_data_struct LasCalData

 typedef struct hess_run_end_statistics_struct RunStat

 typedef struct hess_run_end_mc_statistics_struct MCRunStat

• typedef struct hess_all_data_struct AllHessData

Functions

- void check_hessio_max (int ncheck, int max_tel, int max_pix, int max_sectors, int max_drawers, int max_pixsectors, int max_slices, int max_hotpix, int max_profile, int max_d_temp, int max_c_temp, int max_gains)
 Support for checking if user functions are compiled with the same limits as the library.
- void show_hessio_max (void)

7.28.1 Detailed Description

Definition and structures for H.E.S.S. /CTA data in eventio format.

This file contains definitions and data structures used for writing and reading HESS data (both Monte Carlo and real data) in the eventio format. It was then extended to include potential additional CTA data.

Author

Konrad Bernlöhr

Date

```
initial version: July 2000
```

```
CVS $Date: 2015/06/15 17:40:58 $
```

Version

```
CVS $Revision: 1.91 $
```

7.28.2 Macro Definition Documentation

```
7.28.2.1 #define H_CHECK_MAX( )
```

Value:

```
check_hessio_max(11,H_MAX_TEL,H_MAX_PIX,H_MAX_SECTORS,\
    H_MAX_DRAWERS,H_MAX_PIXSECTORS,H_MAX_SLICES,H_MAX_HOTPIX,
    H_MAX_PROFILE,\
    H_MAX_D_TEMP,H_MAX_C_TEMP,H_MAX_GAINS);
```

Macro expanding into a function call checking if user function.

is taking the same maximum array sizes as the library.

Referenced by main().

7.28.2.2 #define H_MAX_FSHAPE 1000

Max.

number of (sub-) samples of reference pulse shapes.

Referenced by read hess pixelset().

7.28.2.3 #define H_MAX_HOTPIX 5

The max.

size of the list of hottest pix.

Referenced by check_hessio_max().

7.28.2.4 #define H_MAX_PIX_TIMES 7

In addition to ADC we may (optionally) also have timing data.

Referenced by pixel_timing_analysis(), and read_hess_pixtime().

7.28.2.5 #define H_MAX_PROFILE 10

The max.

number of MC shower profiles.

Referenced by check_hessio_max(), and read_hess_mc_shower().

7.28.2.6 #define H_MAX_SLICES 128

Maximum number of time slices handled.

Referenced by check_hessio_max(), nb_peak_integration(), print_hess_teladc_samples(), read_hess_teladc_samples(), and write_hess_televent().

7.28.2.7 #define HI_GAIN 0

Which index refers to which type of channel:

Index to high-gain channels in adc_sum, adc_sample, pedestal, ...

Referenced by calibrate_amplitude(), calibrate_pixel_amplitude(), hesscam_ps_plot(), local_peak_integration(), nb_peak_integration(), read_hess_teladc_sums(), and write_hess_teladc_sums().

7.28.2.8 #define LO_GAIN 1

Index to low-gain channels in adc_sum, adc_sample, pedestal, ...

Referenced by calibrate_amplitude(), calibrate_pixel_amplitude(), hesscam_ps_plot(), local_peak_integration(), nb_peak_integration(), read_hess_teladc_sums(), and write_hess_teladc_sums().

7.28.2.9 #define PIX_TIME_PEAKPOS_TYPE 1

Position of peak in time (slices since readout).

Referenced by pixel_timing_analysis().

```
7.28.2.10 #define PIX_TIME_STARTPOS_ABS_TYPE 3
```

Position of first rise above absolute threshold.

```
7.28.2.11 #define PIX_TIME_STARTPOS_REL_TYPE 2
```

Position of first rise above fraction of peak ampl.

Referenced by pixel_timing_analysis().

```
7.28.2.12 #define PIX_TIME_WIDTH_ABS_TYPE 5
```

Width of pulse over absolute threshold (time over threshold).

Referenced by pixel timing analysis().

```
7.28.2.13 #define PIX_TIME_WIDTH_REL_TYPE 4
```

Width of pulse over fraction of peak ampl.

Referenced by pixel_timing_analysis().

7.28.3 Function Documentation

7.28.3.1 void check_hessio_max (int ncheck, int max_tel, int max_pix, int max_sectors, int max_drawers, int max_pixsectors, int max_slices, int max_hotpix, int max_profile, int max_d_temp, int max_c_temp, int max_gains)

Support for checking if user functions are compiled with the same limits as the library.


References H_MAX_GAINS, H_MAX_HOTPIX, H_MAX_PROFILE, H_MAX_SLICES, and H_MAX_TEL.

7.29 io_histogram.c File Reference

This file implements I/O for 1-D and 2-D histograms.

```
#include "initial.h"
#include "io_basic.h"
#include "histogram.h"
#include "io_histogram.h"
#include "fileopen.h"
```

Include dependency graph for io_histogram.c:



Functions

- int write_all_histograms (const char *fname)
 - Save all available histograms into the file with the given name.
- int read_histogram_file (const char *fname, int add_flag)
- int read_histogram_file_x (const char *fname, int add_flag, const long *xcld_ids, int nxcld)
- int write_histograms (HISTOGRAM **phisto, int nhisto, IO_BUFFER *iobuf)

Save specific histograms or all allocated histograms.

- int read histograms (HISTOGRAM **phisto, int nhisto, IO BUFFER *iobuf)
 - Read and allocate histograms and optionally return histogram pointers to caller.
- int read_histograms_x (HISTOGRAM **phisto, int nhisto, const long *xcld_ids, int nxcld, IO_BUFFER *iobuf)

 Read and allocate histograms and optionally return histogram pointers to caller.
- int print_histograms (IO_BUFFER *iobuf)

Print out some basics about histogram data as we read it.

7.29.1 Detailed Description

This file implements I/O for 1-D and 2-D histograms.

Author

Konrad Bernloehr

Date

1993 to 2010

CVS \$Date: 2013/10/21 12:53:31 \$

Version

CVS \$Revision: 1.20 \$

7.29.2 Function Documentation

7.29.2.1 int print_histograms ($IO_BUFFER * iobuf$)

Print out some basics about histogram data as we read it.

Parameters

iobuf	The input iobuf descriptor.
-------	-----------------------------

Returns

```
>= 0 (O.k., no. of histograms read), -1 (error), -2 (e.o.d.)
```

References Histogram_Extension::content_inside.

Referenced by main().

7.29.2.2 int read_histograms (HISTOGRAM ** phisto, int nhisto, IO_BUFFER * iobuf)

Read and allocate histograms and optionally return histogram pointers to caller.

Parameters

phisto	Pointer to vector of histogram pointers or NULL.
nhisto	The no. of elements in the phisto vector, i.e. the max. no. of histograms of which the
	histogram pointer can be returned to the caller. If negative, histograms contents are added to
	existing histograms of the same ID.
iobuf	The input iobuf descriptor.

Returns

```
>= 0 (O.k., no. of histograms read), -1 (error), -2 (e.o.d.)
```

References read histograms x().

Referenced by main().

7.29.2.3 int read_histograms_x (HISTOGRAM ** phisto, int nhisto, const long * xcld_ids, int nxcld, IO_BUFFER * iobuf)

Read and allocate histograms and optionally return histogram pointers to caller.

This extended version allows to exclude a list of histogram IDs from being kept or added.

Parameters

phisto	Pointer to vector of histogram pointers or NULL.
nhisto	The no. of elements in the phisto vector, i.e. the max. no. of histograms of which the
	histogram pointer can be returned to the caller. If negative, histograms contents are added to
	existing histograms of the same ID.
xcld_ids	Pointer to vector of histogram IDs to be excluded.
ncxld	Number of histogram IDs to be excluded.
iobuf	The input iobuf descriptor.

Returns

```
>= 0 (O.k., no. of histograms read), -1 (error), -2 (e.o.d.)
```

References add_histogram(), alloc_2d_int_histogram(), alloc_2d_real_histogram(), alloc_int_histogram(), alloc_real_histogram(), alloc_int_histogram(), alloc_int_histogram_extension::content_all, Histogram_extension::content_all, Histogram_extension::content_inside, Histogram_extension::data, describe_histogram(), histogram:intension::fdata, free_histogram(), get_histogram_by_ident(), Histogram_Parameters::integer, histogram::overflow, histogram::overflow_2d, Histogram_Parameters::sum, histogram::tentries, Histogram_Parameters::tsum, histogram::type, histogram::underflow, and histogram::underflow_2d.

Referenced by read_histograms().

7.29.2.4 int write_histograms (HISTOGRAM ** phisto, int nhisto, IO_BUFFER * iobuf)

Save specific histograms or all allocated histograms.

Parameters

phisto	Pointer to vector of histogram pointers or NULL.
nhisto	The no. of histograms to be saved or -1. If phisto==NULL and nhisto==-1 then all allocated
	histograms (in the linked list of histograms) are saved.
iobuf	The output iobuf descriptor.

Returns

0 (O.k.) or -1 (error)


References histogram::counts, histogram::entries, histogram::extension, get_first_histogram(), histogram::ident, Histogram_Parameters::inwer_limit, histogram::nbins, histogram::nbins_2d, histogram::next, histogram::overflow, histogram::overflow_2d, Histogram_Parameters::real, Histogram_Parameters::sum, histogram::tentries, histogram::title, Histogram_Parameters::tsum, histogram::type, histogram::underflow, histogram::underflow_2d, and Histogram_Parameters::upper_limit.

Referenced by main(), write_all_histograms(), and write_dst_histos().


7.30 io_histogram.h File Reference

Declarations for eventio I/O of histograms.

#include "histogram.h"
Include dependency graph for io_histogram.h:



This graph shows which files directly or indirectly include this file:



Functions

int write_histograms (HISTOGRAM **phisto, int nhisto, IO_BUFFER *iobuf)

Save specific histograms or all allocated histograms.

• int read_histograms (HISTOGRAM **phisto, int nhisto, IO_BUFFER *iobuf)

Read and allocate histograms and optionally return histogram pointers to caller.

- int read_histograms_x (HISTOGRAM **phisto, int nhisto, const long *xcld_ids, int nxcld, IO_BUFFER *iobuf)

 Read and allocate histograms and optionally return histogram pointers to caller.
- int print_histograms (IO_BUFFER *iobuf)

Print out some basics about histogram data as we read it.

int write_all_histograms (const char *fname)

Save all available histograms into the file with the given name.

- int read histogram file (const char *fname, int add flag)
- int read_histogram_file_x (const char *fname, int add_flag, const long *xcld_ids, int nxcld)

7.30.1 Detailed Description

Declarations for eventio I/O of histograms.

Author

Konrad Bernloehr

Date

```
CVS $Date: 2013/10/21 12:53:31 $
```

Version

```
CVS $Revision: 1.11 $
```

7.30.2 Function Documentation

```
7.30.2.1 int print_histograms ( IO_BUFFER * iobuf )
```

Print out some basics about histogram data as we read it.

Parameters

Returns

```
>= 0 (O.k., no. of histograms read), -1 (error), -2 (e.o.d.)
```

References Histogram Extension::content inside.

Referenced by main().

7.30.2.2 int read_histograms (HISTOGRAM ** phisto, int nhisto, IO_BUFFER * iobuf)

Read and allocate histograms and optionally return histogram pointers to caller.

phisto	Pointer to vector of histogram pointers or NULL.
nhisto	The no. of elements in the phisto vector, i.e. the max. no. of histograms of which the
	histogram pointer can be returned to the caller. If negative, histograms contents are added to
	existing histograms of the same ID.
iobuf	The input iobuf descriptor.

Returns

>= 0 (O.k., no. of histograms read), -1 (error), -2 (e.o.d.)

References read histograms x().

Referenced by main().

7.30.2.3 int read histograms x (HISTOGRAM ** phisto, int nhisto, const long * xcld ids, int nxcld, IO BUFFER * iobuf)

Read and allocate histograms and optionally return histogram pointers to caller.

This extended version allows to exclude a list of histogram IDs from being kept or added.

Parameters

phisto	Pointer to vector of histogram pointers or NULL.
nhisto	The no. of elements in the phisto vector, i.e. the max. no. of histograms of which the
	histogram pointer can be returned to the caller. If negative, histograms contents are added to
	existing histograms of the same ID.
xcld_ids	Pointer to vector of histogram IDs to be excluded.
ncxld	Number of histogram IDs to be excluded.
iobuf	The input iobuf descriptor.

Returns

>= 0 (O.k., no. of histograms read), -1 (error), -2 (e.o.d.)

References add_histogram(), alloc_2d_int_histogram(), alloc_2d_real_histogram(), alloc_int_histogram(), alloc_real_histogram(), alloc_int_histogram(), alloc_int_histogram_extension::content_all, Histogram_extension::content_inside, Histogram_extension::content_all, Histogram_extension::content_all, Histogram_extension::content_inside, Histogram_extension::data, describe_histogram(), histogram(), histogram(), histogram(), alloc_int_histogram(), alloc_int_histogram_extension::content_all, Histogram_extension::content_all, Histogram_extension::conten

Referenced by read_histograms().

7.30.2.4 int write_histograms (HISTOGRAM ** phisto, int nhisto, IO_BUFFER * iobuf)

Save specific histograms or all allocated histograms.

Parameters

phisto	Pointer to vector of histogram pointers or NULL.
nhisto	The no. of histograms to be saved or -1. If phisto==NULL and nhisto==-1 then all allocated
	histograms (in the linked list of histograms) are saved.
iobuf	The output iobuf descriptor.

Returns

References histogram::counts, histogram::entries, histogram::extension, get_first_histogram(), histogram::ident, Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, histogram::next, histogram::overflow, histogram::overflow_2d, Histogram_Parameters::real, Histogram_Parameters::sum, histogram::tentries, histogram::title, Histogram_Parameters::tsum, histogram::type, histogram::underflow, histogram::underflow_2d, and Histogram_Parameters::upper_limit.


Referenced by main(), write_all_histograms(), and write_dst_histos().

7.31 io_history.c File Reference

Record history of configuration settings/commands.

```
#include "initial.h"
#include "io_basic.h"
#include "history.h"
#include "current.h"
#include "hconfig.h"
```

Include dependency graph for io_history.c:



Data Structures

· struct history_struct

Use to build a linked list of configuration history.

Typedefs

• typedef struct history_struct HSTRUCT

Functions

- static void listtime (time_t t, FILE *f)
- int push_command_history (int argc, char **argv)
- int push_config_history (const char *line, int noreplace)
- int write_history (long id, IO_BUFFER *iobuf)
- int write_config_history (const char *htext, long htime, long id, IO_BUFFER *iobuf)
- int list_history (IO BUFFER *iobuf, FILE *file)

Variables

• static char * cmdline = NULL

A copy of the program's command line.

static time_t cmdtime

The time when the program was started.

 static HSTRUCT * configs = NULL Start of configuration history.

7.31.1 Detailed Description

Record history of configuration settings/commands. This code has not been adapted for multi-threading.

Author

Konrad Bernloehr

Date

```
1997 to 2010
```

```
CVS $Date: 2014/02/20 11:40:42 $
```

Version

CVS \$Revision: 1.8 \$

7.31.2 Variable Documentation

```
7.31.2.1 char* cmdline = NULL [static]
```

A copy of the program's command line.

```
7.31.2.2 time_t cmdtime [static]
```

The time when the program was started.


```
7.31.2.3 HSTRUCT* configs = NULL [static]
```

Start of configuration history.

7.32 io_history.h File Reference

Record history of configuration settings/commands.

```
#include "initial.h"
Include dependency graph for io_history.h:
```



time.h

math.h

stdlib.h

sys/types.h

string.h

stdio.h

Functions

- int push command history (int argc, char **argv)
- int push_config_history (const char *line, int noreplace)
- int write_history (long id, IO_BUFFER *iobuf)
- int write_config_history (const char *htext, long htime, long id, IO_BUFFER *iobuf)
- int list_history (IO_BUFFER *iobuf, FILE *file)

7.32.1 Detailed Description

Record history of configuration settings/commands.

Author

Konrad Bernloehr

Date

```
1997 to 2010
```

```
CVS $Date: 2014/02/20 11:40:42 $
```

Version


```
CVS $Revision: 1.5 $
```

7.33 io simtel.c File Reference

Write and read CORSIKA blocks and simulated Cherenkov photon bunches.

```
#include "initial.h"
#include "io_basic.h"
#include "mc_tel.h"
#include "fileopen.h"
```

Include dependency graph for io_simtel.c:



Functions

- int write_tel_block (IO_BUFFER *iobuf, int type, int num, real *data, int len)

 Write a CORSIKA block as given type number (see mc_tel.h).
- int read_tel_block (IO_BUFFER *iobuf, int type, real *data, int maxlen)

Read a CORSIKA header/trailer block of given type (see mc_tel.h)

• int print_tel_block (IO_BUFFER *iobuf)

Print a CORSIKA header/trailer block of any type (see mc_tel.h)

int write_input_lines (IO_BUFFER *iobuf, struct linked_string *list)

Write a linked list of character strings (normally containing the text of the CORSIKA inputs file) as a dedicated block.

int read input lines (IO BUFFER *iobuf, struct linked string *list)

Read a block with several character strings (normally containing the text of the CORSIKA inputs file) into a linked list.

• int write_tel_pos (IO_BUFFER *iobuf, int ntel, double *x, double *y, double *z, double *r)

Write positions of telescopes/detectors within a system or array.

int read_tel_pos (IO_BUFFER *iobuf, int max_tel, int *ntel, double *x, double *y, double *z, double *r)

Read positions of telescopes/detectors within a system or array.

int print_tel_pos (IO_BUFFER *iobuf)

Print positions of telescopes/detectors within a system or array.

• int write_tel_offset (IO_BUFFER *iobuf, int narray, double toff, double *xoff, double *yoff)

Write offsets of randomly scattered arrays with respect to shower core.

- int write_tel_offset_w (IO_BUFFER *iobuf, int narray, double toff, double *xoff, double *yoff, double *weight)

 Write offsets and weights of randomly scattered arrays with respect to shower core.
- int read_tel_offset (IO_BUFFER *iobuf, int max_array, int *narray, double *toff, double *xoff, double *yoff)

 Read offsets of randomly scattered arrays with respect to shower core.
- int read_tel_offset_w (IO_BUFFER *iobuf, int max_array, int *narray, double *toff, double *xoff, double *yoff, double *weight)

Read offsets and weights of randomly scattered arrays with respect to shower core.

int print_tel_offset (IO_BUFFER *iobuf)

Print offsets and weights of randomly scattered arrays with respect to shower core.

int begin write tel array (IO BUFFER *iobuf, IO ITEM HEADER *ih, int array)

Begin writing data for one array of telescopes/detectors.

int end_write_tel_array (IO_BUFFER *iobuf, IO_ITEM_HEADER *ih)

End writing data for one array of telescopes/detectors.

int begin_read_tel_array (IO_BUFFER *iobuf, IO_ITEM_HEADER *ih, int *array)

Begin reading data for one array of telescopes/detectors.

• int end read tel array (IO BUFFER *iobuf, IO ITEM HEADER *ih)

End reading data for one array of telescopes/detectors.

int write_tel_array_head (IO_BUFFER *iobuf, IO_ITEM_HEADER *ih, int array)

Begin writing data for one array of telescopes/detectors.

• int write tel array end (IO BUFFER *iobuf, IO ITEM HEADER *ih, int array)

End writing data for one array of telescopes/detectors.

int read_tel_array_head (IO_BUFFER *iobuf, IO_ITEM_HEADER *ih, int *array)

Begin reading data for one array of telescopes/detectors.

• int read tel array end (IO BUFFER *iobuf, IO ITEM HEADER *ih, int *array)

End reading data for one array of telescopes/detectors.

• int write_tel_photons (IO_BUFFER *iobuf, int array, int tel, double photons, struct bunch *bunches, int nbunches, int ext_bunches, char *ext_fname)

Write all the photon bunches for one telescope to an I/O buffer.

• int write_tel_compact_photons (IO_BUFFER *iobuf, int array, int tel, double photons, struct compact_bunch *cbunches, int nbunches, int ext_bunches, char *ext_fname)

Write all the photon bunches for one telescope to an I/O buffer.

 int read_tel_photons (IO_BUFFER *iobuf, int max_bunches, int *array, int *tel, double *photons, struct bunch *bunches, int *nbunches)

Read bunches of Cherenkov photons for one telescope/detector.

• int print_tel_photons (IO_BUFFER *iobuf)

Print bunches of Cherenkov photons for one telescope/detector.

 int write_shower_longitudinal (IO_BUFFER *iobuf, int event, int type, double *data, int ndim, int np, int nthick, double thickstep)

Write CORSIKA shower longitudinal distributions.

• int read_shower_longitudinal (IO_BUFFER *iobuf, int *event, int *type, double *data, int ndim, int *np, int *nthick, double *thickstep, int max_np)

Read CORSIKA shower longitudinal distributions.

int write_camera_layout (IO_BUFFER *iobuf, int itel, int type, int pixels, double *xp, double *xp,

Write the layout (pixel positions) of a camera used for converting from photons to photo-electrons in a pixel.

int read_camera_layout (IO_BUFFER *iobuf, int max_pixels, int *itel, int *type, int *pixels, double *xp, double *yp)

Read the layout (pixel positions) of a camera used for converting from photons to photo-electrons in a pixel.

int print_camera_layout (IO_BUFFER *iobuf)

Print the layout (pixel positions) of a camera used for converting from photons to photo-electrons in a pixel.

• int write_photo_electrons (IO_BUFFER *iobuf, int array, int tel, int npe, int flags, int pixels, int *pe_counts, int *tstart, double *t, double *a)

Write the photo-electrons registered in a Cherenkov telescope camera.

• int read_photo_electrons (IO_BUFFER *iobuf, int max_pixels, int max_pe, int *array, int *tel, int *npe, int *pixels, int *flags, int *pe_counts, int *tstart, double *t, double *a)

Read the photoelectrons registered in a Cherenkov telescope camera.

• int print photo electrons (IO BUFFER *iobuf)

List the the photoelectrons registered in a Cherenkov telescope camera.

- int write shower extra parameters (IO BUFFER *iobuf, struct shower extra parameters *ep)
- int read_shower_extra_parameters (IO_BUFFER *iobuf, struct shower_extra_parameters *ep)
- int print shower extra parameters (IO BUFFER *iobuf)
- int init_shower_extra_parameters (struct shower_extra_parameters *ep, size_t ni_max, size_t nf_max)

Initialize, resize, clear shower extra parameters.

int clear_shower_extra_parameters (struct shower_extra_parameters *ep)

Similar to init_shower_extra_parameters() but without any attempts to re-allocate or resize buffers.

struct shower_extra_parameters * get_shower_extra_parameters ()

Variables

· static struct

shower extra parameters private shower extra parameters

There is one global (more precisely: static) block of extra shower parameters as, for example, used in the CORSIKA IACT interface.

7.33.1 Detailed Description

Write and read CORSIKA blocks and simulated Cherenkov photon bunches. This file provides functions for writing and reading of CORSIKA header and trailer blocks, positions of telescopes/detectors, lists of simulated Cherenkov photon bunches before any detector simulation for the telescopes as well as of photoelectrons after absorption, telescope ray-tracing and quantum efficiency applied.

Author

Konrad Bernloehr

Date

1997 to 2010

```
CVS $Date: 2015/04/27 10:10:29 $
```

Version

```
CVS $Revision: 1.26 $
```

7.33.2 Function Documentation

7.33.2.1 int begin_read_tel_array (IO_BUFFER * iobuf, IO_ITEM_HEADER * ih, int * array)

Begin reading data for one array of telescopes/detectors.

Note: this function does not finish reading from the I/O block but after reading of the photons a call to end_read_tel_array() is needed.

Parameters

iobuf	- I/O buffer descriptor
ih	- I/O item header (for item opened here)
array	- Number of array

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

Referenced by print_hess_mc_phot(), and read_hess_mc_phot().

7.33.2.2 int begin_write_tel_array (IO_BUFFER * iobuf, IO_ITEM_HEADER * ih, int array)

Begin writing data for one array of telescopes/detectors.

Note: this function does not finish writing to the I/O block but after writing of the photons a call to end_write_tel_array() is needed.

Parameters

iobuf	I/O buffer descriptor
ih	I/O item header (for item opened here)
array	Number of array

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.33.2.3 int clear_shower_extra_parameters (struct shower_extra_parameters * ep)

Similar to init_shower_extra_parameters() but without any attempts to re-allocate or resize buffers.

Just clear contents.

Parameters

ер	Pointer to parameter block. A NULL value indicates that the static block is meant.

References shower_extra_parameters::fparam, shower_extra_parameters::id, shower_extra_parameters::iparam, shower_extra_parameters::is_set, shower_extra_parameters::nfparam, shower_extra_parameters::niparam, and shower extra parameters::weight.

Referenced by read_hess_mc_shower().

7.33.2.4 int end_read_tel_array (IO_BUFFER * iobuf, IO_ITEM_HEADER * ih)

End reading data for one array of telescopes/detectors.

Parameters

iobuf	I/O buffer descriptor
ih	I/O item header (as opened in begin_write_tel_array())

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

Referenced by print_hess_mc_phot(), and read_hess_mc_phot().

7.33.2.5 int end_write_tel_array (IO_BUFFER * iobuf, IO_ITEM_HEADER * ih)

End writing data for one array of telescopes/detectors.

Parameters

iobuf	I/O buffer descriptor
ih	I/O item header (as opened in begin_write_tel_array())

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.33.2.6 int init_shower_extra_parameters (struct shower_extra_parameters * ep, size_t ni_max, size_t nf_max)

Initialize, resize, clear shower extra parameters.

Parameters

ер	Pointer to parameter block. A NULL value indicates that the static block is meant.
ni_max	The number of integer parameters to be used.
nf_max	The number of float parameters to be used.

References shower_extra_parameters::fparam, shower_extra_parameters::id, shower_extra_parameters::iparam, shower_extra_parameters::nfparam, shower_extra_parameters::niparam, and shower_extra_parameters::weight.

7.33.2.7 int print_camera_layout (IO_BUFFER * iobuf)

Print the layout (pixel positions) of a camera used for converting from photons to photo-electrons in a pixel.

Parameters

iobuf	I/O buffer descriptor

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.33.2.8 int print_photo_electrons (IO_BUFFER * iobuf)

List the the photoelectrons registered in a Cherenkov telescope camera.

Parameters

iobuf	I/O buffer descriptor	

Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

Referenced by print_hess_mc_phot().

7.33.2.9 int print_tel_block (IO_BUFFER * iobuf)

Print a CORSIKA header/trailer block of any type (see mc_tel.h)

Parameters

iobuf	I/O buffer descriptor
-------	-----------------------

Returns

Referenced by main().

7.33.2.10 int print_tel_offset (IO_BUFFER * iobuf)

Print offsets and weights of randomly scattered arrays with respect to shower core.

Parameters

iobuf I/O buffer descriptor

Returns

Referenced by main().

7.33.2.11 int print_tel_photons (IO_BUFFER * iobuf)

Print bunches of Cherenkov photons for one telescope/detector.

The data format may be either the more or less compact one.

Parameters

iobuf	I/O buffer descriptor

Returns

References bunch::ctime, bunch::cy, bunch::lambda, bunch::photons, compact_bunch::photons, bunch::y, and bunch::zem.

Referenced by main(), and print_hess_mc_phot().

7.33.2.12 int print_tel_pos (IO_BUFFER * iobuf)

Print positions of telescopes/detectors within a system or array.

Parameters

iobuf	I/O buffer descriptor
-------	-----------------------

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

Referenced by main().

7.33.2.13 int read_camera_layout (IO_BUFFER * iobuf, int max_pixels, int * itel, int * type, int * pixels, double * xp, double * vp)

Read the layout (pixel positions) of a camera used for converting from photons to photo-electrons in a pixel.

Parameters

iobuf	I/O buffer descriptor
max_pixels	The maximum number of pixels that can be stored in xp, yp.
itel	telescope number
type	camera type (hex/square)
pixels	number of pixels
хр	X positions of pixels
ур	Y position of pixels

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.33.2.14 int read_input_lines (IO_BUFFER * iobuf, struct linked_string * list)

Read a block with several character strings (normally containing the text of the CORSIKA inputs file) into a linked list.

Parameters

iobuf	I/O buffer descriptor
list	starting point of linked list (on first call this should be a link to an empty list, i.e. the first
	element has text=NULL and next=NULL; on additional calls the new lines will be appended.)

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

Referenced by main().

7.33.2.15 int read_photo_electrons (IO_BUFFER * iobuf, int max_pixels, int max_pe, int * array, int * tel, int * npe, int * pixels, int * flags, int * pe_counts, int * tstart, double * t, double * a)

Read the photoelectrons registered in a Cherenkov telescope camera.

iobuf	I/O buffer descriptor
max_pixels	Maximum number of pixels which can be treated
max_pe	Maximum number of photo-electrons
array	Array number
tel	Telescope number
npe	The total number of photo-electrons read.
pixels	Number of pixels read.
flags	Bit 0: amplitudes available, bit 1: includes NSB p.e.
pe_counts	Numbers of photo-electrons in each pixel
tstart	Offsets in 't' at which data for each pixel starts
t	Time of arrival of photons at the camera.
а	Amplitudes of p.e. signals [mean p.e.] (optional, may be NULL).

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

Referenced by read_hess_mc_phot().

7.33.2.16 int read_shower_longitudinal (IO_BUFFER * iobuf, int * event, int * type, double * data, int ndim, int * np, int * nthick, double * thickstep, int max_np)

Read CORSIKA shower longitudinal distributions.

See tellng_() in iact.c for more detailed parameter description.

Parameters

iobuf	I/O buffer descriptor
event	return event number
type	return 1 = particle numbers, 2 = energy, 3 = energy deposits
data	return set of (usually 9) distributions
ndim	maximum number of entries per distribution
np	return number of distributions (usually 9)
nthick	return number of entries actually filled per distribution (is 1 if called without LONGI being
	enabled).
thickstep	return step size in g/cm**2
max_np	maximum number of distributions for which we have space.

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.33.2.17 int read_tel_array_end (IO_BUFFER * iobuf, IO_ITEM_HEADER * ih, int * array)

End reading data for one array of telescopes/detectors.

Parameters

iobuf	I/O buffer descriptor
ih	I/O item header (as opened in begin_write_tel_array())

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.33.2.18 int read_tel_array_head (IO_BUFFER * iobuf, IO_ITEM_HEADER * ih, int * array)

Begin reading data for one array of telescopes/detectors.

Note: this function does not finish reading from the I/O block but after reading of the photons a call to end_read_tel_array() is needed.

Parameters

iobuf	- I/O buffer descriptor
ih	- I/O item header (for item opened here)
array	- Number of array

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.33.2.19 int read_tel_block (IO_BUFFER * iobuf, int type, real * data, int maxlen)

Read a CORSIKA header/trailer block of given type (see mc_tel.h)

Parameters

iobuf	I/O buffer descriptor
type	block type (see mc_tel.h)
data	area for data to be read
maxlen	maximum number of elements to be read

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.33.2.20 int read_tel_offset (IO_BUFFER * iobuf, int max_array, int * narray, double * toff, double * xoff, double * yoff)

Read offsets of randomly scattered arrays with respect to shower core.

Parameters

iobuf	I/O buffer descriptor
max_array	Maximum number of arrays that can be treated
narray	Number of arrays of telescopes/detectors
toff	Time offset (ns, from first interaction to ground)
xoff	X offsets of arrays
yoff	Y offsets of arrays

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

References read_tel_offset_w().

7.33.2.21 int read_tel_offset_w (IO_BUFFER * iobuf, int max_array, int * narray, double * toff, double * xoff, double * yoff, double * weight)

Read offsets and weights of randomly scattered arrays with respect to shower core.

Parameters

iobuf	I/O buffer descriptor
max_array	Maximum number of arrays that can be treated
narray	Number of arrays of telescopes/detectors
toff	Time offset (ns, from first interaction to ground)
xoff	X offsets of arrays
yoff	Y offsets of arrays
weight	Area weight for uniform or importance sampled core offset. For old version data (uniformly
	sampled), 0.0 is returned.

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

Referenced by read tel offset().

7.33.2.22 int read_tel_photons (IO_BUFFER * iobuf, int max_bunches, int * array, int * tel, double * photons, struct bunch * bunches, int * nbunches)

Read bunches of Cherenkov photons for one telescope/detector.

The data format may be either the more or less compact one.

Parameters

iobuf	I/O buffer descriptor
max_bunches	maximum number of bunches that can be treated
array	array number
tel	telescope number
photons	sum of photons (and fractions) in this device
bunches	list of photon bunches
nbunches	number of elements in bunch list

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

References bunch::ctime, bunch::cy, compact_bunch::cy, bunch::lambda, bunch::photons, bunch::y, and bunch::zem.

Referenced by read_hess_mc_phot().

7.33.2.23 int read_tel_pos (IO_BUFFER * iobuf, int max_tel, int * ntel, double * x, double * y, double * z, double * r)

Read positions of telescopes/detectors within a system or array.

iobuf	I/O buffer descriptor
max_tel	maximum number of telescopes allowed
ntel	number of telescopes/detectors
Х	X positions
У	Y positions

Z	Z positions
r	radius of spheres including the whole devices

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.33.2.24 int write_camera_layout (IO_BUFFER * iobuf, int itel, int type, int pixels, double * xp, double * yp)

Write the layout (pixel positions) of a camera used for converting from photons to photo-electrons in a pixel.

Parameters

iobuf	I/O buffer descriptor
itel	telescope number
type	camera type (hex/square)
pixels	number of pixels
хр	X positions of pixels
ур	Y position of pixels

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.33.2.25 int write_input_lines (IO_BUFFER * iobuf, struct linked_string * list)

Write a linked list of character strings (normally containing the text of the CORSIKA inputs file) as a dedicated block.

Parameters

iobuf	I/O buffer descriptor
list	starting point of linked list

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.33.2.26 int write_photo_electrons (IO_BUFFER * iobuf, int array, int tel, int npe, int flags, int pixels, int * pe_counts, int * tstart, double * t, double * a)

Write the photo-electrons registered in a Cherenkov telescope camera.

iobuf	I/O buffer descriptor
array	array number
tel	telescope number
npe	Total number of photo-electrons in the camera.
pixels	No. of pixels to be written
flags	Bit 0: amplitudes available, bit 1: includes NSB p.e.

pe_counts	Numbers of photo-electrons in each pixel
tstart	Offsets in 't' at which data for each pixel starts
t	Time of arrival of photons at the camera.
а	Amplitudes of p.e. signals [mean p.e.] (optional, may be NULL).

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.33.2.27 int write_shower_longitudinal (IO_BUFFER * iobuf, int event, int type, double * data, int ndim, int np, int nthick, double thickstep)

Write CORSIKA shower longitudinal distributions.

See tellng_() in iact.c for more detailed parameter description.

Parameters

iobuf	I/O buffer descriptor
event	event number
type	1 = particle numbers, 2 = energy, 3 = energy deposits
data	set of (usually 9) distributions
ndim	maximum number of entries per distribution
np	number of distributions (usually 9)
nthick	number of entries actually filled per distribution (is 1 if called without LONGI being enabled).
thickstep	step size in g/cm**2

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.33.2.28 int write_tel_array_end (IO_BUFFER * iobuf, IO_ITEM_HEADER * ih, int array)

End writing data for one array of telescopes/detectors.

Parameters

iobuf	I/O buffer descriptor
ih	I/O item header (as opened in begin_write_tel_array())

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.33.2.29 int write_tel_array_head (IO_BUFFER * iobuf, IO_ITEM_HEADER * ih, int array)

Begin writing data for one array of telescopes/detectors.

Note: this function does not finish writing to the I/O block but after writing of the photons a call to end_write_tel_array() is needed.

iobuf	I/O buffer descriptor
ih	I/O item header (for item opened here)
array	Number of array

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.33.2.30 int write_tel_block (IO_BUFFER * iobuf, int type, int num, real * data, int len)

Write a CORSIKA block as given type number (see mc_tel.h).

Parameters

iobuf	I/O buffer descriptor
type	block type (see mc_tel.h)
num	Run or event number depending on type
data	Data as passed from CORSIKA
len	Number of elements to be written

Returns

0 (OK), -1, -2, -3 (error, as usual in eventio)

7.33.2.31 int write_tel_compact_photons (IO_BUFFER * iobuf, int array, int tel, double photons, struct compact_bunch * cbunches, int nbunches, int ext_bunches, char * ext_fname)

Write all the photon bunches for one telescope to an I/O buffer.

Usually, calls to this function for each telescope in an array should be enclosed within calls to begin_write_tel_array() and end_write_tel_array(). This routine writes the more compact format (16 bytes per bunch). The more compact format should usually be used to save memory and disk space.

Parameters

iobuf	I/O buffer descriptor
array	array number
tel	telescope number
photons	sum of photons (and fractions) in this device
cbunches	list of photon bunches
nbunches	number of elements in bunch list
ext_bunches	number of elements in external file
ext_fname	name of external (temporary) file

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

References compact_bunch::ctime, compact_bunch::cy, fileclose(), fileopen(), compact_bunch::lambda, compact_bunch::log_zem, compact_bunch::photons, and compact_bunch::y.

7.33.2.32 int write_tel_offset (IO_BUFFER * iobuf, int narray, double toff, double * xoff, double * yoff)

Write offsets of randomly scattered arrays with respect to shower core.

iobuf	I/O buffer descriptor
narray	Number of arrays of telescopes/detectors
toff	Time offset (ns, from first interaction to ground)
xoff	X offsets of arrays
yoff	Y offsets of arrays

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

References write tel offset w().

7.33.2.33 int write_tel_offset_w (IO_BUFFER * iobuf, int narray, double * toff, double * xoff, double * yoff, double * weight)

Write offsets and weights of randomly scattered arrays with respect to shower core.

With respect to the backwards-compatible non-weights version write_tel_offset(), this version adds a weight to each offset position which should be normalized in such a way that with uniform sampling it should be the area over which showers are thrown divided by the number of array in each shower. With importance sampling the same relation should hold on average. So in either case, the average sum of weights for the different offsets in one shower equals just the area over which cores are randomized. This leaves the possibility to change the number of offsets from shower to shower.

Parameters

iobuf	I/O buffer descriptor
narray	Number of arrays of telescopes/detectors
toff	Time offset (ns, from first interaction to ground)
xoff	X offsets of arrays
yoff	Y offsets of arrays
weight	Area weight for uniform or importance sampled core offset.

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

Referenced by write tel offset().

7.33.2.34 int write_tel_photons (IO_BUFFER * iobuf, int array, int tel, double photons, struct bunch * bunches, int nbunches, int ext_bunches, char * ext_fname)

Write all the photon bunches for one telescope to an I/O buffer.

Usually, calls to this function for each telescope in an array should be enclosed within calls to begin_write_tel_array() and end_write_tel_array(). This routine writes the less compact format (32 bytes per bunch).

Parameters

iobuf	I/O buffer descriptor
array	array number
tel	telescope number
photons	sum of photons (and fractions) in this device
bunches	list of photon bunches
nbunches	number of elements in bunch list
ext_bunches	number of elements in external file
ext_fname	name of external (temporary) file

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

References bunch::ctime, bunch::cy, fileclose(), fileopen(), bunch::lambda, bunch::photons, bunch::y, and bunch::zem.

7.33.2.35 int write_tel_pos (IO_BUFFER * iobuf, int ntel, double * x, double * y, double * z, double * r)

Write positions of telescopes/detectors within a system or array.

Parameters

iobuf	I/O buffer descriptor
ntel	number of telescopes/detectors
X	X positions
у	Y positions
Z	Z positions
r	radius of spheres including the whole devices

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.33.3 Variable Documentation

7.33.3.1 struct shower_extra_parameters private_shower_extra_parameters [static]

There is one global (more precisely: static) block of extra shower parameters as, for example, used in the CORSIKA IACT interface.


Get a pointer to this block.

7.34 io_trgmask.c File Reference

EventIO plus helper functions for trigger type bit patterns extracted from sim_telarray log files (only relevant for simulations with multiple trigger types using sim_telarray versions before mid-2013).

```
#include "initial.h"
#include "io_basic.h"
#include "fileopen.h"
#include "io_trgmask.h"
```

Include dependency graph for io_trgmask.c:



Macros

• #define TMS_ALLOCS 100

Functions

int trgmask_scan_log (struct trgmask_set *tms, const char *fname)
 Scan a sim_telarray log file for lines related to trigger type mask bit patterns.

• int write_trgmask (IO_BUFFER *iobuf, struct trgmask_set *tms)

Write the accumulated trigger mask bit patterns as an I/O block.

• int print_trgmask (IO_BUFFER *iobuf)

Print the trigger mask bit patterns contained in an I/O block.

int read_trgmask (IO_BUFFER *iobuf, struct trgmask_set *tms)

Read the trigger mask bit patterns contained in an I/O block.

int trgmask fill hashed (struct trgmask set *tms, struct trgmask hash set *ths)

Fill an array of linked lists of trgmask entries, suitable for hashing.

struct trgmask_entry * find_trgmask (struct trgmask_hash_set *ths, long event, int tel_id)

Find the trgmask entry for a given event and telescope in the hashed list.

• void print hashed trgmasks (struct trgmask hash set *ths)

Print the collected trgmask entries in the order as hashed.

7.34.1 Detailed Description

EventIO plus helper functions for trigger type bit patterns extracted from sim_telarray log files (only relevant for simulations with multiple trigger types using sim_telarray versions before mid-2013).

7.34.2 Function Documentation

7.34.2.1 struct trgmask entry* find trgmask (struct trgmask hash set * ths, long event, int tel id)

Find the trgmask entry for a given event and telescope in the hashed list.

Hash collisions are handled by linear search through the linked list at each hash entry.

Parameters

	ths	The trgmask hash set.
ſ	event	The event number in the search.
ľ	tel_id	The telescope ID in the search.

Returns

A pointer to the trgmask entry searched for, or NULL for not found.

References trgmask_entry::event, trgmask_hash_set::h_e, trgmask_entry::next, and trgmask_entry::tel_id.

7.34.2.2 void print_hashed_trgmasks (struct trgmask hash set * ths)

Print the collected trgmask entries in the order as hashed.

Referenced by main(), and merge data from io block().

Also show the maximum number of colliding entries under one hash value.

References trgmask_entry::event, trgmask_hash_set::h_e, trgmask_entry::next, trgmask_entry::tel_id, and trgmask_entry::trg_mask.

7.34.2.3 int trgmask_fill_hashed (struct trgmask_set * tms, struct trgmask_hash_set * ths)

Fill an array of linked lists of trgmask entries, suitable for hashing.

Hash collisions are handled by linear search through the linked list at each hash entry.

References trgmask_entry::event, trgmask_hash_set::h_e, trgmask_entry::next, and trgmask_entry::tel_id.

Referenced by check_autoload_trgmask(), main(), and merge_data_from_io_block().

7.34.2.4 int trgmask_scan_log (struct trgmask_set * tms, const char * fname)

Scan a sim_telarray log file for lines related to trigger type mask bit patterns.

Parameters

tms	The trigger mask structure into which results should be filled in.
fname	The name of the log file to be opened.

Returns


0 (OK), -1 (invalid parameters or file not found), -2 (allocation error, partially filled)

References trgmask_entry::event, fileclose(), fileopen(), trgmask_entry::next, trgmask_entry::tel_id, and trgmask_entry::trg_mask.

7.35 io_trgmask.h File Reference

EventIO plus helper functions for trigger type bit patterns extracted from sim_telarray log files (only relevant for simulations with multiple trigger types using sim_telarray versions before mid-2013).

This graph shows which files directly or indirectly include this file:



Data Structures

- struct trgmask_entry
- struct trgmask set
- struct trgmask_hash_set

Macros

- #define IO_TYPE_HESS_XTRGMASK 2090
 - Extra (or external not in normal data file) trigger mask data block type.
- #define TRGMASK PRIME 15269
- #define TRGMASK_HASH(ev, ti) (((ti)*10000+(ev))%TRGMASK_PRIME)

Functions

- int trgmask_scan_log (struct trgmask_set *tms, const char *fname)
 - Scan a sim_telarray log file for lines related to trigger type mask bit patterns.
- int write trgmask (IO BUFFER *iobuf, struct trgmask set *tms)
 - Write the accumulated trigger mask bit patterns as an I/O block.
- int print_trgmask (IO_BUFFER *iobuf)
 - Print the trigger mask bit patterns contained in an I/O block.
- int read trgmask (IO BUFFER *iobuf, struct trgmask set *tms)
 - Read the trigger mask bit patterns contained in an I/O block.
- int trgmask_fill_hashed (struct trgmask_set *tms, struct trgmask_hash_set *ths)

Fill an array of linked lists of trgmask entries, suitable for hashing.

struct trgmask_entry * find_trgmask (struct trgmask_hash_set *ths, long event, int tel_id)

Find the trgmask entry for a given event and telescope in the hashed list.

void print hashed trgmasks (struct trgmask hash set *ths)

Print the collected trgmask entries in the order as hashed.

7.35.1 Detailed Description

EventIO plus helper functions for trigger type bit patterns extracted from sim_telarray log files (only relevant for simulations with multiple trigger types using sim telarray versions before mid-2013).

7.35.2 Macro Definition Documentation

7.35.2.1 #define IO_TYPE_HESS_XTRGMASK 2090

Extra (or external - not in normal data file) trigger mask data block type.

Referenced by main(), merge data from io block(), print trgmask(), read trgmask(), and write trgmask().

7.35.3 Function Documentation

7.35.3.1 struct trgmask_entry* find_trgmask(struct trgmask_hash_set * ths, long event, int tel_id)

Find the trgmask entry for a given event and telescope in the hashed list.

Hash collisions are handled by linear search through the linked list at each hash entry.

Parameters

ths	The trgmask hash set.
event	The event number in the search.
tel_id	The telescope ID in the search.

Returns

A pointer to the trgmask entry searched for, or NULL for not found.

References trgmask_entry::event, trgmask_hash_set::h_e, trgmask_entry::next, and trgmask_entry::tel_id.

Referenced by main(), and merge_data_from_io_block().

7.35.3.2 void print_hashed_trgmasks (struct trgmask hash set * ths)

Print the collected trgmask entries in the order as hashed.

Also show the maximum number of colliding entries under one hash value.

References trgmask_entry::event, trgmask_hash_set::h_e, trgmask_entry::next, trgmask_entry::tel_id, and trgmask_entry::trg_mask.

7.35.3.3 int trgmask_fill_hashed (struct trgmask_set * tms, struct trgmask_hash_set * ths)

Fill an array of linked lists of trgmask entries, suitable for hashing.

Hash collisions are handled by linear search through the linked list at each hash entry.

References trgmask_entry::event, trgmask_hash_set::h_e, trgmask_entry::next, and trgmask_entry::tel_id.

Referenced by check_autoload_trgmask(), main(), and merge_data_from_io_block().

7.35.3.4 int trgmask_scan_log (struct trgmask_set * tms, const char * fname)

Scan a sim_telarray log file for lines related to trigger type mask bit patterns.

Parameters

tms	The trigger mask structure into which results should be filled in.
fname	The name of the log file to be opened.

Returns

0 (OK), -1 (invalid parameters or file not found), -2 (allocation error, partially filled)


References trgmask_entry::event, fileclose(), fileopen(), trgmask_entry::next, trgmask_entry::tel_id, and trgmask_entry::trg_mask.

7.36 list_histograms.c File Reference

Utility program for listing histograms.

```
#include "initial.h"
#include "histogram.h"
#include "io_basic.h"
#include "io_histogram.h"
#include "fileopen.h"
```

Include dependency graph for list_histograms.c:



Functions

• int main (int argc, char **argv)

Main program.

7.36.1 Detailed Description

Utility program for listing histograms.

```
Syntax: list_histograms [ input_file ... ]
```

The default input file name is 'testpattern.hdata'. The histograms may be within multiple I/O blocks of the input file.

Author

Konrad Bernloehr

Date

```
CVS $Date: 2013/10/21 12:53:31 $
```


Version

```
CVS $Revision: 1.2 $
```


7.37 mc_tel.h File Reference

Definitions and structures for CORSIKA Cherenkov light interface.

```
#include "io_basic.h"
Include dependency graph for mc_tel.h:
```



This graph shows which files directly or indirectly include this file:



Data Structures

· struct bunch

Photons collected in bunches of identical direction, position, time, and wavelength.

struct compact_bunch

The compact_bunch struct is equivalent to the bunch struct except that we try to use less memory.

struct photo_electron

A photo-electron produced by a photon hitting a pixel.

· struct linked_string

The linked_string is mainly used to keep CORSIKA input.

· struct shower extra parameters

Extra shower parameters of unspecified nature.

Macros

- #define MC_TEL_LOADED 2
- #define IO TYPE MC BASE 1200
- #define IO TYPE MC RUNH (IO TYPE MC BASE+0)
- #define IO TYPE MC TELPOS (IO TYPE MC BASE+1)
- #define IO TYPE MC EVTH (IO TYPE MC BASE+2)
- #define IO_TYPE_MC_TELOFF (IO_TYPE_MC_BASE+3)
- #define IO_TYPE_MC_TELARRAY (IO_TYPE_MC_BASE+4)
- #define IO_TYPE_MC_PHOTONS (IO_TYPE_MC_BASE+5)
- #define IO_TYPE_MC_LAYOUT (IO_TYPE_MC_BASE+6)
- #define IO TYPE MC TRIGTIME (IO TYPE MC BASE+7)
- #define IO_TYPE_MC_PE (IO_TYPE_MC_BASE+8)
- #define IO_TYPE_MC_EVTE (IO_TYPE_MC_BASE+9)
- #define IO TYPE MC RUNE (IO TYPE MC BASE+10)
- #define IO TYPE MC LONGI (IO TYPE MC BASE+11)
- #define IO TYPE MC INPUTCFG (IO TYPE MC BASE+12)
- #define IO_TYPE_MC_TELARRAY_HEAD (IO_TYPE_MC_BASE+13)
- #define IO TYPE MC TELARRAY END (IO TYPE MC BASE+14)
- #define IO_TYPE_MC_EXTRA_PARAM (IO_TYPE_MC_BASE+15)

Typedefs

- · typedef float real
- typedef short INT16
- · typedef unsigned short UINT16
- typedef int INT32
- typedef unsigned int UINT32

Functions

int write_tel_block (IO_BUFFER *iobuf, int type, int num, real *data, int len)

Write a CORSIKA block as given type number (see mc_tel.h).

• int read_tel_block (IO_BUFFER *iobuf, int type, real *data, int maxlen)

Read a CORSIKA header/trailer block of given type (see mc_tel.h)

• int print tel block (IO BUFFER *iobuf)

Print a CORSIKA header/trailer block of any type (see mc_tel.h)

int write_input_lines (IO_BUFFER *iobuf, struct linked_string *list)

Write a linked list of character strings (normally containing the text of the CORSIKA inputs file) as a dedicated block.

int read_input_lines (IO_BUFFER *iobuf, struct linked_string *list)

Read a block with several character strings (normally containing the text of the CORSIKA inputs file) into a linked list.

• int write_tel_pos (IO_BUFFER *iobuf, int ntel, double *x, double *y, double *z, double *r)

Write positions of telescopes/detectors within a system or array.

• int read_tel_pos (IO_BUFFER *iobuf, int max_tel, int *ntel, double *x, double *y, double *z, double *r)

Read positions of telescopes/detectors within a system or array.

int print_tel_pos (IO_BUFFER *iobuf)

Print positions of telescopes/detectors within a system or array.

int write_tel_offset (IO_BUFFER *iobuf, int narray, double toff, double *xoff, double *yoff)

Write offsets of randomly scattered arrays with respect to shower core.

- int write_tel_offset_w (IO_BUFFER *iobuf, int narray, double toff, double *xoff, double *yoff, double *weight)

 Write offsets and weights of randomly scattered arrays with respect to shower core.
- int read_tel_offset (IO_BUFFER *iobuf, int max_array, int *narray, double *toff, double *xoff, double *yoff)

 Read offsets of randomly scattered arrays with respect to shower core.
- int read_tel_offset_w (IO_BUFFER *iobuf, int max_array, int *narray, double *toff, double *xoff, double *yoff, double *weight)

Read offsets and weights of randomly scattered arrays with respect to shower core.

int print_tel_offset (IO_BUFFER *iobuf)

Print offsets and weights of randomly scattered arrays with respect to shower core.

int begin write tel array (IO BUFFER *iobuf, IO ITEM HEADER *ih, int array)

Begin writing data for one array of telescopes/detectors.

int end_write_tel_array (IO_BUFFER *iobuf, IO_ITEM_HEADER *ih)

End writing data for one array of telescopes/detectors.

• int begin_read_tel_array (IO_BUFFER *iobuf, IO_ITEM_HEADER *ih, int *array)

Begin reading data for one array of telescopes/detectors.

int end_read_tel_array (IO_BUFFER *iobuf, IO_ITEM_HEADER *ih)

End reading data for one array of telescopes/detectors.

• int write tel array head (IO BUFFER *iobuf, IO ITEM HEADER *ih, int array)

Begin writing data for one array of telescopes/detectors.

• int write_tel_array_end (IO_BUFFER *iobuf, IO_ITEM_HEADER *ih, int array)

End writing data for one array of telescopes/detectors.

• int read_tel_array_head (IO_BUFFER *iobuf, IO_ITEM_HEADER *ih, int *array)

Begin reading data for one array of telescopes/detectors.

• int read_tel_array_end (IO_BUFFER *iobuf, IO_ITEM_HEADER *ih, int *array)

End reading data for one array of telescopes/detectors.

• int write_tel_photons (IO_BUFFER *iobuf, int array, int tel, double photons, struct bunch *bunches, int nbunches, int ext_bunches, char *ext_fname)

Write all the photon bunches for one telescope to an I/O buffer.

• int write_tel_compact_photons (IO_BUFFER *iobuf, int array, int tel, double photons, struct compact_bunch *cbunches, int nbunches, int ext_bunches, char *ext_fname)

Write all the photon bunches for one telescope to an I/O buffer.

• int read_tel_photons (IO_BUFFER *iobuf, int max_bunches, int *array, int *tel, double *photons, struct bunch *bunches, int *nbunches)

Read bunches of Cherenkov photons for one telescope/detector.

int print_tel_photons (IO_BUFFER *iobuf)

Print bunches of Cherenkov photons for one telescope/detector.

• int write_shower_longitudinal (IO_BUFFER *iobuf, int event, int type, double *data, int ndim, int np, int nthick, double thickstep)

Write CORSIKA shower longitudinal distributions.

• int read_shower_longitudinal (IO_BUFFER *iobuf, int *event, int *type, double *data, int ndim, int *np, int *nthick, double *thickstep, int max np)

Read CORSIKA shower longitudinal distributions.

• int write camera layout (IO BUFFER *iobuf, int itel, int type, int pixels, double *xp, double *yp)

Write the layout (pixel positions) of a camera used for converting from photons to photo-electrons in a pixel.

int read_camera_layout (IO_BUFFER *iobuf, int max_pixels, int *itel, int *type, int *pixels, double *xp, double *xp)

Read the layout (pixel positions) of a camera used for converting from photons to photo-electrons in a pixel.

int print_camera_layout (IO_BUFFER *iobuf)

Print the layout (pixel positions) of a camera used for converting from photons to photo-electrons in a pixel.

• int write_photo_electrons (IO_BUFFER *iobuf, int array, int tel, int npe, int pixels, int flags, int *pe_counts, int *tstart, double *t, double *a)

Write the photo-electrons registered in a Cherenkov telescope camera.

• int read_photo_electrons (IO_BUFFER *iobuf, int max_pixel, int max_pe, int *array, int *tel, int *npe, int *pixels, int *flags, int *pe_counts, int *tstart, double *t, double *a)

Read the photoelectrons registered in a Cherenkov telescope camera.

• int print_photo_electrons (IO_BUFFER *iobuf)

List the the photoelectrons registered in a Cherenkov telescope camera.

- int write shower extra parameters (IO BUFFER *iobuf, struct shower extra parameters *ep)
- int read_shower_extra_parameters (IO_BUFFER *iobuf, struct shower_extra_parameters *ep)
- int print_shower_extra_parameters (IO_BUFFER *iobuf)
- int init_shower_extra_parameters (struct shower_extra_parameters *ep, size_t ni_max, size_t nf_max)

Initialize, resize, clear shower extra parameters.

int clear_shower_extra_parameters (struct shower_extra_parameters *ep)

Similar to init_shower_extra_parameters() but without any attempts to re-allocate or resize buffers.

struct shower extra parameters * get shower extra parameters (void)

7.37.1 Detailed Description

Definitions and structures for CORSIKA Cherenkov light interface. This file contains definitions of data structures and of function prototypes as needed for the Cherenkov light extraction interfaced to the modified CORSIKA code.

Author

Konrad Bernloehr

Date

```
1997 to 2010
```

```
CVS $Date: 2014/02/20 10:53:06 $
```

Version

```
CVS $Revision: 1.15 $
```

7.37.2 Function Documentation

```
7.37.2.1 int begin_read_tel_array ( IO_BUFFER * iobuf, IO_ITEM_HEADER * ih, int * array )
```

Begin reading data for one array of telescopes/detectors.

Note: this function does not finish reading from the I/O block but after reading of the photons a call to end_read_tel_array() is needed.

Parameters

iobuf	- I/O buffer descriptor
ih	- I/O item header (for item opened here)
array	- Number of array

Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

Referenced by print_hess_mc_phot(), and read_hess_mc_phot().

7.37.2.2 int begin_write_tel_array (IO_BUFFER * iobuf, IO_ITEM_HEADER * ih, int array)

Begin writing data for one array of telescopes/detectors.

Note: this function does not finish writing to the I/O block but after writing of the photons a call to end_write_tel_array() is needed.

Parameters

iobuf	I/O buffer descriptor
ih	I/O item header (for item opened here)
array	Number of array

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.37.2.3 int clear_shower_extra_parameters (struct shower_extra_parameters * ep)

Similar to init_shower_extra_parameters() but without any attempts to re-allocate or resize buffers.

Just clear contents.

Parameters

ep	Pointer to parameter block. A NULL value indicates that the static block is meant.

References shower_extra_parameters::fparam, shower_extra_parameters::id, shower_extra_parameters::iparam, shower_extra_parameters::is_set, shower_extra_parameters::nfparam, shower_extra_parameters::niparam, and shower_extra_parameters::weight.

Referenced by read hess mc shower().

7.37.2.4 int end_read_tel_array (IO_BUFFER * iobuf, IO_ITEM_HEADER * ih)

End reading data for one array of telescopes/detectors.

Parameters

iobuf	I/O buffer descriptor
ih	I/O item header (as opened in begin_write_tel_array())

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

Referenced by print_hess_mc_phot(), and read_hess_mc_phot().

7.37.2.5 int end_write_tel_array (IO_BUFFER * iobuf, IO_ITEM_HEADER * ih)

End writing data for one array of telescopes/detectors.

Parameters

iobuf	I/O buffer descriptor
ih	I/O item header (as opened in begin_write_tel_array())

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.37.2.6 int init_shower_extra_parameters (struct shower_extra_parameters * ep, size_t ni_max, size_t nf_max) Initialize, resize, clear shower extra parameters.

Parameters

ер	Pointer to parameter block. A NULL value indicates that the static block is meant.
ni_max	The number of integer parameters to be used.
nf_max	The number of float parameters to be used.

References shower_extra_parameters::fparam, shower_extra_parameters::id, shower_extra_parameters::iparam, shower_extra_parameters::nfparam, shower_extra_parameters::niparam, and shower_extra_parameters::weight.

7.37.2.7 int print_camera_layout (IO_BUFFER * iobuf)

Print the layout (pixel positions) of a camera used for converting from photons to photo-electrons in a pixel.

Parameters

iobuf	I/O buffer descriptor

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.37.2.8 int print_photo_electrons (IO_BUFFER * iobuf)

List the the photoelectrons registered in a Cherenkov telescope camera.

Parameters

iobuf	I/O buffer descriptor

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

Referenced by print_hess_mc_phot().

7.37.2.9 int print_tel_block (IO_BUFFER * iobuf)

Print a CORSIKA header/trailer block of any type (see mc_tel.h)

Parameters

iobuf	I/O buffer descriptor

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

Referenced by main().

7.37.2.10 int print_tel_offset (IO_BUFFER * iobuf)

Print offsets and weights of randomly scattered arrays with respect to shower core.

Parameters

iobuf	I/O buffer descriptor
-------	-----------------------

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

Referenced by main().

7.37.2.11 int print_tel_photons (IO_BUFFER * iobuf)

Print bunches of Cherenkov photons for one telescope/detector.

The data format may be either the more or less compact one.

Parameters

iobuf	I/O buffer descriptor

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

References bunch::ctime, bunch::cy, bunch::lambda, bunch::photons, compact_bunch::photons, bunch::y, and bunch::zem.

Referenced by main(), and print hess mc phot().

7.37.2.12 int print_tel_pos (IO_BUFFER * iobuf)

Print positions of telescopes/detectors within a system or array.

Parameters

iobuf	I/O buffer descriptor

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

Referenced by main().

7.37.2.13 int read_camera_layout (IO_BUFFER * iobuf, int max_pixels, int * itel, int * type, int * pixels, double * xp, double * yp)

Read the layout (pixel positions) of a camera used for converting from photons to photo-electrons in a pixel.

iobuf	I/O buffer descriptor
max_pixels	The maximum number of pixels that can be stored in xp, yp.
itel	telescope number
type	camera type (hex/square)

pixels	number of pixels
хр	X positions of pixels
ур	Y position of pixels

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.37.2.14 int read_input_lines (IO_BUFFER * iobuf, struct linked_string * list)

Read a block with several character strings (normally containing the text of the CORSIKA inputs file) into a linked list.

Parameters

iobuf	I/O buffer descriptor
list	starting point of linked list (on first call this should be a link to an empty list, i.e. the first
	element has text=NULL and next=NULL; on additional calls the new lines will be appended.)

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

Referenced by main().

7.37.2.15 int read_photo_electrons (IO_BUFFER * iobuf, int max_pixels, int max_pe, int * array, int * tel, int * npe, int * pixels, int * flags, int * pe_counts, int * tstart, double * t, double * a)

Read the photoelectrons registered in a Cherenkov telescope camera.

Parameters

iobuf	I/O buffer descriptor
max_pixels	Maximum number of pixels which can be treated
max_pe	Maximum number of photo-electrons
array	Array number
tel	Telescope number
npe	The total number of photo-electrons read.
pixels	Number of pixels read.
flags	Bit 0: amplitudes available, bit 1: includes NSB p.e.
pe_counts	Numbers of photo-electrons in each pixel
tstart	Offsets in 't' at which data for each pixel starts
t	Time of arrival of photons at the camera.
а	Amplitudes of p.e. signals [mean p.e.] (optional, may be NULL).

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

Referenced by read_hess_mc_phot().

7.37.2.16 int read_shower_longitudinal (IO_BUFFER * iobuf, int * event, int * type, double * data, int ndim, int * np, int * nthick, double * thickstep, int max_np)

Read CORSIKA shower longitudinal distributions.

See tellng_() in iact.c for more detailed parameter description.

Parameters

iobuf	I/O buffer descriptor
event	return event number
type	return 1 = particle numbers, 2 = energy, 3 = energy deposits
data	return set of (usually 9) distributions
ndim	maximum number of entries per distribution
np	return number of distributions (usually 9)
nthick	return number of entries actually filled per distribution (is 1 if called without LONGI being
	enabled).
thickstep	return step size in g/cm**2
max_np	maximum number of distributions for which we have space.

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.37.2.17 int read_tel_array_end (IO_BUFFER * iobuf, IO_ITEM_HEADER * ih, int * array)

End reading data for one array of telescopes/detectors.

Parameters

iobuf	I/O buffer descriptor
ih	I/O item header (as opened in begin_write_tel_array())

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.37.2.18 int read_tel_array_head (IO_BUFFER * iobuf, IO_ITEM_HEADER * ih, int * array)

Begin reading data for one array of telescopes/detectors.

Note: this function does not finish reading from the I/O block but after reading of the photons a call to end_read_tel_array() is needed.

Parameters

iobuf	- I/O buffer descriptor
ih	- I/O item header (for item opened here)
array	- Number of array

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.37.2.19 int read_tel_block (IO_BUFFER * iobuf, int type, real * data, int maxlen)

Read a CORSIKA header/trailer block of given type (see mc tel.h)

Parameters

raiailleteis

iobuf	I/O buffer descriptor
type	block type (see mc_tel.h)
data	area for data to be read
maxlen	maximum number of elements to be read

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.37.2.20 int read_tel_offset (IO_BUFFER * iobuf, int max_array, int * narray, double * toff, double * xoff, double * yoff)

Read offsets of randomly scattered arrays with respect to shower core.

Parameters

iobuf	I/O buffer descriptor
max_array	Maximum number of arrays that can be treated
narray	Number of arrays of telescopes/detectors
toff	Time offset (ns, from first interaction to ground)
xoff	X offsets of arrays
yoff	Y offsets of arrays

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

References read_tel_offset_w().

7.37.2.21 int read_tel_offset_w (IO_BUFFER * iobuf, int max_array, int * narray, double * toff, double * xoff, double * yoff, double * weight)

Read offsets and weights of randomly scattered arrays with respect to shower core.

Parameters

iobuf	I/O buffer descriptor
max_array	Maximum number of arrays that can be treated
narray	Number of arrays of telescopes/detectors
toff	Time offset (ns, from first interaction to ground)
xoff	X offsets of arrays
yoff	Y offsets of arrays
weight	Area weight for uniform or importance sampled core offset. For old version data (uniformly
	sampled), 0.0 is returned.

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

Referenced by read_tel_offset().

7.37.2.22 int read_tel_photons (IO_BUFFER * iobuf, int max_bunches, int * array, int * tel, double * photons, struct bunch * bunches, int * nbunches)

Read bunches of Cherenkov photons for one telescope/detector.

The data format may be either the more or less compact one.

Parameters

iobuf	I/O buffer descriptor
max_bunches	maximum number of bunches that can be treated
array	array number
tel	telescope number
photons	sum of photons (and fractions) in this device
bunches	list of photon bunches
nbunches	number of elements in bunch list

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

References bunch::ctime, bunch::cy, compact_bunch::cy, bunch::lambda, bunch::photons, bunch::y, and bunch::zem.

Referenced by read_hess_mc_phot().

7.37.2.23 int read_tel_pos (IO_BUFFER * iobuf, int max_tel, int * ntel, double * x, double * y, double * z, double * r)

Read positions of telescopes/detectors within a system or array.

Parameters

iobuf	I/O buffer descriptor
max_tel	maximum number of telescopes allowed
ntel	number of telescopes/detectors
Х	X positions
У	Y positions
Z	Z positions
r	radius of spheres including the whole devices

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.37.2.24 int write_camera_layout (IO_BUFFER * iobuf, int itel, int type, int pixels, double * xp, double * yp)

Write the layout (pixel positions) of a camera used for converting from photons to photo-electrons in a pixel.

Parameters

iobuf	I/O buffer descriptor
itel	telescope number
type	camera type (hex/square)
pixels	number of pixels
хр	X positions of pixels
ур	Y position of pixels

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.37.2.25 int write_input_lines (IO_BUFFER * iobuf, struct linked_string * list)

Write a linked list of character strings (normally containing the text of the CORSIKA inputs file) as a dedicated block.

Parameters

iobuf	I/O buffer descriptor
list	starting point of linked list

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.37.2.26 int write_photo_electrons (IO_BUFFER * iobuf, int array, int tel, int npe, int flags, int pixels, int * pe_counts, int * tstart, double * t, double * a)

Write the photo-electrons registered in a Cherenkov telescope camera.

Parameters

iobuf	I/O buffer descriptor
array	array number
tel	telescope number
npe	Total number of photo-electrons in the camera.
pixels	No. of pixels to be written
flags	Bit 0: amplitudes available, bit 1: includes NSB p.e.
pe_counts	Numbers of photo-electrons in each pixel
tstart	Offsets in 't' at which data for each pixel starts
t	Time of arrival of photons at the camera.
а	Amplitudes of p.e. signals [mean p.e.] (optional, may be NULL).

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.37.2.27 int write_shower_longitudinal (IO_BUFFER * iobuf, int event, int type, double * data, int ndim, int np, int nthick, double thickstep)

Write CORSIKA shower longitudinal distributions.

See tellng_() in iact.c for more detailed parameter description.

Parameters

iobuf	I/O buffer descriptor
event	event number
type	1 = particle numbers, 2 = energy, 3 = energy deposits
data	set of (usually 9) distributions
ndim	maximum number of entries per distribution
np	number of distributions (usually 9)
nthick	number of entries actually filled per distribution (is 1 if called without LONGI being enabled).
thickstep	step size in g/cm**2

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.37.2.28 int write_tel_array_end (IO_BUFFER * iobuf, IO_ITEM_HEADER * ih, int array)

End writing data for one array of telescopes/detectors.

Parameters

iobuf	I/O buffer descriptor
ih	I/O item header (as opened in begin_write_tel_array())

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.37.2.29 int write_tel_array_head (IO_BUFFER * iobuf, IO_ITEM_HEADER * ih, int array)

Begin writing data for one array of telescopes/detectors.

Note: this function does not finish writing to the I/O block but after writing of the photons a call to end_write_tel_array() is needed.

Parameters

iobuf	I/O buffer descriptor
ih	I/O item header (for item opened here)
array	Number of array

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.37.2.30 int write_tel_block (IO_BUFFER * iobuf, int type, int num, real * data, int len)

Write a CORSIKA block as given type number (see mc_tel.h).

Parameters

iobuf	I/O buffer descriptor
type	block type (see mc_tel.h)
num	Run or event number depending on type
data	Data as passed from CORSIKA
len	Number of elements to be written

Returns

0 (OK), -1, -2, -3 (error, as usual in eventio)

7.37.2.31 int write_tel_compact_photons (IO_BUFFER * iobuf, int array, int tel, double photons, struct compact_bunch * cbunches, int nbunches, int ext_bunches, char * ext_fname)

Write all the photon bunches for one telescope to an I/O buffer.

Usually, calls to this function for each telescope in an array should be enclosed within calls to begin_write_tel_array() and end-write_tel_array(). This routine writes the more compact format (16 bytes per bunch). The more compact format should usually be used to save memory and disk space.

Parameters 4 8 1	Pa	ra	m	e	te	rs
------------------	----	----	---	---	----	----

iobuf	I/O buffer descriptor
array	array number
tel	telescope number
photons	sum of photons (and fractions) in this device
cbunches	list of photon bunches
nbunches	number of elements in bunch list
ext_bunches	number of elements in external file
ext_fname	name of external (temporary) file

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

References compact_bunch::ctime, compact_bunch::cy, fileclose(), fileopen(), compact_bunch::lambda, compact_bunch::log_zem, compact_bunch::photons, and compact_bunch::y.

7.37.2.32 int write_tel_offset (IO_BUFFER * iobuf, int narray, double toff, double * xoff, double * yoff)

Write offsets of randomly scattered arrays with respect to shower core.

Parameters

iobuf	I/O buffer descriptor
narray	Number of arrays of telescopes/detectors
toff	Time offset (ns, from first interaction to ground)
xoff	X offsets of arrays
yoff	Y offsets of arrays

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

References write_tel_offset_w().

7.37.2.33 int write_tel_offset_w (IO_BUFFER * iobuf, int narray, double * toff, double * xoff, double * yoff, double * weight)

Write offsets and weights of randomly scattered arrays with respect to shower core.

With respect to the backwards-compatible non-weights version write_tel_offset(), this version adds a weight to each offset position which should be normalized in such a way that with uniform sampling it should be the area over which showers are thrown divided by the number of array in each shower. With importance sampling the same relation should hold on average. So in either case, the average sum of weights for the different offsets in one shower equals just the area over which cores are randomized. This leaves the possibility to change the number of offsets from shower to shower.

Parameters

iobuf	I/O buffer descriptor
narray	Number of arrays of telescopes/detectors
toff	Time offset (ns, from first interaction to ground)
xoff	X offsets of arrays
yoff	Y offsets of arrays
weight	Area weight for uniform or importance sampled core offset.

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

Referenced by write_tel_offset().

7.37.2.34 int write_tel_photons (IO_BUFFER * iobuf, int array, int tel, double photons, struct bunch * bunches, int nbunches, int ext_bunches, char * ext_fname)

Write all the photon bunches for one telescope to an I/O buffer.

Usually, calls to this function for each telescope in an array should be enclosed within calls to begin_write_tel_array() and end_write_tel_array(). This routine writes the less compact format (32 bytes per bunch).

Parameters

iobuf	I/O buffer descriptor
array	array number
tel	telescope number
photons	sum of photons (and fractions) in this device
bunches	list of photon bunches
nbunches	number of elements in bunch list
ext_bunches	number of elements in external file
ext_fname	name of external (temporary) file

Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

References bunch::ctime, bunch::cy, fileclose(), fileopen(), bunch::lambda, bunch::photons, bunch::y, and bunch::zem.

7.37.2.35 int write_tel_pos (IO_BUFFER * iobuf, int ntel, double * x, double * y, double * z, double * r)

Write positions of telescopes/detectors within a system or array.

Parameters

iobuf	I/O buffer descriptor
ntel	number of telescopes/detectors
X	X positions
у	Y positions
Z	Z positions
r	radius of spheres including the whole devices

Returns


0 (o.k.), -1, -2, -3 (error, as usual in eventio)

7.38 merge_simtel.c File Reference

A program for merging events from separate telescope simulations of the same showers.

```
#include "initial.h"
#include "io_basic.h"
#include "mc_tel.h"
#include "history.h"
#include "io_hess.h"
#include "histogram.h"
#include "io_histogram.h"
#include "fileopen.h"
#include "straux.h"
#include "warning.h"
#include "io_trgmask.h"
#include "eventio_version.h"
#include <signal.h>
```

Include dependency graph for merge_simtel.c:



Data Structures

• struct map_tel_struct

Structure with per output telescope information keeping track of prerequisites.

Functions

void stop_signal_function (int isig)

Stop the program gracefully when it catches an INT or TERM signal.

static void syntax (const char *program)

Show program syntax.

• int find_in_tel_idx (int tel_id, int ifile)

Offset of an input telescope of given ID within the input structures.

• int find_out_tel_idx (int tel_id, int ifile)

Offset of an input telescope of given ID within the output structures.

int find_mapped_telescope (int tel_id, int ifile)

Mapping from telescope ID on input to telescope ID on output, with check.

• int write_io_block_to_file (IO_BUFFER *iobuf, FILE *f)

Write an I/O block as-is to another file than foreseen for the I/O buffer.

int check_for_delayed_write (IO_ITEM_HEADER *item_header, int ifile, AllHessData *hsdata_out, IO_BU-FFER *iobuf out)

• int merge_data_from_io_block (IO_BUFFER *iobuf, IO_ITEM_HEADER *item_header, int ifile, AllHessData *hsdata, AllHessData *hsdata_out, IO_BUFFER *iobuf_out)

Processing and merging of I/O blocks from the two input files, hopefully presented in the right order.

int check_autoload_trgmask (const char *input_fname, IO_BUFFER *iobuf, int ifile)

Check for a 'trgmask.gz' file matching the given input data file name and, if it exists, extract the corrected trigger bit patterns from it.

- void **print_process_status** (int prev_type1, int this_type1, int prev_type2, int this_type2)
- int read map (const char *map fname)
- int main (int argc, char **argv)

Main program.

Variables

- · static int interrupted
- static int verbose = 0
- struct map_tel_struct map_tel [H_MAX_TEL]
- int map_to [2][H_MAX_TEL+1]

Mapping structures from input telescope ID to output telescope ID.

int tel_idx [2][H_MAX_TEL+1]

Mapping from telescope IDs to offsets in the data structures, first for input telescope IDs.

int tel_idx_out [H_MAX_TEL+1]

Mapping from output telescope ID to offset in output data structures.

- · int ntel1
- · int ntel2
- int ntel
- int nrtel1
- int nrtel2
- long **event1** = -1
- long **event2** = 0
- long ev_hess_event = 0
- long ev_pe_sum = 0

For delayed writing.

- int run1 = -1
- int run2 = -1
- int **min_trg** = 2
- static struct trgmask_set * tms [2] = { NULL, NULL }
- static struct trgmask hash set * ths [2] = { NULL, NULL }
- static int **events** [2] = { 0, 0 }
- static int **mcshowers** [2] = { 0, 0 }
- static int **mcevents** [2] = { 0, 0 }
- static int max list = 999

7.38.1 Detailed Description

A program for merging events from separate telescope simulations of the same showers.

```
The program will read sim_telarray raw or DST data on two input files, map telescope ID according to a mapping file and write the merged blocks to an output file.

Inputs expected - and the action to be performed:

Type
Once per run:
```

```
70 (history)
                    - Write as-is, impossible to merge
  2000 (run_header) - Merging needed for telescope list and positions
  2001 (MC run header) - Only one of two MC run-headers needed (should be identical)
   1212 (input config = CORSIKA inputs) - Only one needed (should be identical, duplicate)
 Once per telescope (and per run for raw & DST levels 0-2; just once for DST level 3):
   2002 (camera settings) - Write after mapping of telescope ID (if mapped)
   2003 (camera organization) - Write after mapping of telescope ID (if mapped)
  2004 (pixel settings) - Write after mapping of telescope ID (if mapped)
   2005 (pixel disable) - Write after mapping of telescope ID (if mapped)
   2006 (camera software settings) - Write after mapping of telescope ID (if mapped)
  2008 (tracking settings) - Write after mapping of telescope ID (if mapped)
  2007 (pointing corrections) - Write after mapping of telescope ID (if mapped)
   2022 (telescope monitoring) - Write after mapping of telescope ID (if mapped)
  2023 (Laser calibration) - Write after mapping of telescope ID (if mapped)
 Per shower:
  once:
  2020 (MC shower) - Only one of two MC run-headers needed (should be identical)
  per arrav:
  2021 (MC event) - Only one of two blocks needed (anything to get merged?)
 Optional per event; not immediately written but delayed until next MC etc. block:
  2026 (MC pe sum) - ???
  1204 (photo-electrons individually) - ???
  2010 (event) - Needs remapping and merging at all levels
 At end of run:
   2024 (run statistics - usually not present)
   2025 (MC run statistics - usually not present)
   100 (histograms) - Cannot be merged properly. Histograms of generated showers
          should agree, but for triggered showers we cannot tell how many are common.
 FIXME: Ignoring 'trgmask' files initially - include them later on.
Syntax: merge_simtel [ options ] map-file input1 input2 output
     --auto-trgmask : Load trgmask.gz files for each input file where available.
     --min-trg-tel n : Require at least n telescopes in merged event (default: 2).
                   : Show events being merged.
@author Konrad Bernloehr
        @verbatim CVS $Date: 2015/05/31 13:02:40 $
```

Version


CVS Revision: 1.6\$

7.39 moments.c File Reference

Calculate mean, rms, skewness, and kurtosis of data.

#include "histogram.h"

Include dependency graph for moments.c:



Functions

• MOMENTS * alloc moments (HISTVALUE REAL low, HISTVALUE REAL high)

Allocate a structure for sums of powers of data.

void clear_moments (MOMENTS *mom)

Initialize an existing moments structure (except for its range limits).

void free_moments (MOMENTS *mom)

Deallocates memory previously allocated to a moments structure.

• void fill_moments (MOMENTS *mom, HISTVALUE_REAL value)

Add up those things needed to compute mean, standard deviation, skewness, and kurtosis (both for all data and separately for data in a range defined in alloc_moments().

void fill_mean_and_sigma (MOMENTS *mom, HISTVALUE_REAL value)

Add up those things needed to compute – mean, – standard deviation, (both for all data and separately for data in a range defined in alloc moments().

• void fill_mean (MOMENTS *mom, HISTVALUE_REAL value)

Add up those things needed to compute – mean, (both for all data and separately for data in a range defined in alloc_moments().

• void fill_real_moments (MOMENTS *mom, HISTVALUE_REAL value, double weight)

Add up those things needed to compute – mean, – standard deviation, – skewness, and – kurtosis (both for all data and separately for data in a range defined in alloc_moments().

• void fill_real_mean_and_sigma (MOMENTS *mom, HISTVALUE_REAL value, double weight)

Add up those things needed to compute – mean, – standard deviation, (both for all data and separately for data in a range defined in alloc_moments().

• void fill_real_mean (MOMENTS *mom, HISTVALUE_REAL value, double weight)

Add up those things needed to compute – mean, (both for all data and separately for data in a range defined in alloc_moments().

int stat_moments (MOMENTS *mom, struct momstat *stmom)

Calculate moments (mean, rms, skewness, kurtosis) from the sums of powers of data values.

7.39.1 Detailed Description

Calculate mean, rms, skewness, and kurtosis of data.

Author

Konrad Bernloehr

Date

1995 to 2010

Date:

2011/02/28 09:56:42

Revision:

1.3

7.39.2 Function Documentation

7.39.2.1 MOMENTS* alloc_moments (HISTVALUE_REAL low, HISTVALUE_REAL high)

Allocate a structure for sums of powers of data.

Returns NULL if no structure could be allocated.

Parameters

low	Lower limit of range for truncation
high	Upper limit of range for truncation

Returns

Pointer to allocated structure or NULL.

References clear_moments().

Referenced by user init().

7.39.2.2 void clear_moments (MOMENTS * mom)

Initialize an existing moments structure (except for its range limits).

Parameters

mom	Pointer to moments structure

Referenced by alloc_moments(), and user_event_fill().

7.39.2.3 void fill_mean (MOMENTS * mom, HISTVALUE_REAL value)

Add up those things needed to compute – mean, (both for all data and separately for data in a range defined in alloc_moments().

Parameters

mom	Pointer to previously allocated MOMENTS structure.
value	One measurement value

7.39.2.4 void fill_mean_and_sigma (MOMENTS * mom, HISTVALUE_REAL value)

Add up those things needed to compute – mean, – standard deviation, (both for all data and separately for data in a range defined in alloc_moments().

Parameters

mom	Pointer to previously allocated MOMENTS structure.
value	One measurement value

7.39.2.5 void fill_moments (MOMENTS * mom, HISTVALUE_REAL value)

Add up those things needed to compute mean, standard deviation, skewness, and kurtosis (both for all data and separately for data in a range defined in alloc moments().

Parameters

mom	Pointer to previously allocated MOMENTS structure.
value	One measurement value

Referenced by user_event_fill().

7.39.2.6 void fill_real_mean (MOMENTS * mom, HISTVALUE_REAL value, double weight)

Add up those things needed to compute – mean, (both for all data and separately for data in a range defined in alloc_moments().

Parameters

mom	Pointer to previously allocated MOMENTS structure.
value	One measurement value
weight	Weighting factor of this value

7.39.2.7 void fill real mean and sigma (MOMENTS * mom, HISTVALUE REAL value, double weight)

Add up those things needed to compute – mean, – standard deviation, (both for all data and separately for data in a range defined in alloc_moments().

Parameters

mom	Pointer to previously allocated MOMENTS structure.
value	One measurement value
weight	Weighting factor of this value

7.39.2.8 void fill real moments (MOMENTS * mom, HISTVALUE REAL value, double weight)

Add up those things needed to compute – mean, – standard deviation, – skewness, and – kurtosis (both for all data and separately for data in a range defined in alloc_moments().

Parameters

mom	Pointer to previously allocated MOMENTS structure.
value	One measurement value
weight	Weighting factor of this value

7.39.2.9 void free_moments (MOMENTS * mom)

Deallocates memory previously allocated to a moments structure.

Parameters

mom	Pointer to previously allocated structure

7.39.2.10 int stat_moments (MOMENTS * mom, struct momstat * stmom)

Calculate moments (mean, rms, skewness, kurtosis) from the sums of powers of data values.

Parameters

mom	'moments' structure with the sums of the powers of data values (only 1st power if only mean
	to be calculated, also 2nd power if r.m.s. to be calculated, and also 3rd and 4th if skewness
	and kurtosis wanted.
stmom	Pointer to structure for computed moments

Returns

```
0 (o.k.), -1 and -2 (invalid data)
```


Referenced by user_event_fill().

7.40 read hess.c File Reference

A program reading simulated data, optionally analysing the data, and also optionally also writing summary ("DST") data.

```
#include "initial.h"
#include "io_basic.h"
#include "mc_tel.h"
#include "history.h"
#include "io_hess.h"
#include "histogram.h"
#include "io_histogram.h"
#include "fileopen.h"
#include "straux.h"
#include "rec_tools.h"
#include "reconstruct.h"
#include "user analysis.h"
#include "warning.h"
#include "camera_image.h"
#include "basic_ntuple.h"
#include "io_trgmask.h"
#include "eventio_version.h"
#include <sys/time.h>
#include <signal.h>
```

Include dependency graph for read_hess.c:



Data Structures

- · struct next file struct
- · struct range_list_struct

Macros

• #define CALIB_SCALE 0.92

The factor needed to transform from mean p.e.

Typedefs

- typedef struct next_file_struct NextFile
- typedef struct range_list_struct RangeList

Functions

void stop_signal_function (int isig)

Stop the program gracefully when it catches an INT or TERM signal.

- static void init_rand (int is)
- double grand48 (double mean, double sigma)

Like RandFlat() from rndm2.c but using the drand48 engine.

• static void mc_event_fill (AllHessData *hsdata, double d_sp_idx)

Fill histogram(s) for DST writing which require all MC shower and event data and which cannot be filled from DST level >= 2 data.

static int write_dst_histos (IO_BUFFER *iobuf2)

Write histograms for DST book-keeping and clear them afterwards.

- static void show_run_summary (AllHessData *hsdata, int nev, int ntrg, double plidx, double wsum_all, double wsum_trg, double rmax_x, double rmax_y, double rmax_r)
- static void syntax (char *program)

Show program syntax.

- NextFile * add_next_file (const char *fn, NextFile *nxt)
- RangeList * add_range (long f, long t, RangeList *rl)
- int is_in_range (long n, RangeList *rl)
- int main (int argc, char **argv)

Main program.

Variables

- · struct basic ntuple bnt
- · static int interrupted
- · static int dst processing
- · static int g48 set
- · static double q48 next

7.40.1 Detailed Description

A program reading simulated data, optionally analysing the data, and also optionally also writing summary ("DST") data

```
This program started as a skeleton for reading H.E.S.S. data in eventio format (which is what the read_hess_nr program is now intended for). The read_hess program reads the whole range of hessio item types into a single tree of data structures but normally does nothing with the data.
```

It can be instructed to create nice camera images similar to those generated in $sim_hessarray$.

It can also be instructed to redo the image cleaning (with the simple 10/5 tail-cut algorithm) and the shower reconstruction, writing ASCII output of the results.

In addition, it includes an interface for a full-scale analysis which can optionally be activated.

And finally, it can be instructed to extract DST-level data in order to reduce the amount of data by a large factor. This depends on the dst-level flag: 1) Remove all raw data (you cannot redo image cleaning) afterwards. 2) Remove also all MC data from non-triggered event (you should better stay with the spectral index used for DST extraction because you have to rely on its histograms for MC energy distribution). 3) and 4) Keep only user-defined events (with or without raw data).

```
Syntax: read_hess [ options ] [ - | input_fname ... ]
Options:
  -p ps_filename (Write a PostScript file with camera images.)
                   (Use 10/5 tail-cut image cleaning and redo reconstruction.)
   -r level
                   level >= 1: show parameters from sim_hessarray.
                   level >= 2: redo shower reconstruction
                   level >= 3: redo image cleaning (and shower reconstruction
                               with new image parameters)
                   level >= 4: redo amplitude summation
                   level >= 5: PostScript file includes original and
                               new shower reconstruction.
                   (More verbose output)
   -q
                   (Much more quiet output)
                   (Show data explained)
                   (Show data explained, including raw data)
   -S
   --history (-h) (Show contents of history data block)
                   (Ignore unknown data block types)
                   (Call user-defined analysis function)
   -u
   --global-peak
                  (For image analysis use amplitude sums around global peak
                    in 'on-line' pulse shape analysis.)
   --local-peak
                   (For image analysis use amplitude sums around local peaks
                    in 'on-line' pulse shape analysis.)
   --powerlaw x
                   (Use this spectral index for events weights in output.)
                   (Default spectral index is -2.7)
   --only-run run1[,run2-run3[,...]] (Select runs being processed.)
   --not-run run1[,run2-run3[,...]]
   --only-telescope id1[,id2-i3[,...]] (Select telescopes being used.)
   --not-telescope id1[,id2-id3[,...]]
   --auto-trgmask (Automatically load matching .trgmask.gz files.)
   --trgmask-path dir (Search the trgmask files in this path first.)
   --trg-required b * (Required trigger bits, e.g. 5=1|4 -> majo or asum)
   --type nt[,id1,id2,A,f,npix] (Set [requirements for] telescope type nt.)
                  *(The minimum number of tel. images required in analysis.)
```

```
(The maximum number of tel. images required in analysis.)
   --max-tel tmx
   --min-trg-tel n (Minimum number of telescopes in system trigger.)
  --min-amp npe \phantom{a}\star (\texttt{Minimum image amplitude for shower reconstruction.})
   --min-pix npix
                  * (Minimum number of pixels for shower reconstruction.)
   --max-events n (Skip remaining data after so many triggered events.)
   --max-theta d (Maximum angle between source and shower direction [deg].)
   --min-theta d (Where cut angle is multiplicity dependent, use this
                    as the lower limit [deg].)
   --theta-scale f (Scale fixed and optimized theta cut by this factor.)
   --theta-E-scale t0,ts,min,max (Energy-dependent scaling beyond multiplicity.)
  --tail-cuts 1,h[,n,f] *(Low and high level tail cuts to be applied in analysis.)
   --nb-radius r1[,r2[,r3]] *(Maximum distance of neighbour pixels [px diam.])
   --ext-radius r \star (Radius to extend preserved pixels beyond cleaning [px diam.])
   --dE2-cut c
                   (Cut parameter for dE2 cut.)
   --hess-standard-cuts (Apply HESS-style selection with standard cuts.)
   --hess-hard-cuts (Apply HESS-style selection with hard cuts.)
   --hess-loose-cuts (Apply HESS-style selection with loose cuts.)
   --hess-style-cuts (No shape parameter rescaling as HESS-style.)
   --shape-cuts wmn,wmx,lmn,lmx (Shape cut parameters: mscrw/l min/max).
   --dE-cut c
                  (Scale parameter for dE cut strictness, def=1.0).
   --hmax-cut c
                  (Scale parameter for hmax cut strictness, def=1.0).
   --min-img-angle a (Only use image pairs intersecting at angle > a deg, def=0).
   --min-disp d *(Do not use round images with disp = (1-w/1) < d, def=0).
   --max-core-distance r \star (Only use images from telescope not further from core).
   --impact-range r,x,y (Accept only events with reconstructed core in range).
   --true-impact-range r,x,y (Accept only events with true core in range).
                   Note that r is in shower plane but x, y ranges are on surface.
   --clip-camera-radius r \star (In image reconstruction clip camera at radius r deg.)
   --clip-camera-diameter d \star (Same as before but with diameter d deg.)
  --clip-pixel-amplitude a *(Calibrated pixel ampl. does not exceed a mean p.e.)
   --only-high-gain (Use only high-gain channel and ignore low gain.)
   --only-low-gain (Use only low-gain channel and ignore high gain.)
   --max-events (Stop after having processed this many events.)
   --broken-pixels-fraction (Add random broken/dead pixels on run-by-run basis.)
   --dead-time-fraction (Set telescopes randomly as dead from prior triggers.)
   --integration-scheme n \star (Set the integration scheme for sample-mode data.)
  --integration-window w,o \star (Set integration window width and offset.)
   --integration-treshold h[,1] *(Set significance thresholds for integration.)
   --integration-no-rescale *(Don't rescale pulse sum for integration with
                  windows narrower than a single-p.e. pulse.)
   --integration-rescale *(Rescale for single-p.e. fraction in window; default)
   --calib-scale f \star (Rescale from mean p.e. to experiment units. Default: 0.92)
  --calib-error f (Random pixel relative calibration error. Default: 0.)
                 (Store calibrated pixel intensities to DST file, if possible.)
   --only-calibrated (Like '--calibrate' but omit raw data from DST.)
  --diffuse-mode (True shower position assumed as source position.)
   --random-seed n|auto (Initialize random number generator.)
   --off-axis-range al,a2 (Only for diffuse mode, restricting range in deg.)
                  (Automatically generate lookup table (gammas only).)
   --auto-lookup
   --lookup-file name (Override automatic naming of lookup files.)
                   (Imaging cleaning setting: 0=no, 1=sums, 2=samples, 3=both)
   --cleaning n
   --dst-level n
                   (Level of data reduction when writing DST-type output.)
                   Valid levels: 0, 1, 2, 3, 10, 11, 12, 13.
                   Raw data is stripped off at all levels except 0 and 10.
                   Level 0 has any sample mode data reduced to sums,
                   Level 1 includes all MC shower/event blocks,
                   level 2 only for triggered events,
                   level 3 has many config/calib blocks only once, not per run.
                   Levels 10-13 include only selected gamma-like events.
   --dst-file name (Name of output file for DST-type output.)
   --histogram-file name (Name of histogram file.)
  -f fname
                   (Get list of input file names from fname.)
Parameters followed by a '\star' can be telescope-type-specific if preceded by a
'--type' option. Their interpretation is thus position-dependent.
Qauthor Konrad Bernloehr
         @verbatim CVS $Date: 2015/04/30 09:47:11 $
```

Version

```
CVS $Revision: 1.114 $
This program started as a skeleton for reading H.E.S.S. data in eventio
format (which is what the read_hess_nr program is now intended for).
The read_hess program reads the whole range of hessio item types into a
single tree of data structures but normally does nothing with the data.
It can be instructed to create nice camera images similar to
those generated in sim_hessarray.
It can also be instructed to redo the image cleaning (with the simple
10/5 tail-cut algorithm) and the shower reconstruction, writing
ASCII output of the results.
In addition, it includes an interface for a full-scale analysis which
can optionally be activated.
And finally, it can be instructed to extract DST-level data in order
to reduce the amount of data by a large factor. This depends on the
dst-level flag: 1) Remove all raw data (you cannot redo image cleaning)
afterwards. 2) Remove also all MC data from non-triggered event (you
because you have to rely on its histograms for MC energy distribution).
3) and 4) Keep only user-defined events (with or without raw data).
Syntax: read_hess [ options ] [ - | input_fname ... ]
Options:
   -p ps_filename (Write a PostScript file with camera images.)
                   (Use 10/5 tail-cut image cleaning and redo reconstruction.)
   -r level
                   level >= 1: show parameters from sim_hessarray.
                   level >= 2: redo shower reconstruction
                   level >= 3: redo image cleaning (and shower reconstruction
                               with new image parameters)
                   level >= 4: redo amplitude summation
                   level >= 5: PostScript file includes original and
                               new shower reconstruction.
                   (More verbose output)
   -q
                   (Much more quiet output)
   -s
                   (Show data explained)
                   (Show data explained, including raw data)
   -S
   --history (-h) (Show contents of history data block)
                   (Ignore unknown data block types)
   -i
   -11
                   (Call user-defined analysis function)
   --global-peak
                   (For image analysis use amplitude sums around global peak
                    in 'on-line' pulse shape analysis.)
                   (For image analysis use amplitude sums around local peaks
   --local-peak
                   in 'on-line' pulse shape analysis.)
   --powerlaw x
                   (Use this spectral index for events weights in output.)
                   (Default spectral index is -2.7)
   --only-telescope id1[,id2[,...]]
   --not-telescope id1[,id2[,...]]
                  (The minimum number of tel. images required in analysis.)
   --min-tel tmn
   --max-tel tmx
                  (The maximum number of tel. images required in analysis.)
   --min-trg-tel n (Minimum number of telescopes in system trigger.)
   --min-amp npe (Minimum image amplitude for shower reconstruction.)
   --min-pix npix (Minimum number of pixels for shower reconstruction.)
   --max-events n (Skip remaining data after so many triggered events.)
   --max-theta d (Maximum angle between source and shower direction [deg].) --theta-scale f (Scale fixed and optimized theta cut by this factor.)
   --theta-E-scale t0,ts,min,max (Energy-dependent scaling beyond multiplicity.)
   --tail-cuts l,h[,n,f] (Low and high level tail cuts to be applied in analysis.)
                  (Cut parameter for dE2 cut.)
   --dE2-cut c
   --hess-standard-cuts (Apply HESS-style selection with standard cuts.)
   --hess-hard-cuts (Apply HESS-style selection with hard cuts.)
   --hess-loose-cuts (Apply HESS-style selection with loose cuts.)
   --hess-style-cuts (No shape parameter rescaling as HESS-style.)
   --shape-cuts wmn, wmx, lmn, lmx (Shape cut parameters: mscrw/l min/max).
   --dE-cut c
                (Scale parameter for dE cut strictness, def=1.0).
   --hmax-cut c
                   (Scale parameter for hmax cut strictness, def=1.0).
```

--clip-camera-radius r \star (In image reconstruction clip camera at radius r deg.)

--clip-camera-diameter d *(Same as before but with diameter d deg.)


```
(Automatically generate lookup table (gammas only).)
   --auto-lookup
   --lookup-file name (Override automatic naming of lookup files.)
   --dst-level n
                   (Level of data reduction when writing DST-type output.)
                   Valid levels: 1, 2, 3, 10, 11, 12, 13.
                   Raw data is stripped off at all levels except 10.
                   Level 1 includes all MC shower/event blocks,
                   level 2 only for triggered events,
                   level 3 has many config/calib blocks only once, not per run.
                   Levels 10-13 include only selected gamma-like events.
   --dst-file name (Name of output file for DST-type output.)
  --dst-process
                  (Telescope configuration etc. may appear only once.)
                   (Get list of input file names from fname.)
  -f fname
Parameters followed by a '\star' can be type-specific if preceded by a
'--type' option. Their interpretation is thus position-dependent.
@author Konrad Bernloehr
@dat.e
         @verbatim CVS $Date: 2010/03/19 18:09:32 $
Version
    CVS $Revision: 1.76 $
```

7.41 read_hess_nr.c File Reference

A skeleton program reading H.E.S.S.

```
#include "initial.h"
#include "io_basic.h"
#include "mc_tel.h"
#include "history.h"
#include "io_hess.h"
#include "io_histogram.h"
#include "io_histogram.h"
#include "fileopen.h"
#include "straux.h"
#include "rec_tools.h"
#include "warning.h"
#include "camera_image.h"
#include <signal.h>
```

Include dependency graph for read_hess_nr.c:



Macros

- #define UNUSED
- #define CALIB SCALE 0.92

The factor needed to transform from mean p.e.

Functions

- double calibrate_pixel_amplitude (AllHessData *hsdata, int itel, int ipix, int dummy, double cdummy)
 Calibrate a single pixel amplitude, for cameras with two gains per pixel.
- double calibrate_pixel_amplitude (AllHessData *hsdata, int itel, int ipix, _UNUSED_ int dummy, _UNUSED_ b_ double cdummy)
- void stop_signal_function (int isig)

Stop the program gracefully when it catches an INT or TERM signal.

- static void **show_run_summary** (AllHessData *hsdata, int nev, int ntrg, double plidx, double wsum_all, double wsum_trg, double rmax_x, double rmax_y, double rmax_r)
- static void syntax (char *program)

Show program syntax.

int main (int argc, char **argv)

Main program.

Variables

· static int interrupted

7.41.1 Detailed Description

A skeleton program reading H.E.S.S. data.

As a skeleton for programs reading H.E.S.S. data in eventio format, this program reads the whole range of hessio item types into a single tree of data structures but normally does nothing with the data.

It can be instructed, though, to create nice camera images similar to those generated in sim_hessarray.

```
Syntax: read_hess_nr [ options ] [ - | input_fname ... ]
Options:
   -p ps_filename (Write a PostScript file with camera images.)
   -r level (Reconstruction level not fully used in this program version.)
level >= 1: show parameters from sim_hessarray.
                      (More verbose output)
                     (Much more quiet output)
   -q
                    (Show data explained)
   -S (Show data explained, including raw data)
--history (-h) (Show contents of history data block)
                     (Ignore unknown data block types)
                     (Call user-defined analysis function)
   -u
   --powerlaw x (Use this spectral index for events weights in output.) (Default spectral index is -2.7)
   --max-events n (Skip remaining data after so many triggered events.)
@author Konrad Bernloehr
          @verbatim CVS $Date: 2011/07/21 16:07:26 $
@date
```


Version

```
CVS $Revision: 1.16 $
```

7.42 rec_tools.h File Reference

Tools for shower geometric reconstruction.

This graph shows which files directly or indirectly include this file:



Functions

 void angles_to_offset (double obj_azimuth, double obj_altitude, double azimuth, double altitude, double focallength, double *xoff, double *yoff)

Transform telescope and object Alt/Az to offset in camera.

• void offset_to_angles (double xoff, double yoff, double azimuth, double altitude, double focal_length, double *obj_azimuth, double *obj_altitude)

Transform from offset in camera to corresponding Az/Alt.

• void get shower trans matrix (double azimuth, double altitude, double trans[][3])

Calculate transformation matrix.

void cam_to_ref (double ximg, double yimg, double phi, double ref_azimuth, double ref_altitude, double cam_rot, double azimuth, double altitude, double focal_length, double *axref, double *ayref, double *phiref)

Transform from one camera to common reference frame.

• int intersect_lines (double xp1, double yp1, double phi1, double xp2, double yp2, double phi2, double *xs, double *ys, double *sang)

Intersect pairs of lines.

• int shower_geometric_reconstruction (int ntel, const double *amp, const double *ximg, const double *yimg, const double *phi, const double *disp, const double *xtel, const double *ytel, const double *ztel, const double *ztel, const double *az, const double *alt, const double *flen, const double *cam_rot, double ref_az, double ref_alt, int flag, double *shower_az, double *shower_alt, double *var_dir, double *xc, double *yc, double *var_core)

Simple reconstruction by intersecting pairs of lines.

double angle_between (double azimuth1, double altitude1, double azimuth2, double altitude2)

Calculate the angle between two directions given in spherical coordinates.

double line_point_distance (double xp1, double yp1, double zp1, double cx, double cx, double cz, double x, double y, double z)

Distance between a straight line and a point in space.

7.42.1 Detailed Description

Tools for shower geometric reconstruction. Shower geometric reconstruction based on the major axes of the telescope images. The image parameters from each telescope are transformed to a common reference frame first before the average intersection point of all images is calculated in plane coordinates.

Author

Konrad Bernloehr

Date

2000, 2009

CVS \$Date: 2014/05/07 13:08:25 \$

Version

```
CVS $Revision: 1.17 $
```

7.42.2 Function Documentation

7.42.2.1 double angle_between (double azimuth1, double altitude1, double azimuth2, double altitude2)

Calculate the angle between two directions given in spherical coordinates.

Returns

The angle between the two directions in units of radians.

Referenced by main(), shower_reconstruct(), user_event_fill(), and user_init().

7.42.2.2 void angles_to_offset (double *obj_azimuth*, double *obj_altitude*, double *azimuth*, double *altitude*, double *focal_length*, double * xoff, double * yoff)

Transform telescope and object Alt/Az to offset in camera.

Transform from given telescope and object angles (Az/Alt) to the offset the object has in the camera plane.

Transform from given telescope and object angles (Az/Alt) to the offset the object has in the camera plane.

This does not account for any rotation of the camera and its pixels.

Referenced by cam_to_ref(), hesscam_ps_plot(), and user_event_fill().

7.42.2.3 void cam_to_ref (double *ximg*, double *yimg*, double *phi*, double *ref_azimuth*, double *ref_altitude*, double *cam_rot*, double *azimuth*, double *altitude*, double *focal_length*, double * *axref*, double * *ayref*, double * *phiref*)

Transform from one camera to common reference frame.

Transform from the camera plane coordinate system of a telescope looking to altitude/azimuth to a plane coordinate system of a potential telescope looking to a reference direction ref_azimuth,ref_altitude and having unit focal length. Rotation of image angles is accounted for but not imaging errors.

References angles to offset(), and offset to angles().

Referenced by shower_geometric_reconstruction().

7.42.2.4 void get shower trans matrix (double azimuth, double altitude, double trans[][3])

Calculate transformation matrix.

Calculate transformation matrix from horizontal reference frame to one z axis in the given Az/Alt direction and the x axis in the plane defined by Az/Alt and zenith.

Referenced by shower_geometric_reconstruction().

7.42.2.5 int intersect_lines (double xp1, double yp1, double phi1, double xp2, double yp2, double phi2, double xp1, double xp2, double xp3, double xp

Intersect pairs of lines.

Intersect a pair of straight lines in a plane and return the intersection point and the angle at which the lines intersect. Referenced by shower_geometric_reconstruction().

7.42.2.6 double line_point_distance (double xp1, double yp1, double zp1, double cx, do

Distance between a straight line and a point in space.

Parameters

xp1,yp1,zp1,:	reference point on the line
cx,cy,cz,:	direction cosines of the line
<i>x,y,z,:</i>	point in space

Returns

distance

Referenced by main(), mc event fill(), second moments(), user event fill(), and user mc event fill().

7.42.2.7 void offset_to_angles (double *xoff*, double *yoff*, double *azimuth*, double *altitude*, double *focal_length*, double * *obj_azimuth*, double * *obj_altitude*)

Transform from offset in camera to corresponding Az/Alt.

Transform from the offset an object or image has in the camera plane of a telescope to the corresponding Az/Alt.

Transform from the offset an object or image has in the camera plane of a telescope to the corresponding Az/Alt.

This does not account for any rotation of the camera and its pixels. (xoff and yoff are assumed to be corrected for camera rotation).

Referenced by cam_to_ref(), and shower_geometric_reconstruction().

7.42.2.8 int shower_geometric_reconstruction (int *ntel*, const double * *amp*, const double * *ximg*, const double * *yimg*, const double * *phi*, const double * *disp*, const double * *xtel*, const double * *ytel*, const double * *ztel*, const double * *az*, const double * *alt*, const double * *flen*, const double * *cam_rot*, double *ref_az*, double *ref_alt*, int *flag*, double * *shower_az*, double * *shower_alt*, double * *var_dir*, double * *xc*, double * *yc*, double * *var_core*)

Simple reconstruction by intersecting pairs of lines.

Simple geometric shower reconstruction by intersecting pairs of straigh lines (from major axis of second moments ellipses after transformation to a common plane), first for the shower direction and then for the core position. No errors on reconstructed direction or core position are calculated. This should sooner or later be superceded by a fit procedure taking advantage of estimated errors on image positions and angles.

Parameters

ntel	The number of telescopes with suitable images.
amp	The image amplitudes in each suitable telescope [p.e.].
ximg	The image c.o.g. x positions in the local camera coordinate systems.
yimg	The image c.o.g. y positions in the local camera coordinate systems.
phi	The image major axis direction [rad].
disp	The DISP parameter (1width/length), used for giving preference to elongated images. Set
	all to 1.0 if unknown or no preference wanted. Can also be passed as a NULL pointer instead.
xtel	The x coordinate of the telescope positions within array [m].
ytel	The y coordinate of the telescope positions within array [m].
ztel	The z coordinate of the telescope positions within array [m].
az	The azimuth angles to which the telescopes are pointing (N->E->S->W) [rad].
alt	The altitude angles to which the telescopes are pointing [rad].
flen	The focal length to which ximg and yimg are scaled (1.0 if in units of radians, otherwise flen
	is in meters).
cam_rot	Camera rotation angle [rad].
ref_az	The reference azimuth angle (system nominal azimuth) [rad].
ref_alt	The reference altitude angle (system nominal altitude) [rad].
flag	Use the reconstucted direction to derive the core position (0) or use the nominal direction for
	that (1 or any other non-zero). The second version may sightly improve core distance and
	thus energy accuracy for well-defined point sources.
shower_az	Return the reconstructed shower azimuth angle (N->E->S->W) [rad].
shower_alt	Return the reconstructed shower altitude angle [rad].
var_dir	Variance (dx**2+dy**2)/ntel of reconstructed direction for more than two images. Can be
	NULL if you are not interested in it.
XC	Return the reconstructed core position x coordinate (at z=0) [m].
yc	Return the reconstructed core position y coordinate (at z=0) [m].
var_core	Variance (dx**2+dy**2)/ntel of reconstructed core position for more than two images. Can
	be NULL if you are not interested in it.

References cam_to_ref(), get_shower_trans_matrix(), intersect_lines(), and offset_to_angles().


Referenced by shower_reconstruct().

7.43 reconstruct.c File Reference

Second moments type image analysis.

```
#include "initial.h"
#include "io_hess.h"
#include "rec_tools.h"
#include "reconstruct.h"
#include "user_analysis.h"
```

Include dependency graph for reconstruct.c:



Macros

• #define CALIB SCALE 0.92

The factor needed to transform from mean p.e.

- #define H MAX NB1 8
- #define H MAX NB2 24

Functions

• int set_disabled_pixels (AllHessData *hsdata, int itel, double broken_pixels_fraction)

Set up pixels to be ignored (regarded as zero amplitude) in the analysis if they either have HV disabled or the camera active radius is clipped.

static int find_neighbours (CameraSettings *camset, int itel)

Find the list of neighbours for each pixel.

- int store camera radius (CameraSettings *camset, int itel)
- double **get_camera_radius** (int itel, int maxflag)
- void select_calibration_channel (int chn)

Control if only low-gain or high-gain should get used instead of both.

• int calibrate amplitude (AllHessData *hsdata, int itel, int flag amp tm, double clip amp)

Calibrate amplitudes in all pixels of a camera.

double calibrate_pixel_amplitude (AllHessData *hsdata, int itel, int ipix, int flag_amp_tm, int itime, double clip_amp)

Calibrate a single pixel amplitude.

• static int simple_integration (AllHessData *hsdata, int itel, int nsum, int nskip)

Integrate sample-mode data (traces) over a common and fixed interval.

static int global_peak_integration (AllHessData *hsdata, int itel, int nsum, int nbefore, int *sigamp)

Integrate sample-mode data (traces) over a common interval around a global signal peak.

• static int local peak integration (AllHessData *hsdata, int itel, int nsum, int nbefore, int *sigamp)

Integrate sample-mode data (traces) around a pixel-local signal peak.

static int nb peak integration (AllHessData *hsdata, int lwt, int itel, int nsum, int nbefore, int *sigamp)

Integrate sample-mode data (traces) around a peak in the signal sum of neighbouring pixels.

- static double qpol (double x, int np, double *yval)
- static int set_integration_correction (AllHessData *hsdata, int itel, int nbins, int noff)
- static int pixel_integration (AllHessData *hsdata, int itel, struct user_parameters *up)

Pixel integration steering function.

• static int clean_image_tailcut (AllHessData *hsdata, int itel, double al, double ah, int lref, double minfrac)

Use dual-level tail-cut image cleaning procedure to get pixel list.

static int second_moments (AllHessData *hsdata, int itel, int cut_id, int nimg, double clip_amp)

Reconstruction of second moments parameters from cleaned image.

• static int pixel_timing_analysis (AllHessData *hsdata, int itel, int nimg)

Calculate summary results from pixel timing data.

• static int image_reconstruct (AllHessData *hsdata, int itel, int cut_id, double tcl, double tch, int lref, double minfrac, int nimg, int flag_amp_tm, double clip_amp)

Calibrate and clean image pixels and reconstruct second moments parameters from images.

static int shower_reconstruct (AllHessData *hsdata, const double *min_amp_tel, const size_t *min_pix_tel, int cut id)

Shower reconstruction (geometrical reconstruction only)

• int reconstruct (AllHessData *hsdata, int reco_flag, const double *min_amp, const size_t *min_pix, const double *tcl, const double *tcl, const double *tch, const int *lref, const double *minfrac, int nimg, int flag_amp_tm)

Image/shower reconstruction function.

void set_reco_verbosity (int v)

Variables

- static int neighbours1 [H MAX TEL][H MAX PIX][H MAX NB1]
- static int nnb1 [H_MAX_TEL][H_MAX_PIX]
- static int has_nblist [H_MAX_TEL]
- static int px shape type [H MAX TEL]
- static int image_list [H_MAX_TEL][H_MAX_PIX]
- static int image_numpix [H_MAX_TEL]
- static double pixel_amp [H_MAX_TEL][H_MAX_PIX]
- static int show_total_amp = 0
- static int pixel_sat [H_MAX_TEL]
- static char pixel_disabled [H_MAX_TEL][H_MAX_PIX]
- static int any_disabled [H_MAX_TEL]
- static double camera_radius_eff [H_MAX_TEL]
- static double camera_radius_max [H_MAX_TEL]
- static double integration_correction [H_MAX_TEL][H_MAX_GAINS]
- static int verbosity = 0
- static int **no_low_gain** = 0
- static int no_high_gain = 0

7.43.1 Detailed Description

Second moments type image analysis.

Date

```
CVS $Revision: 1.58 $
```

Version

```
CVS $Date: 2015/05/27 11:36:48 $
```

7.43.2 Macro Definition Documentation

7.43.2.1 #define CALIB_SCALE 0.92

The factor needed to transform from mean p.e.

units to units of the single-p.e. peak: Depends on the collection efficiency, the asymmetry of the single p.e. amplitude distribution and the electronic noise added to the signals. Default value is for HESS.

Referenced by calibrate_amplitude(), and calibrate_pixel_amplitude().

7.43.3 Function Documentation

```
7.43.3.1 int calibrate_amplitude ( AllHessData * hsdata, int itel, int flag_amp_tm, double clip_amp )
```

Calibrate amplitudes in all pixels of a camera.

This function is operating only on pulse sums, either from normal raw data or from timing/pulse shape analysis. Use calibrate_pixel_amplitude() for calibration of individual samples.

Parameters

hsdata	Pointer to all available data and configurations.
itel	Index of telescope in the relevant arrays (not the ID).
flag_amp_tm	0: Use normal integrated amplitude. 1: Use integration around global peak position from
	pulse shape analysis. May include all pixels or only selected. 2: Use integration around local
	peak position from pulse shape analysis. Return 0 for pixels without a fairly significant peak.
clip_amp,:	if >0, any calibrated amplitude is clipped not to exceed this value [mean p.e.].

References hess_tel_event_adc_struct::adc_known, hess_tel_event_adc_struct::adc_list, hess_tel_event_adc-struct::adc_list, hess_tel_event_adc-struct::adc_list, hess_tel_event_adc-struct::adc_struct: _struct::adc_sum, hess_pixel_timing_struct::after_peak, hess_pixel_timing_struct::before_peak, hess_laser_calib_data_struct::calib, CALIB_SCALE, user_parameters::calib_scale, hess_event_data_struct::central, user_parameters::clip_amp, H_MAX_GAINS, H_MAX_TEL, HI_GAIN, hess_pixel_calibrated_struct::int_method, hess-_tel_event_adc_struct::known, hess_pixel_timing_struct::known, hess_pixel_calibrated_struct::known, hess_tel-_event_adc_struct::list_known, hess_pixel_calibrated_struct::list_known, hess_tel_event_adc_struct::list_size, hess pixel calibrated struct::list size, LO GAIN, hess pixel setting struct::min pixel mult, hess tel event-_adc_struct::num_gains, hess_camera_settings_struct::num_pixels, hess_pixel_calibrated_struct::num_pixels, hess_central_event_data_struct::num_teltata, hess_central_event_data_struct::num_teltrg, hess_tel_monitor_struct::pedestal, hess_tel_event_data_struct::pixcal, hess_pixel_calibrated_struct::pixel_list, hess_pixel_list::pixellist, hess pixel calibrated struct::pixel pe, hess pixel list::pixels, hess tel event data struct::pixtm, hess pixel_timing_struct::pulse_sum_glob, hess_pixel_timing_struct::pulse_sum_loc, hess_tel_event_data_struct::raw, hess_tel_event_adc_struct::significant, hess_pixel_calibrated_struct::significant, hess_tel_event_adc_struct::tel_id, hess_pixel_calibrated_struct::tel_id, hess_tel_event_data_struct::tel_id, hess_event_data_struct::teldata, hess_central event data struct::teldata list, hess central event data struct::teldata pattern, hess central event data_struct::teltrg_list, hess_central_event_data_struct::teltrg_pattern, hess_pixel_timing_struct::threshold, hess_pixel_timing_struct::timval, hess_tel_event_data_struct::trigger_pixels, and user_get_type().

Referenced by image_reconstruct(), and main().

7.43.3.2 double calibrate_pixel_amplitude (AllHessData * hsdata, int itel, int ipix, int flag_amp_tm, int itime, double clip_amp)

Calibrate a single pixel amplitude.

Parameters

hsdata	Pointer to all available data and configurations.
itel	Index of telescope in the relevant arrays (not the ID).
ipix	The pixel number (0 npix-1).
flag_amp_tm	0: Use normal integrated amplitude. 1: Use integration around global peak position from
	pulse shape analysis. May include all pixels or only selected. 2: Use integration around local
	peak position from pulse shape analysis. Return 0 for pixels without a fairly significant peak.
itime	-1: sum of samples of type as given in flag_amp_tm 0(nsamples-1): sample data (if avail-
	able) for one time slice
clip_amp,:	if >0, any calibrated amplitude is clipped not to exceed this value [mean p.e.].

Returns

Pixel amplitude in peak p.e. units (based on conversion factor from H.E.S.S.).

References hess_tel_event_adc_struct::adc_known, hess_tel_event_adc_struct::adc_sample, hess_tel_event_adc_struct::adc_sum, hess_pixel_timing_struct::after_peak, hess_pixel_timing_struct::before_peak, hess_laser_calib_data_struct::calib, CALIB_SCALE, user_parameters::calib_scale, user_parameters::clip_amp, H_MAX_GA-INS, H_MAX_TEL, HI_GAIN, hess_tel_event_adc_struct::known, hess_pixel_timing_struct::known, hess_pixel_calibrated_struct::known, LO_GAIN, hess_tel_event_adc_struct::num_gains, hess_camera_settings_struct::num_pixels, hess_tel_event_adc_struct::num_samples, hess_tel_monitor_struct::pedestal, hess_tel_event_data_struct::pixcal, hess_pixel_calibrated_struct::pixel_pe, hess_tel_event_data_struct::pixtm, hess_pixel_timing_struct::pulse_sum_glob, hess_pixel_timing_struct::pulse_sum_loc, hess_tel_event_data_struct::raw, hess_tel_event_adc_struct::significant, hess_pixel_calibrated_struct::significant, hess_event_data_struct::teldata, hess_pixel_-

timing_struct::threshold, hess_pixel_timing_struct::timval, user_get_type(), and hess_tel_event_adc_struct::zero_sup_mode.

7.43.3.3 static int clean_image_tailcut (AllHessData * hsdata, int itel, double al, double ah, int lref, double minfrac)
[static]

Use dual-level tail-cut image cleaning procedure to get pixel list.

In contrast to the classical dual-level tail-cuts this function has an optional restriction to only those pixels having an amplitude above a given fraction of the n-th hottest pixel. This should almost stop the increase of width and length with increasing intensity after some point.

Parameters

hsdata	Pointer to all available data and configurations.
itel	Sequence number of the telescope being processed.
al	The lower of the two tail-cut thresholds.
ah	The higher of the two tail-cut thresholds.
Iref	Determines which pixel, after sorting by amplitude, will be used as providing the reference
	amplitude. Example: use 3 for the third hottest pixel. If this number is \leq = 0, the classical
	scheme is used.
minfrac	Which fraction of the reference amplitude is required for pixels to be included in the final
	image. If this number is \leq = 0.0, the classical scheme is used.

References H_MAX_TEL, hess_tel_event_data_struct::image_pixels, hess_tel_event_adc_struct::known, hess_camera_settings_struct::num_pixels, hess_pixel_list::pixel_list::pixel_list::pixels, hess_tel_event_data_struct::raw, and hess_event_data_struct::teldata.

Referenced by image_reconstruct().

7.43.3.4 static int find_neighbours (CameraSettings * camset, int itel) [static]

Find the list of neighbours for each pixel.

References hess_camera_settings_struct::area, hess_camera_settings_struct::num_pixels, hess_camera_settings_struct::size, hess_camera_settings_struct::tel_id, hess_camera_settings_struct::xpix, and hess_camera_settings_struct::ypix.

Referenced by image_reconstruct(), and nb_peak_integration().

7.43.3.5 static int global_peak_integration (AllHessData * hsdata, int itel, int nsum, int nbefore, int * sigamp) [static]

Integrate sample-mode data (traces) over a common interval around a global signal peak.

The integration window can be anywhere in the available length of the traces. Since the calibration function subtracts a pedestal that corresponds to the total length of the traces we may also have to add a pedestal contribution for the samples not summed up. No weighting of individual samples is applied.

Parameters

hsdata	Pointer to all available data and configurations.
itel	Sequence number of the telescope being processed.
nsum	Number of samples to sum up (is reduced if exceeding available length).
nbefore	Start the integration a number of samples before the peak, as long as it fits into the available
	data range. Note: for multiple gains, this results in identical integration regions.

sigamp	Amplitude in ADC counts above pedestal at which a signal is considered as significant (sep-
	arate for high gain/low gain).

References hess_tel_event_adc_struct::adc_known, hess_tel_event_adc_struct::adc_sample, hess_tel_event_adc_struct::adc_sum, hess_event_data_struct::central, hess_central_event_data_struct::glob_count, H_MAX_TE-L, hess_tel_event_adc_struct::known, hess_tel_event_adc_struct::num_gains, hess_tel_event_adc_struct::num_pixels, hess_tel_event_adc_struct::num_samples, hess_tel_monitor_struct::pedestal, hess_tel_event_data_struct::raw, hess_tel_event_adc_struct::significant, hess_tel_event_data_struct::tel_id, hess_event_data_struct::teldata, and hess_tel_event_adc_struct::zero_sup_mode.

Referenced by pixel_integration().

7.43.3.6 static int image_reconstruct (AllHessData * hsdata, int itel, int cut_id, double tcl, double tch, int lref, double minfrac, int nimg, int flag_amp_tm, double clip_amp) [static]

Calibrate and clean image pixels and reconstruct second moments parameters from images.

References calibrate_amplitude(), clean_image_tailcut(), hess_tel_image_struct::cut_id, find_neighbours(), H_-MAX_TEL, hess_tel_event_data_struct::img, hess_tel_event_adc_struct::known, hess_tel_image_struct::known, hess_tel_event_data_struct::num_image_sets, pixel_timing_analysis(), hess_tel_event_data_struct::raw, second_moments(), and hess_event_data_struct::teldata.

Referenced by reconstruct().

7.43.3.7 static int local_peak_integration (AllHessData * hsdata, int itel, int nsum, int nbefore, int * sigamp) [static]

Integrate sample-mode data (traces) around a pixel-local signal peak.

The integration window can be anywhere in the available length of the traces. Since the calibration function subtracts a pedestal that corresponds to the total length of the traces we may also have to add a pedestal contribution for the samples not summed up. No weighting of individual samples is applied.

Parameters

hsdata	Pointer to all available data and configurations.
itel	Sequence number of the telescope being processed.
nsum	Number of samples to sum up (is reduced if exceeding available length).
nbefore	Start the integration a number of samples before the peak, as long as it fits into the available data range. Note: for multiple gains, this may result in identical integration regions (depending on signal).
sigamp	Amplitude in ADC counts above pedestal at which a signal is considered as significant (separate for high gain/low gain).

References hess_tel_event_adc_struct::adc_known, hess_tel_event_adc_struct::adc_sample, hess_tel_event_adc_struct::adc_sample, hess_tel_event_adc_struct::adc_sum, H_MAX_TEL, HI_GAIN, hess_tel_event_adc_struct::known, LO_GAIN, hess_tel_event_adc_struct::num_gains, hess_tel_event_adc_struct::num_pixels, hess_tel_event_adc_struct::num_samples, hess_tel_event_adc_struct::pedestal, hess_tel_event_data_struct::raw, hess_tel_event_adc_struct::significant, hess_event_data_struct::teldata, and hess_tel_event_adc_struct::zero_sup_mode.

Referenced by pixel_integration().

7.43.3.8 static int nb_peak_integration (AllHessData * hsdata, int lwt, int itel, int nsum, int nbefore, int * sigamp) [static]

Integrate sample-mode data (traces) around a peak in the signal sum of neighbouring pixels.

The integration window can be anywhere in the available length of the traces. Since the calibration function subtracts a pedestal that corresponds to the total length of the traces we may also have to add a pedestal contribution for the samples not summed up. No weighting of individual samples is applied.

Parameters

hsdata	Pointer to all available data and configurations.
lwt	Weight of the local pixel (0: peak from neighbours only, 1: local pixel counts as much as any
	neighbour).
itel	Sequence number of the telescope being processed.
nsum	Number of samples to sum up (is reduced if exceeding available length).
nbefore	Start the integration a number of samples before the peak, as long as it fits into the available
	data range. Note: for multiple gains, this results in identical integration regions.
sigamp	Amplitude in ADC counts above pedestal at which a signal is considered as significant (sep-
	arate for high gain/low gain).

References hess_tel_event_adc_struct::adc_known, hess_tel_event_adc_struct::adc_sample, hess_tel_event_adc_struct::adc_sum, find_neighbours(), H_MAX_SLICES, H_MAX_TEL, HI_GAIN, hess_tel_event_adc_struct::known, LO_GAIN, hess_tel_event_adc_struct::num_gains, hess_tel_event_adc_struct::num_pixels, hess_tel_event_adc_struct::num_samples, hess_tel_event_adc_struct::raw, hess_tel_event_adc_struct::raw, hess_tel_event_adc_struct::significant, hess_event_data_struct::teldata, and hess_tel_event_adc_struct::zero_sup_mode.

Referenced by pixel integration().

7.43.3.9 static int pixel_integration (AllHessData * hsdata, int itel, struct user_parameters * up) [static]

Pixel integration steering function.

Work is done in selected integration function.

References global_peak_integration(), user_parameters::integ_param, user_parameters::integ_thresh, user_parameters::integrator, local peak integration(), nb peak integration(), and simple integration().

Referenced by reconstruct().

7.43.3.10 static int pixel timing analysis (AllHessData * hsdata, int itel, int nimg) [static]

Calculate summary results from pixel timing data.

References hess_camera_settings_struct::flen, H_MAX_PIX_TIMES, H_MAX_TEL, hess_tel_event_data_struct::img, hess_pixel_timing_struct::known, hess_tel_event_data_struct::num_image_sets, hess_pixel_timing_struct::num_pixels, hess_pixel_timing_struct::num_types, hess_tel_image_struct::phi, PIX_TIME_PEAKPOS_TYPE, PIX_TIME_STARTPOS_REL_TYPE, PIX_TIME_WIDTH_ABS_TYPE, PIX_TIME_WIDTH_REL_TYPE, hess_tel_event_data_struct::pixtm, hess_event_data_struct::teldata, hess_pixel_timing_struct::time_level, hess_pixel_setting_struct::time_slice, hess_pixel_timing_struct::time_type, hess_pixel_timing_struct::timval, hess_tel_image_struct::tm_residual, hess_tel_image_struct::tm_residual, hess_tel_image_struct::tm_width1, hess_tel_image_struct::tm_width2, hess_tel_image_struct::xpix, hess_tel_image_struct::ypix.

Referenced by image_reconstruct().

7.43.3.11 int reconstruct (AllHessData * hsdata, int reco_flag, const double * min_amp, const size_t * min_pix, const double * tcl, const double * tch, const int * lref, const double * minfrac, int nimg, int flag_amp_tm)

Image/shower reconstruction function.

Parameters

hsdata	Pointer to all available data and configurations.
reco_flag	If $>= 3$ then redo image cleaning before shower reconstruction. If $>= 4$ then the total im-
	age intensities are re-determined and that may change which images are used or not in the shower reconstruction.

min_amp	The minimum amplitude required in images (telescope-specific, that means requiring an array
	of at least size H_MAX_TEL).
min_pix	The minimum number of pixels required in images (telescope-specific).
tcl	The lower of the two tail-cut thresholds (telescope-specific).
tch	The higher of the two tail-cut thresholds (telescope-specific).
Iref	Determines which pixel, after sorting by amplitude, will be used as providing the reference
	amplitude (telescope-specific). Example: use 3 for the third hottest pixel. If this number is
	<= 0, the classical scheme is used.
minfrac	Which fraction of the reference amplitude is required for pixels to be included in the final
	image (telescope-specific). If this number is \leq = 0.0, the classical scheme is used.
nimg	Which of (sometimes) several images should be filled? Use -1 to replace an existing image
	of the same cut id (if such an image exists) or add another image (if there is free space for it)
	or replace the first image (if all else fails). Use -2 to indicate that image analysis from normal
	integrated amplitude should go into first image and (if available) that from pixel timing (around
	local peak position or otherwise global peak position) should go into the second image.
flag_amp_tm	0: Use normal integrated amplitude. 1: Use integration around global peak position from
	pulse shape analysis. May include all pixels or only selected. 2: Use integration around local
	peak position from pulse shape analysis. Return 0 for pixels without a fairly significant peak.

References user_parameters::clip_amp, image_reconstruct(), hess_tel_event_data_struct::img, user_parameters::integrator, hess_tel_event_adc_struct::known, hess_run_header_struct::ntel, pixel_integration(), hess_tel_event_data_struct::raw, shower_reconstruct(), hess_event_data_struct::teldata, and user_get_type().

Referenced by main().

7.43.3.12 static int second_moments (AllHessData * hsdata, int itel, int cut_id, int nimg, double clip_amp) [static]

Reconstruction of second moments parameters from cleaned image.

References hess_mc_shower_struct::altitude, hess_tel_image_struct::amplitude, hess_mc_shower_struct::azimuth, hess_camera_settings_struct::cam_rot, user_parameters::clip_amp, hess_tel_image_struct::clip_amp, hess_tel_image_struct::cut_id, hess_mc_shower_struct::energy, hess_mc_event_struct::event, hess_camera_settings_struct::flen, H_MAX_TEL, hess_mc_shower_struct::hmax, hess_tel_event_data_struct::img, hess_tel_event_adc_struct::known, hess_tel_image_struct::known, hess_tel_image_struct::kurtosis, hess_tel_image_struct::l, line_point_distance(), hess_tel_event_data_struct::num_image_sets, hess_camera_settings_struct::num_pixels, hess_tel_image_struct::phi, hess_tel_image_struct::pixels, hess_tel_event_data_struct::raw, hess_tel_image_struct::skewness, hess_camera_settings_struct::tel_id, hess_run_header_struct::tel_pos, hess_event_data_struct::teldata, hess_tel_image_struct::w, hess_tel_image_struct::x, hess_mc_event_struct::xcore, hess_mc_shower_struct::xmax, hess_camera_settings_struct::xpix, hess_tel_image_struct::y, hess_mc_event_struct::ycore, and hess_camera_settings_struct::xpix.

Referenced by image_reconstruct().

7.43.3.13 void select_calibration_channel (int chn)

Control if only low-gain or high-gain should get used instead of both.

Parameters

chn	0 (both channels), 1 (only high gain), 2 (only low gain)

Referenced by main().

7.43.3.14 int set_disabled_pixels (AIIHessData * hsdata, int itel, double broken_pixels_fraction)

Set up pixels to be ignored (regarded as zero amplitude) in the analysis if they either have HV disabled or the camera active radius is clipped.

Parameters

hsdata	Pointer to all available data and configurations.
itel	Telescope index where we set new values.
broken_pixels	Optional fraction of additional pixels to be set like dead pixels (not usable for analysis).
fraction	

Disabled pixels are ignored in the evaluation of the camera radius.

References user_parameters::camera_clipping_deg, hess_camera_settings_struct::flen, H_MAX_TEL, hess_camera_settings_struct::num_pixels, hess_camera_settings_struct::size, which_telescope_type(), hess_camera_settings_struct::ypix.

Referenced by main().

7.43.3.15 static int simple_integration (AllHessData * hsdata, int itel, int nsum, int nskip) [static]

Integrate sample-mode data (traces) over a common and fixed interval.

The integration window can be anywhere in the available length of the traces. Since the calibration function subtracts a pedestal that corresponds to the total length of the traces we may also have to add a pedestal contribution for the samples not summed up. No weighting of individual samples is applied.

Parameters

hsdata	Pointer to all available data and configurations.
itel	Sequence number of the telescope being processed.
nsum	Number of samples to sum up (is reduced if exceeding available length).
nskip	Number of initial samples skipped (adapted such that interval fits into what is available). Note:
	for multiple gains, this results in identical integration regions.

References hess_tel_event_adc_struct::adc_known, hess_tel_event_adc_struct::adc_sample, hess_tel_event_adc_struct::adc_sum, H_MAX_TEL, hess_tel_event_adc_struct::known, hess_tel_event_adc_struct::num_gains, hess_tel_event_adc_struct::num_pixels, hess_tel_event_adc_struct::num_samples, hess_tel_monitor_struct::pedestal, hess_tel_event_data_struct::raw, hess_tel_event_adc_struct::significant, hess_event_data_struct::teldata, and hess_tel_event_adc_struct::zero_sup_mode.

Referenced by pixel_integration().

7.44 rh_sens_comp.cc File Reference

Combine a few basic columns from two sensitivity and and other performance listing files as produced by the rh3 utility and then optimized by the best_of utility.

```
#include "stdtools/strtools.hh"
#include "fileopen.h"
```

Include dependency graph for rh_sens_comp.cc:



Functions

- string pad_to (const string &s, size_t nmin)
- vector< vector< string > > read_table (const char *fname, size_t n_min)
- int **main** (int argc, char **argv)

7.44.1 Detailed Description

Combine a few basic columns from two sensitivity and and other performance listing files as produced by the rh3 utility and then optimized by the best_of utility. This is most convenient for producing performance ratio plots.

7.45 rndm2.h File Reference

Prototypes for random number generators adapted from HEP Random C++ code.

Macros

- #define rndm(idummy) RandFlat()
 - Backwards compatibility with rndm.c.
- #define rannor(mean, sigma) RandGauss(mean, sigma)
- #define rdmin(iseed) Ranlux setSeed(iseed,3);
- #define rdmout(piseed) fprintf(stderr,"rdmout() not implemented; use Ranlux_getStatus/Ranlux_setStatus instead\n");
- #define irndm(idummy) ((long)(RandFlat()*2147483648.))

Typedefs

- · typedef int HepBoolean
- typedef double(* PFVD_t)(void)

Functions

- void **SetRandomEngine** (PFVD t f)
- · void Ranlux_setSeed (long seed, int lux)
- void Ranlux_setSeeds (long *seeds, int lux)
- void Ranlux_getStatus (int *pseed, int seed_table[24], int *pi_lag, int *pj_lag, int *pcount24, double *pcarry)
- void Ranlux_setStatus (int *pseed, int seed_table[24], int *pi_lag, int *pj_lag, int *pcount24, double *pcarry)
- void Ranlux_saveStatus (const char *fname)
- void Ranlux_restoreStatus (const char *fname)
- void Ranlux_showStatus (void)
- double Ranlux_RandFlat (void)
- void Ranlux_RandFlatArray (int size, double *vect)
- double RandFlat (void)
- void RandFlatArray (int size, double *vect)
- void RandGauss_setFlag (HepBoolean val)
- HepBoolean RandGauss getFlag (void)
- void RandGauss setVal (double nextVal)
- · double RandGauss_getVal (void)
- double RandGauss (double mean, double sigma)
- · void RandPoisson_setOldMean (double val)
- double RandPoisson_getOldMean (void)
- double RandPoisson_getMaxMean (void)
- void RandPoisson_setPStatus (double sq, double alxm, double g)
- double * RandPoisson_getPStatus (void)
- long RandPoisson (double xm)
- double RandExponential (double mean)

7.45.1 Detailed Description

Prototypes for random number generators adapted from HEP Random C++ code.

Author

Konrad Bernloehr

Date

```
11 July 1997
```


```
CVS $Date: 2009/12/07 18:27:28 $
CVS $Revision: 1.5 $
```

7.46 straux.c File Reference

Check for abbreviations of strings and get words from strings.

```
#include "initial.h"
#include <ctype.h>
#include "straux.h"
```

Include dependency graph for straux.c:



Macros

• #define NO_INITIAL_MACROS 1

Functions

int abbrev (CONST char *s, CONST char *t)

Compare strings s and t.

• int getword (CONST char *s, int *spos, char *word, int maxlen, char blank, char endchar)

Copies a blank or '\0' or < endchar > delimeted word from position *spos of the string s to the string word and increment *spos to the position of the first non-blank character after the word.

• int stricmp (CONST char *a, CONST char *b)

Case independent comparison of character strings.

7.46 straux.c File Reference 297

7.46.1 Detailed Description

Check for abbreviations of strings and get words from strings.

Author

Konrad Bernloehr

Date

```
CVS $Date: 2010/07/20 13:37:45 $
```

Version

```
CVS $Revision: 1.4 $
```

7.46.2 Function Documentation

7.46.2.1 int abbrev (CONST char * s, CONST char * t)

Compare strings s and t.

s may be an abbreviation of t. Upper/lower case in s is ignored. s has to be at least as long as the leading upper case, digit, and '_' part of t.

Parameters

S	The string to be checked.
t	The test string with minimum part in upper case.

Returns

1 if s is an abbreviation of t, 0 if not.

Referenced by do_config(), find_config_item(), and init_config().

7.46.2.2 int getword (CONST char * s, int * spos, char * word, int maxlen, char blank, char endchar)

Copies a blank or '0' or < endchar > delimeted word from position *spos of the string s to the string word and increment *spos to the position of the first non-blank character after the word.

The word must have a length less than or equal to maxlen.

Parameters

S	string with any number of words.
spos	position in the string where we start and end.
word	the extracted word.
maxlen	the maximum allowed length of word.
blank	has the same effect as '', i.e. end-of-word.
endchar	his terminates the whole string (as '\0').

Returns

-2: Invalid string or NULL -1: The word was longer than maxlen (without the terminating '\0'); 0: There were no more words in the string s. 1: ok, we have a word and there are still more of them in the string s. 2: ok, but this was the last word

Referenced by addpath(), do_config(), initpath(), main(), prog_path(), reconfig(), and user_set_tel_type_param_by_str().

7.46.2.3 int stricmp (CONST char * a, CONST char * b)

Case independent comparison of character strings.

Parameters

a,b	- strings to be compared.


Returns

 $\bf 0$: strings are equal (except perhaps for case) $>\!\!0$: a is lexically 'greater' than b $<\!\!0$: a is lexically 'smaller' than b

7.47 straux.h File Reference

Check for abbreviations of strings and get words from strings.

This graph shows which files directly or indirectly include this file:



Macros

• #define CONST const

Functions

- int abbrev (CONST char *s, CONST char *t)
 - Compare strings s and t.
- int getword (CONST char *s, int *spos, char *word, int maxlen, char blank, char endchar)

Copies a blank or '\0' or < endchar > delimeted word from position *spos of the string s to the string word and increment *spos to the position of the first non-blank character after the word.

• int stricmp (CONST char *a, CONST char *b)

Case independent comparison of character strings.

7.47.1 Detailed Description

Check for abbreviations of strings and get words from strings.

Author

Konrad Bernloehr

Date

```
CVS $Date: 2010/07/20 13:37:45 $
```

Version

```
CVS $Revision: 1.2 $
```

7.47.2 Function Documentation

7.47.2.1 int abbrev (CONST char * s, CONST char * t)

Compare strings s and t.

s may be an abbreviation of t. Upper/lower case in s is ignored. s has to be at least as long as the leading upper case, digit, and '_' part of t.

Parameters

S	The string to be checked.
t	The test string with minimum part in upper case.

Returns

1 if s is an abbreviation of t, 0 if not.

7.47.2.2 int getword (CONST char * s, int * spos, char * word, int maxlen, char blank, char endchar)

Copies a blank or '\0' or < endchar > delimeted word from position *spos of the string s to the string word and increment *spos to the position of the first non-blank character after the word.

The word must have a length less than or equal to maxlen.

Parameters

S	string with any number of words.
spos	position in the string where we start and end.
word	the extracted word.
maxlen	the maximum allowed length of word.
blank	has the same effect as '', i.e. end-of-word.
endchar	his terminates the whole string (as '\0').

Returns

-2: Invalid string or NULL -1: The word was longer than maxlen (without the terminating '\0'); 0: There were no more words in the string s. 1: ok, we have a word and there are still more of them in the string s. 2: ok, but this was the last word

7.47.2.3 int stricmp (CONST char * a, CONST char * b)

Case independent comparison of character strings.

Parameters

a,b	- strings to be compared.

Returns


0: strings are equal (except perhaps for case) > 0: a is lexically 'greater' than b < 0: a is lexically 'smaller' than b

7.48 tohbook.c File Reference

Convert my histograms to HBOOK (PAW) histograms.

```
#include "initial.h"
#include "histogram.h"
#include "tohbook.h"
```

Include dependency graph for tohbook.c:



Functions

- void convert_histograms_to_hbook (const char *fname)
- int histogram_to_hbook (int ihisto, HISTOGRAM *histo)

7.48.1 Detailed Description


Convert my histograms to HBOOK (PAW) histograms.

7.49 toroot.cc File Reference

Functions for conversion of eventio histograms to ROOT format.

```
#include "TFile.h"
#include "TH1.h"
#include "TH2.h"
#include <string>
#include <sstream>
#include "initial.h"
#include "histogram.h"
#include "toroot.hh"
```

Include dependency graph for toroot.cc:



Functions

• string num2str (int i)

Convert an int to a string using the STL.

• string num2str (double d)

Convert a double to a string using the STL.

template<class T > string num2str (T num)

Convert various sorts of numbers to a string.

void convert_histograms_to_root (const char *fname)

Open a ROOT file for output, convert all histograms known and write to file.

• int histogram_to_root (int ihisto, HISTOGRAM *histo)

Create a ROOT histogram from the eventio histogram.

7.49.1 Detailed Description

Functions for conversion of eventio histograms to ROOT format.

Author

Konrad Bernloehr

Date

```
CVS $Date: 2011/04/15 13:48:04 $
```

Version

```
CVS $Revision: 1.12 $
```

7.49.2 Function Documentation

7.49.2.1 void convert_histograms_to_root (const char * fname)

Open a ROOT file for output, convert all histograms known and write to file.

Parameters

fname	Name of ROOT output file.
-------	---------------------------

References get_first_histogram(), histogram_to_root(), and histogram::next.

7.49.2.2 int histogram_to_root (int ihisto, HISTOGRAM * histo)

Create a ROOT histogram from the eventio histogram.

Create a ROOT histogram and fill it with the contents of the given histogram, if it contains any entries. If the histogram has an ID number, it is booked with this Id. Otherwise, 90000 + a sequential number is used.

Parameters

ihisto	Histogram sequential number
histo	Histogram pointer

Returns

0 (ok), -1 (invalid histogram)

References histogram::counts, Histogram_Extension::ddata, histogram::entries, histogram::extension, Histogram_Extension::fdata, get_histogram_by_ident(), histogram::ident, Histogram_Parameters::integer, Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, num2str(), histogram::overflow, histogram::overflow_2d, Histogram_Parameters::real, histogram::title, histogram::type, histogram::underflow, histogram::underflow_2d, and Histogram_Parameters::upper_limit.


Referenced by convert_histograms_to_root().

7.50 user_analysis.c File Reference

Code for analysis of simulated (and reconstructed) showers within the framework of the read_hess program.

```
#include <limits.h>
#include "initial.h"
#include "io_basic.h"
#include "mc_tel.h"
#include "io_hess.h"
#include "io_histogram.h"
#include "fileopen.h"
#include "rec_tools.h"
#include "reconstruct.h"
#include "user_analysis.h"
#include "atmprof.h"
#include "straux.h"
#include "basic_ntuple.h"
```

Include dependency graph for user_analysis.c:



Data Structures

- · struct tel type param
- · struct telescope_list
- · struct ebias_cor_data

Macros

#define MAX_TEL_TYPES 10

Functions

static void interp (double x, double *v, int n, int *ipl, double *rpl)

Linear interpolation with binary search algorithm.

static double rpol (double *x, double *y, int n, double xp)

Linear interpolation with binary search algorithm.

void user_set_lookup_file (const char *fname)

Override the automatic naming for lookup files.

void user set histogram file (const char *fname)

Override the automatic naming for histogram files.

void user_set_telescope_type (int itype)

Select a specific telescope type for setting user parameters.

int user_set_tel_type_param_by_str (const char *str)

Set telescope type parameters from a string (e.g.

int which_telescope_type (const struct hess_camera_settings_struct *cam_set)

Find out to which telescope type a telescope belongs, by best matching in the required parameters.

- struct user_parameters * user_get_parameters (int tp)
- int user_get_type (int itel)

Get the best matching telescope type for a given telescope index.

• static double eval cut param (double *cut, double lgE)

Evaluate energy-dependent cut parameters with.

- void <u>__attribute__</u> ((constructor))
- void user_set_flags (int uf)

Set user-defined flags: used to active HESS-style analysis.

• void user_set_spectrum (double di)

Set the difference between generated MC spectrum and the assumed source spectrum.

• void user_set_impact_range (double *impact_range)

Set the acceptable ranges for reconstructed impact positions.

void user_set_true_impact_range (double *true_impact_range)

Set the acceptable ranges for true impact positions.

• void user_set_max_core_distance (double rt)

Set the maximum core distance for telescopes if their images should be used beyond geometrical reconstruction.

void user_set_min_amp (double a)

Set the minimum amplitude of images usable for the analysis.

• void user set tail cuts (double tcl, double tch, int lref, double minfrac)

Set the lower and upper tail cuts for the standard two-level tail-cut scheme.

void user_set_min_pix (int mpx)

Set the minimum number of significant pixels in usable images.

· void user set reco flag (int rf)

Set the reconstruction level flag ('-r' option in read_hess).

void user_set_tel_img (int tmn, int tmx)

Set the minimum and maximum number of usable images for events used in analysis.

void user_set_tel_list (size_t min_tel, size_t ntel, int *tel_id)

You may have alternative selections of (fewer) telescopes.

void user set max theta (double thmax, double thscale, double thmin)

Set the maximum angle between source and reconstructed shower direction.

void user set theta escale (double *thes)

By default the angular acceptance is the 80% containment radius.

void user set de cut (double *dec)

The dE cut can be made more or less strict by a scale parameter which should be 1.0 by default and is below 1 for a stricter cut and above 1 for a looser cut.

• void user_set_de2_cut (double *de2c)

Since the dE2 cut is not always of any help with default cut parameters, you can change the parameter to your needs.

void user_set_hmax_cut (double hmaxc)

The hmax cut can be made or or less strict by a scale parameter which should be 1.0 by default and is below 1 for a stricter cut and above 1 for a looser cut.

void user_set_shape_cuts (double wmin, double wmax, double lmin, double lmax)

Set shape cut parameters.

void user set width max cut (double *wmax)

Set energy dependent scaled width limit.

void user_set_length_max_cut (double *Imax)

Set energy dependent scaled length limit.

void user_set_clipping (double dc)

Set the maximum radius to be used of a camera.

• void user_set_clipamp (double cpa)

Set the maximum amplitude in a pixel.

void user_set_trg_req (int trg_req)

Set the required trigger type(s) as a bit pattern.

- void user_set_diffuse_mode (int dm, double oar[])
- void user_set_verbosity (int v)
- int user_selected_event ()
- void user_set_auto_lookup (int al)
- void user_set_integrator (int scheme)
- void user_set_integ_window (int nsum, int noff)
- void user_set_integ_threshold (int ithg, int itlg)
- void user set integ no rescale (int no)
- void user_set_calib_scale (double s)
- void user_set_nb_radius (double *r)
- void user_set_nxt_radius (double r)
- static double expected_max_height (double E, double theta, double height)

Expected height of the shower maximum above the detector for gamma rays, based on simple analytical formula and exponential atmospheric profile.

• static double expected max distance (double E, double theta, double height)

Expected distance of the shower maximum from the detector for gamma rays, based on simple analytical formula and exponential atmospheric profile.

static int img_norm (double w, double I, double A, double IgA, double rc, int tel_type, double *scrw, double *scrl, double *scr, double *scr, double *rco, double *rcor, double *dimgo, double *dimgor)

Get scaled + reduced scaled image parameters (both HEGRA and HESS type scaling) as well as energy scaling from the lookups.

double ebias correction (double IgE)

Ask for a correction to log10(reconstructed energy), if available.

void set_ebias_correction (HISTOGRAM *h)

Set correction to log10(reconstructed energy), if available.

• static void user_init (AllHessData *hsdata)

Initialisation of user analysis, booking of histograms etc.

• static void user_mc_shower_fill (AllHessData *hsdata)

Work to be done once per generated shower.

static void user mc event fill (AllHessData *hsdata)

Work to be done once per shower usage.

static void user_event_fill (AllHessData *hsdata, int stage)

Fill (triggered) event specific histograms etc.

static void user_done (AllHessData *hsdata)

After all data for a file (usually one run) was processed.

static char * prog_path (void)

Find the path from which the current program was started.

static void user_finish (AllHessData *hsdata)

Final call before program terminates.

• int do_user_ana (AllHessData *hsdata, unsigned long item_type, int stage)

Variables

- static int verbosity = 0
- static int user init done = 0
- static int current_tel_type = 0
- static struct tel_type_param def_tel_type_param [MAX_TEL_TYPES]
- static int saved_tel_type [H_MAX_TEL]
- static char user_lookup_fname [1024]
- static char hist_fname [1024]
- static struct telescope list * alt list = NULL
- static size_t **n_list** = 0
- static double max_theta = 0.2 * (M_PI/180.)
- static double min_theta = 0.2 * (M_PI/180.)
- static struct user_parameters up [MAX_TEL_TYPES+2]
- · static int nparams

Number of parameters, including: the gamma-ray source offset plus d_sp_idx, min_amp, tailcut_low, tailcut_high, min pix, reco flag, min tel img, max tel img, max theta, theta scale.

- static int nparams_i
- · static int nparams d
- static double * params
- static double opt_theta_cut [7][H_MAX_TEL]

Angular cut limit is multiplicity dependent.

- static int diffuse mode = 0
- static double **diffuse off axis min** = 0.
- static double diffuse_off_axis_max = M_PI/2.
- static int event_selected = 0
- static int auto_lookup = 0
- static int telescope_type [H_MAX_TEL]

Declare local (static) data here ...

- static char lookup_fname [1024]
- · static double Az_src
- · static double Alt src
- static double Az_nom
- · static double Alt nom
- · static double source offset
- static MOMENTS * pixmom = NULL
- · static struct ebias cor data ebias
- struct basic_ntuple bnt

7.50.1 Detailed Description

Code for analysis of simulated (and reconstructed) showers within the framework of the read_hess program. Users wanting to make use of such analysis should modify the user_* functions provided here or the do_user_ana() function. Except for the do_user_ana() function and the user_set_...() functions, all functions are declared as static to emphasize that their interfaces can be changed here to the user's desires.

Author

Konrad Bernloehr

Date

initial version: August 2006

CVS \$Date: 2015/04/30 09:47:11 \$

Version

CVS \$Revision: 1.70 \$

7.50.2 Function Documentation

7.50.2.1 double ebias_correction (double IgE)

Ask for a correction to log10(reconstructed energy), if available.

Returns

Bias in log10(energy), to be subtracted from log10(energy), or 0.

References rpol().

Referenced by user_event_fill().

7.50.2.2 static double eval_cut_param (double * cut, double lgE) [static]

Evaluate energy-dependent cut parameters with.

Parameters

	cut[0]	the cut parameter at 1 TeV (IgE=0),
	cut[1]	the slope of the cut parameters versus IgE,
	cut[2]	the minimum cut parameter,
Ī	cut[3]	the maximum cut parameter.

Referenced by user_event_fill().

7.50.2.3 static double expected_max_distance (double E, double theta, double height) [static]

Expected distance of the shower maximum from the detector for gamma rays, based on simple analytical formula and exponential atmospheric profile.

Parameters

Ε	The energy of the shower [TeV].
theta	Then zenith angle of the shower [radians].
height	The height above sea level of the experiment [m].

Returns

Distance of shower maximum from detector [m]

References expected_max_height().

Referenced by user_event_fill().

7.50.2.4 static double expected_max_height (double *E*, double theta, double height) [static]

Expected height of the shower maximum above the detector for gamma rays, based on simple analytical formula and exponential atmospheric profile.

Parameters

Ε	The energy of the shower [TeV].
theta	Then zenith angle of the shower [radians].
height	The height above sea level of the experiment [m].

Returns

Height of shower maximum above detector [m]

Referenced by expected_max_distance().

7.50.2.5 static int img_norm (double w, double l, double A, double lgA, double rc, int tel_type, double * scrw, double * scrl, double * sce, double * sce, double * rco, double * rco, double * rco, double * dimgo, double * dimgo, double * dimgo) [static]

Get scaled + reduced scaled image parameters (both HEGRA and HESS type scaling) as well as energy scaling from the lookups.

All variables for the results are optional. For variables which are of no interest, pass a NULL pointer.

Parameters

W	Image width [rad].
1	Image length [rad].
Α	Image amplitude [peak p.e.].
lgA	log10(A)
rc	Reconstructed core distance.
tel_type	Telescope type (for multiple lookups).
scrw	Variable getting the scaled reduced width (HESS style).
scrl	Variable getting the scaled reduced length (HESS style).
SCW	Variable getting the scaled width (HEGRA style).
scl	Variable getting the scaled length (HEGRA style).
sce	Variable getting the expected energy [TeV] for the given amplitude at the given core distance.
scer	Variable getting the relative fluctuation of energy/amplitude at this point.

rco	Variable getting the expected core distance based on width/length and amplitude.
rcor	Variable getting the relative error in the core distance estimate.
dimgo	Variable getting the expected distance in the image (as for rco).
dimgor	Variable getting the relative error in the image distance estimate.

References Histogram_Extension::ddata, histogram::extension, get_histogram_by_ident(), Histogram_Parameters::lower_limit, histogram::nbins, histogram::nbins_2d, Histogram_Parameters::real, and Histogram_Parameters::upper_limit.

Referenced by user_event_fill().

7.50.2.6 static void interp (double x, double *v, int n, int *ipl, double *rpl) [static]

Linear interpolation with binary search algorithm.

Linear interpolation between data point in sorted (i.e. monotonic ascending or descending) order. This function determines between which two data points the requested coordinate is and where between them. If the given coordinate is outside the covered range, the value for the corresponding edge is returned.

A binary search algorithm is used for fast interpolation.

Parameters

Х	Input: the requested coordinate
V	Input: tabulated coordinates at data points
n	Input: number of data points
ipl	Output: the number of the data point following the requested coordinate in the given sorting
	$(1 \le ipl \le n-1)$
rpl	Output: the fraction $(x-v[ipl-1])/(v[ipl]-v[ipl-1])$ with $0 \le rpl \le 1$

Referenced by rpol().

7.50.2.7 static char * prog_path (void) [static]

Find the path from which the current program was started.

References getword().

Referenced by user_finish().

7.50.2.8 static double rpol (double * x, double * y, int n, double xp) [static]

Linear interpolation with binary search algorithm.

Linear interpolation between data point in sorted (i.e. monotonic ascending or descending) order. The resulting interpolated value is returned as a return value.

This function calls interp() to find out where to interpolate.

Parameters

X	Input: Coordinates for data table
у	Input: Corresponding values for data table
n	Input: Number of data points
хр	Input: Coordinate of requested value

Returns

Interpolated value

References interp().

Referenced by ebias_correction().

7.50.2.9 static void user_done (AllHessData * hsdata) [static]

After all data for a file (usually one run) was processed.

7.50.2.10 static void user_event_fill (AllHessData * hsdata, int stage) [static]

Fill (triggered) event specific histograms etc.

- < true energy [TeV]
- < Event for desired spectral slope
- < true core distance [m]
- < reconstructed core distance [m]
- < image amplitude [peak p.e.]
- < image width [rad]
- < image length [rad]
- < radius of image c.o.g. in camera plane
- < distance of image c.o.g. to source [rad]
- < Amplitude and edge distance are ok

References basic ntuple::acceptance, basic_ntuple::alt, hess_shower_parameter::Alt, basic_ntuple::alt_true, hess-_mc_shower_struct::altitude, hess_tracking_event_data_struct::altitude_cor, hess_tracking_event_data_struct-::altitude_raw, hess_tel_image_struct::amplitude, angle_between(), angles_to_offset(), hess_mc_run_headerstruct::atmosphere, basic ntuple::az, hess shower parameter::Az, basic ntuple::az true, hess mc showerstruct::azimuth, hess tracking event data struct::azimuth cor, hess tracking event data struct::azimuth-_raw, calibrate_pixel_amplitude(), hess_event_data_struct::central, basic_ntuple::chi2_e, clear_moments(), user_parameters::clip_amp, hess_tracking_event_data_struct::cor_known, user_parameters::d_sp_idx, ebias_correction(), hess shower parameter::energy, hess mc shower struct::energy, hess shower parameter::err-_dir1, hess_shower_parameter::err_dir2, eval_cut_param(), basic_ntuple::event, hess_mc_event_struct::event, expected_max_distance(), fill_histogram_by_ident(), fill_moments(), hess_mc_shower_struct::h_first_int, H_-MAX_TEL, hess_tel_image_struct::hot_amp, hess_tel_event_data_struct::image_pixels, hess_tel_event_datastruct::img, img norm(), user parameters::impact range, init atmprof(), hess tel event adc struct::known, hess_tel_image_struct::known, hess_tel_image_struct::l, basic_ntuple::lg_e, basic_ntuple::lg_e_true, line_point-_distance(), basic_ntuple::mdisp, user_parameters::min_amp, user_parameters::min_pix, user_parameters::min-_tel_img, hess_shower_parameter::mscl, basic_ntuple::mscrl, basic_ntuple::mscrw, hess_shower_parameter-::mscw, basic ntuple::n fail, basic ntuple::n img, basic ntuple::n pix, basic ntuple::n trg, basic ntuple::n tsl0, hess_run_header_struct::ntel, hess_tel_image_struct::num_hot, hess_tel_event_data_struct::num_image_sets, hess_shower_parameter::num_img, hess_central_event_data_struct::num_teltrg, hess_mc_run_header_struct-::obsheight, opt_theta_cut, hess_tel_image_struct::phi, hess_pixel_list::pixel_list, hess_pixel_list::pixels, hess_tel image struct::pixels, basic ntuple::primary, hess mc shower struct::primary id, hess tel event data struct-::raw, basic_ntuple::rcm, refidx(), hess_shower_parameter::result_bits, basic_ntuple::run, hess_run_header_struct-::run, hess_event_data_struct::shower, basic_ntuple::sig_e, basic_ntuple::sig_mscrl, basic_ntuple::sig_mscrw, basic_ntuple::sig_theta, basic_ntuple::sig_xmax, stat_moments(), hess_tel_event_data_struct::tel_id, hess_run-_header_struct::tel_pos, hess_event_data_struct::teldata, basic_ntuple::theta, user_parameters::theta_escale, thickx(), hess tel image struct::tm residual, hess tel image struct::tm rise, hess tel image struct::tm slope, hess tel image struct::tm width1, hess tel image struct::tm width2, hess event data struct::trackdata, user parameters::true impact range, basic ntuple::tslope, basic ntuple::tsphere, user parameters::user flags, hesstel image struct::w, basic ntuple::weight, hess tel image struct::x, basic ntuple::xc, hess shower parameter-::xc, basic_ntuple::xc_true, hess_mc_event_struct::xcore, basic_ntuple::xfirst_true, basic_ntuple::xmax, hess_shower parameter::xmax, hess mc shower struct::xmax, basic ntuple::xmax true, hess tel image struct::y, basic ntuple::yc, hess shower parameter::yc, basic ntuple::yc true, and hess mc event struct::ycore.

7.50.2.11 static void user_finish (AllHessData * hsdata) [static]

Final call before program terminates.

References hess_mc_shower_struct::primary_id, prog_path(), and write_all_histograms().

7.50.2.12 int user_get_type (int itel)

Get the best matching telescope type for a given telescope index.

If user analysis is not activated, this will always be type 0.

References H_MAX_TEL.

Referenced by calibrate_amplitude(), calibrate_pixel_amplitude(), main(), and reconstruct().

7.50.2.13 static void user_mc_event_fill (AllHessData * hsdata) [static]

Work to be done once per shower usage.

Depending on sim_hessarray flags this might be called only for triggered events or also for non-triggered events (default).

References hess_mc_shower_struct::altitude, hess_mc_shower_struct::azimuth, user_parameters::d_sp_idx, hess_mc_shower_struct::energy, fill_histogram_by_ident(), line_point_distance(), hess_mc_event_struct::xcore, and hess_mc_event_struct::ycore.

7.50.2.14 static void user_mc_shower_fill (AllHessData * hsdata) [static]

Work to be done once per generated shower.

7.50.2.15 void user_set_clipping (double dc)

Set the maximum radius to be used of a camera.

References user_parameters::camera_clipping_deg.

Referenced by main().

7.50.2.16 void user_set_flags (int uf)

Set user-defined flags: used to active HESS-style analysis.

Parameters

uf 0: not exactly HESS-style analysis; 1: HESS-style standard cuts; 2: HESS-style hard cuts;
 3: HESS-style loose cuts. >=4: HESS-style (no re-scaling) but user-defined cut parameters.

References user_parameters::user_flags.

Referenced by main().

7.50.2.17 void user_set_length_max_cut (double * Imax)

Set energy dependent scaled length limit.

Referenced by main().

```
7.50.2.18 int user_set_tel_type_param_by_str ( const char * str )
```

Set telescope type parameters from a string (e.g.

on the command line).

Can be used to set all relevant parameters (others set to 0) or just to switch the active type (no parameters other than the type number).

References getword().

Referenced by main().

```
7.50.2.19 void user_set_theta_escale ( double * thes )
```

By default the angular acceptance is the 80% containment radius.

Performance may improve by using a smaller radius at low energies (stricter cut) and a larger radius at high energies (looser cut). This sets an additional lg(E) dependent scaling factor.

References user_parameters::theta_escale.

Referenced by main().

```
7.50.2.20 void user_set_width_max_cut ( double * wmax )
```

Set energy dependent scaled width limit.

Referenced by main().

7.50.3 Variable Documentation

```
7.50.3.1 double opt_theta_cut[7][H_MAX_TEL] [static]
```

Angular cut limit is multiplicity dependent.

Referenced by user_event_fill(), and user_init().

```
7.50.3.2 int telescope_type[H_MAX_TEL] [static]
```


Declare local (static) data here ...

7.51 warning.c File Reference

Pass warning messages to the screen or a usr function as set up.

```
#include "initial.h"
#include "warning.h"
#include <errno.h>
```

Include dependency graph for warning.c:



Data Structures

· struct warn_specific_data

A struct used to store thread-specific data.

Macros

- #define __WARNING_MODULE 1
- #define get_warn_specific() (&warn_defaults)

Functions

- void warn_f_warning (const char *msgtext, const char *msgorigin, int msglevel, int msgno)

 Issue a warning to screen or other configured target.
- int set_warning (int level, int mode)

Set a specific warning level and mode.

- int set default warning (int level, int mode)
- void warning_status (int *plevel, int *pmode)

Inquire status of warning settings.

• void set_logging_function (void(*user_function)(const char *, const char *, int, int))

Set user-defined function for logging warnings and errors.

- void set default logging function (void(*user function)(const char *, const char *, int, int))
- int set_log_file (const char *fname)

Set a new log file name and save it in local storage.

void warn_f_output_text (const char *text)

Print a text string (without appending a newline etc.) on the screen or send it to a controlling process, depending on the setting of the output function.

void flush_output ()

Flush buffered output.

void set_output_function (void(*user_function)(const char *))

Set a user-defined function as the function to be used for normal text output.

- void set_default_output_function (void(*user_function)(const char *))
- void set_aux_warning_function (char *(*auxfunc)(void))

Set an auxilliary function for warnings.

void set_default_aux_warning_function (char *(*auxfunc)(void))

Variables

static struct warn_specific_data warn_defaults

7.51.1 Detailed Description

Pass warning messages to the screen or a usr function as set up.

```
@author    Konrad Bernloehr
@date    @verbatim CVS $Date: 2014/02/20 10:53:06 $

Version
    CVS $Revision: 1.9 $
```

One of the most import parameter for setting up the bevaviour is the warning level:

7.51.2 Function Documentation

```
7.51.2.1 void flush_output (void)
```

Flush buffered output.

Output is flushed, no matter if it is standard output or a special output function;

Returns

(none)

Referenced by set_output_function().

```
7.51.2.2 void set_aux_warning_function ( char *(*)(void) auxfunc )
```

Set an auxilliary function for warnings.

This function may be used to insert time and date or origin etc. at the beginning of the warning text.

Parameters

```
auxfunc - Pointer to a function taking no argument and returning a character string.
```

Returns

(none)

7.51.2.3 int set_log_file (const char * fname)

Set a new log file name and save it in local storage.

If there was a log file with a different name opened previously, close it.

Parameters

fname	New name of log file for warnings

Returns

```
0 (o.k.), -1 (error)
```

References warn_specific_data::logfname.

7.51.2.4 void set_logging_function (void(*)(const char *, const char *, int, int) user_function)

Set user-defined function for logging warnings and errors.

Set a user-defined function as the function to be used for logging warnings and errors. To enable usage of this function, bit 2 of the warning mode must be set and other bits reset, if logging to screen and/or disk file is no longer wanted.

Parameter userfunc: Pointer to a function taking two strings (the message text and the origin text, which may be NULL) and two integers (message level and message number).

Returns

(none)

7.51.2.5 void set_output_function (void(*)(const char *) user_function)

Set a user-defined function as the function to be used for normal text output.

Such a function may be used to send output back to a remote control process via network.

Parameter userfunc: Pointer to a function taking a string (the text to be displayed) as argument.

Returns

(none)

References flush_output().

7.51.2.6 int set_warning (int level, int mode)

Set a specific warning level and mode.

Parameters

level	Warnings with level below this are ignored.
mode	To screen, to file, with user function

Returns

0 if ok, -1 if level and/or mode could not be set.

7.51.2.7 void warn_f_output_text (const char * text)

Print a text string (without appending a newline etc.) on the screen or send it to a controlling process, depending on the setting of the output function.

Parameters

text	A text string to be displayed.
ιολι	A tokt offing to be displayed.

Returns

(none)

7.51.2.8 void warn_f_warning (const char * msgtext, const char * msgorigin, int msglevel, int msgno)

Issue a warning to screen or other configured target.

Issue a warning to screen and/or file if the warning has a sufficiently large message 'level' (high enough severity). This function should best be called through the macros 'Information', 'Warning', and 'Error'. The name of this function has been changed from 'warning' to '_warning' to avoid trouble if you call 'warning' instead of 'Warning'. Now such a typo causes an error in the link step.

Parameters

msgtext	Warning or error text.
msgorigin	Optional origin (e.g. function name) or NULL.
msglevel Level of message importance: negative: debugging if needed, 0-9: informative, 10-	
	ing, 20-29: error.
msgno	Number of message or 0.

Returns

(none)

References warn_specific_data::logfname.

7.51.2.9 void warning_status (int * plevel, int * pmode)

Inquire status of warning settings.

Parameters

plevel	Pointer to variable for storing current level.
pmode	Pointer to store the current warning mode.

Returns

(none)

7.51.3 Variable Documentation

7.51.3.1 struct warn specific data warn_defaults [static]


Initial value:

```
0,
1+8,
"",
"warning.log",
",
0,
NULL,
NULL,
NULL,
NULL,
```

7.52 warning.h File Reference

Pass warning messages to the screen or a usr function as set up.

This graph shows which files directly or indirectly include this file:



Macros

- #define WARNING_ORIGIN (char *) NULL
- #define Information(string) warn f warning(string, WARNING ORIGIN, 0, 0)
- #define Warning(string) warn_f_warning(string,WARNING_ORIGIN,10,0)
- #define **Error**(string) warn_f_warning(string,WARNING_ORIGIN,20,0)
- #define Output(string) warn_f_output_text(string)

Functions

void warn_f_warning (const char *text, const char *origin, int level, int msgno)

Issue a warning to screen or other configured target.

int set_warning (int level, int mode)

Set a specific warning level and mode.

- int set_default_warning (int level, int mode)
- void warning_status (int *plevel, int *pmode)

Inquire status of warning settings.

void set_logging_function (void(*user_function)(const char *, const char *, int, int))

Set user-defined function for logging warnings and errors.

- void set_default_logging_function (void(*user_function)(const char *, const char *, int, int))
- int set_log_file (const char *fname)

Set a new log file name and save it in local storage.

void warn_f_output_text (const char *text)

Print a text string (without appending a newline etc.) on the screen or send it to a controlling process, depending on the setting of the output function.

void flush_output (void)

Flush buffered output.

void set_output_function (void(*user_function)(const char *))

Set a user-defined function as the function to be used for normal text output.

- void set_default_output_function (void(*user_function)(const char *))
- void set aux warning function (char *(*auxfunc)(void))

Set an auxilliary function for warnings.

- void set_default_aux_warning_function (char *(*auxfunc)(void))
- char * warn_f_get_message_buffer (void)

7.52.1 Detailed Description

Pass warning messages to the screen or a usr function as set up.

Author

Konrad Bernloehr

Date

```
CVS $Date: 2010/07/20 13:37:45 $
```

Version

```
CVS $Revision: 1.5 $
```

7.52.2 Function Documentation

```
7.52.2.1 void flush_output (void)
```

Flush buffered output.

Output is flushed, no matter if it is standard output or a special output function;

Returns

(none)

Referenced by set_output_function().

7.52.2.2 void set_aux_warning_function (char *(*)(void) auxfunc)

Set an auxilliary function for warnings.

This function may be used to insert time and date or origin etc. at the beginning of the warning text.

Parameters

```
auxfunc - Pointer to a function taking no argument and returning a character string.
```

Returns

(none)

7.52.2.3 int set_log_file (const char * fname)

Set a new log file name and save it in local storage.

If there was a log file with a different name opened previously, close it.

Parameters

fname	New name of log file for warnings

Returns

References warn_specific_data::logfname.

7.52.2.4 void set_logging_function (void(*)(const char *, const char *, int, int) user_function)

Set user-defined function for logging warnings and errors.

Set a user-defined function as the function to be used for logging warnings and errors. To enable usage of this function, bit 2 of the warning mode must be set and other bits reset, if logging to screen and/or disk file is no longer wanted.

Parameter userfunc: Pointer to a function taking two strings (the message text and the origin text, which may be NULL) and two integers (message level and message number).

Returns

(none)

7.52.2.5 void set_output_function (void(*)(const char *) user_function)

Set a user-defined function as the function to be used for normal text output.

Such a function may be used to send output back to a remote control process via network.

Parameter userfunc: Pointer to a function taking a string (the text to be displayed) as argument.

Returns

(none)

References flush_output().

7.52.2.6 int set_warning (int level, int mode)

Set a specific warning level and mode.

Parameters

level	Warnings with level below this are ignored.
mode	To screen, to file, with user function

Returns

0 if ok, -1 if level and/or mode could not be set.

7.52.2.7 void warn_f_output_text (const char * text)

Print a text string (without appending a newline etc.) on the screen or send it to a controlling process, depending on the setting of the output function.

Parameters

text	A text string to be displayed.

Returns

(none)

7.52.2.8 void warn_f_warning (const char * msgtext, const char * msgorigin, int msglevel, int msgno)

Issue a warning to screen or other configured target.

Issue a warning to screen and/or file if the warning has a sufficiently large message 'level' (high enough severity). This function should best be called through the macros 'Information', 'Warning', and 'Error'. The name of this function has been changed from 'warning' to '_warning' to avoid trouble if you call 'warning' instead of 'Warning'. Now such a typo causes an error in the link step.

Parameters

msgtext	Warning or error text.
msgorigin	Optional origin (e.g. function name) or NULL.
msglevel Level of message importance: negative: debugging if needed, 0-9: informative, 10-	
	ing, 20-29: error.
msgno	Number of message or 0.

Returns

(none)

References warn_specific_data::logfname.

7.52.2.9 void warning_status (int * plevel, int * pmode)

Inquire status of warning settings.

Parameters

plevel	Pointer to variable for storing current level.
pmode	Pointer to store the current warning mode.

Returns

(none)

Index

STR	atmprof.c, 108
hconfig.h, 157	heighx, 109
	init_atmprof, 109
A, 31	interp, 110
abbrev	refidx, 110
hconfig.h, 157	rhofx, 110
straux.c, 291	rpol, 111
straux.h, 294	thickx, 111
acceptance	aweight
basic_ntuple, 33	hess mc event struct, 62
add_histogram	az
histogram.c, 165	basic ntuple, 33
histogram.h, 185	az true
add_histograms.c, 107	basic_ntuple, 34
addexepath	ap.e, • .
fileopen.c, 136	B, 31
fileopen.h, 139	basic_ntuple, 31
addpath	acceptance, 33
fileopen.c, 136	alt, 33
fileopen.h, 139	alt true, 33
alloc_2d_int_histogram	az, 33
histogram.c, 166	az_true, 34
histogram.h, 185	chi2 e, 34
alloc_2d_real_histogram	lg_e, 34
histogram.c, 166	lg_e_true, 34
histogram.h, 186	mdisp, 34
alloc_int_histogram	mscrl, 34
-	
histogram.c, 167	mscrw, 34
histogram.h, 186	n_fail, 34
alloc_moments	n_img, 34
histogram.h, 186	n_pix, 35
moments.c, 267	n_trg, 35
alloc_real_histogram	n_tsl0, 35
histogram.c, 167	primary, 35
histogram.h, 187	rcm, 35
allocate_histogram	run, 35
histogram.c, 167	sig_e, 35
histogram.h, 187	sig_mscrl, 35
alt	sig_mscrw, 35
basic_ntuple, 33	sig_theta, 36
alt_az_arrow	sig_xmax, 36
camera_image.c, 117	theta, 36
alt_true	tslope, 36
basic_ntuple, 33	tsphere, 36
angle_between	weight, 36
rec_tools.h, 277	xc, 36
angles_to_offset	xc_true, 36
rec_tools.h, 277	xfirst_true, 37
atime	xmax, 37
photo_electron, 97	xmax_true, 37

yc, 37	ps_head1, 118
yc_true, 37	ps_trailer, 118
basic_ntuple.h, 111	check_autoload_trgmask
list_ntuple, 112	The merge_simtel program, 23
begin_read_tel_array	check_hessio_max
io_simtel.c, 231	io_hess.c, 209
mc_tel.h, 251	io_hess.h, 220
begin_write_tel_array	check_trgmask.c, 118
io_simtel.c, 231	chi2_e
mc_tel.h, 251	basic_ntuple, 34
best_of.cc, 113	clean_image_tailcut
best_value, 38	reconstruct.c, 283
Binary_Interface_Chain, 39	clear_histogram
binary_config	histogram.c, 169
ConfigValues, 50	histogram.h, 189
book_1d_histogram	clear_moments
histogram.c, 168	histogram.h, 189
histogram.h, 187	moments.c, 268
book_histogram	clear_shower_extra_parameters
histogram.c, 168	io_simtel.c, 231
histogram.h, 188	mc_tel.h, 252
book_int_histogram	clip_amp
histogram.c, 169	user_parameters, 103
histogram.h, 188	cmdline
bound	io_history.c, 227
ConfigIntern, 46	cmdtime
build_config	io_history.c, 227
hconfig.c, 148	cmp_popen
hconfig.h, 157	fileopen.c, 136
bunch, 39	code
CALIB SCALE	hess_pixel_list, 70
CALIB_SCALE	hess_pixel_list, 70 coinc_count
reconstruct.c, 281	_ -
reconstruct.c, 281 The read_hess (aka read_simtel, read_cta) pro-	coinc_count
reconstruct.c, 281 The read_hess (aka read_simtel, read_cta) program, 25	coinc_count hess_tel_monitor_struct, 85
reconstruct.c, 281 The read_hess (aka read_simtel, read_cta) program, 25 The read_hess_nr program, 27	coinc_count hess_tel_monitor_struct, 85 compact_bunch, 40
reconstruct.c, 281 The read_hess (aka read_simtel, read_cta) program, 25 The read_hess_nr program, 27 CFG_MUTEX	coinc_count hess_tel_monitor_struct, 85 compact_bunch, 40 Config_Binary_Item_Interface, 40
reconstruct.c, 281 The read_hess (aka read_simtel, read_cta) program, 25 The read_hess_nr program, 27 CFG_MUTEX hconfig.h, 157	coinc_count hess_tel_monitor_struct, 85 compact_bunch, 40 Config_Binary_Item_Interface, 40 copy_func, 41
reconstruct.c, 281 The read_hess (aka read_simtel, read_cta) program, 25 The read_hess_nr program, 27 CFG_MUTEX hconfig.h, 157 calib	coinc_count hess_tel_monitor_struct, 85 compact_bunch, 40 Config_Binary_Item_Interface, 40 copy_func, 41 delete_func, 41
reconstruct.c, 281 The read_hess (aka read_simtel, read_cta) program, 25 The read_hess_nr program, 27 CFG_MUTEX hconfig.h, 157 calib hess_laser_calib_data_struct, 60	coinc_count hess_tel_monitor_struct, 85 compact_bunch, 40 Config_Binary_Item_Interface, 40 copy_func, 41 delete_func, 41 elem_size, 41
reconstruct.c, 281 The read_hess (aka read_simtel, read_cta) program, 25 The read_hess_nr program, 27 CFG_MUTEX hconfig.h, 157 calib hess_laser_calib_data_struct, 60 calib_scale	coinc_count hess_tel_monitor_struct, 85 compact_bunch, 40 Config_Binary_Item_Interface, 40 copy_func, 41 delete_func, 41 elem_size, 41 io_item_type, 41
reconstruct.c, 281 The read_hess (aka read_simtel, read_cta) program, 25 The read_hess_nr program, 27 CFG_MUTEX hconfig.h, 157 calib hess_laser_calib_data_struct, 60 calib_scale user_parameters, 103	coinc_count hess_tel_monitor_struct, 85 compact_bunch, 40 Config_Binary_Item_Interface, 40 copy_func, 41 delete_func, 41 elem_size, 41 io_item_type, 41 list_func, 42
reconstruct.c, 281 The read_hess (aka read_simtel, read_cta) program, 25 The read_hess_nr program, 27 CFG_MUTEX hconfig.h, 157 calib hess_laser_calib_data_struct, 60 calib_scale user_parameters, 103 calibrate_amplitude	coinc_count hess_tel_monitor_struct, 85 compact_bunch, 40 Config_Binary_Item_Interface, 40 copy_func, 41 delete_func, 41 elem_size, 41 io_item_type, 41 list_func, 42 new_func, 42 read_func, 42
reconstruct.c, 281 The read_hess (aka read_simtel, read_cta) program, 25 The read_hess_nr program, 27 CFG_MUTEX hconfig.h, 157 calib hess_laser_calib_data_struct, 60 calib_scale user_parameters, 103 calibrate_amplitude reconstruct.c, 281	coinc_count hess_tel_monitor_struct, 85 compact_bunch, 40 Config_Binary_Item_Interface, 40 copy_func, 41 delete_func, 41 elem_size, 41 io_item_type, 41 list_func, 42 new_func, 42 read_func, 42 readtext_func, 42
reconstruct.c, 281 The read_hess (aka read_simtel, read_cta) program, 25 The read_hess_nr program, 27 CFG_MUTEX hconfig.h, 157 calib hess_laser_calib_data_struct, 60 calib_scale user_parameters, 103 calibrate_amplitude reconstruct.c, 281 calibrate_pixel_amplitude	coinc_count hess_tel_monitor_struct, 85 compact_bunch, 40 Config_Binary_Item_Interface, 40 copy_func, 41 delete_func, 41 elem_size, 41 io_item_type, 41 list_func, 42 new_func, 42 read_func, 42 readtext_func, 42 write_func, 42
reconstruct.c, 281 The read_hess (aka read_simtel, read_cta) program, 25 The read_hess_nr program, 27 CFG_MUTEX hconfig.h, 157 calib hess_laser_calib_data_struct, 60 calib_scale user_parameters, 103 calibrate_amplitude reconstruct.c, 281 calibrate_pixel_amplitude reconstruct.c, 282	coinc_count hess_tel_monitor_struct, 85 compact_bunch, 40 Config_Binary_Item_Interface, 40 copy_func, 41 delete_func, 41 elem_size, 41 io_item_type, 41 list_func, 42 new_func, 42 read_func, 42 readfext_func, 42 write_func, 42 config_binary_convert_data
reconstruct.c, 281 The read_hess (aka read_simtel, read_cta) program, 25 The read_hess_nr program, 27 CFG_MUTEX hconfig.h, 157 calib hess_laser_calib_data_struct, 60 calib_scale user_parameters, 103 calibrate_amplitude reconstruct.c, 281 calibrate_pixel_amplitude reconstruct.c, 282 The read_hess_nr program, 27	coinc_count hess_tel_monitor_struct, 85 compact_bunch, 40 Config_Binary_Item_Interface, 40 copy_func, 41 delete_func, 41 elem_size, 41 io_item_type, 41 list_func, 42 new_func, 42 read_func, 42 readfext_func, 42 write_func, 42 config_binary_convert_data hconfig.h, 158
reconstruct.c, 281 The read_hess (aka read_simtel, read_cta) program, 25 The read_hess_nr program, 27 CFG_MUTEX hconfig.h, 157 calib hess_laser_calib_data_struct, 60 calib_scale user_parameters, 103 calibrate_amplitude reconstruct.c, 281 calibrate_pixel_amplitude reconstruct.c, 282 The read_hess_nr program, 27 cam_to_ref	coinc_count hess_tel_monitor_struct, 85 compact_bunch, 40 Config_Binary_Item_Interface, 40 copy_func, 41 delete_func, 41 elem_size, 41 io_item_type, 41 list_func, 42 new_func, 42 read_func, 42 readtext_func, 42 write_func, 42 config_binary_convert_data hconfig.h, 158 config_binary_read_text
reconstruct.c, 281 The read_hess (aka read_simtel, read_cta) program, 25 The read_hess_nr program, 27 CFG_MUTEX hconfig.h, 157 calib hess_laser_calib_data_struct, 60 calib_scale user_parameters, 103 calibrate_amplitude reconstruct.c, 281 calibrate_pixel_amplitude reconstruct.c, 282 The read_hess_nr program, 27 cam_to_ref rec_tools.h, 277	coinc_count hess_tel_monitor_struct, 85 compact_bunch, 40 Config_Binary_Item_Interface, 40 copy_func, 41 delete_func, 41 elem_size, 41 io_item_type, 41 list_func, 42 new_func, 42 read_func, 42 readtext_func, 42 write_func, 42 config_binary_convert_data hconfig.h, 158 config_binary_read_text hconfig.h, 158
reconstruct.c, 281 The read_hess (aka read_simtel, read_cta) program, 25 The read_hess_nr program, 27 CFG_MUTEX hconfig.h, 157 calib hess_laser_calib_data_struct, 60 calib_scale user_parameters, 103 calibrate_amplitude reconstruct.c, 281 calibrate_pixel_amplitude reconstruct.c, 282 The read_hess_nr program, 27 cam_to_ref rec_tools.h, 277 camera_clipping_deg	coinc_count hess_tel_monitor_struct, 85 compact_bunch, 40 Config_Binary_Item_Interface, 40 copy_func, 41 delete_func, 41 elem_size, 41 io_item_type, 41 list_func, 42 new_func, 42 read_func, 42 readtext_func, 42 write_func, 42 config_binary_convert_data hconfig.h, 158 config_binary_read_text hconfig_binary_text_length
reconstruct.c, 281 The read_hess (aka read_simtel, read_cta) program, 25 The read_hess_nr program, 27 CFG_MUTEX hconfig.h, 157 calib hess_laser_calib_data_struct, 60 calib_scale user_parameters, 103 calibrate_amplitude reconstruct.c, 281 calibrate_pixel_amplitude reconstruct.c, 282 The read_hess_nr program, 27 cam_to_ref rec_tools.h, 277 camera_clipping_deg user_parameters, 103	coinc_count hess_tel_monitor_struct, 85 compact_bunch, 40 Config_Binary_Item_Interface, 40 copy_func, 41 delete_func, 41 elem_size, 41 io_item_type, 41 list_func, 42 new_func, 42 read_func, 42 readtext_func, 42 write_func, 42 config_binary_convert_data hconfig.h, 158 config_binary_read_text hconfig_binary_text_length hconfig.h, 158
reconstruct.c, 281 The read_hess (aka read_simtel, read_cta) program, 25 The read_hess_nr program, 27 CFG_MUTEX hconfig.h, 157 calib hess_laser_calib_data_struct, 60 calib_scale user_parameters, 103 calibrate_amplitude reconstruct.c, 281 calibrate_pixel_amplitude reconstruct.c, 282 The read_hess_nr program, 27 cam_to_ref rec_tools.h, 277 camera_clipping_deg user_parameters, 103 camera_image.c, 115	coinc_count hess_tel_monitor_struct, 85 compact_bunch, 40 Config_Binary_Item_Interface, 40 copy_func, 41 delete_func, 41 elem_size, 41 io_item_type, 41 list_func, 42 new_func, 42 read_func, 42 readfunc, 42 write_func, 42 config_binary_convert_data hconfig.h, 158 config_binary_text_length hconfig_binary_write_name
reconstruct.c, 281 The read_hess (aka read_simtel, read_cta) program, 25 The read_hess_nr program, 27 CFG_MUTEX hconfig.h, 157 calib hess_laser_calib_data_struct, 60 calib_scale user_parameters, 103 calibrate_amplitude reconstruct.c, 281 calibrate_pixel_amplitude reconstruct.c, 282 The read_hess_nr program, 27 cam_to_ref rec_tools.h, 277 camera_clipping_deg user_parameters, 103 camera_image.c, 115 alt_az_arrow, 117	coinc_count hess_tel_monitor_struct, 85 compact_bunch, 40 Config_Binary_Item_Interface, 40 copy_func, 41 delete_func, 41 elem_size, 41 io_item_type, 41 list_func, 42 new_func, 42 read_func, 42 readtext_func, 42 write_func, 42 config_binary_convert_data hconfig.h, 158 config_binary_text_length hconfig.h, 158 config_binary_write_name hconfig.h, 158
reconstruct.c, 281 The read_hess (aka read_simtel, read_cta) program, 25 The read_hess_nr program, 27 CFG_MUTEX hconfig.h, 157 calib hess_laser_calib_data_struct, 60 calib_scale user_parameters, 103 calibrate_amplitude reconstruct.c, 281 calibrate_pixel_amplitude reconstruct.c, 282 The read_hess_nr program, 27 cam_to_ref rec_tools.h, 277 camera_clipping_deg user_parameters, 103 camera_image.c, 115 alt_az_arrow, 117 find_neighbours, 116	coinc_count hess_tel_monitor_struct, 85 compact_bunch, 40 Config_Binary_Item_Interface, 40 copy_func, 41 delete_func, 41 elem_size, 41 io_item_type, 41 list_func, 42 new_func, 42 read_func, 42 readtext_func, 42 write_func, 42 config_binary_convert_data hconfig.h, 158 config_binary_text_length hconfig.h, 158 config_binary_write_name hconfig.h, 158 config_binary_write_text
reconstruct.c, 281 The read_hess (aka read_simtel, read_cta) program, 25 The read_hess_nr program, 27 CFG_MUTEX hconfig.h, 157 calib hess_laser_calib_data_struct, 60 calib_scale user_parameters, 103 calibrate_amplitude reconstruct.c, 281 calibrate_pixel_amplitude reconstruct.c, 282 The read_hess_nr program, 27 cam_to_ref rec_tools.h, 277 camera_clipping_deg user_parameters, 103 camera_image.c, 115 alt_az_arrow, 117 find_neighbours, 116 hesscam_ps_plot, 116	coinc_count hess_tel_monitor_struct, 85 compact_bunch, 40 Config_Binary_Item_Interface, 40 copy_func, 41 delete_func, 41 elem_size, 41 io_item_type, 41 list_func, 42 new_func, 42 read_func, 42 readtext_func, 42 write_func, 42 config_binary_convert_data hconfig.h, 158 config_binary_read_text hconfig.h, 158 config_binary_text_length hconfig.h, 158 config_binary_write_name hconfig.h, 158 config_binary_write_text hconfig_binary_write_text hconfig.h, 158
reconstruct.c, 281 The read_hess (aka read_simtel, read_cta) program, 25 The read_hess_nr program, 27 CFG_MUTEX hconfig.h, 157 calib hess_laser_calib_data_struct, 60 calib_scale user_parameters, 103 calibrate_amplitude reconstruct.c, 281 calibrate_pixel_amplitude reconstruct.c, 282 The read_hess_nr program, 27 cam_to_ref rec_tools.h, 277 camera_clipping_deg user_parameters, 103 camera_image.c, 115 alt_az_arrow, 117 find_neighbours, 116 hesscam_ps_plot, 116 print_pix_col, 117	coinc_count hess_tel_monitor_struct, 85 compact_bunch, 40 Config_Binary_Item_Interface, 40 copy_func, 41 delete_func, 41 elem_size, 41 io_item_type, 41 list_func, 42 new_func, 42 read_func, 42 readtext_func, 42 write_func, 42 config_binary_convert_data hconfig.h, 158 config_binary_read_text hconfig.h, 158 config_binary_write_name hconfig.h, 158 config_binary_write_text hconfig_binary_write_text hconfig_binary_write_text hconfig_defaults
reconstruct.c, 281 The read_hess (aka read_simtel, read_cta) program, 25 The read_hess_nr program, 27 CFG_MUTEX hconfig.h, 157 calib hess_laser_calib_data_struct, 60 calib_scale user_parameters, 103 calibrate_amplitude reconstruct.c, 281 calibrate_pixel_amplitude reconstruct.c, 282 The read_hess_nr program, 27 cam_to_ref rec_tools.h, 277 camera_clipping_deg user_parameters, 103 camera_image.c, 115 alt_az_arrow, 117 find_neighbours, 116 hesscam_ps_plot, 116 print_pix_col, 117 ps_begin_page1, 117	coinc_count hess_tel_monitor_struct, 85 compact_bunch, 40 Config_Binary_Item_Interface, 40 copy_func, 41 delete_func, 41 elem_size, 41 io_item_type, 41 list_func, 42 new_func, 42 read_func, 42 readfunc, 42 write_func, 42 config_binary_convert_data hconfig.h, 158 config_binary_read_text hconfig.h, 158 config_binary_text_length hconfig.h, 158 config_binary_write_name hconfig.h, 158 config_binary_write_text hconfig.h, 158 config_binary_write_text hconfig.h, 158 config_binary_write_text hconfig.h, 158 config_defaults hconfig.c, 152
reconstruct.c, 281 The read_hess (aka read_simtel, read_cta) program, 25 The read_hess_nr program, 27 CFG_MUTEX hconfig.h, 157 calib hess_laser_calib_data_struct, 60 calib_scale user_parameters, 103 calibrate_amplitude reconstruct.c, 281 calibrate_pixel_amplitude reconstruct.c, 282 The read_hess_nr program, 27 cam_to_ref rec_tools.h, 277 camera_clipping_deg user_parameters, 103 camera_image.c, 115 alt_az_arrow, 117 find_neighbours, 116 hesscam_ps_plot, 116 print_pix_col, 117	coinc_count hess_tel_monitor_struct, 85 compact_bunch, 40 Config_Binary_Item_Interface, 40 copy_func, 41 delete_func, 41 elem_size, 41 io_item_type, 41 list_func, 42 new_func, 42 read_func, 42 readtext_func, 42 write_func, 42 config_binary_convert_data hconfig.h, 158 config_binary_read_text hconfig.h, 158 config_binary_write_name hconfig.h, 158 config_binary_write_text hconfig_binary_write_text hconfig_binary_write_text hconfig_defaults

ConfigBoundary, 43	time_string, 122
ConfigDataPointer, 44	current.h, 122
ConfigIntern, 44	current_localtime, 123
bound, 46	current_time, 123
elem_size, 46	mkgmtime, 124
itype, 46	reset_local_offset, 124
Ibound hard, 46	set_current_offset, 124
Ibound soft, 46	set_local_offset, 124
locked, 46	time string, 125
ubound hard, 46	current localtime
— · · · · · · · · · · · · · · · · · · ·	current.c, 121
ubound_soft, 46	current.h, 123
values, 46	
ConfigltemStruct, 47	current_time
data, 48	current b. 122
flags, 48	current.h, 123
function, 48	cvt2.c, 125
initial, 48	cvt3.cc, 126
internal, 48	d into a naram
Ibound, 48	d_integ_param
name, 48	user_parameters, 103
res1, 48	d_sp_idx
res2, 49	user_parameters, 103
size, 49	data
type, 49	ConfigItemStruct, 48
ubound, 49	data_changed
validate, 49	ConfigValues, 50
ConfigValues, 49	data_saved
binary_config, 50	ConfigValues, 50
data_changed, 50	ddata
	Histogram_Extension, 91
data_saved, 50	default_config
elem_size, 50	hconfig.c, 152
elements, 50	delete func
itype, 50	Config_Binary_Item_Interface, 41
list_mod, 50	describe histogram
max_mod, 51	histogram.c, 169
mod_flag, 51	histogram.h, 189
name, 51	dhsort
nmod, 51	dhsort.c, 128
section, 51	dhsort.c, 127
configs	dhsort, 128
io_history.c, 227	direction
conv_depth	hess_run_header_struct, 75
hess run header struct, 75	disable_permissive_pipes
conv_ref_pos	
hess run header struct, 75	fileopen.c, 136
convert_histograms_to_root	fileopen.h, 139
toroot.cc, 296	display_2d_histogram
copy_func	histogram.c, 170
Config_Binary_Item_Interface, 41	display_all_histograms
current	histogram.c, 170
	histogram.h, 190
hess_tel_monitor_struct, 85	display_histogram
current.c, 119	histogram.c, 170
current_localtime, 121	histogram.h, 190
current_time, 121	drawer_temp
mkgmtime, 121	hess_tel_monitor_struct, 85
reset_local_offset, 121	
set_current_offset, 121	ebias_cor_data, 51
set_local_offset, 122	ebias_correction

user_analysis.c, 301	listpath, 137
elem_size	permissive_pipes, 138
Config_Binary_Item_Interface, 41	root_exe_path, 138
ConfigIntern, 46	root_path, 138
ConfigValues, 50	set_permissive_pipes, 137
elements	uri_popen, 137
ConfigValues, 50	fileopen.h, 138
enable_permissive_pipes	addexepath, 139
fileopen.c, 136	addpath, 139
fileopen.h, 139	disable_permissive_pipes, 139
end_read_tel_array	enable_permissive_pipes, 139
io_simtel.c, 231	fileclose, 139
mc_tel.h, 252	fileopen, 139
end_write_tel_array	initpath, 140
io_simtel.c, 232	listpath, 140
mc_tel.h, 252	set_permissive_pipes, 140
entries	fill_2d_int_histogram
histogram, 89	histogram.c, 171
ev_reg_chain, 52	histogram.h, 190
eval_cut_param	fill_2d_real_histogram
user_analysis.c, 301	histogram.c, 171
eventio_registry.c, 128	histogram.h, 191
find_ev_reg_std, 129	fill_2d_weighted_histogram
read_eventio_registry, 129	histogram.c, 172
set_ev_reg_std, 130	histogram.h, 191
eventio_registry.h, 130	fill_gaps
find_ev_reg_std, 131	gen_lookup.c, 142
read_eventio_registry, 131	fill_histogram
set_ev_reg_std, 131	histogram.c, 172
exe_popen	histogram.h, 192
fileopen.c, 136	fill_histogram_by_ident
expected_max_distance	histogram.c, 173
user_analysis.c, 301	histogram.h, 192
expected_max_height	fill_int_histogram
user_analysis.c, 302	histogram.c, 173
extract_hess.c, 132	histogram.h, 192
fact stat bistoryana	fill mean
fast_stat_histogram	histogram.h, 193
histogram.c, 171	moments.c, 268
histogram.h, 190	fill_mean_and_sigma
fcat.c, 133	histogram.h, 193
filectose	moments.c, 268
fileopen.c, 136	fill moments
fileopen.h, 139	histogram.h, 193
fileopen fileopen.c, 137	moments.c, 268
• •	fill_real_histogram
fileopen.h, 139	histogram.c, 173
fileopen.c, 133	histogram.h, 193
addexepath, 136	fill_real_mean
addpath, 136	histogram.h, 194
cmp_popen, 136	moments.c, 268
disable_permissive_pipes, 136	fill_real_mean_and_sigma
enable_permissive_pipes, 136	histogram.h, 194
exe_popen, 136	_
filectose, 136	moments.c, 269
fileopen, 137	fill_real_moments
freeexepath, 137	histogram.h, 194
freepath, 137	moments.c, 269
initpath, 137	fill_weighted_histogram

histogram.c, 174	rec_tools.h, 277
histogram.h, 194	getword
find_config_item	hconfig.h, 159
hconfig.c, 148	straux.c, 291
hconfig.h, 158	straux.h, 294
find_ev_reg_std	global_peak_integration
eventio_registry.c, 129	reconstruct.c, 283
eventio_registry.h, 131	granularity
find_neighbours	hess_pixel_timing_struct, 72
camera_image.c, 116	H CHECK MAX
reconstruct.c, 283	H_CHECK_MAX
find_tel_idx	io_hess.h, 218
io_hess.c, 209	H_MAX_FSHAPE
find_trgmask	io_hess.h, 218
io_trgmask.c, 243	H_MAX_HOTPIX
io_trgmask.h, 246	io_hess.h, 218
first_config_block	H_MAX_PIX_TIMES
hconfig.c, 153	io_hess.h, 218
flags	H_MAX_PROFILE
ConfigItemStruct, 48	io_hess.h, 219
flush_output	H_MAX_SLICES
warning.c, 308	io_hess.h, 219
warning.h, 313	HI_GAIN
fparam	io_hess.h, 219
shower_extra_parameters, 99	HISTCOUNT
free_all_histograms	histogram.h, 184
histogram.c, 174	HISTVALUE_REAL
histogram.h, 195	histogram.h, 184
free_histo_contents	hconfig.c, 143
histogram.c, 174	build_config, 148
free_histogram	config_defaults, 152
histogram.c, 175	default_config, 152
histogram.h, 195	find_config_item, 148
free moments	first_config_block, 153
histogram.h, 195	get_config_filename, 148
moments.c, 269	get_config_preprocessor, 148
freeexepath	init_config, 150
fileopen.c, 137	read_config_lines, 150
freepath	read_config_status, 150
fileopen.c, 137	reconfig, 151
function	reload_config, 151
ConfigItemStruct, 48	set_config_filename, 151
Gormgitom Gradet, 10	set config history, 151
gen lookup.c, 140	set_config_preprocessor, 152
fill gaps, 142	set_config_stack, 152
gen_trgmask.c, 143	hconfig.h, 153
get_config_filename	_STR_, 157
hconfig.c, 148	abbrev, 157
hconfig.h, 159	build_config, 157
get_config_preprocessor	CFG_MUTEX, 157
hconfig.c, 148	config_binary_convert_data, 158
hconfig.h, 159	config_binary_read_text, 158
get_first_histogram	config_binary_text_length, 158
histogram.c, 175	config_binary_write_name, 158
histogram.h, 195	config_binary_write_text, 158
get_histogram_by_ident	find_config_item, 158
histogram.c, 175	get_config_filename, 159
histogram.h, 196	get_config_preprocessor, 159
get_shower_trans_matrix	getword, 159
300.10.10uu.iv	90

init_config, 159	offset_fov, 75
read_config_lines, 160	reverse_flag, 75
read_config_status, 160	run, 76
reconfig, 160	run_type, 76
reload_config, 161	tel_pos, 76
set_config_filename, 161	tracking_mode, 76
set_config_history, 161	hess_shower_parameter, 76
set_config_preprocessor, 161	hess_tel_event_adc_struct, 77
set_config_stack, 162	hess tel event data struct, 79
heighx	hess_tel_image_struct, 80
atmprof.c, 109	l, 82
hess_all_data_struct, 52	num_hot, 82
hess_camera_organisation_struct, 54	phi, <mark>82</mark>
hess_camera_settings_struct, 54	tm_slope, 82
mirror_area, 55	x, 82
hess camera software setting struct, 56	hess_tel_monitor_struct, 82
zero_sup_mode, 56	coinc_count, 85
hess_central_event_data_struct, 57	current, 85
teldata pattern, 58	drawer_temp, 85
teltrg_pattern, 58	hess_time_struct, 85
teltrg_time, 58	hess tracking event data struct, 86
hess_event_data_struct, 58	hess_tracking_setup_struct, 86
hess_laser_calib_data_struct, 59	range_low_az, 87
	-
calib, 60	hesscam_ps_plot
max_int_frac, 60	camera_image.c, 116
max_pixtm_frac, 60	hessio_doc.h, 162
hess_mc_event_struct, 61	HistOutput
aweight, 62	histogram.c, 165
hess_mc_pe_list, 62	histogram, 87
hess_mc_pe_sum_struct, 62	entries, 89
photons_atm_qe, 63	next, 89
hess_mc_photons, 63	overflow, 89
hess_mc_run_header_struct, 64	overflow_2d, 89
shower_prog_id, 66	tentries, 89
hess_mc_shower_profile_struct, 66	type, 89
id, 66	underflow, 90
hess_mc_shower_struct, 67	underflow_2d, 90
primary_id, 68	histogram.c, 162
xmax, 68	add_histogram, 165
hess_pixel_calibrated_struct, 68	alloc_2d_int_histogram, 166
hess_pixel_disabled_struct, 69	alloc_2d_real_histogram, 166
hess_pixel_list, 69	alloc_int_histogram, 167
code, 70	alloc_real_histogram, 167
hess_pixel_setting_struct, 70	allocate_histogram, 167
hess_pixel_timing_struct, 71	book_1d_histogram, 168
granularity, 72	book_histogram, 168
pulse_sum_glob, 72	book_int_histogram, 169
pulse_sum_loc, 72	clear_histogram, 169
threshold, 72	describe_histogram, 169
time_level, 72	display_2d_histogram, 170
timval, 72	display_all_histograms, 170
hess_pointing_correction_struct, 73	display_histogram, 170
hess_run_end_mc_statistics_struct, 73	fast_stat_histogram, 171
hess_run_end_statistics_struct, 73	fill_2d_int_histogram, 171
hess_run_header_struct, 74	fill_2d_real_histogram, 171
conv_depth, 75	fill_2d_weighted_histogram, 172
conv_ref_pos, 75	fill_histogram, 172
direction, 75	fill_histogram_by_ident, 173
•	_ 3 _ 7 7

fill_int_histogram, 173	HISTCOUNT, 184
fill_real_histogram, 173	HISTVALUE_REAL, 184
fill_weighted_histogram, 174	histogram_hashing, 196
free_all_histograms, 174	histogram_matching, 196
free_histo_contents, 174	histogram_to_lookup, 196
free_histogram, 175	list_histograms, 198
get_first_histogram, 175	locate_histogram_fraction, 198
get_histogram_by_ident, 175	lookup_int, 198
HistOutput, 165	lookup_real, 199
histogram_hashing, 175	print_histogram, 199
histogram_matching, 177	set_first_histogram, 199
histogram_to_lookup, 177	sort_histograms, 200
list_histograms, 177	stat_histogram, 200
locate_histogram_fraction, 177	stat_moments, 200
lookup_int, 178	unlink_histogram, 200
lookup_real, 178	Histogram_Extension, 90
primetab, 180	ddata, 91
print_histogram, 178	Histogram_Parameters, 91
set_first_histogram, 179	integer, 92
sort_histograms, 179	inverse_binwidth, 92
stat_histogram, 179	real, 92
unlink_histogram, 180	histogram_hashing
histogram.h, 180	histogram.c, 175
add histogram, 185	histogram.h, 196
alloc_2d_int_histogram, 185	histogram_matching
alloc_2d_real_histogram, 186	histogram.c, 177
alloc int histogram, 186	histogram.h, 196
alloc_moments, 186	histogram_to_lookup
alloc_real_histogram, 187	histogram.c, 177
allocate_histogram, 187	histogram.h, 196
_ ·	histogram_to_root
book_1d_histogram, 187	toroot.cc, 297
book_histogram, 188	history.h, 201
book_int_histogram, 188	history_struct, 92
clear_histogram, 189	histstat, 93
clear_moments, 189	
describe_histogram, 189	id
display_all_histograms, 190 display histogram, 190	hess_mc_shower_profile_struct, 66
	shower_extra_parameters, 99
fast_stat_histogram, 190	image_reconstruct
fill_2d_int_histogram, 190	reconstruct.c, 284
fill_2d_real_histogram, 191	img_norm
fill_2d_weighted_histogram, 191	user_analysis.c, 302
fill_histogram, 192	impact_range
fill_histogram_by_ident, 192	user_parameters, 103
fill_int_histogram, 192	incpath, 93
fill_mean, 193	init_atmprof
fill_mean_and_sigma, 193	atmprof.c, 109
fill_moments, 193	init_config
fill_real_histogram, 193	hconfig.c, 150
fill_real_mean, 194	hconfig.h, 159
fill_real_mean_and_sigma, 194	init_shower_extra_parameters
fill_real_moments, 194	io_simtel.c, 232
fill_weighted_histogram, 194	mc_tel.h, 252
free_all_histograms, 195	initial
free_histogram, 195	ConfigItemStruct, 48
free_moments, 195	initial.h, 202
get_first_histogram, 195	initpath
get_histogram_by_ident, 196	fileopen.c, 137

fileopen.h, 140	cmdline, 227
integ_no_rescale	cmdtime, 227
user parameters, 104	configs, 227
integ_param	io_history.h, 227
user parameters, 104	io_item_type
integer	Config Binary Item Interface, 41
Histogram_Parameters, 92	io_simtel.c, 228
integrator	begin_read_tel_array, 231
user_parameters, 104	begin_write_tel_array, 231
internal	clear_shower_extra_parameters, 231
ConfigItemStruct, 48	end_read_tel_array, 231
interp	end_write_tel_array, 232
atmprof.c, 110	init_shower_extra_parameters, 232
user_analysis.c, 303	print_camera_layout, 232
intersect_lines	print_photo_electrons, 232
rec_tools.h, 278	print_tel_block, 233
inverse_binwidth	print_tel_offset, 233
Histogram Parameters, 92	print_tel_photons, 233
io_hess.c, 204	print tel pos, 233
check_hessio_max, 209	private_shower_extra_parameters, 242
find tel idx, 209	read_camera_layout, 234
print_hess_pixcalib, 209	read_input_lines, 234
read_hess_pixcalib, 209	read_photo_electrons, 234
set_tel_idx, 209	read_shower_longitudinal, 235
set_tel_idx_ref, 210	read_tel_array_end, 235
write_hess_event, 210	read_tel_array_head, 235
write_hess_laser_calib, 210	read_tel_block, 236
write_hess_mc_event, 210	read_tel_offset, 236
write_hess_mc_pe_sum, 210	read_tel_offset_w, 236
write_hess_mc_shower, 211	read_tel_photons, 237
write_hess_pixcalib, 211	read_tel_pos, 237
write_hess_run_stat, 211	write_camera_layout, 238
write_hess_shower, 211	write_input_lines, 238
write_hess_tel_monitor, 212	write_photo_electrons, 238
write_hess_teladc_samples, 212	write_shower_longitudinal, 239
write_hess_teladc_sums, 212	write_tel_array_end, 239
write_hess_televent, 213	write_tel_array_head, 239
io_hess.h, 213	write_tel_block, 239
check_hessio_max, 220	write_tel_compact_photons, 240
H_CHECK_MAX, 218	write_tel_offset, 240
H_MAX_FSHAPE, 218	write_tel_offset_w, 240
H_MAX_HOTPIX, 218	write_tel_photons, 241
H_MAX_PIX_TIMES, 218	write_tel_pos, 241
H_MAX_PROFILE, 219	io_trgmask.c, 242
H_MAX_SLICES, 219	find_trgmask, 243
HI_GAIN, 219	print_hashed_trgmasks, 243
LO_GAIN, 219	trgmask_fill_hashed, 243
io_histogram.c, 220	trgmask_scan_log, 243
print_histograms, 221	io_trgmask.h, 245
read_histograms, 221	find_trgmask, 246
read_histograms_x, 221	print_hashed_trgmasks, 246
write_histograms, 222	trgmask_fill_hashed, 246
io_histogram.h, 222	trgmask_scan_log, 246
print_histograms, 224	iparam
read_histograms, 224	shower_extra_parameters, 99
read_histograms_x, 224	is_set
write_histograms, 225	shower_extra_parameters, 99
io_history.c, 225	itype

ConfigIntern, 46	map_tel_struct, 94
ConfigValues, 50	map_to
	The merge_simtel program, 23
	max_int_frac
hess_tel_image_struct, 82	hess_laser_calib_data_struct, 60
LO_GAIN	max mod
io_hess.h, 219	ConfigValues, 51
lambda	max_pixtm_frac
photo_electron, 97	hess_laser_calib_data_struct, 60
lbound	mc_tel.h, 248
ConfigItemStruct, 48	begin read tel array, 251
Ibound hard	begin write tel array, 251
ConfigIntern, 46	clear_shower_extra_parameters, 252
lbound_soft	
ConfigIntern, 46	end_read_tel_array, 252
lg_e	end_write_tel_array, 252
basic ntuple, 34	init_shower_extra_parameters, 252
lg e true	print_camera_layout, 254
basic_ntuple, 34	print_photo_electrons, 254
line_point_distance	print_tel_block, 254
rec_tools.h, 278	print_tel_offset, 254
linked_string, 94	print_tel_photons, 255
list func	print_tel_pos, 255
-	read_camera_layout, 255
Config_Binary_Item_Interface, 42	read_input_lines, 256
list_histograms	read_photo_electrons, 256
histogram.c, 177	read_shower_longitudinal, 256
histogram.h, 198	read_tel_array_end, 257
list_histograms.c, 247	read_tel_array_head, 257
list_mod	read_tel_block, 257
ConfigValues, 50	read_tel_offset, 258
list_ntuple	read_tel_offset_w, 258
basic_ntuple.h, 112	read_tel_photons, 258
listpath	read_tel_pos, 259
fileopen.c, 137	write_camera_layout, 259
fileopen.h, 140	write_input_lines, 259
local_peak_integration	write photo electrons, 260
reconstruct.c, 284	
locate_histogram_fraction	write_shower_longitudinal, 260
histogram.c, 177	write_tel_array_end, 260
histogram.h, 198	write_tel_array_head, 261
locked	write_tel_block, 261
ConfigIntern, 46	write_tel_compact_photons, 261
logfname	write_tel_offset, 262
warn_specific_data, 105	write_tel_offset_w, 262
lookup_int	write_tel_photons, 263
histogram.c, 178	write_tel_pos, 263
histogram.h, 198	mdisp
lookup_real	basic_ntuple, 34
histogram.c, 178	merge_simtel.c, 263
histogram.h, 199	min_amp
	user_parameters, 104
main	min_pix
The add_histograms program, 13	user_parameters, 104
The extract_hess program, 20	min_tel_img
The hdata2hbook program (cvt2), 29	user parameters, 104
The list_histogram program, 17	mirror_area
The read_hess (aka read_simtel, read_cta) pro-	hess_camera_settings_struct, 55
gram, 25	mkgmtime
The read_hess_nr program, 27	current.c, 121
······································	, ·-·

ourrant h 194	hiotogram 90
current.h, 124	histogram, 89
mod_flag	permissive_pipes
ConfigValues, 51	fileopen.c, 138
moments, 95	phi
moments.c, 266	hess tel image struct, 82
alloc_moments, 267	
clear_moments, 268	photo_electron, 97
fill_mean, 268	atime, 97
fill_mean_and_sigma, 268	lambda, 97
fill_moments, 268	pixel, 97
fill_real_mean, 268	photons_atm_qe
fill_real_mean_and_sigma, 269	hess_mc_pe_sum_struct, 63
fill_real_moments, 269	pixel
free_moments, 269	photo_electron, 97
stat_moments, 269	pixel_integration
momstat, 96	reconstruct.c, 285
mscrl	pixel_timing_analysis
basic_ntuple, 34	reconstruct.c, 285
mscrw	primary
	basic_ntuple, 35
basic_ntuple, 34	primary_id
n fail	hess_mc_shower_struct, 68
_	primetab
basic_ntuple, 34	histogram.c, 180
n_img	_
basic_ntuple, 34	print_camera_layout
n_pix	io_simtel.c, 232
basic_ntuple, 35	mc_tel.h, 254
n_trg	print_hashed_trgmasks
basic_ntuple, 35	io_trgmask.c, 243
n_tsl0	io_trgmask.h, 246
basic_ntuple, 35	print_hess_pixcalib
name	io_hess.c, 209
ConfigItemStruct, 48	print_histogram
ConfigValues, 51	histogram.c, 178
nb_peak_integration	histogram.h, 199
reconstruct.c, 284	print_histograms
new_func	io_histogram.c, 221
Config_Binary_Item_Interface, 42	io_histogram.h, 224
next	print photo electrons
histogram, 89	io_simtel.c, 232
next_file_struct, 96	mc tel.h, 254
nfparam	print_pix_col
shower extra parameters, 99	camera_image.c, 117
	print_tel_block
niparam	io simtel.c, 233
shower_extra_parameters, 99	mc_tel.h, 254
nmod	
ConfigValues, 51	print_tel_offset
num_hot	io_simtel.c, 233
hess_tel_image_struct, 82	mc_tel.h, 254
	print_tel_photons
offset_fov	io_simtel.c, 233
hess_run_header_struct, 75	mc_tel.h, 255
offset_to_angles	print_tel_pos
rec_tools.h, 278	io_simtel.c, 233
opt_theta_cut	mc_tel.h, 255
user_analysis.c, 306	private_shower_extra_parameters
overflow	io_simtel.c, 242
histogram, 89	prog_path
overflow_2d	user_analysis.c, 303
	· ·

ps_begin_page1	io_simtel.c, 235
camera_image.c, 117	mc_tel.h, 257
ps_begin_page2	read_tel_block
camera_image.c, 118	io_simtel.c, 236
ps_end_page	mc_tel.h, 257
camera_image.c, 118	read_tel_offset
ps_head1	io_simtel.c, 236
camera_image.c, 118	mc_tel.h, 258
ps_trailer	read_tel_offset_w
camera_image.c, 118	io_simtel.c, 236
pulse_sum_glob	mc tel.h, 258
hess_pixel_timing_struct, 72	read_tel_photons
pulse_sum_loc	io_simtel.c, 237
hess_pixel_timing_struct, 72	mc_tel.h, 258
	read_tel_pos
r_nb	io_simtel.c, 237
user_parameters, 104	mc_tel.h, 259
range_list_struct, 98	readtext_func
range_low_az	Config_Binary_Item_Interface, 42
hess_tracking_setup_struct, 87	real
rcm	Histogram Parameters, 92
basic_ntuple, 35	_
read_camera_layout	rec_tools.h, 276
io_simtel.c, 234	angle_between, 277
mc_tel.h, 255	angles_to_offset, 277
read_config_lines	cam_to_ref, 277
hconfig.c, 150	get_shower_trans_matrix, 277
hconfig.h, 160	intersect_lines, 278
read_config_status	line_point_distance, 278
hconfig.c, 150	offset_to_angles, 278
hconfig.h, 160	shower_geometric_reconstruction, 278
read_eventio_registry	reconfig
eventio_registry.c, 129	hconfig.c, 151
eventio_registry.h, 131	hconfig.h, 160
read_func	reconstruct
Config_Binary_Item_Interface, 42	reconstruct.c, 285
read_hess.c, 270	reconstruct.c, 279
read_hess_nr.c, 274	CALIB_SCALE, 281
read_hess_pixcalib	calibrate_amplitude, 281
io_hess.c, 209	calibrate_pixel_amplitude, 282
read_histograms	clean_image_tailcut, 283
io_histogram.c, 221	find_neighbours, 283
io_histogram.h, 224	global_peak_integration, 283
read_histograms_x	image_reconstruct, 284
io_histogram.c, 221	local_peak_integration, 284
io_histogram.h, 224	nb_peak_integration, 284
read_input_lines	pixel_integration, 285
io_simtel.c, 234	pixel_timing_analysis, 285
mc_tel.h, 256	reconstruct, 285
read_photo_electrons	second_moments, 286
io_simtel.c, 234	select_calibration_channel, 286
mc_tel.h, 256	set_disabled_pixels, 286
read_shower_longitudinal	simple_integration, 288
io_simtel.c, 235	refidx
mc_tel.h, 256	atmprof.c, 110
read_tel_array_end	reload_config
io_simtel.c, 235	hconfig.c, 151
mc_tel.h, 257	hconfig.h, 161
read_tel_array_head	res1

ConfigItemStruct, 48	current.h, 124
res2	set_log_file
ConfigItemStruct, 49	warning.c, 308
reset_local_offset	warning.h, 313
current.c, 121	set_logging_function
current.h, 124	warning.c, 309
reverse_flag	warning.h, 313
hess_run_header_struct, 75	set_output_function
rh_sens_comp.cc, 288	warning.c, 309
rhofx	warning.h, 314
atmprof.c, 110	set_permissive_pipes
rndm2.h, 289	fileopen.c, 137
root_exe_path	fileopen.h, 140
fileopen.c, 138	set_tel_idx
root_path	io_hess.c, 209
fileopen.c, 138	set_tel_idx_ref
rpol	io_hess.c, 210
atmprof.c, 111	set_warning
user_analysis.c, 303	warning.c, 309
run	warning.h, 314
basic_ntuple, 35	shower extra parameters, 98
hess_run_header_struct, 76	fparam, 99
run_type	id, 99
hess_run_header_struct, 76	iparam, 99
	is_set, 99
second_moments	nfparam, 99
reconstruct.c, 286	niparam, 99
section	•
ConfigValues, 51	weight, 99
select_calibration_channel	shower_geometric_reconstruction
reconstruct.c, 286	rec_tools.h, 278
set_aux_warning_function	shower_prog_id
warning.c, 308	hess_mc_run_header_struct, 66
warning.h, 313	sig_e
set_config_filename	basic_ntuple, 35
hconfig.c, 151	sig_mscrl
hconfig.h, 161	basic_ntuple, 35
set_config_history	sig_mscrw
hconfig.c, 151	basic_ntuple, 35
hconfig.h, 161	sig_theta
set_config_preprocessor	basic_ntuple, 36
hconfig.c, 152	sig_xmax
hconfig.h, 161	basic_ntuple, 36
set_config_stack	simple_integration
hconfig.c, 152	reconstruct.c, 288
hconfig.h, 162	size
set_current_offset	ConfigItemStruct, 49
current.c, 121	sort_histograms
current.h, 124	histogram.c, 179
set_disabled_pixels	histogram.h, 200
reconstruct.c, 286	stat_histogram
set ev reg std	histogram.c, 179
eventio_registry.c, 130	histogram.h, 200
eventio_registry.h, 131	stat_moments
set_first_histogram	histogram.h, 200
histogram.c, 179	moments.c, 269
histogram.h, 199	stop_signal_function
set_local_offset	The read_hess (aka read_simtel, read_cta) pro
current.c, 122	gram, 26
Janonico, ILL	9.4,

The road hace or program 29	main 27
The read_hess_nr program, 28 straux.c, 290	main, 27 stop_signal_function, 28
abbrev, 291	theta
getword, 291	basic_ntuple, 36
stricmp, 291	theta_escale
straux.h, 293	user parameters, 105
abbrev, 294	thickx
getword, 294	atmprof.c, 111
stricmp, 294	threshold
stricmp	hess pixel timing struct, 72
straux.c, 291	time level
straux.h, 294	hess_pixel_timing_struct, 72
otradikiri, 201	time_string
tailcut_low	current.c, 122
user_parameters, 104	current.h, 125
tel_idx	timval
The merge_simtel program, 23	hess_pixel_timing_struct, 72
tel_idx_out	tm_slope
The merge_simtel program, 23	hess_tel_image_struct, 82
tel_pos	tohbook.c, 294
hess_run_header_struct, 76	toroot.cc, 295
tel_type_param, 99	convert_histograms_to_root, 296
teldata_pattern	histogram_to_root, 297
hess_central_event_data_struct, 58	tracking mode
telescope_list, 100	hess_run_header_struct, 76
telescope_type	trgmask_entry, 100
user_analysis.c, 306	trgmask_fill_hashed
teltrg_pattern	io_trgmask.c, 243
hess_central_event_data_struct, 58	io_trgmask.h, 246
teltrg_time	trgmask_hash_set, 101
hess_central_event_data_struct, 58	trgmask_scan_log
tentries	io_trgmask.c, 243
histogram, 89	io_trgmask.h, 246
The add_histograms program, 13	trgmask set, 101
main, 13	tslope
The best_of program, 14	basic ntuple, 36
The check_trgmask program, 19	tsphere
The extract_hess program, 20	basic_ntuple, 36
main, 20	type
The fcat program, 16	ConfigItemStruct, 49
The gen_trgmask program, 21	histogram, 89
The hdata2hbook program (cvt2), 29	3 to , to
main, 29	ubound
The hdata2root program (cvt3), 30	ConfigItemStruct, 49
The list_histogram program, 17	ubound_hard
main, 17	ConfigIntern, 46
The merge_simtel program, 22	ubound_soft
check_autoload_trgmask, 23	ConfigIntern, 46
map_to, 23	underflow
tel_idx, 23	histogram, 90
tel_idx_out, 23	underflow_2d
The read_hess (aka read_simtel, read_cta) program, 24	histogram, 90
CALIB_SCALE, 25	unlink_histogram
main, 25	histogram.c, 180
stop_signal_function, 26	histogram.h, 200
The read_hess sensitivity comparison tool, 18	uri_popen
The read_hess_nr program, 27	fileopen.c, 137
CALIB_SCALE, 27	user_analysis.c, 297
calibrate_pixel_amplitude, 27	ebias_correction, 301

eval_cut_param, 301	user_set_tel_type_param_by_str
expected_max_distance, 301	user_analysis.c, 305
expected_max_height, 302	user_set_theta_escale
img_norm, 302	user_analysis.c, 306
interp, 303	user_set_width_max_cut
opt_theta_cut, 306	user_analysis.c, 306
prog_path, 303	volidata
rpol, 303	validate
telescope_type, 306	ConfigItemStruct, 49 values
user_done, 303	ConfigIntern, 46
user_event_fill, 304	Coringintern, 46
user_finish, 304	warn defaults
user_get_type, 305	warning.c, 311
user_mc_event_fill, 305	warn_f_output_text
user_mc_shower_fill, 305	warning.c, 309
user_set_clipping, 305	warning.h, 314
user_set_flags, 305	warn_f_warning
user_set_length_max_cut, 305	warning.c, 311
user_set_tel_type_param_by_str, 305	warning.h, 314
user_set_theta_escale, 306	warn_specific_data, 105
user_set_width_max_cut, 306	logfname, 105
user_done	warning.c, 306
user_analysis.c, 303	flush_output, 308
user_event_fill	set_aux_warning_function, 308
user_analysis.c, 304	set_log_file, 308
user_finish	set_logging_function, 309
user_analysis.c, 304	set_output_function, 309
user_flags	set_warning, 309
user_parameters, 105	warn_defaults, 311
user_get_type	warn_f_output_text, 309
user_analysis.c, 305	warn_f_warning, 311
user_mc_event_fill	warning status, 311
user_analysis.c, 305	warning.h, 312
user_mc_shower_fill	flush_output, 313
user_analysis.c, 305	set_aux_warning_function, 313
user_parameters, 102	set_log_file, 313
calib_scale, 103	set_logging_function, 313
camera_clipping_deg, 103	set_output_function, 314
clip_amp, 103	set_warning, 314
d_integ_param, 103	warn_f_output_text, 314
d_sp_idx, 103	warn_f_warning, 314
impact_range, 103	warning_status, 315
integ_no_rescale, 104	warning_status
integ_param, 104	warning.c, 311
integrator, 104	warning.h, 315
min_amp, 104	weight
min_pix, 104	basic_ntuple, 36
min_tel_img, 104	shower_extra_parameters, 99
r_nb, 104	write_camera_layout
tailcut_low, 104	io_simtel.c, 238
theta_escale, 105	mc_tel.h, 259
user_flags, 105	write_func
user_set_clipping	Config_Binary_Item_Interface, 42
user_analysis.c, 305	write_hess_event
user_set_flags	io_hess.c, 210
user_analysis.c, 305	write_hess_laser_calib
user_set_length_max_cut	io_hess.c, 210
user_analysis.c, 305	write_hess_mc_event

io hess.c, 210	basic_ntuple, 36
write_hess_mc_pe_sum	xc_true
io hess.c, 210	basic_ntuple, 36
write_hess_mc_shower	xfirst_true
io_hess.c, 211	basic_ntuple, 37
write_hess_pixcalib	xmax
io_hess.c, 211	basic_ntuple, 37
write_hess_run_stat	hess_mc_shower_struct, 68
io hess.c, 211	
-	xmax_true
write_hess_shower	basic_ntuple, 37
io_hess.c, 211	VC
write_hess_tel_monitor	yc
io_hess.c, 212	basic_ntuple, 37
write_hess_teladc_samples	yc_true
io_hess.c, 212	basic_ntuple, 37
write_hess_teladc_sums	zoro aun modo
io_hess.c, 212	zero_sup_mode
write_hess_televent	hess_camera_software_setting_struct, 56
io_hess.c, 213	
write_histograms	
io_histogram.c, 222	
io_histogram.h, 225	
write_input_lines	
io_simtel.c, 238	
mc_tel.h, 259	
write_photo_electrons	
io_simtel.c, 238	
mc_tel.h, 260	
write_shower_longitudinal	
io_simtel.c, 239	
mc_tel.h, 260	
write_tel_array_end	
io_simtel.c, 239	
mc_tel.h, 260	
write_tel_array_head	
io_simtel.c, 239	
mc_tel.h, 261	
write_tel_block	
io_simtel.c, 239	
mc_tel.h, 261	
write_tel_compact_photons	
io_simtel.c, 240	
mc_tel.h, 261	
write_tel_offset	
io_simtel.c, 240	
mc_tel.h, 262	
write_tel_offset_w	
io_simtel.c, 240	
mc_tel.h, 262	
write_tel_photons	
io_simtel.c, 241	
mc_tel.h, 263	
write_tel_pos	
io_simtel.c, 241	
mc_tel.h, 263	
_ ,	
X	
hess_tel_image_struct, 82	
YC .	