Runtime Access to Variables

Roadmap

Last Time

Parameter passing strategies

This time

- How do we deal with variables and scope
- How do we store variables on stack

Scope

We mostly worry about 3 flavors

- Local
 - Declared and used in the same function
 - Further divided into "block" scope in your language
- Global
 - Declared at the outermost level of the program
- Non-local
 - For static scope: variables declared in an outer nested subprogram
 - For dynamic scope: variables declared in the calling context

Local variables: Examples

What are the local variables here?

```
int fun(int a, int b) {
   int c;
   c = 1;
   if (a == 0) {
      int d;
      d = 4;
   }
}
```

How do we access the Stack?

Need a little MIPS knowledge


- Full tutorial next week
- General anatomy of a MIPS instruction

opcode Operand1 Operand2

How do we access the Stack?

Use "load" and "store" instructions

- Recall that every memory cell has an address
- Calculate that memory address, then move data from/to that address




Basic memory operations

lw register memoryAddress


sw register memoryAddress

Load Word Example


opcode register memoryAddress



Load Word in Action



Store Word in Action




Relative Access for Locals

Why do we access locals from \$fp?

That's where the activation record starts

What if we used \$sp instead?



Simple Memory-Allocation Scheme

Reserve a slot for each variable in the function

0x3d4	
0x3dc	(v)
0x3e0	(u)
0x3e4	(t)
0x3e8	(s)
0x3ec	(b)
0x3f0	(a)
0x3f4	(control link)
0x3f8	(return addr)
0x3fc	(y)
0x400	(x)

Simple Memory-Allocation Algorithm

For each function Set offset = 0for each parameter add name to symbol table offset -= size of parameter offset -= size of return address offset -= size of control link offset -= size of callee saved registers for each local add name to symbol table offset -= size of variable

Simple Memory-Allocation Implementation

Add an offset field to each symbol table entry
During name analysis, add the offset along with
the name (Wait until Project 6 to do this)
Walk the AST performing decrements at each
declaration node

Algorithm Example

```
int test (int x, int y) {
  int a, b;
  if (x) {
    int s;
  } else {
    int t, u, v;
    u = b + y;
  }
}
```

Handling Global Variables

In a sense, globals easier to handle than locals

- Space allocated directly at compile time instead of indirectly via \$fp and \$sp registers
- Never needs to be deallocated

Place in static data area

- In MIPS, handling with a special storage directive
- Variables referred to by name, not by address

Memory Region Example

```
.data
x: .word 10
y: .byte 1
z: .asciiz "I am a string"
.text
lw $t0, x #Load from x into $t0
sw $t0, x #Store from $to into x
```

Accessing non-local variables

Static scope

 Variable declared in one procedure and accessed in a nested one

Dynamic scope

Any variable use not locally declared

Static non-local scope example

Each function has it's own AR

Inner function accesses the outer AR

```
function main() {
   int a = 0;
   function subprog() {
      a = a + 1;
   }
}
```

Static non-local scope memory access

```
void procA() { // level 1
  int x, y;
  void procB() { // level 2
    void procC() { //level 3
      int z;
      void procD() {
        int x;
        x = z + y;
        procB();
      x = 4;
      z = 2;
      procB();
      procD();
    x = 3;
    y = 5;
```


Access Links

Add an additional field to the AR

- Points to the locals area of the outer function
- Sometimes called the static link (since it refers to the static nesting)

Level 3 AR

Level 2 AR



How Access Links Work


We know how many *levels* to traverse statically

Example: In nesting level 3

 and the variable is in nesting
 level 1: go back access links
 (3 – 1) 2 levels

Level 3 AR

Level 2 AR



Setting up access links

Using 1 access link


lw \$t0,
$$-4$$
(\$fp)
lw \$t0, -12 (\$t0)

Where \$fp -4 is the location of the access link and the variable in the outer scope is at offset 12 from outer AR

Using 2 access links

Level 3 AR

Level 2 AR



Thinking about access links

We know the variable we want to access statically

Why don't we just index into the parent's AR using a large positive offset from \$fp?

lw \$t0 38(\$fp)

Displays

High-level idea:


- Keep the transitive effects of multiple access link traversals
- Uses a side-table of this info

Tradeoffs vs Access Links?

- Faster to call far up the hierarchy
- Takes extra space

Level 3 AR

Level 2 AR



Questions about Static Scope?

Dynamic non-local scope example

```
function main(){
   a = 0;
   fun();
function fun() {
   a = a + 1;
```

Dynamic Scope Storage

Key point

 We don't know which non-local variable we are referring to

Two ways to set up dynamic access

- 1. Deep Access somewhat similar to Access links
- 2. Shallow Access somewhat similar to displays

Deep Access

If the variable isn't local

- Follow the control link to the caller's AR
- Check to see if it defines the variable
- If not, follow the next control link down the stack
- Note that we somehow need to know if a variable is defined by name in an AR
- Usually means we'll have to associate a name with a stack slot

Shallow Access

Keep a table with an entry for each variable declaration

- Compile a direct reference to that entry
- At a function call
 - Save all locals in the caller's AR
 - Restore locals when the callee is finished

Roadmap

We learned about variable access

- Local vs global variables
- Static vs dynamic scopes

Next time

- We'll start getting into the details of MIPS
- Code generation