## Chemical potential profile

Jacob Jeffries

February 2024

## 1 Chemical Potentials at Equilibrium

Consider a reference system with free energy  $G^{\circ}$  over domain  $\Omega$ . Then, adding one atom of type  $\alpha$  yields a system with a new free energy:

$$G = G^{\circ} + \mu_{\alpha} \tag{1}$$

Or, adding a type of  $\alpha'$  instead:

$$G' = G^{\circ} + \mu_{\alpha'} \tag{2}$$

Therefore, the free energy difference between the system with one extra  $\alpha$  atom and one extra  $\alpha'$  atom is:

$$G' - G = \mu_{\alpha'} - \mu_{\alpha} \tag{3}$$

Assuming 0 K and 0 bar, we can equate this to a difference in internal energy, therefore:

$$\mu_{\alpha'} - \mu_{\alpha} = \left\langle E_{\sigma}^{(\alpha')} - E_{\sigma}^{(\alpha)} \right\rangle_{\Omega} \tag{4}$$

where  $E_{\sigma}^{(\alpha)}$  is the energy of the lattice with an atom of type  $\alpha$  occupying site  $\sigma$ , and  $\langle \cdot \rangle_{\Omega}$  indicates averaging over the domain  $\Omega$ . Additionally, we have the Euler equation (at 0 K and 0 bar):

$$u = \sum_{\alpha} x_{\alpha} \mu_{\alpha} \tag{5}$$

where u is the potential energy per atom of some reference configuration. If we have a reference configuration defined by a map t, where  $t(\sigma)$  is the type occupying site  $\sigma$  in the reference configuration, then:

$$\frac{1}{N} \left\langle E_{\sigma}^{(t(\sigma))} \right\rangle_{\Omega} = \sum_{\alpha} x_{\alpha} \mu_{\alpha} \tag{6}$$

where N is the number of lattice sites and  $x_{\alpha}$  is the atomic fraction of type  $\alpha$ .

The equations from 4 and 6 form either a perfectly determined system or an overdetermined system, and can thus by solved with least-squares for chemical potentials.

## 2 Chemical Potentials at Non-Equilibrium

Instead, we assume that the chemical potentials vary over subdomains  $\omega \subseteq \Omega$  (where  $\Omega$  is the entire spatial domain). Then, we can solve for the chemical potential in each subdomain  $\omega$  with:

$$\mu_{\alpha'}(\omega) - \mu_{\alpha}(\omega) = \frac{|\omega|}{|\Omega|} \left\langle E_{\sigma}^{(\alpha')} - E_{\sigma}^{(\alpha)} \right\rangle_{\omega}$$

$$\sum_{\alpha} x_{\alpha}(\omega) \mu_{\alpha}(\omega) = \frac{1}{N} \frac{|\omega|}{|\Omega|} \left\langle E_{\sigma}^{(t(\sigma))} \right\rangle_{\omega}$$
(7)

where  $|\Omega| = \int d\Omega$  is the volume of the domain  $\Omega$ . Here, the volume rescaling is necessary or else the cohesive energy of the subdomain  $\omega$  is overestimated. For large subdomains, we have  $|\omega|/|\Omega| \to N(\omega)/N = p(\omega)$ , where  $N(\omega)$  is the number of atoms in subdomain  $\omega$ . Therefore, we solve the following overdetermined system in each subdomain:

$$\mu_{\alpha'}(\omega) - \mu_{\alpha}(\omega) = p(\omega) \left\langle E_{\sigma}^{(\alpha')} - E_{\sigma}^{(\alpha)} \right\rangle_{\omega}$$

$$\sum_{\alpha} x_{\alpha}(\omega) \mu_{\alpha}(\omega) = \frac{p(\omega)}{N} \left\langle E_{\sigma}^{(t(\sigma))} \right\rangle_{\omega}$$
(8)