# Elasticity

Jinyuan Wu

May 20, 2023

# 1 The theoretical framework

# 1.1 The displacement field

For now, we use r to refer to the position vector of a position in a continuum, and r'(r,t) its corresponding position at time t – but note that in this note sometimes we will need to use the symbol r to refer to r' (Section 1.3.2). The displacement field is therefore

$$\boldsymbol{u}(\boldsymbol{r},t) = \boldsymbol{r}'(\boldsymbol{r},t) - \boldsymbol{r}. \tag{1}$$

A rough estimation of the number of degrees of freedom implies that all information about the material – the position of each atom – has already been stored in u(r,t). To see why, note that we can do Fourier transform to u(r,t) in variable r. Suppose the size of the system is  $\sim L^d$ , where d is the dimension of the system, and the microscopic length scale of the system is  $\sim a$ . The wave vector components of  $k_{x,y,z}$  therefore are confined to the sequence that starts with 0 and ends with  $2\pi/a$  (the microscopic cutoff), with a step of  $2\pi/L$ ; the total length of this sequence is  $\simeq L/a$ , and thus the total number of possible wave vectors is  $(L/a)^d$ . Thus the number of real number variables included in the field variable u(r,t) at a given time step is  $d \cdot (L/a)^d$ : the prefactor d comes from the d components of u.

On the other hand, there are  $\simeq (L/a)^d$  atoms in the system, and each of them has d directions of motion, and therefore, we find that number of real number variables included in  $\boldsymbol{u}(\boldsymbol{r},t)$  is the same as the number of real number variables of the atoms, and thus  $\boldsymbol{u}(\boldsymbol{r},t)$  contains all the information contained in the system. This should not be surprising: that we have a wave vector cutoff  $\simeq 2\pi/a$  means we have a real space resolution of  $\simeq a$ , so at each time step t,  $\boldsymbol{u}(\boldsymbol{r},t)$  can be completely described by a real space grid with the separation between the sample points being  $\simeq a$  – and the points in the grid is just equivalent to the initial positions of the atoms.

There are however some subtleties in the above argument. If the material is not a crystal, when  $k \simeq 2\pi/a$ , the translational symmetry is already broken, and therefore the wave vector is not well-defined any more; thus the wave vector cutoff should be set to a much lower value. If the system is an insulator, we can take a to be the length scale of the primitive unit cell, and  $2\pi/a$  is the magnitude of the width of the first Brillouin zone. If there is only one kind of atom, then indeed u(r,t) contains all information in the system; but often we have more than one kind of atoms (two atoms that are not connected by any symmetry operations should be considered to be two kinds of atoms, even when they are of the same species), and then u(r,t) only contains the acoustic phonon modes.

So in conclusion, the displacement field u(r,t) only contains the acoustic modes, both in crystals and non-crystals; in both cases there may be additional hidden microscopic degrees of freedom. These hidden degrees of freedom, like dislocation, can be treated by introducing various discontinuities to u(r).

Below we often use  $u_i$  to represent u, since we are going to deal with tensors frequently and it's a good idea to keep the notation the same as that of higher order tensors.

## 1.2 General guidelines of elastic dynamics

Let's now move to the following question of what the dynamics of an elastic solid system looks like. In this section we progressively introduce assumptions on this topic.

### 1.2.1 Dynamic variables: $u_i$ only

The first assumption we introduce is the dynamics of the system should be able to be cast into a form that is only about  $u_i$  and its conjugate momentum. Note that even when more dynamic variables are involved, we still can use, say, Mori-Zwanzig formalism to get a theory about  $u_i$  only, and thus in order for this approximation to be truly restrictive, we need to impose some implicit constraints on the formalism used when modeling the dynamics. If we constrain the formalism to be Hamiltonian dynamics plus some dissipation terms, then essentially we are assuming that the material is elastic (Section 1.2.2).

This assumption means the system we are investigating into doesn't have typical fluid behavior: in Navier-Stokes equation, the density  $\rho(\mathbf{r},t)$  is also a dynamic variable which can be used to decide p on the RHS of the equation; this isn't necessary in solid mechanics: even when we do have  $\rho$  dependence in the EOMs, it should be able to be decided explicitly by, say,  $\nabla \cdot \mathbf{u}$ .

In other words, when T=0, the Hamiltonian of the system is basically a Hamiltonian of phonons. The quantum Hamiltonian of fluid, on the other hand, involves  $\rho$  and  $\boldsymbol{v}$  (and a strange commutation relation between them) [1].

Sometimes we do need corrections to this assumption: it's possible that long-range electromagnetic fields are created, and in this case E and B should also be included into the dynamic variables (or otherwise we have memory effects, retardation effects, etc.). The approximation therefore may be loosened to no degree of freedom other that  $u_i$  that is about the atomic positions in the system is needed in the  $\overline{dynamics}$ .

#### 1.2.2 Elasticity: statelessness and immediate response

Elasticity is sometimes defined as the follows: <u>when we stop applying force to the system, it always goes back to one equilibrium shape</u>. In other words, if we push the system and then stop, the system bounces back.

This definition is too weak: it may be possible that after a loading-unloading process, although the system goes back to its original shape, its inner structure has changed and its reaction to another round of loading and unloading is different from that of the previous round. So we need to impose a stronger formulation of elasticity: the deformation of the system has nothing to do with its history and is completely decided by the force applied to it. This formulation implies the weaker version: when no load is present, the system has one and only one configuration.

The above formulation however has some ambiguity. In experiments usually the force applied to the system is changed very slowly, and the system is quasi-static. In dynamics, however, we may be interested in oscillation, where the force applied changes quickly, and now it's possible that the response of the system is retarded; if we go to frequency space, we may find that the response of the system has frequency dependence. This is of course possible, and we may still say that the deformation of the system is decided by the force applied to it. Often, we make a even stronger assumption: the deformation of the system in a particular moment is complete decided by the force applied to it in that very moment. This means the system has immediate response to the force applied to it.

#### 1.2.3 Dissipation and finite temperature effects

When T=0, we may want to use a Hamiltonian formalism (a quantum many-body theory for phonons, actually) to describe the elastic system; this however is usually not sufficient since we have various dissipations: it's inevitable that some weight flows into the hidden degrees of freedom that we lose track of.<sup>4</sup> An accurate formalism for dissipation is hard since it involves quantum master equation of the density matrix and dissipative quantum jump channels; but in ordinary elastic theory, usually we don't care about what happens to the quantum many-body

<sup>&</sup>lt;sup>1</sup>When the fluid is incompressible, p needs to be used in place of  $\rho$  as a dynamic variable.

<sup>&</sup>lt;sup>2</sup>Note that solid-like dynamics is not the logical opposition of fluid-like dynamics: it's possible to have systems with both solid-like and fluid-like behaviors. These materials are studied in rheology.

<sup>&</sup>lt;sup>3</sup>Note that as is known in effective field theory, the response of the system to external driving force and internal force should be the same, as long as the external driving force is coupled to the deformation of the system in the same way internal forces are coupled to the deformation system, and since we call external forces "force" this should be true.

<sup>&</sup>lt;sup>4</sup>It's still possible that even the system does have a dissipation-less Hamiltonian description, there is still damping behavior for a single mode, when the mixing between modes is too severe (as in, say, Landau damping). Since all degrees of freedom are well kept track of, this is "dissipation-less damping".

wave function, and all we want to know is  $\langle u_i \rangle$ , ignoring its higher order correlations. Thus usually dissipation is just modeled by adding a term like  $\partial_t u_i$  to the EOM.

Another issue is finite temperature effects. Here we do local equilibrium approximation: we assume that when  $T \neq 0$ , there can be T gradience in the system, but at each given point, we have local equilibrium with the local temperature, the force and the deformation being thermodynamic coordinates, and the relaxation time is ignored. Local equilibrium approximation is equivalent to the condition that  $\omega \tau \ll 1$ , where  $\omega$  is the characteristic frequency scale of the dynamic and  $\tau$  the relaxation time. This corresponds to the  $\omega \tau \ll 1$  limit in Fermi liquid kinetics, where we have ordinary hydrodynamics and ordinary sound mode [2]. Again, the most accurate treatment of finite temperature effects involves quantum kinetic theory, but in the  $\omega \tau \ll 1$  limit the quantum kinetic theory is reduced to local thermodynamics.

## 1.2.4 The form of EOM

The variables  $u_i$  and the internal force density  $f_i$  are not thermalized; as [2] says, they are subject to conservation laws, and from momentum conservation we get Newton's second and third laws, so the EOM of the system looks like

$$\rho \frac{\partial^2 u_i}{\partial t^2} = \frac{\delta F[\mathbf{u}]}{\delta u_i} + f_i^{\text{dissipation}}(\partial_t \mathbf{u}, \partial_t^2 \mathbf{u}, \dots), \tag{2}$$

where F is the free energy, and the functional derivative is taken by keeping the temperature variable constant. But this formalism works even when the temperature changes: the change of the temperature is reflected by the temperature dependence of  $\delta F[u]/\delta u_i$  after we take the derivative. When  $T \to 0$ , F becomes the total energy of the system and we go back to Hamiltonian dynamics.

It's kind of silly to spend so much time to get (2), but we have seen that for many frequently seen materials, we need to go beyond (2): when the system has strong fluid-like behavior, when we have plastic deformation, and when there is retardation.

## 1.3 Stress

#### 1.3.1 There are only surface forces

For real elastic systems, the form of the EOM often can be further constrained. First, F[u] is usually local, and thus we have

$$\frac{\delta F[\mathbf{u}]}{\delta u_i} = \frac{\partial f}{\partial u_i}, \quad F = \int d^d \mathbf{r} f, \tag{3}$$

where f is the volume density of free energy; in the rest of this note we simply use F to refer to the volume density of free energy, because f may be confused with "force". Moreover, we can assume that the length scale of the interaction between atoms is very small – if we have an interaction channel with a large length scale then we just introduce the relevant part of electromagnetic field into dynamic variables – and since the spatial resolution of u is taken to be much larger than a, effectively we can assume that  $\underline{the\ internal\ forces\ are\ all\ surface\ forces}$ , and therefore we write down<sup>5</sup>

$$\rho \frac{\partial^2 u_i}{\partial t^2} = \partial_j \sigma_{ji} + f_i^{\text{dissipation}}, \tag{4}$$

where we have replaced the internal force with the divergence of a second order tensor  $\sigma_{ji}$ , so that

$$\int_{V} d^{d} \mathbf{r} \, \partial_{j} \sigma_{ji} = \int_{\partial V} d^{d-1} s_{j} \, \sigma_{ji}. \tag{5}$$

We can alternatively get  $\sigma_{ji}$  by writing down the conservation equation of the momentum and then  $\sigma_{ji}$  is the "current of momentum". We call  $\sigma_{ij}$  the **Cauchy stress tensor**. From (5) we immediately get the boundary condition about force passing: if the force acting on a surface element  $d^{d-1}s_i$  is  $p_i d^{d-1}s_i$ , then at the position of the surface element, we have

$$p_i = n_i \sigma_{ii}, \tag{6}$$

<sup>&</sup>lt;sup>5</sup>The meaning of  $\partial_t$  on LHS has a subtlety discussed immediately below.

where  $n_j$  is the jth component of the normal vector  $\boldsymbol{n}$  of the surface element  $d^{d-1}s_i$ , and we have

$$d^{d-1}s_i = n_i ds. (7)$$

There is however an important subtlety in (4). When we take the time derivative on the LHS, we are doing so with  $\mathbf{u} = \mathbf{u}(\mathbf{r}, t)$ , and  $\mathbf{r}$  is kept unchanged when we change t (recall that  $\mathbf{r}$  is actually the continuous version of the index of atoms in the system). On the RHS, however, what I call  $\mathbf{r}$  is actually  $\mathbf{r}'$ ! this can be easily found by looking at (6): definitely the direction of  $\mathbf{u}$  is decided by the surface after deformation, not before deformation. Now since  $\mathbf{n}$  is defined in terms of  $\mathbf{r}'$ , then so is  $\mathrm{d}^{d-1}s_j$  and hence  $\mathrm{d}^d\mathbf{r}$ : the last is just  $\mathrm{d}^d\mathbf{r}'$ .

In order to keep the meaning of  $\partial_t$  and  $\partial_r$  the same on both sides of (2), some remarks on the relation between u(r,t) and u(r',t) is needed. This is done in the next section.

## 1.3.2 Interlude: Lagrangian and Eulerian description

We say we are working with Lagrangian<sup>6</sup> description of the system if we work with r and t, and Eulerian description of the system if we work with r' and t.

The time derivative in the Lagrangian framework (it appears on the LHS of (2) and (4)) can be written in terms of Eulerian derivatives as follows:

$$\left(\frac{\partial}{\partial t}\right)_{\mathbf{r}} = \left(\frac{\partial}{\partial t}\right)_{\mathbf{r}'} + \left(\frac{\partial \mathbf{r}'}{\partial t}\right)_{\mathbf{r}} \cdot \left(\frac{\partial}{\partial \mathbf{r}'}\right)_{t} \\
= \left(\frac{\partial}{\partial t}\right)_{\mathbf{r}'} + \underbrace{\left(\frac{\partial \mathbf{u}}{\partial t}\right)_{\mathbf{r}}}_{=:\mathbf{r}} \cdot \left(\frac{\partial}{\partial \mathbf{r}'}\right)_{t}, \tag{8}$$

where v can be evaluated directly from u in the Lagrangian description but is better regarded as a dynamic variable in the Eulerian description (as in Navier-Stokes equation). People sometimes call  $(\partial_t)_r$  the **material derivative** and use a distinct symbol to represent it, sometimes D/Dt; I will just use d/dt, the meaning of which is self-evident if we regard r as a discrete index.

So the correct form of (4), in the Eulerian framework, is

$$\rho\left(\frac{\partial \boldsymbol{v}}{\partial t} + \boldsymbol{v} \cdot \boldsymbol{\nabla}' \boldsymbol{v}\right) = \frac{\partial \sigma_{ji}}{\partial r_i'} + f_i^{\text{dissipation}},\tag{9}$$

or, if we want to consistently work in the Eulerian framework, we can just rename r' as r and ignore r, and now the equation is

$$\rho\left(\frac{\partial \boldsymbol{v}}{\partial t} + \boldsymbol{v} \cdot \boldsymbol{\nabla} \boldsymbol{v}\right) = \frac{\partial \sigma_{ji}}{\partial r_i} + f_i^{\text{dissipation}},\tag{10}$$

and we also have the additional equation about the definition of v:

$$\boldsymbol{v} = \frac{\partial \boldsymbol{u}}{\partial t} + \boldsymbol{v} \cdot \boldsymbol{\nabla} \boldsymbol{u}. \tag{11}$$

Note that the density is always the density changed by possible deformation and not the original density: we need the third equation – just the mass conservation equation

$$\frac{\partial \rho}{\partial t} + \nabla \cdot \rho \mathbf{v} = 0 \tag{12}$$

to complete the equation system about u, v and  $\rho$ .

Note that the equation system also works for fluids; we still need to assume that  $\sigma_{ij}$  and  $f_i^{\text{dissipation}}$  are only dependent to  $\boldsymbol{u}$  and its derivatives to confine the equation system to the regime of solids.

(10), (11) and (12) contain an additional variable v. We can alternatively describe everything within the Lagrangian framework and get rid of the v variable, but this means we need another stress tensor defined in the Lagrangian framework that's different from the Cauchy stress tensor which is hard to conceptualize intuitively, so I just skip this part. In practice, however, the above formalisms are almost useless for elastic theory, because u almost will always be small; when u is not that small, usually we are just dealing with very complicated static problem and minimizing the free energy should be enough.

From now on, most of the time we will work in the Eulerian framework.

<sup>&</sup>lt;sup>6</sup>Not to be confused with Lagrangian  $\mathcal{L}$ .

#### 1.3.3 Is the Cauchy stress tensor symmetric?

An additional constraint on  $\sigma_{ij}$  that is not necessary but works for most elastic bodies is that  $\underline{\sigma_{ij}}$  is symmetric. This constraint is equivalent to the condition that there is no body torsion: the torsion on a volume is

$$M_{ij} = \int d^{d} \mathbf{r} \left( r_{i} \partial_{k} \sigma_{kj} - \partial_{k} \sigma_{ki} r_{j} \right)$$

$$= \int d^{d} \mathbf{r} \left( \partial_{k} (r_{i} \sigma_{kj}) - \sigma_{kj} \delta_{ik} - \partial_{k} (r_{j} \sigma_{ki}) + \sigma_{ki} \delta_{jk} \right)$$

$$= \int d^{d-1} s_{k} \left( r_{i} \sigma_{kj} - r_{j} \sigma_{ki} \right) - \int d^{d} \mathbf{r} \left( \sigma_{ij} - \sigma_{ji} \right),$$
(13)

and it can be seen that the first term is just the torsion caused by the forces applied to the surface of this volume; if we assume that there is no body torsion, then the second term should always be zero regardless of the exact shape and position of the volume, and this condition is equivalent to

$$\sigma_{ij} = \sigma_{ji}. \tag{14}$$

Of course, we don't have body torsion in an equilibrium system, since if we have, then a part of the system will begin to rotate. However we do have body torsion sometimes: in a liquid crystal system, for example, if a group of rod-like molecules get an angle difference from the rods near them, they will be pulled back, and in this *transient* process a torsion is created.

Since this note is about quasi-static behaviors of ordinary elastic materials, we will just adopt the assumption (14).

#### 1.3.4 Stress and free energy

Now we explicitly derive the relation between the free energy density F and the stress  $\sigma_{ij}$ . In order to "mold" the configuration of the elastic body (without causing any real plastic deformation, of course), we need to introduce a static external force  $f_i$  such that

$$f_i + \partial_k \sigma_{ki} = 0. (15)$$

Essentially  $f_i$  is the Lagrange multiplier to fix the deformation configuration of the system to what we want. Thus when we change the deformation of the system, work is done by  $f_i$ , and we have (below we use  $\delta$  to refer to infinitesimal change caused by variance of the deformation, and d to refer to things like volume element that come from the coordinate system background)

$$\delta U = T \, \delta S + f_i \, \delta u_i \,, \quad \delta F = \delta U - \delta T S = -S \, \delta T + f_i \, \delta u_i \,. \tag{16}$$

The total free energy changes as

$$\delta \int F \, \mathrm{d}^{d} \boldsymbol{r} = -\int S \, \delta T \, \mathrm{d}^{d} \boldsymbol{r} + \int \mathrm{d}^{d} \boldsymbol{r} \, f_{i} \, \delta u_{i}$$

$$= -\int S \, \delta T \, \mathrm{d}^{d} \boldsymbol{r} - \int \mathrm{d}^{d} \boldsymbol{r} \, \partial_{k} \sigma_{ki} \, \delta u_{i}$$

$$= -\int S \, \delta T \, \mathrm{d}^{d} \boldsymbol{r} - \oint \mathrm{d}^{d-1} s_{k} \, \sigma_{ki} \, \delta u_{i} + \int \mathrm{d}^{d} \boldsymbol{r} \, \sigma_{ki} \, \delta(\partial_{k} u_{i}) \,.$$

$$(17)$$

The three variables appearing after  $\delta$  – the temperature in the bulk, the displacement on the boundary, and the gradient of the displacement in the bulk – are all independent variables. Thus, we find

$$\sigma_{ki} = \frac{\delta}{\delta \partial_k u_i} \int F \, \mathrm{d}^d \mathbf{r} = \frac{\partial F}{\partial (\partial_k u_i)}. \tag{18}$$

This is a very important finding: it seems we need to focus on the gradient of u, instead of u itself; and indeed this is true, since we can trivially add a global translation to the system and have a very large u; besides the global translation, the global rotation component of  $\partial_k u_i$ , if any, is also trivial; to get rid of these we can simply require that u = 0 at  $\infty$ .

#### 1.4 Strain

#### 1.4.1 Decomposition of deformation gradient

$$E_{ij} = \tag{19}$$

It should be noted that there is no guarantee that the antisymmetric component of  $\partial_i u_j$  is not involved in the expression of F. For example, if we analyze the deformation by analyzing the change of the metric, we may want to define another type of stress:

$$u_{ij} = \frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i} + \frac{\partial u_l}{\partial x_i} \frac{\partial u_l}{\partial x_j}$$
 (20)

and its third term can only be obtained by using  $a_{il}a_{jl}$ . What we can say is the symmetric component of the deformation gradient, when appearing in F, is able to have an order that is lower than any other components.

TODO: transport theorem, etc.

TODO: from microscopic theory to this

#### 1.4.2

TODO: in r or r'

## 1.5 Summary

Now I list what we get in the discussion above, and their conditions.

- In a solid the dynamics of the system is mainly about the displacement field u and its time derivative, possibly with other variables like the electromagnetic field.
- When the deformation of a system at a moment is completely decided by the force applied to it at that very moment, without any retardation or memory effect, we say the system is elastic.
- When the thermodynamic relaxation time is much smaller than  $1/\omega$ , with  $\omega$  being the frequency scale we are interested in, we can assume local thermodynamic equilibrium and use the derivative of the free energy to find the relation between deformation and internal force.
- When the interaction length scale is small enough, the internal interaction in a system is described by the Cauchy stress tensor  $\sigma_{ij}$ . Furthermore, when we don't consider any transient internal torsion, we have  $\sigma_{ij} = \sigma_{ji}$ . The Cauchy stress tensor can be obtained from the free energy by taking its derivative with respect to the deformation gradient.
- The Cauchy stress tensor  $\sigma_{ij}$  guides the time evolution of the system according to (10), (11) and (12). Note that the form of the equation system, without constraints over what  $\sigma_{ij}$  depends to, also works for fluids. When the deformation is small, terms like v can be removed in the equations.

All underlined sentences have well-known counterexamples. In a liquid the density is a very important dynamic variable. Plastic deformation is common. Non-equilibrium behaviors can be seen in, say, zero sound modes of Fermi liquid. We may work in a very small length scale where the internal forces in a system can no longer be described as surface forces. Large deformation does exist.

# 2 Linear elasticity for bulk system

Three-dimensional elastic systems generally have neither large  $\boldsymbol{u}$  (with no global translation or rotation, of course) nor large strain. This sometimes may not be the case for 2D or 1D systems. Therefore, the elastic theory of three-dimensional systems is usually linear and therefore can be decided completely by symmetry.

# 3 Statics of boards

# 3.1 Föppl-von Kármán equations for large deflections of thin flat plates

A brief overview of Föppl-von Kármán equations can be found in § 14 in [3]. The theory is based on the following assumptions, many of which are faced with questions:

• The von Kármán strain is linearly linked to the stress tensor. One may expect this to be true since the von Kármán strain is a natural generalization of the engineering strain; but then we can also say that since a high order term appears in F, similarly a high order term of the engineering strain can appear in F as well. The linear relation between the von Kármán strain is therefore not theoretically justified, and experimental demonstration of this constitutive relation is hard to carry out.

# References

- [1] Alexander G. Abanov and Paul B. Wiegmann. "Quantum Hydrodynamics, the Quantum Benjamin-Ono Equation, and the Calogero Model". In: *Physical Review Letters* 95.7 (2005). ISSN: 1079-7114. DOI: 10.1103/physrevlett.95.076402. URL: http://dx.doi.org/10.1103/PhysRevLett.95.076402.
- [2] D Belitz and TR Kirkpatrick. "Soft modes in Fermi liquids at arbitrary temperatures". In: *Physical Review B* 105.24 (2022), p. 245146.
- [3] Lev Davidovich Landau et al. Theory of elasticity: volume 7. Vol. 7. Elsevier, 1986.