# Lecture 17 — Scheduling Algorithm Evaluation; UNIX & Windows

Jeff Zarnett jzarnett@uwaterloo.ca

Department of Electrical and Computer Engineering
University of Waterloo

March 22, 2023

ECE 350 Spring 2023 1/15

## Part I

## Windows & UNIX Scheduling

ECE 350 Spring 2023 2/15

## Scheduling in Desktop OSes

In this lecture we will examine how real commercial operating systems schedule their processes and threads.

We will examine UNIX and Windows scheduling.

We will see what approaches are used and what is interesting/novel about them.

ECE 350 Spring 2023 3/15

The traditional UNIX scheduling is really ancient; as in System V R3 and BSD 4.3. It was replaced in SVR4 (which had some real-time support).

Multilevel feedback system using Round Robin within each of the queues.

Time slicing is implemented and the default time slice is a (very long) 1 second.

So if a process does not block or complete within 1 s, then it will be preempted.

Priority is based on the process type as well as the execution history.

ECE 350 Spring 2023 4/15

Processor utilization for a process *j* is calculated for an interval *i* as:

$$CPU_j(i) = \frac{CPU_j(i-1)}{2}$$

And the priority is for process *j* at interval *i* is calculated by the formula:

$$P_j(i) = B_j + \frac{CPU_j}{2} + N_j$$

where  $B_i$  is the base priority of process j and  $N_i$  is the "nice" value of process j.

ECE 350 Spring 2023 5/15

The "nice" value is a UNIX way to allow a user to voluntarily reduce the priority of a process to be "nice" to other users (but honestly, who uses this?).

Actually, the answer to that question is: system administrators.

An admin can "re-nice" a process and make it somewhat nicer than it would otherwise be.

ECE 350 Spring 2023 6/15

The CPU and N components of the equation are restricted to prevent a process from migrating outside of its assigned category.

A process is assigned to a given category based on what kind of process it is.

To put it in simple terms, the OS puts its own needs first and tries to make the best use of resources it can.

ECE 350 Spring 2023 7/15

From highest to lowest priority, the categories are:

- Swapper (move processes to and from disk)
- 2 Block I/O device control (e.g., disk)
- 3 File manipulation
- Character I/O device control (e.g., keyboard)
- 5 User processes

ECE 350 Spring 2023 8 / 15

Yes, unfortunately, user processes get piled at the bottom of the list.

It should provide for efficient use of I/O devices and tends to penalize processor-bound processes at the expense of I/O bound processes.

CPU-bound processes should be able to carry on executing when an I/O-bound process waits for the I/O operation to complete.

When an I/O operation is finished, we would like to start the next I/O operation so the I/O device is not waiting.

This strategy is reasonably effective for a general-purpose, time-sharing operating system.

ECE 350 Spring 2023 9/15

## Windows Scheduling

Windows schedules threads using a priority-based, preemptive scheduling algorithm, ensuring that the highest priority thread runs.

The official name for the selection routine is the dispatcher.

A thread runs until it is preempted, blocks, terminates, or its time slice expires.

ECE 350 Spring 2023 10 / 15

## **Windows Scheduling**

If a higher priority thread is unblocked, it will preempt a lower priority thread.

Windows has 32 different priority levels, the regular (priority 1 to 15) and real-time classes (16 to 31).

A memory management task runs at priority 0.

The dispatcher maintains a queue for each of the scheduling priorities and goes through them from highest to lowest until it finds something to do.

If there is nothing else currently ready, the System Idle Process will "run".

ECE 350 Spring 2023 11/15

## **Windows Priority Classes**

There are six priority classes you can set a process to via Task Manager:

- 1 Realtime
- 2 High
- 3 Above Normal
- 4 Normal
- 5 Below Normal
- 6 Low

A process is usually in the Normal class.

ECE 350 Spring 2023 12/15

## **Windows Thread Priorities**

	real- time	high	above normal	normal	below normal	idle priority
time-critical	31	15	15	15	15	15
highest	26	15	12	10	8	6
above normal	25	14	11	9	7	5
normal	24	13	10	8	6	4
below normal	23	12	9	7	5	3
lowest	22	11	8	6	4	2
idle	16	1	1	1	1	1

ECE 350 Spring 2023 13 / 15

## **Windows Time Slicing**

If a process reaches the end of a time slice, the thread is interrupted.

Unless it is in the real-time category, its priority will be lowered, to a minimum of the base priority of each class.

When a process that was blocked on something (e.g., a wait or I/O), its priority is temporarily boosted (unless it is real-time, in which case it cannot be boosted).

The amount of the boost depends on what the event was.

A process that was waiting for keyboard input gets a bigger boost than one that was waiting for a disk operation, for example.

ECE 350 Spring 2023 14/15

## Windows Priority: UI

The operating system also gives a priority to whatever process is running in the selected foreground window.

This is different from foreground vs. background processes, because the definition of a foreground process was one that was user-interactive.

Here, the distinction is which of the user-interactive processes is currently "on top" in the UI.

Not only does this process get a priority boost, but it also gets longer time slices.

It highlights the different heritages of Windows and UNIX...

ECE 350 Spring 2023 15/15