ECOTE - Introductory Project

Semester: 20L

Author: Kacper Wojakowski 293064

Subject: Simple Macrogenerator - one level of definitions and calls

I. General Overview and Assumptions

The task is to design a macrogenerator supporting one level of calls and definitions. The macrogenerator also uses named arguments – that means that the arguments must be declared in the macro definition, with a unique name, and then used in the definition body with the correct name. The macrogenerator should support following discriminants:

Discriminant Meaning

#	Start of macro definition
\$	Start of macro call

With following additional special symbols used in macro definitions and calls:

Symbol	Meaning
(Start of macro argument list
)	End of macro argument list
{	Start of macro definition body
}	End of macro definition body
&	Macro argument
,	Argument separator

It was assumed that, since macro argument names can be longer than one symbol, they are marked by the discriminant '&' at both beginning and end of the name in a macro body.

Therefore, an example macro definition and call would be:

```
#MACRO1(P1, P2)
{hello&P1&macro&P2&world}
$MACRO1(33,44)
```

Which would result in the following text:

```
hello33macro44world
```

Since the macro generator should only support one level of calls and definitions, an assumption was made that using a definition/call inside another definition/call results in an error.

Whitespace assumptions:

- 1. Whitespace in macro names is not allowed therefore whitespace appearing between a '#' and a '(' symbol is treated as an error.
- 2. Whitespace in parameter names is not allowed therefore whitespace appearing between a '&' symbol and a ',' or ')' is treated as an error (only in macro definitions)
- 3. Macro definition argument declarations can be separated by whitespace for visibility, therefore whitespace is allowed between ',' and '&' symbols (but not in macro calls)

- 4. Macro definition body can be separated from the macro definition name and argument list by whitespace. Therefore, whitespace between ')' and '{' symbols is ignored. For consistency, the whitespace between '}' and the next non-whitespace character is also ignored, as is whitespace between '#' and last preceding non-whitespace character.
- 5. Whitespace is not ignored in macro call argument lists and macro definition bodies, as they contain free text which may contain whitespace.

Therefore, the following are equivalent:

#M(1, 2){a&1&b&2&}	=	#M(1,2){a&1&b&2&}
#M(1, 2){a&1&b&2&}	=	#M(1, 2)
		{a&1&b&2&}

While the following are not:

\$M(aa, bb)	≠	\$M(aa,bb)
#M(1, 2)	≠	#M(1, 2)
{a&1&b&2&}		{a &1& b &2&}

And the following are not allowed (result in errors):

```
#MACRO NAME(1, 2)

#M(PARAM 1, PARAM 2)
```

II. Functional Requirements

The general purpose of a macrogenerator is text transformation with the use of macro definitions and calls. The transformation is dynamic, as the macro definitions are provided inside the transformed text, alongside macro calls and free text. This means that a macro library is needed, in which all of the macro definitions encountered in the source text will be stored and then used to resolve macro calls. This data structure is further described in the *Data structures* section. The macrogenerator evaluates each character, changing its behaviour if it encounters a macro definition or call, or another special symbol (depending on context – e.g. argument separator in an argument list). The special symbols of this macrogenerator are:

Symbol	Meaning
#	Macro definition
\$	Macro call
(Start of macro argument list
)	End of macro argument list
{	Start of macro definition body
}	End of macro definition body
&	Macro argument
,	Argument separator
1	Escape character

The escape character '\' is implemented to allow the use of special characters in free text. Therefore, to output '\' we need '\\' as input. The macrogenerator can also output errors and warnings, if incorrect, unexpected or inadvisable input sequence is encountered. To create useful error/warning outputs, the macrogenerator counts the lines in input text and stores at which line the error or warning occurred, to then inform the user. The exact types of errors and warnings are described in the *Input/output description* section.

III. Implementation

General Architecture

The program consists of four main modules:

- Main Module responsible for the Command Line Interface and File I/O
- MacroGenerator Module responsible for the text transformation
- Error Module responsible for the list of descriptions of errors and warnings
- Symbol Module describes the special symbols used by the generator as constants

The class diagram and description is presented below:




Figure 1: Class Diagram

Class MacroGenerator

macro_library: MacroLibrary	MacroLibrary object storing macro definitions
transform(source_text: str): str, list of Log	Main macro generator function. It transforms the source text — when a definition or call is encountered, the appropriate methods are called. It prepares a list of Log objects of all warnings encountered, and in case of an Error throws the Log instead. Then, the output text is returned as string, and a list of warnings.
macro_definiton(source_text: str): void	A method called when a macro definition is encountered. It extracts the name, arguments and body from the source text and inputs, and adds the macro to the library.
macro_call(source_text: str): str	A method called when a macro call is encountered. It extracts the name and arguments, then fetches the macro definition from the library and performs substitution. Returns the substituted text.

Class MacroLibrary

Library: list of Macro	A list of Macro objects – macro definitions in the library
get_macro(name: str): Macro	A method returning a Macro object given a macro name.
insert_macro(element: Macro): void	A method inserting a new Macro object into the library.

Class Macro

name: str	The name of the macro
arguments: list of str	A list of all argument names in the macro
body: str	The macro definition body

Class Log

err_code: str	The error/warning code encountered
line: int	The line at which the error/warning occurred
args: list of str	List of additional arguments, used to produce the
args. 115t of 5ti	verbose error description, e.g. macro name.

Class ErrorLibrary

library: list of Error	A list of Error objects
get_error(code: str): Error	A method returning an Error object given the error code
what_short(log: Log): str	A method generating a short error description based on a Log object
what_long(log: Log): str	A method generating a verbose error description based on a Log object

Class Error

code: str	The error code
name: str	The name of the error
what_short(line: int): str	Method returning short error description
what_long(line: int, args: list of str): str	Method returning verbose error description

Data Structures

Structure	Description
	List of macro definitions. It consists of Macro
MacroLibrary	objects. As the macro names are unique, it
	should be a list that allows such behaviour.
	List of error and warning definitions. It consists
ErrorLibrary	of Error objects. As the error codes are unique, it
	should be a list that allows such behaviour

The remaining structures in the program are just simple lists, which can use any implementation.

Module Descriptions

The two most important parts of the modules are presented below: the execution of the main module, and execution of the MacroGenerator module, which is the module performing the most crucial part of the macro generator operation.




Figure 2: Main Module Flowchart




Figure 3: MacroGenerator Module Flowchart

The flowchart for MacroGenerator does not include error handling. At any point in the execution, when an error or a warning occurs, an exception will be thrown, or a warning will be added to the log list.

Input/Output Description

The program uses a text file as input, and outputs transformed text into another input file. The macro generator transformation itself works as previously described. Below are some basic examples of usage of this macro generator.

Input	Output
#SIGNATURE(){John Brown}	John Brown
\$SIGNATURE()	
Example 1: Basic macro with no arguments	
Input	Output
<pre>Input #COPYRIGHT(NAME, YEAR)</pre>	Output Made by John Brown in 2003
<u> </u>	_

Example 2: Basic macro with two arguments

Input Output

#SIGNATURE(){John Brown}	Error e23: Nested Call
#COPYRIGHT(NAME, YEAR)	
{Made by &NAME& in &YEAR&}	
\$COPYRIGHT(\$SIGNATURE,2003)	

Example 3: Incorrect usage - nested call (more on errors in the Errors and Warnings section)

Input Output

#TOTAL(PRICE)	The total price is \$750
{The total price is \\$&PRICE&}	
\$TOTAL(749)	

Example 4: Usage of the escape character '\'

Command Line Interface

The program is operated with a command line interface (CLI). It supports a few options regarding the error/warning output. The basic use case for this CLI is as follows:

The program takes 'input_file' as the source file with text to be transformed and outputs the transformed text into 'output_file'. The errors and warnings are outputted to stdout. If the program is run with only one argument, it uses it as the input, and outputs to a text file called 'mg_out' instead. Running the program with no arguments or too many arguments results in an error, and it is not executed. The program also supports options to control the error and warning output, that can be inserted before the I/O files. The option summary can be seen in the table below.

Option	Short version	Arguments	Description
silent	-S	None	Mutes the error and warning
			output
nowarn	-n	None	Mutes the warning output
output	-0	Filename	Redirects the error and warning
			output to a file. If no argument is
			given, it defaults to mg_log
verbose	-V	None	Makes the error and warning
			output more verbose to give a
			clearer error information

Choosing a non-existent option or incompatible options (like -s + -v) will result in an error and the program will abort execution.

Errors and Warnings

The macrogenerator program can encounter some errors and warnings when transforming text, as a result of incorrect or unexpected input. In case of an error, the program informs the user of said error and stops execution. In case of a warning the program informs the user and continues text transformation. The way of informing the user can be controlled via the CLI, described further in the *Command Line Interface* section. Errors and warnings are divided into categories, and each of them is given a distinct code. The errors and warnings are presented in the tables below.

Category	Code	Error Name	Description	
	e10	Incorrect Macro Name	The macro name in a macro definition contains an incorrect character — whitespace or one of the special characters (#,\$,(,),{,},&,\)	
	e11	Macro Already Defined	The macro definition defines a macro with a name that already exists in the name library	
Macro Definition Error	e12	Incorrect Parameter Name	The parameter name in a macro definition contains an incorrect character — whitespace or one of the special characters (#,\$,(,),{,},&,\)	
	e13	Missing Macro Body	A non-whitespace character was encountered between ')' and '{' in a macro definition	
	e14	Parameter Undefined	A parameter name used in the macro body is not present in the argument list	
	e15	Nested Call	A macro call was encountered inside a macro body	
	e16	Nested Definition	A macro definition was encountered inside a macro definition	
	e20	Undefined Macro	A macro name called was not found in the macro library	
	e21	Too Few Arguments	Macro was called with less arguments than in the definition	
Macro Call Error	e22	Incorrect Macro Call	Macro name that was called contains an incorrect character – whitespace or one of the special characters (#,\$,(,),{,},&,\)	
	e23	Nested Call	A macro call was encountered inside a macro call	
	e24	Nested Definition	A macro definition was encountered inside a macro call	
	e81	Incompatible Options	Incompatible options were selected, e.gs and -v	
CLI Error	e82	Unknown Option	An unknown option was supplied to the program	
	e83	No Input File	The input file was not specified	
	e98	I/O Error	There was an error with file I/O	
Other	e99	Internal Error	There was an internal error caused by a third party	

Category	Code	Warning Name	Description
	w10	Unused Parameter	Parameter from the definition is not used
Macro Definition			inside the macro body
Warning	w11	Empty Macro Body	The macro body was left empty
	w12	Unused Macro	Macro definition was never called
	w10	Too Many Arguments	The macro was called with more
			arguments than the definition
Macro Call	w11	Empty Argument	The argument supplied to the call was
Warning			empty – nothing between two ','
	w12	Whitespace Argument	The argument supplied starts with
			whitespace – possible error from the user
CLI Warning	w80	Overwrite Warning	The input file is the same as the output file
Other	w90	Escape Character Error	The escape character '\' was used on a
Other			non-special character

IV. Functional Test Cases

The following test cases check all the warnings and errors available in the MacroGenerator and a few correct usage cases. The tests don't include the CLI tests.

Correct Usage

Test Case	Input	Expected Output
Basic single macro with no	<pre>#MACRO(){test macro}</pre>	test macro
arguments	\$MACRO()	
Basic single macro with	#MACRO(P1, P2)	34+20*34
arguments	{&P1&+&P2&*&P1&}	
	\$MACRO(34,20)	
Multiple basic macros	<pre>#MACRO1(){test macro}</pre>	34+20*34
	#MACRO2(P1, P2)	test macro
	{&P1&+&P2&*&P1&}	
	\$MACRO2(34,20)	
	\$MACRO1() free text	free text
Multiple macros with free text	#MACRO1(){test macro}	34+20*34
	#MACRO2(P1, P2)	test macro
	{&P1&+&P2&*&P1&}	MORE TEXT
	\$MACRO2(34,20)	TIONE TEXT
	\$MACRO1()	
	MORE TEXT	
Escape symbol in free text	Price: /\$20	Price: \$20
Escape symbol in macro body	#MACRO(A){B\&&A&}	B&C
	\$MACRO(C)	
Escape symbol in argument	<pre>#MACRO(A){hello &A&}</pre>	hello big \$
	\$MACRO(big \\$)	

Macro Definition Errors

Test Case	Input	Expected Output
Incorrect Macro Name	<pre>#MY MACRO(){test macro}</pre>	Error e10
Macro Already Defined	#MACRO(P1, P2){&P1&+&P2&} #MACRO(){hello}	Error e11
Incorrect Parameter Name	#MACRO(MY PARAM) {&MY PARAM& is wrong}	Error e12
Missing Macro Body	<pre>#MACRO()eee{test macro}</pre>	Error e13
Parameter Undefined	#MACRO(P1, P2) {&P1& is less than &P3&}	Error e14
Nested Call	<pre>#HI(){hello} #MACRO(ARG){\$HI &ARG&}</pre>	Error e15
Nested Definition	#MACRO(){#NEST(){no}\$NEST}	Error e16

Macro Call Errors

Test Case	Input	Expected Output
Undefined Macro	\$MACRO(hello)	Error e20
Too Few Arguments	#MACRO(P1, P2){&P1&+&P2&} \$MACRO(23)	Error e21
Incorrect Macro Call	<pre>#MYMACRO(P){&P& is good} \$MY MACRO(John)</pre>	Error e22
Nested Call	#A(P){hello &P&} #B(){John} \$A(\$B)	Error e23
Nested Definition	#A(P){hello &P&} \$A(#B(){John})	Error e24

Macro Definition Warnings

Test Case	Input	Expected Output
Unused Parameter	<pre>#MACRO(P){test macro}</pre>	11
	\$MACRO(11)	Warning w10
Empty Macro Body	#MACRO(P1, P2){}	
	\$MACRO(a,b)	Warning w11
Unused Macro	<pre>#MACRO(P){test macro}</pre>	Warning w12

Macro Call Warnings

Test Case	Input	Expected Output
Too Many Arguments	<pre>#MACRO(){test macro}</pre>	test macro
	\$MACRO(John)	Warning w20
Empty Argument	#MACRO(P1, P2){&P1&+&P2&}	+34
	\$MACRO(,34)	Warning w21
Whitespace Argument	#MACRO(P1, P2){&P1&+&P2&}	32+ 2
	\$MACRO(34, 2)	Warning w22