

RSARMAGEDDON V.1.0 ATHENA

User manual

Vittorio Mignini aka M1gnus — Nalin Dhingra aka Lotus

August 12, 2020

Contents

Ι	Da	ata types	5												
1	list		5												
2	plaintext														
3	ciph	nertext	5												
4	int		6												
II	O	ptions	7												
5	Gen	neral features	7												
	5.1	factor	7												
	5.2	ecm	7												
	5.3	qs	7												
	5.4	isprime	8												
	5.5	show-attacks	8												
	5.6	credits	8												
	5.7	version	8												
6	pen	1	9												
	6.1	key	9												
	6.2	η	9												

	6.3	e											•		•		•	9
	6.4	d																9
	6.5	p				•												9
	6.6	q				•												9
	6.7	output	-priv			•												10
	6.8	output	-pub					•				 •					•	10
	6.9	dumpv	alues															10
	6.10	creater	oub .			•												10
	6.11	creater	oriv .															10
	6.12	format																11
	6.13	genera	te															11
7	ciph	ertool																12
7	_	ertool																
7	ciph 7.1	cipher																12
7	_	cipher	 n															12
7	_	cipher														•		12 12
7	_	cipher 7.1.1	n								•							12 12 12
7	_	cipher 7.1.1 7.1.2 7.1.3	n e															12 12 12 12
7	_	cipher 7.1.1 7.1.2 7.1.3 7.1.4	n e key .	··· text			 	 	 	 	 	 		 				12 12 12 12
7	_	cipher 7.1.1 7.1.2 7.1.3 7.1.4	n e key . plaint	text	 		 	 	 	 	 	 		 	 			12 12 12 12 12
7	_	cipher 7.1.1 7.1.2 7.1.3 7.1.4 7.1.5	n e key . plaint	text text- it-fil	 -file		 	 	 	 	 	 		 	 			12 12 12 12 12 12 13
7	_	cipher 7.1.1 7.1.2 7.1.3 7.1.4 7.1.5 7.1.6	n e key . plaint plaint outpu	text text text				 	 	 	 	 			 			12 12 12 12 12 12 13

		7.2.1	n .							 •								13
		7.2.2	e .												•	•		14
		7.2.3	d .													•	•	14
		7.2.4	p .						•	 •		 •						14
		7.2.5	q .						•	 •								14
		7.2.6	key												•			14
		7.2.7	ciphe	ertex	ct .										•			15
		7.2.8	ciphe	ertex	ct-fil	le <	lis	st>							•			15
		7.2.9	padd	ling														15
		7.2.10	file-p	oadd	ing	•				 •					•		•	15
		7.2.11	outp	ut-fi	le .	•			•	 •					•		•	16
8	atta	ck																16
8			κev															
8	8.1	publick																16
8	8.1 8.2	publick	keydir	:		•			٠	 •	 •	 •		 •	•	•		16 16
8	8.1 8.2 8.3	publick publick attack	keydir 	: 														16 16 16
8	8.1 8.2 8.3 8.4	publick publick attack n	xeydi1 															16 16 16
8	8.1 8.2 8.3 8.4 8.5	publich publich attack n e	xeydir							 	 	 		 			 	16 16 16 16
8	8.1 8.2 8.3 8.4 8.5 8.6	publich publich attack n e n-e-file	keydin							 	 	 	 	 			 	16 16 16 17
8	8.1 8.2 8.3 8.4 8.5 8.6 8.7	publich publich attack n e n-e-file ext	keydin							 	 	 	 	 			 	16 16 16 17 17
8	8.1 8.2 8.3 8.4 8.5 8.6 8.7 8.8	publich attack n e n-e-file ext private	keydir							 	 	 	 	 			 	16 16 16 17 17 17
8	8.1 8.2 8.3 8.4 8.5 8.6 8.7 8.8	publich publich attack n e n-e-file ext	keydir							 	 	 	 	 			 	16 16 16 17 17

8.11	uncipher-file	•	•			•									•		18
8.12	output-file .									•					•		18
8.13	output-dir .																18
8 14	timeout																18

Part I

Data types

1 list

```
string[,string[,...]]
```

List of string. Is possible to insert one of more string separated by a comma.

2 plaintext

string[:type]

Plaintext used during the encryption process, is possible to specify the plaintext type, that can be chosen from the following:

- -str
- -dec
- -hex
- -oct
- -bin

if type is not chosen from this ones or type is not specified, then the type is set to str by default.

3 ciphertext

string[:type]

Ciphertext used during the decryption process, is possible to specify the ciphertext type, that can be choosen from the following:

- -dec
- -hex
- -oct
- -bir

if type is not chosen from this ones or type is not specified, then the type is set to dec by default.

4 int

string[:base]

Integer value. Is possible to use the standard notation for hexadecimal (0x...), octal (0...) and binary (0b...) representations of integers. Is also possible to specify an integer 0 < base < 10. If base <= 0 then base is ignored, if base > 9 then a ValueError exception is raised.

Part II

Options

5 General features

5.1 factor

--factor <int>

factor takes an int value and returns its factors. This feature is a wrapper to Sage's factor function. "Note that Sage's general factor command does nothing but call Pari's factor C library function." – from doc.sagemath.org.

5.2 ecm

--ecm <int>

ecm takes an int value and returns its factors. This feature is a wrapper to Sage's ecm.factor method. ECM factorization is the fastest way to factorize a composite integer if one of its factor is relatively small (25 digits / 80 bit). See doc.sagemath.org for more informations about Sage's ecm.factor method. See wikipedia for more informations about ECM factorization method.

5.3 qs

--qs <int>

qs takes an int value (40 or more digits) and returns its factors. This feature is a wrapper to Sage's qsieve method. The Quadrartic Sieve factorization is the fastest method for integers which have less than 100 digits and the second fastest method known (the fastest is general number field sieve). See doc.sagemath.org for more informations about Sage's qsieve method. See wikipedia for more informations about Quadratic Sieve factorization.

5.4 isprime

--isprime <int>

isprime takes an int value and say if it's prime or not. This feature is a wrapper to Sage's is_prime method.

5.5 show-attacks

--show-attacks

show-attacks shows implemented attacks.

5.6 credits

--credits

credits shows credits.

5.7 version

--version

version shows version number and version name.

6 pem

6.1 key

--key <string>

key takes a string which represent a path to a public/private key file.

6.2 n

-n <int>

n takes an int value which represent RSA public modulus.

6.3 e

-e <int>

e takes an int value which represent RSA public exponent.

6.4 d

-d <int>

d takes an int value which represent RSA private exponent.

6.5 p

-p <int>

p takes an int value which represent the first factor of RSA modulus.

6.6 q

-q <int>

q takes an int value which represent the second factor of RSA modulus.

6.7 output-priv

-output-priv <string>

output-priv takes a string which represent the path of the private key that will be created if --createpriv is specified.

6.8 output-pub

-output-pub <string>

output-pub takes a string which represent the path of the public key that will be created if --createpub is specified.

6.9 dumpvalues

--dumpvalues

dumpvalues shows the numeric values of the key specified by --key.

6.10 createpub

--createpub

createpub will build a public key from the values of n and e given by the user. If a path is not provided with --output-pub then the public key will be printed to stdout. is possible to specify a format for the key file using --format, the choice is between PEM, DER, OpenSSH. If none of the three choices is chosen then the format will be setted to PEM by default.

6.11 createpriv

--createpriv

createpriv will build a private key from the provided numeric values. If a path is not provided with --output-priv then the public key will be printed to stdout. is possible to specify a format for the key file using --format, the choice is between PEM, DER, OpenSSH. If none of the three choices is chosen then the format will be setted to PEM by default. In order to have success

in the creation of a private key the user must provide at least one of the following set of values (/ divide two alternatives):

n, p/q, e/d p, q, e/d.

6.12 format

--format

format takes a string which specify the output files format, the choose is between PEM, DER, OpenSSH. If none of the three choices is chosen then the format will be setted to PEM by default.

6.13 generate

--generate

generate specifies will build a new key pair (2048 bits) using a method of pycryptodome RSA object: RSA.generate(). If e is specified by the user then the public exponent of the new key will be e, otherwise the default value of the public exponent will be 65537. if --output-pub is setted then the public key will be saved in the specified path, otherwise it will be printed to stdout. Same for the private key.

7 ciphertool

7.1 cipher

7.1.1 n

-n <int>

n takes an int value which represent RSA public modulus.

7.1.2 e

-e <int>

e takes an int value which represent RSA public exponent.

7.1.3 key

--key <string>

key takes a string which specify the path for a public/private key that will be used to encrypt the plaintext/plaintext-file. If you don't provide a key, then you must provide n and e.

7.1.4 plaintext

--plaintext <plaintext>

plaintext takes a plaintext which specify the plaintext to encrypt with the provided key. The ciphertext will be printed in decimal, hexadecimal and raw format.

7.1.5 plaintext-file

--plaintext-file <list>

plaintext-file takes a list which specify the path for some files that will be encrypted with the provided key.

7.1.6 output-file

```
--output-file <list>
```

output-file takes a list which specify some names for the encrypted files. If there are more files than names, then the name of the encrypted file will be file_name.enc by default.

7.1.7 padding

--padding <str>

padding takes a string which represent the type of the padding which will be used to pad the plaintext, you can choose one of the following:

pkcs7

iso7816

x923.

7.1.8 file-padding

--file-padding <str>

file-padding takes a string which represent the type of the padding which will be used during the encryption process for the plaintext file, you can choose one of the following:

raw

pkcs7

ssl

oaep

x931

If padding is not provided, then the default value will be pkcs.

7.2 uncipher

7.2.1 n

-n <int>

n takes an int value which represent RSA public modulus.

7.2.2 e

-e <int>

e takes an int value which represent RSA public exponent.

7.2.3 d

-d <int>

d takes an int value which represent RSA private exponent.

7.2.4 p

-p <int>

p takes an int value which represent RSA first modulus factor.

7.2.5 q

-q <int>

q takes an int value which represent RSA second modulus factor.

7.2.6 key

--key <string>

key takes a string which specify the path for a private key that will be used to decrypt the ciphertext/ciphertext-file. If you don't provide a key, then you must provide at least the needed argument to build a private key or the needed arguments to perform the decryption. so one of the following set of values (/ divide two alternatives):

n, p/q, e/d
p, q, e/d
phi, e, n

n, d.

7.2.7 ciphertext

--plaintext <ciphertext>

ciphertext takes a ciphertext which specify the ciphertext to decrypt with the provided key. The plaintext will be printed in decimal, hexadecimal and raw format.

7.2.8 ciphertext-file <list>

--ciphertext-file <list>

ciphertext-file takes a list which specify the path for some files that will be decrypted with the provided key.

7.2.9 padding

--padding <str>

padding takes a string which represent the type of the padding which will be used during the process in the plaintext, you can choose one of the following: pkcs7

iso7816

x923.

7.2.10 file-padding

--file-padding <str>

file-padding takes a string which represent the type of the padding which will be used during the process in the plaintext file, you can choose one of the following:

raw

pkcs7

ssl

oaep

x931

If padding is not provided, then the default value will be pkcs.

7.2.11 output-file

--output-file <list>

output-file takes a list which specify some names for the decrypted files. If there are more files than names, then by default the name of the decrypted file will be file_name.dec.

8 attack

8.1 publickey

--publickey <str>
publickey takes a string which represent a path to a public key file.

8.2 publickeydir

--publickeydir <str>

publickeydir takes a string which represent a path to a directory which contain public key files with extension specified in ext (.pem by default).

8.3 attack

--attack <list>

attack takes a list with the names of the attacks that will be performed on the public key(s).

8.4 n

-n <list>

n takes a list of int with some public key modulus.

8.5 e

-e <list>

e takes a list of int with some public key exponent.

8.6 n-e-file

--n-e-file <str>

n-e-file takes a string which represent a path to a file on which every line is formatted as follows: n:e or n.

8.7 ext

--ext <str>

ext takes a string which specify the extension of public keys in the directory specified by --publickeydir.

8.8 private

--private

private will create a private key file if the private key values is recovered, if output-private is not specified then the private key file will be prompted to stdout.

8.9 output-private

--output-private <str>

output-private takes a string which represent the path where the recovered private key file will be saved if --private flag is setted.

8.10 uncipher

--uncipher <ciphertext>

uncipher takes a ciphertext that will be decrypted if private key values will be recovered.

8.11 uncipher-file

--uncipher-file <str>

uncipher-file takes a string which represent a ciphertext-file that will be decrypted if private key values will be recovered, the decrypted file will be saved in the path specified by output-file.

8.12 output-file

--output-file <str>

output-file takes a string which represent the path where the decrypted ciphertext-file specified by uncipher-file will be saved.

8.13 output-dir

--output-dir <str>

output-dir takes a string which represent the path where the private key files recovered from the public keys in publickeydir will be saved, if --output-dir is not specified then the private key files will be printed to stdout.

8.14 timeout

--timeout <int>

timeout takes an int which represent the max attacks running time. if timeout is not specified then an attack can run indefinitely.