
#### **Lecture 7a – Communication Costs**

- Communication of information between processing elements is one of the major overheads related to parallel computing on distributed-memory systems
- Cost factors include:
  - Startup time, t<sub>s</sub>, is the time required to handle a message at the sending and receiving nodes
  - Per-hop time, t<sub>h</sub>, is the time it takes the header of a message to travel between two directly-connected nodes. This is also known as node latency
  - Per-word transfer time, t<sub>w</sub>, is the average amount of time that a message of size m takes to traverse I links (or hops)

$$time_{communication} = t_s + (mt_w + t_h)l$$
 for store - and - forward routing  
=  $t_s + lt_h + mt_w$  for cut - through routing

th is generally considered to be small compared to ts and two

#### **Routing Strategies**



2

#### **Communication Costs**

- So in order to optimize the cost of message transfers, we need to
  - Communicate in bulk: aggregate a number of small messages into a single large message to reduce the effect of t<sub>s</sub>
  - Minimize the volume of data: reduce the amount of data that is being passed
  - Minimize the distance of data transfer: minimize the number of hops, I, that a message must traverse
- The first and second of these involves programming strategy and techniques
- The third involves the inter-connection of the processing elements

#### **Routing**

- Efficient algorithms to route messages to processors are critical to achieve good parallel performance
- Routing mechanisms:
  - Minimal: always select the shortest path. Provides the minimum t<sub>h</sub> but can lead to congestion
  - Non-minimal: can route messages along longer (than the shortest) paths to avoid congestion
  - Deterministic: a unique path based upon the source and destination
  - Adaptive: a path based upon the current status of the network and selects a path that avoids congestion

#### **Mapping Techniques to Determine Inter-Connections**

- Mapping techniques are used to determine optimal processor inter-connections and predict the efficiency of networks
- Binary Reflected Gray Code (BRG): G(i,d) denotes the i-th entry in a sequence of Gray codes of d bits.
   G(i,d+1) is derived from G(i,d) by reflecting the table and prefixing the reflected entry with 1 and the original entry with 0.

$$G(0,1) = 0$$


$$G(1,1) = 1$$

A linear array composed of 2<sup>d</sup> nodes can be embedded into a d-dimensional hypercube using this mapping


$$G(i, x+1) = \begin{cases} G(i, x), & i < 2^{x} \\ 2^{x} + G(2^{x+1} - 1 - i, x), & i \ge 2^{x} \end{cases}$$

5

#### Example of BRG Code: 8p Ring → 8p hypercube



## 8p ring → 8p hypercube




### **Embedding Other Networks on Hypercubes:**

- Hypercube is a rich topology, many other networks can be "easily" mapped onto it.
- Mapping a linear array into a hypercube:
  - A linear array (or ring) of 2<sup>d</sup> processors can be embedded into a d-dimensional hypercube by mapping processor i onto processor G(i,d) of the hypercube
- Mapping a 2<sup>r</sup> x 2<sup>s</sup> mesh on a hypercube:

$$processor(i,j) --- > G(i,r) || G(j,s)$$
 (|| denote concatenation)

### **Mapping Meshes** → **Hypercubes**



### **Trade-Off Among Different Networks**

| Network              | Minimum latency | Maximum Bw per Proc | Wires      | Switches   | Example        |
|----------------------|-----------------|---------------------|------------|------------|----------------|
| Completely connected | Constant        | Constant            | O(p*p)     | -          | -              |
| Crossbar             | Constant        | Constant            | O(p)       | O(p*p)     | Cray           |
| Bus                  | Constant        | O(1/p)              | O(p)       | O(p)       | SGI Challenge  |
| Mesh                 | O(sqrt p)       | Constant            | O(p)       | -          | Intel ASCI Red |
| Hypercube            | O(log p)        | Constant            | O(p log p) | -          | Sgi Origin     |
| Switched             | O(log p)        | Constant            | O(p log p) | O(p log p) | IBM SP-2       |

10

#### **Beowulf**

### • Cluster built with commodity hardware components

- PC hardware (x86,Alpha,PowerPC)
- Commercial high-speed interconnection (100Base-T, Gigabit Ethernet, Myrinet,SCI)
- Linux, Free-BSD operating system





http://www.beowulf.org

11

# **Apple: PowerPC cluster**







12

#### **Clusters of SMP**

- The next generation of supercomputers will have thousand of SMP nodes connected.
  - Increase the computational power of the single node
  - Keep the number of nodes "low"
  - New programming approach needed, MPI+Threads (OpenMp,Pthreads,....)
  - See www.top500.org







#### Tianhe-2 (1st)

- China's National University of Defense Technology
- 54.9 Petaflops at peak
- 1,024 Terabytes of memory
- 3,120,000 Xeon cores
- Sustained performance of up to 33.8 Petaflops
- http://en.wikipedia.org/wiki/Tianhe-2





14

# Titan (2<sup>nd</sup>)

- DoE Oak Ridge National Lab
- 27.1 Petaflops at peak
- 560,640 core processors (70,080 8-core nodes)
   Opteron with NVIDIA K20x
- 710 Terabytes of memory
- Sustained performance of up to 17.6 Petaflops
- http://en.wikipedia.org/wiki/
   Titan\_(supercomputer)



http://www.llnl.gov/asci



# Sequoia – BlueGene/Q (3<sup>rd</sup>)

- DoE LLNL
- 20.1 Petaflops at peak
- 1,573 Terabytes of memory
- 1,572,864 cores IBM Power BQC
- Sustained performance of up to 17.2 Petaflops
- http://en.wikipedia.org/wiki/ IBM\_Sequoia





15