



LECTURE 8 – Cisco Packet Tracer: Basic Router Configuration

In this lecture, we learn how to configure a simple network on Cisco Packet Tracer using:

- 1 Router
- 1 Switch
- 2 PCs
- Cables
- Basic router setup (IP, speed, enabling interface)
- PC IP configuration
- Passwords: enable password, enable secret
- Console password
- Telnet password
- SSH setup (most important part)

1. Creating a Basic Network in Packet Tracer

Devices Needed

- ✓ One Router
- ✓ One Switch
- ✓ Two PCs
- ✓ Appropriate cables (straight-through cable for PC–Switch, and Switch–Router)

Steps

1. Open Packet Tracer
2. Go to **Network Devices → Routers** → Select **CISCO 2911** (or any router)
3. Add a Switch (ex: 2960)
4. Add 2 PCs

5. Connect:

- PC1 → Switch
 - PC2 → Switch
 - Switch → Router (GigabitEthernet port)
-

2. Showing Interface Speeds & Ports

If port numbers are not visible:

Steps:

1. Go to **Options**
2. Select **Preferences**
3. Tick the option:
✓ “Always Show Port Labels in Logical Workspace”

Now all port numbers will be visible.

3. Router Configuration (Step-by-Step)

Click the Router → CLI →

It asks:

“Would you like to enter the initial configuration dialog?”

Select: **NO**

Press ENTER twice → You reach:

Router>

✓ Enter Privileged EXEC mode

enable

✓ Enter Global Configuration mode

configure terminal

or

conf t

4. Assign IP Address to Router Interface

Go to interface:

interface g0/0

or

int g0/0

Assign IP:

ip address 10.0.0.1 255.0.0.0

Enable the interface (VERY IMPORTANT – by default interfaces are shutdown):

no shutdown

★ Why?

All router interfaces are OFF by default for safety.

no shutdown turns it on.

★ Daily Life Example:

When a new ISP router arrives, the technician enables its WAN/LAN ports before connecting to the internet.

5. PC IP Configuration

Click PC → Desktop → IP Configuration

Enter:

IP Address: (example) 10.0.0.10

Subnet Mask: Automatically fills (255.0.0.0)

Default Gateway: 10.0.0.1 → **router's IP**

★ Why default gateway is needed?

To send traffic outside your own network.

Daily Example:

Your PC uses 192.168.1.1 as default gateway to access Google.

6. Speed Settings on Router Interface

To check speed options:

```
int g0/0
```

```
speed ?
```

Possible values:

- 100
- 1000
- auto

To set speed:

```
speed 100
```

or

```
speed 1000
```



To verify interface status:

```
show int g0/0
```

7. Checking IP & Interface Status

✓ To check ALL interfaces:

```
show ip interface brief
```

Shows:

- Each interface
- IP address
- Status (up/down)

✓ To check a specific interface:

```
show int g0/0
```

8. Description for Interfaces

To add description (useful in companies):

```
int g0/0  
description Connected to PC
```

★ Why important?

Helps engineers understand what each interface connects to.

Example:

In real companies:

- Gi0/0 → Connected to Firewall
- Gi0/1 → Connected to Switch
- Gi0/2 → Internet Link



9. Show Commands in Global Mode

You **cannot** run show commands directly in Global Configuration mode.

You must type:

```
do show ip int brief
```

Why?

“do” executes a privileged command from configuration mode.

10. Router Password Protection

Routers use different types of passwords:

1. Enable Password

2. Enable Secret

3. Console Password

4. Telnet Password

5. SSH Password

A) Enable Password & Enable Secret

Enable Password

enable password 1234

- Uses **MD7 encryption**
- Weak
- Can be cracked easily
- Not recommended in real companies
- Shown as plain-text unless encryption is enabled

Enable Secret (MOST SECURE)

enable secret mysecret123

- Uses **MD5 hashing**
- Strong
- Cannot be reversed easily
- Industry standard
- ALWAYS preferred over enable password

✓ View Password in Running Config

show running-config

Enable password = weak

Enable secret = encrypted

✓ Remove password:

no enable secret

B) Setting the Router Hostname

hostname BranchRouter

Why?

- Helps identify routers in large networks
 - Used in SSH authentication (required)
-

C) Setting Console Password

Console = local access to router.

Commands:

line console 0

password 123

login

★ Why set console password?

To prevent unauthorized people from configuring the router locally.

D) Telnet Password (Remote Access)

Telnet is an **insecure** remote login method.

Commands:

line vty 0 15

```
password telnet12345
```

```
login
```

Meaning:

- VTY 0–15 → allows 16 simultaneous Telnet users
 - Everyone must enter this password
-

● Why Telnet is NOT recommended?

Because Telnet sends:

- username
- password
- commands

in **plain text**.

Anyone can sniff it.



■ E) SSH Configuration (Most Secure) — VERY IMPORTANT

SSH uses encryption and is the preferred remote access method.

Step 1: Set hostname

```
hostname Router1
```

Step 2: Set domain name

```
ip domain-name codingseekho.in
```

Step 3: Generate RSA key

```
crypto key generate rsa
```

It will ask:

How many bits in the modulus?

You can give:

- 1024
- 2048 (recommended)

More bits = more secure.

Step 4: Create a user account

```
username admin privilege 15 secret adminpass123  
privilege 15 = full admin access
```

Step 5: Enable SSH-only access on VTY

```
line vty 0 4  
transport input ssh  
password 12345  
login  
Now only SSH is allowed.
```

★ Daily Life Example of SSH:

When engineers manage routers in:

- Banks
- Data centers
- Cloud networks
- IT companies

They ALWAYS use SSH (port 22).

Telnet is banned.

✓ Saving everything

do write

or

do wr

■ FINAL SUMMARY (Perfect for Revision)

✓ Build network using router + switch + 2 PCs

✓ Assign IP to router interfaces

✓ Enable interfaces using no shutdown

✓ Configure PC IP + subnet mask + gateway

✓ Set interface speed

✓ Check connectivity using show ip int brief

✓ Add interface descriptions

✓ Enable passwords:

- enable password (weak)
- enable secret (strong)

✓ Console password

✓ Telnet password

✓ SSH configuration (recommended)