# **Lab – Securing Network Devices**

This lab has been updated for use on NETLAB+

# **Topology**



# **Addressing Table**

Device	Interface	IP Address	Subnet Mask	Default Gateway
R1	G0/1	192.168.1.1	255.255.255.0	N/A
S1	VLAN 1	192.168.1.11	255.255.255.0	192.168.1.1
PC-A	NIC	192.168.1.3	255.255.255.0	192.168.1.1

#### **Objectives**

Part 1: Configure Basic Device Settings

Part 2: Configure Basic Security Measures on the Router

Part 3: Configure Basic Security Measures on the Switch

# Background / Scenario

It is recommended that all network devices be configured with at least a minimum set of best practice security commands. This includes end user devices, servers, and network devices, such as routers and switches.

In this lab, you will configure the network devices in the topology to accept SSH sessions for remote management. You will also use the IOS CLI to configure common, basic best practice security measures. You will then test the security measures to verify that they are properly implemented and working correctly.

**Note**: The routers used with CCNA hands-on labs are Cisco 1941 ISRs with Cisco IOS Release 15.2(4)M3 (universalk9 image). The switches used are Cisco Catalyst 2960s with Cisco IOS Release 15.0(2) (lanbasek9 image). Other routers, switches, and Cisco IOS versions can be used. Depending on the model and Cisco IOS version, the commands available and output produced might vary from what is shown in the labs. Refer to the Router Interface Summary table at the end of the lab for the correct interface identifiers.

**Note**: Make sure that the routers and switches have been erased and have no startup configurations. If you are unsure, contact your instructor.

# Part 1: Configure Basic Device Settings

In Part 1, you will configure basic settings, such as the interface IP addresses, device access, and passwords on the devices.

#### Step 1: Initialize and reload the router and switch.

#### Step 2: Configure the router and switch.

- a. Console into the device and enable privileged EXEC mode.
- b. Assign the device name according to the Addressing Table.
- c. Disable DNS lookup to prevent the router from attempting to translate incorrectly entered commands as though they were hostnames.
- d. Assign **class** as the privileged EXEC encrypted password.
- e. Assign cisco as the console password and enable login.
- f. Assign **cisco** as the VTY password and enable login.
- g. Create a banner that warns anyone accessing the device that unauthorized access is prohibited.
- h. Configure and activate the G0/1 interface on the router using the information contained in the Addressing Table.
- Configure the default SVI on the switch with the IP address information according to the Addressing Table.
- j. Save the running configuration to the startup configuration file.

# Step 3: Configure PC-A.

- a. Configure PC-A with an IP address and subnet mask referenced in the addressing table.
- b. Configure a default gateway for PC-A

# Part 2: Configure Basic Security Measures on the Router

#### Step 1: Encrypt the clear text passwords.

```
R1(config) # service password-encryption
```

#### Step 2: Strengthen passwords.

An administrator should ensure that passwords meet the standard guidelines for strong passwords. These guidelines could include combining letters, numbers and special characters in the password and setting a minimum length.

**Note**: Best practice guidelines require the use of strong passwords, such as those shown here, in a production environment. However, the other labs in this course use the cisco and class passwords for ease in performing the labs.

a. Change the privileged EXEC encrypted password to meet guidelines.

```
R1(config) # enable secret Enablep@55
```

b. Require that a minimum of 10 characters be used for all passwords.

```
R1(config)# security passwords min-length 10
```

#### Step 3: Enable SSH connections.

a. Assign the domain name as **CCNA-lab.com**.

```
R1(config)# ip domain-name CCNA-lab.com
```

b. Create a local user database entry to use when connecting to the router via SSH. The password should meet strong password standards, and the user should have user EXEC access. If privilege level is not specified in the command, the user will have user EXEC (level 15) access by default.

```
R1(config) # username SSHadmin privilege 1 secret Admin1p@55
```

 Configure the transport input for the VTY lines so that they accept SSH connections, but do not allow Telnet connections.

```
R1(config) # line vty 0 4
R1(config-line) # transport input ssh
```

d. The VTY lines should use the local user database for authentication.

```
R1(config-line)# login local
R1(config-line)# exit
```

e. Generate a RSA crypto key using a modulus of 1024 bits.

```
R1(config) # crypto key generate rsa modulus 1024
```

#### Step 4: Secure the console and VTY lines.

a. You can set the router to log out of a connection that has been idle for a specified time. If a network administrator was logged into a networking device and was suddenly called away, this command automatically logs the user out after the specified time. The following commands cause the line to log out after five minutes of inactivity.

```
R1(config)# line console 0
R1(config-line)# exec-timeout 5 0
R1(config-line)# line vty 0 4
R1(config-line)# exec-timeout 5 0
R1(config-line)# exit
R1(config)#
```

b. The following command impedes brute force login attempts. The router blocks login attempts for 30 seconds if someone fails two attempts within 120 seconds. This timer is set especially low for the purpose of this lab.

```
R1(config) # login block-for 30 attempts 2 within 120
```

What does the 2 within 120 mean in the above command?

What does the block-for 30 mean in the above command?

Step 5: Verify that all unused ports are disabled.

Router ports are disabled by default, but it is always prudent to verify that all unused ports are in an administratively down state. This can be quickly checked by issuing the **show ip interface brief** command. Any unused ports that are not in an administratively down state should be disabled using the **shutdown** command in interface configuration mode.

#### R1# show ip interface brief

Interface	IP-Address	OK?	Method	Status	Protocol
Embedded-Service-Engine0/0	unassigned	YES	NVRAM	administratively down	down
GigabitEthernet0/0	unassigned	YES	NVRAM	administratively down	down
GigabitEthernet0/1	192.168.1.1	YES	manual	up	up

Serial0/0/0

Serial0/0/1

R1# Step 6: Verify that your security measures have been implemented correctly. a. Use Tera Term to telnet to R1. Does R1 accept the Telnet connection? Explain. b. Use Tera Term to SSH to R1. Does R1 accept the SSH connection? c. Intentionally mistype the user and password information to see if login access is blocked after two attempts. What happened after you failed to login the second time? d. From your console session on the router, issue the **show login** command to view the login status. In the example below, the **show login** command was issued within the 30 second login blocking period and shows that the router is in Quiet-Mode. The router will not accept any login attempts for 14 more seconds. R1# show login A default login delay of 1 second is applied. No Quiet-Mode access list has been configured. Router enabled to watch for login Attacks. If more than 2 login failures occur in 120 seconds or less, logins will be disabled for 30 seconds. Router presently in Quiet-Mode. Will remain in Quiet-Mode for 14 seconds. Denying logins from all sources. R1# After the 30 seconds has expired, SSH to R1 again and login using the **SSHadmin** username and Admin1p@55 for the password. After you successfully logged in, what was displayed? \_\_\_\_ Enter privileged EXEC mode and use **Enablep@55** for the password. If you mistype this password, are you disconnected from your SSH session after two failed attempts within 120 seconds? Explain. Issue the **show running-config** command at the privileged EXEC prompt to view the security settings you have applied.

unassigned

unassigned

YES NVRAM administratively down down

YES NVRAM administratively down down

# Part 3: Configure Basic Security Measures on the Switch

#### Step 1: Encrypt the clear text passwords.

```
S1(config)# service password-encryption
```

#### Step 2: Strengthen Passwords on the switch.

Change the privileged EXEC encrypted password to meet strong password guidelines.

```
S1(config) # enable secret Enablep@55
```

**Note**: The security **password min-length** command is not available on the 2960 switch.

#### Step 3: Enable SSH Connections.

a. Assign the domain-name as CCNA-lab.com

```
S1(config) # ip domain-name CCNA-lab.com
```

b. Create a local user database entry for use when connecting to the switch via SSH. The password should meet strong password standards, and the user should have user EXEC access. If privilege level is not specified in the command, the user will have user EXEC (level 1) access by default.

```
S1(config) # username SSHadmin privilege 1 secret Admin1p@55
```

 Configure the transport input for the VTY lines to allow SSH connections but not allow Telnet connections.

```
S1(config) # line vty 0 15
S1(config-line) # transport input ssh
```

d. The VTY lines should use the local user database for authentication.

```
S1(config-line)# login local
S1(config-line)# exit
```

e. Generate an RSA crypto key using a modulus of 1024 bits.

```
S1(config) # crypto key generate rsa modulus 1024
```

#### Step 4: Secure the console and VTY lines.

a. Configure the switch to log out a line that has been idle for 10 minutes.

```
S1(config) # line console 0
S1(config-line) # exec-timeout 10 0
S1(config-line) # line vty 0 15
S1(config-line) # exec-timeout 10 0
S1(config-line) # exit
S1(config) #
```

b. To impede brute force login attempts, configure the switch to block login access for 30 seconds if there are 2 failed attempts within 120 seconds. This timer is set especially low for the purpose of this lab.

```
S1(config) # login block-for 30 attempts 2 within 120
S1(config) # end
```

### Step 5: Verify all unused ports are disabled.

Switch ports are enabled, by default. Shut down all ports that are not in use on the switch.

a. You can verify the switch port status using the **show ip interface brief** command.

### S1# show ip interface brief

Interface	IP-Address	OK?	Method	Status	Protocol
Vlan1	192.168.1.11	YES	manual	up	up
FastEthernet0/1	unassigned	YES	unset	administratively dow	n down
FastEthernet0/2	unassigned	YES	unset	administratively dow	n down
FastEthernet0/3	unassigned	YES	unset	administratively dow	n down
FastEthernet0/4	unassigned	YES	unset	administratively dow	n down
FastEthernet0/5	unassigned	YES	unset	up	up
FastEthernet0/6	unassigned	YES	unset	up	up
FastEthernet0/7	unassigned	YES	unset	down	down
FastEthernet0/8	unassigned	YES	unset	down	down
FastEthernet0/9	unassigned	YES	unset	down	down
FastEthernet0/10	unassigned	YES	unset	down	down
FastEthernet0/11	unassigned	YES	unset	down	down
FastEthernet0/12	unassigned	YES	unset	down	down
FastEthernet0/13	unassigned	YES	unset	down	down
FastEthernet0/14	unassigned	YES	unset	down	down
FastEthernet0/15	unassigned	YES	unset	down	down
FastEthernet0/16	unassigned	YES	unset	down	down
FastEthernet0/17	unassigned	YES	unset	down	down
FastEthernet0/18	unassigned	YES	unset	down	down
FastEthernet0/19	unassigned	YES	unset	down	down
FastEthernet0/20	unassigned	YES	unset	down	down
FastEthernet0/21	unassigned	YES	unset	down	down
FastEthernet0/22	unassigned	YES	unset	down	down
FastEthernet0/23	unassigned	YES	unset	down	down
FastEthernet0/24	unassigned	YES	unset	down	down
GigabitEthernet0/1	unassigned	YES	unset	down	down
GigabitEthernet0/2	unassigned	YES	unset	down	down
S1#					

b. Use the **interface range** command to shut down multiple interfaces at a time.

```
S1(config)# interface range f0/1-4 , f0/7-24 , g0/1-2
S1(config-if-range)# shutdown
S1(config-if-range)# end
S1#
```

c. Verify that all inactive interfaces have been administratively shut down.

#### S1# show ip interface brief

Interface	IP-Address	OK?	Method	Status	Protocol
Vlan1	192.168.1.11	YES	manual	up	up
FastEthernet0/1	unassigned	YES	unset	administratively down	down
FastEthernet0/2	unassigned	YES	unset	administratively down	down
FastEthernet0/3	unassigned	YES	unset	administratively down	down
FastEthernet0/4	unassigned	YES	unset	administratively down	down
FastEthernet0/5	unassigned	YES	unset	up	up
FastEthernet0/6	unassigned	YES	unset	up	up
FastEthernet0/7	unassigned	YES	unset	administratively down	down

FastEthernet0/8	unassigned	YES	unset	${\tt administratively}$	down	down
FastEthernet0/9	unassigned	YES	unset	${\tt administratively}$	down	down
FastEthernet0/10	unassigned	YES	unset	${\tt administratively}$	down	down
FastEthernet0/11	unassigned	YES	unset	${\tt administratively}$	down	down
FastEthernet0/12	unassigned	YES	unset	${\tt administratively}$	down	down
FastEthernet0/13	unassigned	YES	unset	${\tt administratively}$	down	down
FastEthernet0/14	unassigned	YES	unset	${\tt administratively}$	down	down
FastEthernet0/15	unassigned	YES	unset	${\tt administratively}$	down	down
FastEthernet0/16	unassigned	YES	unset	${\tt administratively}$	down	down
FastEthernet0/17	unassigned	YES	unset	${\tt administratively}$	down	down
FastEthernet0/18	unassigned	YES	unset	${\tt administratively}$	down	down
FastEthernet0/19	unassigned	YES	unset	${\tt administratively}$	down	down
FastEthernet0/20	unassigned	YES	unset	${\tt administratively}$	down	down
FastEthernet0/21	unassigned	YES	unset	${\tt administratively}$	down	down
FastEthernet0/22	unassigned	YES	unset	${\tt administratively}$	down	down
FastEthernet0/23	unassigned	YES	unset	${\tt administratively}$	down	down
FastEthernet0/24	unassigned	YES	unset	${\tt administratively}$	down	down
GigabitEthernet0/1	unassigned	YES	unset	${\tt administratively}$	down	down
GigabitEthernet0/2	unassigned	YES	unset	${\tt administratively}$	down	down
S1#						

# Step 6: Verify that your security measures have been implemented correctly.

- a. Verify that Telnet has been disabled on the switch.
- b. SSH to the switch and intentionally mistype the user and password information to see if login access is blocked.
- c. After the 30 seconds has expired, SSH to S1 again and log in using the **SSHadmin** username and **Admin1p@55** for the password.

Did the banner appear after you successfully logged in? \_\_\_\_\_

- d. Enter privileged EXEC mode using **Enablep@55** as the password.
- e. Issue the **show running-config** command at the privileged EXEC prompt to view the security settings you have applied.

### Reflection

	The <b>password cisco</b> command was entered for the console and VTY lines in your basic configuration in Part 1. When is this password used after the best practice security measures have been applied?
2.	Are preconfigured passwords shorter than 10 characters affected by the <b>security passwords min-length 10</b> command.

# **Router Interface Summary Table**

Router Interface Summary						
Router Model	Ethernet Interface #1	Ethernet Interface #2	Serial Interface #1	Serial Interface #2		
1800	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)		
1900	Gigabit Ethernet 0/0 (G0/0)	Gigabit Ethernet 0/1 (G0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)		
2801	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/1/0 (S0/0/0)	Serial 0/1/1 (S0/0/1)		
2811	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)		
2900	Gigabit Ethernet 0/0 (G0/0)	Gigabit Ethernet 0/1 (G0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)		

**Note**: To find out how the router is configured, look at the interfaces to identify the type of router and how many interfaces the router has. There is no way to effectively list all the combinations of configurations for each router class. This table includes identifiers for the possible combinations of Ethernet and Serial interfaces in the device. The table does not include any other type of interface, even though a specific router may contain one. An example of this might be an ISDN BRI interface. The string in parenthesis is the legal abbreviation that can be used in Cisco IOS commands to represent the interface.