Machine-Level Programming I: Basics

Kai Zhang Fudan University

zhangk@fudan.edu.cn

Today: Machine Programming I: Basics

- History of Intel processors and architectures
- Assembly Basics: Registers, operands, move
- Arithmetic & logical operations
- C, assembly, machine code

Intel x86 Processors

Dominate laptop/desktop/server market

Evolutionary design

- Backwards compatible up until 8086, introduced in 1978
- Added more features as time goes on

Complex instruction set computer (CISC)

- Many different instructions with many different formats
 - But, only small subset encountered with Linux programs
- Hard to match performance of Reduced Instruction Set Computers (RISC)
- But, Intel has done just that!
 - In terms of speed. Less so for low power.


Intel x86 Evolution: Milestones

Name	Date	Transistors	MHz
8086	1978	29 K	5-10
First 16-bit I	ntel processor. I	Basis for IBM PC & DOS	
1MB addres	s space		
386	1985	275K	16-33
First 32 bit I	ntel processor , r	referred to as IA32	
Added "flat	addressing", cap	able of running Unix	
Pentium 4E	2004	125M	2800-3800
First 64-bit I	ntel x86 process	or, referred to as x86-64	
Core 2	2006	291M	1060-3333
First multi-c	ore Intel process	or	
Core i7	2008	731M	1600-4400
Four cores			
■ Core i9	2023	4.2B	4600-6000
24 cores			
■ M2 Ultra - 202	23 - 67B - 24-	core CPU, 60-core GPU	J, 32-core Neural Engine

Intel x86 Processors, cont.

Machine Evolution

386	1985	0.3M
Pentium	1993	3.1M
Pentium/MMX	1997	4.5M
PentiumPro	1995	6.5M
Pentium III	1999	8.2M
Pentium 4	2000	42M
Core 2 Duo	2006	291M
Core i7	2008	731M
Core i7 Skylake	2015	1.9B



Added Features

Core i9 Raptorlake 2023

- Instructions to support multimedia operations
- Instructions to enable more efficient conditional operations


4.2B

Transition from 32 bits to 64 bits & More cores

Intel x86 Processors, cont.

	t Generation .st Pentium Pro		Process tech	nology
	st Pentium III	1999	250 nm	
1	.st Pentium 4	2000	180 nm	
• 1	st Core 2 Duo	2006	65 nm	Process technology dimension
Received	ent Generati	ons		= width of narrowest wires
1.	Nehalem	2008	45 nm	(10 nm ≈ 100 atoms wide)
2.	Sandy Bridge	2011	32 nm	
3.	Ivy Bridge	2012	22 nm	
4.	Haswell	2013	22 nm	
5.	Broadwell	2014	14 nm	iPhone:
6.	Skylake	2015	14 nm	A12 – 7nm
7.	Kaby Lake	2016	14 nm	A14 – 5nm
8.	Coffee Lake	2017	14 nm	A16 – 4nm A17 – 3nm
9.	Cannon Lake	2018	10 nm	AL) Jiiii
10.	Raptor Lake	2022	7nm	(while AMD has 7nm in 2019)

2019 Intel Scalable Processor



x86 Clones: Advanced Micro Devices (AMD)

Historically

- AMD has followed just behind Intel
- A little bit slower, a lot cheaper

Then

- Recruited top circuit designers from Digital Equipment Corp. and other downward trending companies
- Built Opteron: tough competitor to Pentium 4
- Developed x86-64, their own extension to 64 bits

Recent Years

- Intel got its act together
 - Still dominate the market
- AMD catched up
 - 7nm Ryzen processor has both high performance and low price
 - 5nm Zen 4

Intel's 64-Bit History

- 2001: Intel Attempts Radical Shift from IA32 to IA64
 - Totally different architecture (Itanium)
 - Executes IA32 code only as legacy
 - Performance disappointing
- 2003: AMD Steps in with Evolutionary Solution
 - x86-64 (now called "AMD64")
- Intel Felt Obligated to Focus on IA64
 - Hard to admit mistake or that AMD is better
- 2004: Intel Announces EM64T extension to IA32
 - Extended Memory 64-bit Technology
 - Almost identical to x86-64!

Our Coverage

■ IA32

The traditional x86

x86-64

- The standard
- mypc> gcc -m32 hello.c
- mypc> gcc -m64 hello.c


Presentation

- Book covers x86-64
- Web aside on IA32
- We will only cover x86-64

Today: Machine Programming I: Basics


- History of Intel processors and architectures
- Assembly Basics: Registers, operands, move
- Arithmetic & logical operations
- C, assembly, machine code

Levels of Abstraction



Nice clean layers, but beware...

Assembly programmer






Computer Designer

Caches, clock freq, layout, ...

Definitions

- Architecture: (also ISA: instruction set architecture) The parts of a processor design that one needs to understand for writing correct machine/assembly code
 - Examples: instruction set specification, registers
 - Machine Code: The byte-level programs that a processor executes
 - Assembly Code: A text representation of machine code
- Microarchitecture: Implementation of the architecture
 - Examples: cache sizes and core frequency
- Example ISAs:
 - Intel: x86, IA32, Itanium, x86-64
 - ARM: Used in almost all mobile phones
 - RISC V: New open-source ISA

Assembly/Machine Code View



Programmer-Visible State

- PC: Program counter
 - Address of next instruction
 - Called "RIP" (x86-64)
- Register file
 - Heavily used program data
- Condition codes
 - Store status information about most recent arithmetic or logical operation
 - Used for conditional branching

Memory

- Byte addressable array
- Code and user data
- Stack to support procedures

Assembly Characteristics: Data Types


- "Integer" data of 1, 2, 4, or 8 bytes
 - Data values
 - Addresses (untyped pointers)
- Floating point data of 4, 8, or 10 bytes
 - Real10, __float80 in x87 FPU
- (SIMD vector data types of 8, 16, 32 or 64 bytes)
- Code: Byte sequences encoding series of instructions
- No aggregate types such as arrays or structures
 - Just contiguously allocated bytes in memory

x86-64 Integer Registers

%rax	%eax	%r8	%r8d
%rbx	%ebx	%r9	%r9d
%rcx	%ecx	%r10	%r10d
%rdx	%edx	%r11	%r11d
%rsi	%esi	%r12	%r12d
%rdi	%edi	%r13	%r13d
%rsp	%esp	%r14	%r14d
%rbp	%ebp	%r15	%r15d

- Can reference low-order 4 bytes (also low-order 1 & 2 bytes)
- Not part of memory (or cache)

Some History: IA32 Registers



Origin (mostly obsolete)

accumulate

counter

data

base

source index

destination index

stack pointer base pointer

Assembly Characteristics: Operations

- Transfer data between memory and register
 - Load data from memory into register
 - Store register data into memory
- Perform arithmetic function on register or memory data
- Transfer control
 - Unconditional jumps to/from procedures
 - Conditional branches
 - Indirect branches

Moving Data

- Moving Data
 - movq Jource, Dest
 - b, $\sqrt{1}$, q quad, 1 word = 16 bits (P119)
- Øperand Types
 - Immediate: Constant integer data
 - Example: \$0x400, \$-533
 - Like C constant, but prefixed with `\$'
 - Register: One of 16 integer registers
 - Example: %rax, %r13
 - But %rsp reserved for special use
 - Others have special uses for particular instructions
 - Memory 8 consecutive bytes of memory at address given by register
 - Simplest example: (%rax)
 - Various other "addressing modes"

%rax

%rcx

%rdx

%rbx

%rsi

%rdi


%rsp

%rbp

%rN

Warning: Intel docs use mov Dest, Source
We use AT&T syntax

movq Operand Combinations



Cannot do memory-memory transfer with a single instruction

Simple Memory Addressing Modes

- Normal (R) Mem[Reg[R]]
 - Register R specifies memory address
 - Aha! Pointer dereferencing in C

```
movq (%rcx),%rax
```

- Displacement D(R) Mem[Reg[R]+D]
 - Register R specifies start of memory region
 - Constant displacement D specifies offset


```
movq 8(%rbp),%rdx
```

Quiz Time!

Exercise 3.2, 3.3

Check Figure 3-4 for all move instructions.


Example of Simple Addressing Modes



Example of Simple Addressing Modes

```
void swap
  (long *xp, long *yp)
{
  long t0 = *xp;
  long t1 = *yp;
  *xp = t1;
  *yp = t0;
}
```

void swap (long *xp, long *yp) { long t0 = *xp; long t1 = *yp; *xp = t1; *yp = t0; }



Memory

Register	Value
%rdi	хр
%rsi	ур
%rax	t0
%rdx	t1

Registers

%rdi	0x120
%rsi	0x100
%rax	
%rdx	


Memory

	Address
123	0x120
	0x118
	0x110
	0x108
456	0x100

swap:

```
movq (%rdi), %rax # t0 = *xp
movq (%rsi), %rdx # t1 = *yp
movq %rdx, (%rdi) # *xp = t1
movq %rax, (%rsi) # *yp = t0
ret
```


swap:




```
movq (%rdi), %rax # t0 = *xp
movq (%rsi), %rdx # t1 = *yp
```


movq %rdx, (%rdi) # *xp = t1

movq %rax, (%rsi) # *yp = t0
ret





ret



```
swap:
  movq     (%rdi), %rax # t0 = *xp
  movq     (%rsi), %rdx # t1 = *yp
  movq     %rdx, (%rdi) # *xp = t1
  movq     %rax, (%rsi) # *yp = t0
```

Quiz Time!

Exercise 3.5

Simple Memory Addressing Modes

- Normal (R) Mem[Reg[R]]
 - Register R specifies memory address
 - Aha! Pointer dereferencing in C

```
movq (%rcx),%rax
```

- Displacement D(R) Mem[Reg[R]+D]
 - Register R specifies start of memory region
 - Constant displacement D specifies offset

```
movq 8(%rbp),%rdx
```

Complete Memory Addressing Modes

Most General Form

D(Rb,Ri,S) Mem[Reg[Rb]+S*Reg[Ri]+D]

- D: Constant "displacement" 1, 2, or 4 bytes
- Rb: Base register: Any of 16 integer registers
- Ri: Index register: Any, except for %rsp
- S: Scale: 1, 2, 4, or 8 (why these numbers?)

Special Cases

(Rb,Ri) Mem[Reg[Rb]+Reg[Ri]]

D(Rb,Ri) Mem[Reg[Rb]+Reg[Ri]+D]

(Rb,Ri,S) Mem[Reg[Rb]+S*Reg[Ri]]

Address Computation Examples

%rdx	0xf000
%rcx	0x0100

D(Rb,Ri,S) Mem[Reg[Rb]+S*Reg[Ri]+D]

- D: Constant "displacement" 1, 2, or 4 bytes
- Rb: Base register: Any of 16 integer registers
- Ri: Index register: Any, except for %rsp
- Scale: 1, 2, 4, or 8 (why these numbers?)

Expression	Address Computation	Address
0x8(%rdx)		
(%rdx,%rcx)		
(%rdx,%rcx,4)		
0x80(,%rdx,2)		

Quiz Time!

Exercise 3.1

Check Figure 3-3 for all formats.

Today: Machine Programming I: Basics

- History of Intel processors and architectures
- Assembly Basics: Registers, operands, move
- Arithmetic & logical operations
- C, assembly, machine code

Address Computation Instruction

■ leaq Src, Dst

- Src is address mode expression
- Set Dst to address denoted by expression

Uses

- Computing addresses without a memory reference
 - E.g., translation of p = &x[i];
- Computing arithmetic expressions of the form x + k*y
 - k = 1, 2, 4, or 8

Example

```
long m12(long x)
{
   return x*12;
}
```

Converted to ASM by compiler:

```
leaq (%rdi,%rdi,2), %rax # t = x+2*x
salq $2, %rax # return t<<2</pre>
```

Quiz Time!

Exercise 3.6, 3.7

Some Arithmetic Operations

Two Operand Instructions:

```
Format
           Computation
                      Dest = Dest + Src
  addq
           Src,Dest
  subq Src,Dest
                      Dest = Dest - Src
                      Dest = Dest * Src
  imulq Src,Dest
  salq
         Src,Dest
                      Dest = Dest << Src
                                            Also called shlq
                                            Arithmetic
  sarq Src,Dest
                      Dest = Dest >> Src
  shrq Src,Dest
                      Dest = Dest >> Src
                                            Logical
  xorq Src,Dest
                      Dest = Dest ^ Src
  andq
           Src,Dest
                      Dest = Dest & Src
           Src,Dest
                      Dest = Dest | Src
  orq
```

- Watch out for argument order! Src,Dest
 (Warning: Intel docs use "op Dest,Src")
- No distinction between signed and unsigned int (why?)

Some Arithmetic Operations

One Operand Instructions

```
incq Dest Dest = Dest + 1

decq Dest Dest = Dest - 1

negq Dest Dest = - Dest

notq Dest Dest = \simDest
```

See book for more instructions

Arithmetic Expression Example

```
long arith
(long x, long y, long z)
  long t1 = x+y;
  long t2 = z+t1;
  long t3 = x+4;
  long t4 = y * 48;
  long t5 = t3 + t4;
  long rval = t2 * t5;
  return rval;
```

```
arith:
  leaq (%rdi,%rsi), %rax
  addq %rdx, %rax
  leaq (%rsi,%rsi,2), %rdx
  salq $4, %rdx
  leaq 4(%rdi,%rdx), %rcx
  imulq %rcx, %rax
  ret
```

Interesting Instructions

- leaq: address computation
- salq: shift
- imulq: multiplication
 - But, only used once

Understanding Arithmetic Expression Example

```
long arith
(long x, long y, long z)
  long t1 = x+y;
  long t2 = z+t1;
  long t3 = x+4;
  long t4 = y * 48;
  long t5 = t3 + t4;
  long rval = t2 * t5;
  return rval;
```

```
arith:
  leaq (%rdi,%rsi), %rax # t1
  addq %rdx, %rax # t2
  leaq (%rsi,%rsi,2), %rdx
  salq $4, %rdx # t4
  leaq 4(%rdi,%rdx), %rcx # t5
  imulq %rcx, %rax # rval
  ret
```

Register	Use(s)
%rdi	Argument x
%rsi	Argument y
%rdx	Argument z , t4
%rax	t1, t2, rval
%rcx	t5

Quiz Time!


Exercise 3.10

Today: Machine Programming I: Basics

- History of Intel processors and architectures
- Assembly Basics: Registers, operands, move
- Arithmetic & logical operations
- C, assembly, machine code

Turning C into Object Code

- Code in files p1.c p2.c
- Compile with command: gcc -Og p1.c p2.c -o p
 - Use basic optimizations (-Og) [New to recent versions of GCC]
 - Put resulting binary in file p



Compiling Into Assembly

C Code (sum.c)

Generated x86-64 Assembly

```
sumstore:
   pushq %rbx
   movq %rdx, %rbx
   call plus
   movq %rax, (%rbx)
   popq %rbx
   ret
```

Obtain with command

```
gcc -Og -S sum.c
```

Produces file sum. s

Warning: Will get very different results on different machines (Linux, Mac OS-X, ...) due to different versions of gcc and different compiler settings.

What it really looks like

```
.globl sumstore
       .type sumstore, @function
sumstore:
.LFB35:
       .cfi startproc
       pushq %rbx
       .cfi def cfa offset 16
       .cfi offset 3, -16
       movq %rdx, %rbx
       call plus
       movq %rax, (%rbx)
       popq %rbx
       .cfi def cfa offset 8
       ret
       .cfi endproc
.LFE35:
       .size sumstore, .-sumstore
```

What it really looks like

```
.globl sumstore
       .type sumstore, @function
sumstore:
.LFB35:
       .cfi startproc
       pushq %rbx
       .cfi def cfa offset 16
       .cfi offset 3, -16
       movq %rdx, %rbx
       call plus
       movq %rax, (%rbx)
       popq %rbx
       .cfi def cfa offset 8
       ret
       .cfi endproc
.LFE35:
       .size sumstore, .-sumstore
```

Things that look weird and are preceded by a ''are generally directives (指示符).

```
sumstore:
   pushq %rbx
   movq %rdx, %rbx
   call plus
   movq %rax, (%rbx)
   popq %rbx
   ret
```

Assembly Characteristics: Data Types

- "Integer" data of 1, 2, 4, or 8 bytes
 - Data values
 - Addresses (untyped pointers)
- Floating point data of 4, 8, or 10 bytes
- (SIMD vector data types of 8, 16, 32 or 64 bytes)
- Code: Byte sequences encoding series of instructions
- No aggregate types such as arrays or structures
 - Just contiguously allocated bytes in memory

Assembly Characteristics: Operations

- Transfer data between memory and register
 - Load data from memory into register
 - Store register data into memory
- Perform arithmetic function on register or memory data
- Transfer control
 - Unconditional jumps to/from procedures
 - Conditional branches

Object Code

Code for sumstore

0×0400595 : 0x530x480x890xd30xe8 0xf20xff 0xff 0xff Total of 14 bytes 0x48**Each instruction** 0x891, 3, or 5 bytes 0x030x5bStarts at address

0x0400595

0xc3

Assembler

- Translates .s into .o
- Binary encoding of each instruction
- Nearly-complete image of executable code
- Missing linkages between code in different files

Linker

- Resolves references between files
- Combines with static run-time libraries
 - E.g., code for malloc, printf
- Some libraries are dynamically linked
 - Linking occurs when program begins execution

Machine Instruction Example

```
movq %rax, (%rbx)
```

0x40059e: 48 89 03

C Code

Store value t where designated by dest

Assembly

- Move 8-byte value to memory
 - Quad words in x86-64 parlance
- Operands:

t: Register %rax

dest: Register %rbx

*dest: Memory M[%rbx]

Object Code

- 3-byte instruction
- Stored at address 0x40059e

Disassembling Object Code

Disassembled

```
0000000000400595 <sumstore>:
 400595:
          53
                                  %rbx
                           push
 400596: 48 89 d3
                                  %rdx,%rbx
                           mov
 400599: e8 f2 ff ff ff callq 400590 <plus>
 40059e: 48 89 03
                                  %rax, (%rbx)
                           mov
 4005a1: 5b
                                  %rbx
                           pop
  4005a2: c3
                           reta
```

Disassembler

```
objdump -d sum
```

- Useful tool for examining object code
- Analyzes bit pattern of series of instructions
- Produces approximate rendition of assembly code
- Can be run on either a .out (complete executable) or .o file

Alternate Disassembly

Disassembled

```
Dump of assembler code for function sumstore:
    0x0000000000400595 <+0>: push     %rbx
    0x000000000400596 <+1>: mov     %rdx,%rbx
    0x000000000400599 <+4>: callq     0x400590 <plus>
    0x00000000040059e <+9>: mov     %rax,(%rbx)
    0x0000000004005a1 <+12>:pop     %rbx
    0x00000000004005a2 <+13>:retq
```

Within gdb Debugger

Disassemble procedure

```
gdb sum
disassemble sumstore
```

Alternate Disassembly

Object Code

```
0 \times 0400595:
   0x53
   0x48
   0x89
   0xd3
   0xe8
   0xf2
   0xff
   0xff
   0xff
   0x48
   0x89
   0x03
   0x5b
   0xc3
```

Disassembled

```
Dump of assembler code for function sumstore:
    0x0000000000400595 <+0>: push %rbx
    0x0000000000400596 <+1>: mov %rdx,%rbx
    0x0000000000400599 <+4>: callq 0x400590 <plus>
    0x000000000040059e <+9>: mov %rax,(%rbx)
    0x00000000004005a1 <+12>:pop %rbx
    0x000000000004005a2 <+13>:retq
```

Within gdb Debugger

Disassemble procedure

```
gdb sum
disassemble sumstore
```

Examine the 14 bytes starting at sumstore

```
x/14xb sumstore
```

What Can be Disassembled?

```
% objdump -d WINWORD.EXE
WINWORD.EXE: file format pei-i386
No symbols in "WINWORD.EXE".
Disassembly of section .text:
30001000 <.text>:
30001000:
30001001:
               Reverse engineering forbidden by
30001003:
             Microsoft End User License Agreement
30001005:
3000100a:
```

- Anything that can be interpreted as executable code
- Disassembler examines bytes and reconstructs assembly source

Machine Programming I: Summary

History of Intel processors and architectures

Evolutionary design leads to many quirks and artifacts

C, assembly, machine code

- New forms of visible state: program counter, registers, ...
- Compiler must transform statements, expressions, procedures into low-level instruction sequences

Assembly Basics: Registers, operands, move

 The x86-64 move instructions cover wide range of data movement forms

Arithmetic

 C compiler will figure out different instruction combinations to carry out computation