## **Introduction to High Performance Computing**

Oguz Kaya

Assistant Professor Université Paris-Saclay et ParSys Team of LISN, Gif-sur-Yvette, France





#### **Outline**

- Introduction
- Parallel computing, why?
- Basic of parallel computing
- Types of parallelism
- Parallel Architecture





### **Outline**

- Introduction
- 2 Parallel computing, why?
- Basic of parallel computing
- 4 Types of parallelism
- Parallel Architecture

### **Objectives**


- Get familiar with parallel and high performance computing (HPC)
- Discover applications that require HPC
- Explore modern parallel computer achitectures
- Present the main parallel programing models
- Introduce fundamental concepts in HPC
- Fournir quelques conseils pour développer des programmes parallèles efficaces
- Provide advices for efficient parallel programming and code optimization



## **Sequential programs**

Introduction

Traditionally, programs are based on a **sequential** execution:




- A problem is split into a series of basic instructions.
- These instructions are executed sequentially one after the other.
- Elles sont exécutées par un seul processeur.
- Instructions are executed by a single processor
- À un instant donné, une seule instruction est exécutée.
- At a given time unite (clock tick), a single instruction is executed.
- Runtime of the program (or performance) mostly depends on the frequency (Hz) of the processoria

## Parallel programs

Introduction

A parallel program enables the utilization of multiple processing units to solve a problem:



- A problem is split into subproblems that can be executed simultaneously.
- Each subproblem is split into basic instructions.
- Instructions in each subproblem are executed in parallel by using one processor per subproblem.
- The performance is mostly determined by:
  - frequency (Hz)
  - number of processors
  - degree of parallelization of the problem
  - and other characteristics (load balancing, overheads due to parallelism)




### **Outline**

- Introduction
- 2 Parallel computing, why?
- Basic of parallel computing
- Types of parallelism
- Parallel Architecture

## **Applications of parallel computing**

Introduction

Numerous applications require immense compute power in diverse domains: bigskip



- Scientific computing: Simulations in physics, chemistry, biologie, . . .
- Machine learning: Neural networks, big data analysis, . . .
- Computer graphics: Rendering, games, video editing, . . .
- Operating systems: Linux, Android, . . .
- and many others (computational finance, CAD, medicine, . . . )



What is the maximum frequency of a CPU in 2002?



• 3.06 GHz

Intel Pentium 4, Northwood



## Maximum frequency of a CPU in 2020

What is the maximum frequency of a CPU in 2020?



Intel Core i9-10900K, Comet Lake

- 5.3 GHz
- What about peak performance? 5.3 operations/s?
- No!  $\approx$ 1.7Tops/s (1700Gflops/s) How?
- Thanks to the parallelism inside the CPU (10 cores, each having two 8-wide vector units)



### **Outline**

- Introduction
- 2 Parallel computing, why?
- Basic of parallel computing
- Types of parallelism
- Parallel Architecture

#### Moore's Law

The number of transistors in integrated circuits double every two years.



Moore's Law


- What is it's importance?
- $\bullet$  More transistors  $\rightarrow$  more performance potential
- Moore's Law is still mostly valid today (yet slowed down slightly)





## **Dennard Scaling**

If the feature size is reduced by 30% (0.7x) in each generation of transistors, it yields



Dennard Scaling

- Circuit size reduction of 50%
- Latency reduction of 30%
- As a result, frequency increase of 40% (10/7  $\approx$  1.4).
  - Higher frequency difficult to attain due to quantum effects!
  - Resort to multi-cores, or "wider" cores.
- energy  $\sim$  frequence<sup>2</sup>
  - $\bullet$  Use more cores at a lower frequency  $\to$  more performance in the same power window.



## Acceleration and efficiency

Introduction

Acceleration/Speedup: How much faster does a parallel program run? **Efficiency:** How well are computing resources used?



Cray-1 Supercomputer (1975) with peak performance of  $\approx 160 Mflops/s$ 


- Sequential execution time: T(1)
- Parallel execution time using *N* processors: T(N)
- Acceleration: S(N) = T(1)/T(N)
- Efficiency: E(N) = S(N)/N





#### Amdahl's Law

How much faster can a program run? What's the limit?




Amdahl's Law

- Introduced in 1967 by Gene Amdahl
- Let s and p be sequential and parallel franctions of a program (s + p = 1.0).
- Attainable acceleration is limited by  $A(N) = \frac{T(1)}{T(N)} \le \frac{T(1)}{pT(1)/N + sT(1)} = \frac{1}{p/N + s}$
- **Strong scaling:** Parallel scaling for a fixed problem size with increasing #processors.
- Loss of hope for parallel computing?
  - Typically, s diminishes with the problem size for almost all problems.



## **Example: Sum of an array**



Parallel sum


$$\sum_{i=0}^{N-1} A[i]$$

- N-1 additions
- For N = 8, 7 additions where 3 must be sequential,  $S \le 7/3 = 2.34$
- For N=16, 15 additions where 4 must be sequential,  $S \le 15/4 = 3.75$
- In general, N-1 additions where log N must be sequential,  $S \leq (N-1)/\log N$



#### Gustafson's Law

How much acceleration can be obtained if the problem size increases proportionally with the #processors?




Gustafson's Law

- Amdalh: Difficult to accelerate a fixed computation with more processors.
- Gustafson: Possible to solve a bigger problem in a similar amount of time with more processors.
- Which one is more important nowadays?
- Weak scaling: Parallel scaling with proportional increase in the problem size and #processors.



## Flynn's classification of parallel machines

#### A $2 \times 2$ matrix to classify parallel machines




- Popular classification, used since 1966
- X axis: single/multiple instruction
- Y axis: single/multiple data

Flynn's classification



## Single Instruction, Single Data (SISD)



SISD processor


- Completely sequential and scalar machine
- "single" instruction: A single instruction is executed at each clock cycle
- "single" data: A single data element is used/modified (a.k.a. scalar).
- Execution is deterministic.
- Most ancient CPU architectures (e.g., basic computer achitecture course).




Parallel Architecture

## Single Instruction, Multiple Data (SIMD)

- An example of a parallel machine
- "single" instruction: All compute units execute the same instruction at each clock cycle
- "multiple" data: Each compute unit operates on a different data piece
- Useful for numerous problems and applications (matrix computations, image processing, . . . )









## Multiple Instruction, Single Data (MISD)

- A rare example of a parallel machine
- "single" data: A single data element is used/modified (a.k.a. scalar) by all compute units.
- "multiple" instructions: Each compute unit operates on the same data but executes a different instruction.
- A few example use cases:
  - applying multiple frequency filters on the same signal simultenously
  - multiple cryptography algorithms to decipher a single message
  - redundant operation for safety.









## Multiple Instruction, Multiple Data (MIMD)

- A more modern example of a parallel machine
- "multiple" instructions: Each compute unit executes a different instruction.
- "multiple" data: Each compute unit operates on a different data piece
- Execution can be synchronous or asynchronous, deterministic or non-deterministic.
- Most processors today are in this category.
- Good for exploiting instruction level parallelism, and accelerate single threaded execution.
- Most MIMD architectures involve many SIMD components inside.








### **Outline**

- Introduction
- 2 Parallel computing, why?
- Basic of parallel computing
- Types of parallelism
- Parallel Architecture

### Bit-level parallelism

It has to do with the word-size of the processor.



Intel C4004, 4-bit (1971) processor

- Was more important in the past (1970..1986).
- ullet Word-size: 4-bit o 8-bit o 16-bit o 32-bit
- Converged to 64-bit today, rarely need higher sizes (and can emulate with multiple instructions).



### Instruction-level parallelism

Enables to execute independent instructions simultenously in a program.



Non-pipelined and scalar execution



Pipelined and superscalar execution

• 
$$a = b + c$$
;  $c = d + e$ ;  $f = a + c$ ;  $g = c - a$ ;

- Possibility 1: Pipeline. Different stages of two (in)dependent instructions can be executed in the pipeline at the same time.
- Possibility 2: Superscalar execution.
   Independent instructions can use multiple execution units (ALUs, load/store, vector/floating units, . . . ) in a single MIMD processor.
- Most modern processors are superscalar and have very deep pipelines.

  PARIS-SACLAY

  PARIS-SACLA

#### **Data Parallelism**

Carry out same operations on a vector/array of data elements.




Sum of two arrays

- Uses the SIMD-type parallelism
- Most processors have efficient hardware for such computations (vector units in CPU and GPU)
- Very widespread use in scientific computing, AI, computer graphics, signal processing, . . .



#### Task Parallelism

Execution of a flow of tasks in parallel by respecting the dependencies.



Task parallelism

- Examples of independent tasks?
  - Function calls: a = f(x); b = g(y);
  - Independent blocks of code in a function/program
  - Execution of a single program with different parameters (e.g., hyperparameter search in simulations, learning, ...)
- Each task executes on a separate compute unit.
- Dependencies must be respected if exist.
  - Load balancing might be a challenge.
  - Effective scheduling of tasks is an entire research domain in itself.




### **Outline**

- Introduction
- 2 Parallel computing, why?
- Basic of parallel computing
- 4 Types of parallelism
- Parallel Architecture

#### **CPU**

Introduction

"Central Processing Unit", compute unit consisting of




AMD Zen 2 architecture

- Multiple execution units (cores)
- Multiple memory types in a hieararchy (registers, L1, L2, L3 cache, RAM)
- Multiple execution ports in each core (ALUs, vector units, load/store units, . . . )
- SIMD/vector units (AVX2, AVX512, Arm Neon, ...)
- Execution of multiple threads (2-4) simultenously.
- Capable of exploiting the instruction-level parallelism (ILP) through micro-op buffer, instruction reordering, register renaming, ...
- A big portion of the circuit is dedicated to ILPuniversite cache.

#### **GPU**

"Graphical Processing Unit", specific vector compute unit consisting of



Nvidia Ampere Architecture

- Multiple execution units (streaming multiprocessors (SM))
- Multiple memory levels (registers, shared memory, L1, L2, GPU RAM, CPU RAM)
- Multiple (2-8) and large (16-32 floats) vector units in each SM
- Simultenous execution of thousands of threads with fast context-switching.
- Very big register file (65K)
- Most of the circuit is dedicated to vector computations and thread cohabitation
- Paralllelization takes programming effort





## **Supercomputer / Cluster**

A group of machines having CPU+GPU connected through a high-speed network



Jolio Curie supercomputer, 300K CPU cores, 1024 GPUs

- Connection through a network with a specific topology (ring, mesh, torus, clique, ...)
- Efficient communication libraries adapted to the topology
- Capable of treating very large-scale problems
- Today, we exceeded the exaflop scale (10<sup>18</sup> floating point operations per second)




## **Shared memory architecture**

- All processors can access to the memory in a global address space
- Multiple processors can operate independently, but share same memory resources.
- Memory modifications made by a processors are visible by all others.



# Shared memory architecture: Uniform Memory Access (UMA)


- Symmetric multiprocessor architecture (SMP).
- Identical processors.
- Same memory access time by all processors.
- Each processor will still have its cache, others will notified of a change in the cache. This is called **cache coherency**





## Shared memory: Non-Uniform Memory Access (NUMA)

- Most of the time, formed by connecting multiple UMA domains.
- A processor can directly access the memory situated in another UMA region, passing through a bus interconnect.
- Memory accesses have varying costs in latency and bandwidth.
- Cache across multiple UMA regions might or might not be coherent (mostly is).







## **Shared memory architecture**

#### Avantages :

- Global shared address space enables simpler parallel programming and memory management.
- Data sharing among threads in the same UMA region is simple and fast for.

#### ② Disadvantages:

- Architecture scalability is difficult when adding more CPUs and NUMA regions.
   Shared bus and cache coherency becomes difficult to handle when the size of the NUMA region becomes too large.
- Accessing other NUMA regions can degregade performance, it is the programmer's responsability to optimize the memory footprint of each thread (i.e., stay mostly in UMA zone).




## Distributed memory architecture

- Distributed memory systems require a network to connect all processors.
- Each processor has its own memory address space (UMA or NUMA).
- Direct access to other processors' memory is prohibited; explicit communication, coordination, synchronization is needed when data exchange is necessary.



## Distributed memory architecture

 Network can be as simple as Ethernet, or very complicated and high bandwidth (Infiniband, NVLink, ...).





## Distributed memory architecture

#### • Avantages:

- Memory and compute power is scalable with the number of processors.
- Each processor accesses its own memory region rapidly without interference from other processors
- No cache coherency among distributed machines, easier to handle architecture-wise.


#### ② Disadvantages:

- Programmer is responsable for effectively handling the machine (communication, synchronization, ...)
- The algorithm, data structures, and data distribution have to be rethought for this type of architecture, which takes effort.



## Hybrid architecture

- Most modern supercomputers are hybrid architectures, having NUMA shared memory and distributed memory architectures simultaneously.
- Each component/machine is a NUMA with multiple CPUs/GPUs, and a high-speed network topology connects all machines.
- Processing units in the same machine share the same memory address space, need no explicit communication.
- Processing units across different machines need explicit communication through the network for data exchange.







### References

#### Contact

Oguz Kaya Université Paris-Saclay and LISN, Paris, France oguz.kaya@universite-paris-saclay.com www.oguzkaya.com