


CASA Synthesis & Single Dish Reduction Cookbook

Beta Release Edition (Beta Patch 3)



Version: December 24, 2008

CASA Synthesis & Single Dish Reduction Cookbook

Beta Release Edition

Chef Editor: Steven T. Myers
CASA Project Scientist

Sous-Chef: Joe McMullin
CASA Project Manager

CASA SYNTHESIS & SINGLE DISH REDUCTION COOKBOOK, BETA RELEASE EDITION,
Version December 24, 2008,
©2007 National Radio Astronomy Observatory

The National Radio Astronomy Observatory is a facility of the National Science Foundation
operated under cooperative agreement by Associated Universities, Inc.

This tome was scribed by:

The CASA Developers and the NRAO Applications User Group (NAUG)
<http://casa.nrao.edu/>
<http://www.aoc.nrao.edu/~smyers/naug/>

Do you dare to enter CASA Stadium and join battle with the Ironic Chefs?
Let us see whose cuisine reigns supreme . . .

Contents

1	Introduction	20
1.1	About This Beta Release	22
1.1.1	What's New in Patch 3	23
1.1.1.1	Changes in Patch 2	24
1.2	CASA Basics — Information for First-Time Users	25
1.2.1	Before Starting CASA	25
1.2.1.1	Environment Variables	26
1.2.1.2	Where is CASA?	26
1.2.2	Starting CASA	27
1.2.3	Ending CASA	27
1.2.4	What happens if something goes wrong?	27
1.2.5	Aborting CASA execution	28
1.2.6	What happens if CASA crashes?	28
1.2.7	Python Basics for CASA	29
1.2.7.1	Variables	29
1.2.7.2	Lists and Ranges	29
1.2.7.3	Indexes	30
1.2.7.4	Indentation	30
1.2.7.5	System shell access	30
1.2.7.6	Executing Python scripts	31
1.2.8	Getting Help in CASA	31
1.2.8.1	TAB key	31
1.2.8.2	<code>help <taskname></code>	32
1.2.8.3	<code>help</code> and PAGER	34
1.2.8.4	<code>help par.<parameter></code>	34
1.2.8.5	Python <code>help</code>	34
1.3	Tasks and Tools in CASA	35
1.3.1	What Tasks are Available?	36
1.3.2	Running Tasks and Tools	39
1.3.2.1	Aborting Synchronous Tasks	41
1.3.3	Getting Return Values	41
1.3.4	Running Tasks Asynchronously	42
1.3.4.1	Monitoring Asynchronous Tasks	42
1.3.4.2	Aborting Asynchronous Tasks	44

1.3.5	Setting Parameters and Invoking Tasks	44
1.3.5.1	The scope of parameters in CASA	46
1.3.5.2	The <code>default</code> Command	46
1.3.5.3	The <code>go</code> Command	47
1.3.5.4	The <code>inp</code> Command	48
1.3.5.5	The <code>saveinputs</code> Command	50
1.3.5.6	The <code>tget</code> Command	52
1.3.5.7	The <code>.last</code> file	52
1.3.6	Tools in CASA	53
1.4	Getting the most out of CASA	54
1.4.1	Your command line history	54
1.4.2	Logging your session	54
1.4.2.1	Starup options for the <code>logger</code>	57
1.4.2.2	Setting priority levels in the <code>logger</code>	58
1.4.3	Where are my data in CASA?	59
1.4.4	What's in my data?	60
1.4.5	Data Selection in CASA	61
1.5	From Loading Data to Images	61
1.5.1	Loading Data into CASA	61
1.5.1.1	VLA: Filling data from VLA archive format	62
1.5.1.2	Filling data from UVFITS format	63
1.5.1.3	Loading FITS images	63
1.5.1.4	Concatenation of multiple MS	63
1.5.2	Data Examination, Editing, and Flagging	63
1.5.2.1	Interactive X-Y Plotting and Flagging	64
1.5.2.2	Flag the Data Non-interactively	64
1.5.2.3	Viewing and Flagging the MS	64
1.5.3	Calibration	64
1.5.3.1	Prior Calibration	65
1.5.3.2	Bandpass Calibration	65
1.5.3.3	Gain Calibration	66
1.5.3.4	Polarization Calibration	66
1.5.3.5	Examining Calibration Solutions	66
1.5.3.6	Bootstrapping Flux Calibration	66
1.5.3.7	Calibration Accumulation	66
1.5.3.8	Correcting the Data	67
1.5.3.9	Splitting the Data	67
1.5.4	Synthesis Imaging	67
1.5.4.1	Cleaning a single-field image or a mosaic	68
1.5.4.2	Feathering in a Single-Dish image	68
1.5.5	Self Calibration	68
1.5.6	Data and Image Analysis	68
1.5.6.1	What's in an image?	69
1.5.6.2	Image statistics	69
1.5.6.3	Moments of an Image Cube	69

1.5.6.4	Image math	69
1.5.6.5	Regridding an Image	70
1.5.6.6	Displaying Images	70
1.5.7	Getting data and images out of CASA	70
2	Visibility Data Import, Export, and Selection	71
2.1	CASA Measurement Sets	72
2.1.1	Under the Hood: Structure of the Measurement Set	72
2.2	Data Import and Export	75
2.2.1	UVFITS Import and Export	75
2.2.1.1	Import using <code>importuvfits</code>	76
2.2.1.2	Export using <code>exportuvfits</code>	76
2.2.2	VLA: Filling data from archive format (<code>importvla</code>)	77
2.2.2.1	Parameter <code>applytsys</code>	78
2.2.2.2	Parameter <code>bandname</code>	79
2.2.2.3	Parameter <code>frequencytol</code>	79
2.2.2.4	Parameter <code>project</code>	79
2.2.2.5	Parameters <code>starttime</code> and <code>stoptime</code>	80
2.2.2.6	Parameter <code>autocorr</code>	80
2.2.2.7	Parameter <code>antnamescheme</code>	80
2.2.3	ALMA: Filling ALMA Science Data Model (ASDM) observations	80
2.3	Summarizing your MS (<code>listobs</code>)	82
2.4	Concatenating multiple datasets (<code>concat</code>)	85
2.5	Data Selection	86
2.5.1	General selection syntax	87
2.5.1.1	String Matching	87
2.5.2	The <code>field</code> Parameter	88
2.5.3	The <code>spw</code> Parameter	89
2.5.3.1	Channel selection in the <code>spw</code> parameter	90
2.5.4	The <code>selectdata</code> Parameters	91
2.5.4.1	The <code>antenna</code> Parameter	91
2.5.4.2	The <code>scan</code> Parameter	93
2.5.4.3	The <code>timerange</code> Parameter	93
2.5.4.4	The <code>uvrange</code> Parameter	94
2.5.4.5	The <code>msselect</code> Parameter	95
3	Data Examination and Editing	96
3.1	Plotting and Flagging Visibility Data in CASA	96
3.2	Managing flag versions with <code>flagmanager</code>	96
3.3	Flagging auto-correlations with <code>flagautocorr</code>	98
3.4	X-Y Plotting and Editing of the Data	98
3.4.1	GUI Plot Control	101
3.4.2	The <code>selectplot</code> Parameters	102
3.4.3	Plot Control Parameters	103
3.4.3.1	<code>iteration</code>	103

3.4.3.2	<code>overplot</code>	105
3.4.3.3	<code>plotrange</code>	105
3.4.3.4	<code>plotsymbol</code>	105
3.4.3.5	<code>showflags</code>	106
3.4.3.6	<code>subplot</code>	106
3.4.4	Averaging in <code>plotxy</code>	107
3.4.5	Interactive Flagging in <code>plotxy</code>	109
3.4.6	Flag extension in <code>plotxy</code>	110
3.4.7	Printing from <code>plotxy</code>	111
3.4.8	Exiting <code>plotxy</code>	111
3.4.9	Example session using <code>plotxy</code>	112
3.5	Non-Interactive Flagging using <code>flagdata</code>	114
3.5.1	Flag Antenna/Channels	116
3.5.1.1	Manual flagging and clipping in <code>flagdata</code>	116
3.5.1.2	Flagging the beginning of scans	117
3.6	Browse the Data	118
3.7	Examples of Data Display and Flagging	118
4	Synthesis Calibration		133
4.1	Calibration Tasks	133
4.2	The Calibration Process — Outline and Philosophy	134
4.2.1	The Philosophy of Calibration in CASA	136
4.2.2	Keeping Track of Calibration Tables	137
4.2.3	The Calibration of VLA data in CASA	138
4.3	Preparing for Calibration	139
4.3.1	System Temperature Correction	139
4.3.2	Antenna Gain-Elevation Curve Calibration	140
4.3.3	Atmospheric Optical Depth Correction	141
4.3.3.1	Determining opacity corrections for VLA data	141
4.3.4	Setting the Flux Density Scale using (<code>setjy</code>)	142
4.3.4.1	Using Calibration Models for Resolved Sources	144
4.3.5	Other <i>a priori</i> Calibrations and Corrections	146
4.4	Solving for Calibration — Bandpass, Gain, Polarization	146
4.4.1	Common Calibration Solver Parameters	146
4.4.1.1	Parameters for Specification : <code>vis</code> and <code>caltable</code>	147
4.4.1.2	Selection: <code>field</code> , <code>spw</code> , and <code>selectdata</code>	147
4.4.1.3	Prior Calibration and Correction: <code>parang</code> , <code>gaincurve</code> and <code>opacity</code>	148
4.4.1.4	Previous Calibration: <code>gaintable</code> , <code>gainfield</code> , <code>interp</code> and <code>spwmap</code>	148
4.4.1.5	Solving: <code>solint</code> , <code>combine</code> , <code>refant</code> , and <code>minsnr</code>	150
4.4.1.6	Action: <code>append</code> and <code>solnorm</code>	151
4.4.2	Spectral Bandpass Calibration (<code>bandpass</code>)	151
4.4.2.1	Bandpass Normalization	152
4.4.2.2	B solutions	153
4.4.2.3	BPOLY solutions	154
4.4.3	Complex Gain Calibration (<code>gaincal</code>)	156

4.4.3.1	Polarization-dependent Gain (G)	157
4.4.3.2	Polarization-independent Gain (T)	158
4.4.3.3	GSPLINE solutions	159
4.4.4	Establishing the Flux Density Scale (<code>fluxscale</code>)	160
4.4.4.1	Using Resolved Calibrators	162
4.4.5	Instrumental Polarization Calibration (D,X)	163
4.4.5.1	Heuristics and Strategies for Polarization Calibration	164
4.4.5.2	A Polarization Calibration Example	165
4.4.6	Baseline-based Calibration (<code>blcal</code>)	166
4.4.7	EXPERIMENTAL: Fringe Fitting (<code>fringecal</code>)	167
4.5	Plotting and Manipulating Calibration Tables	167
4.5.1	Plotting Calibration Solutions (<code>plotcal</code>)	167
4.5.1.1	Examples for <code>plotcal</code>	169
4.5.2	Listing calibration solutions with (<code>listcal</code>)	171
4.5.3	Calibration Smoothing (<code>smoothcal</code>)	174
4.5.4	Calibration Interpolation and Accumulation (<code>accum</code>)	176
4.5.4.1	Interpolation using (<code>accum</code>)	177
4.5.4.2	Incremental Calibration using (<code>accum</code>)	177
4.6	Application of Calibration to the Data	180
4.6.1	Application of Calibration (<code>applycal</code>)	180
4.6.2	Examine the Calibrated Data	183
4.6.3	Resetting the Applied Calibration using (<code>clearcal</code>)	184
4.7	Other Calibration and UV-Plane Analysis Options	185
4.7.1	Splitting out Calibrated uv data (<code>split</code>)	185
4.7.1.1	Averaging in <code>split</code> (EXPERIMENTAL)	185
4.7.2	Hanning smoothing of uv data (<code>hanningsmooth</code>)	186
4.7.3	Model subtraction from uv data (<code>uvsub</code>)	187
4.7.4	UV-Plane Continuum Subtraction (<code>uvcontsub</code>)	187
4.7.5	UV-Plane Model Fitting (<code>uvmodelfit</code>)	189
4.8	Examples of Calibration	192
4.8.1	Spectral Line Calibration for NGC5921	192
4.8.2	Continuum Calibration of Jupiter	205
5	Synthesis Imaging	210
5.1	Imaging Tasks Overview	210
5.2	Common Imaging Task Parameters	211
5.2.1	Parameter <code>cell</code>	211
5.2.2	Parameter <code>field</code>	212
5.2.3	Parameter <code>imagename</code>	212
5.2.4	Parameter <code>imsize</code>	212
5.2.5	Parameter <code>mode</code>	212
5.2.5.1	Mode <code>mfs</code>	213
5.2.5.2	Mode <code>channel</code>	213
5.2.5.3	Mode <code>frequency</code>	213
5.2.5.4	Mode <code>velocity</code>	214

5.2.6	Parameter <code>phasecenter</code>	215
5.2.7	Parameter <code>restfreq</code>	215
5.2.8	Parameter <code>spw</code>	215
5.2.9	Parameter <code>stokes</code>	216
5.2.10	Parameter <code>uvfilter</code>	216
5.2.11	Parameter <code>weighting</code>	217
5.2.11.1	'natural' weighting	217
5.2.11.2	'uniform' weighting	218
5.2.11.3	'superuniform' weighting	218
5.2.11.4	'radial' weighting	218
5.2.11.5	'briggs' weighting	218
5.2.11.6	'briggsabs' weighting	219
5.2.12	Parameter <code>vis</code>	219
5.2.13	Primary beams in imaging	220
5.3	Deconvolution using CLEAN (<code>clean</code>)	221
5.3.1	Parameter <code>psfmode</code>	223
5.3.1.1	The <code>clark</code> algorithm	223
5.3.1.2	The <code>hogbom</code> algorithm	224
5.3.2	The <code>multiscale</code> parameter	224
5.3.3	Parameter <code>gain</code>	225
5.3.4	Parameter <code>imagermode</code>	225
5.3.4.1	Sub-parameter <code>cyclefactor</code>	226
5.3.4.2	Sub-parameter <code>cyclespeedup</code>	227
5.3.4.3	Sub-parameter <code>ftmachine</code>	227
5.3.4.4	Sub-parameter <code>mosweight</code>	228
5.3.4.5	Sub-parameter <code>scaletype</code>	228
5.3.4.6	The <code>threshold</code> revisited	228
5.3.5	Parameter <code>interactive</code>	229
5.3.6	Parameter <code>mask</code>	229
5.3.6.1	Setting clean boxes	230
5.3.6.2	Using clean box files	230
5.3.6.3	Using clean mask images	230
5.3.6.4	Using region files	230
5.3.7	Parameter <code>minpb</code>	231
5.3.8	Parameter <code>modelimage</code>	231
5.3.9	Parameter <code>niter</code>	231
5.3.10	Parameter <code>pbcor</code>	231
5.3.11	Parameter <code>restoringbeam</code>	232
5.3.12	Parameter <code>threshold</code>	232
5.3.13	Example — Interactive Cleaning	232
5.3.14	Example — Mosaicing	236
5.3.15	Mosaic imaging	238
5.3.16	Heterogeneous imaging	238
5.4	Wide-field imaging and deconvolution (<code>widefield</code>)	238
5.4.1	<code>ftmachine</code> modes for <code>widefield</code>	241

5.4.1.1	pure w-projection	241
5.4.1.2	faceting only	241
5.4.1.3	combination of w-projection and faceting	241
5.5	Combined Single Dish and Interferometric Imaging (feather)	242
5.6	Making Deconvolution Masks (makemask)	243
5.7	Transforming an Image Model (ft)	244
5.8	Image-plane deconvolution (deconvolve)	245
5.9	Self-Calibration	246
5.10	Examples of Imaging	247
5.10.1	Spectral Line Imaging with NGC5921	247
5.10.2	Continuum Imaging of Jupiter	250
6	Image Analysis	261
6.1	Common Image Analysis Task Parameters	262
6.1.1	Region Selection (box)	262
6.1.2	Plane Selection (chans , stokes)	262
6.1.3	Lattice Expressions (expr)	263
6.1.4	Masks (mask)	264
6.2	Image Header Manipulation (imhead)	264
6.2.1	Examples for imhead	265
6.3	Continuum Subtraction on an Image Cube (imcontsub)	268
6.3.1	Examples for imcontsub)	268
6.4	Image-plane Component Fitting (imfit)	269
6.5	Mathematical Operations on an Image (immath)	269
6.5.1	Examples for immath	270
6.5.1.1	Simple math	270
6.5.1.2	Polarization manipulation	272
6.5.1.3	Primary beam correction/uncorrection	272
6.5.1.4	Spectral analysis	273
6.5.2	Using masks in immath	273
6.6	Computing the Moments of an Image Cube (immoments)	275
6.6.1	Hints for using (immoments)	277
6.6.2	Examples using (immoments)	277
6.7	Computing image statistics (imstat)	278
6.7.1	Using the task return value	279
6.7.2	Examples using imstat	281
6.8	Extracting data from an image (imval)	282
6.9	Regridding an Image (imregrid)	284
6.10	Image Import/Export to FITS	284
6.10.1	FITS Image Export (exportfits)	285
6.10.2	FITS Image Import (importfits)	285
6.11	Using the CASA Toolkit for Image Analysis	285
6.12	Examples of CASA Image Analysis	288
6.12.1	Spectral Line Image Analysis with NGC5921	288

7	Visualization With The CASA Viewer	292
7.1	Starting the <code>viewer</code>	292
7.1.1	Running the CASA viewer outside <code>casapy</code>	294
7.2	The <code>viewer</code> GUI	295
7.2.1	The Viewer Display Panel	295
7.2.2	Saving and Restoring Display Panel State	299
7.2.3	Region Selection and Positioning	299
7.2.4	The Load Data Panel	300
7.2.4.1	Registered vs. Open Datasets	302
7.3	Viewing Images	302
7.3.1	Viewing a raster map	302
7.3.1.1	Raster Image — Basic Settings	304
7.3.1.2	Raster Image — Other Settings	306
7.3.2	Viewing a contour map	307
7.3.3	Overlay contours on a raster map	307
7.3.4	Spectral Profile Plotting	308
7.3.5	Managing and Saving Regions	309
7.3.6	Adjusting Canvas Parameters/Multi-panel displays	310
7.3.6.1	Setting up multi-panel displays	312
7.3.6.2	Background Color	312
7.4	Viewing Measurement Sets	313
7.4.1	Data Display Options Panel for Measurement Sets	313
7.4.1.1	MS Options — Basic Settings	314
7.4.1.2	MS Options— MS and Visibility Selections	315
7.4.1.3	MS Options — Display Axes	316
7.4.1.4	MS Options — Flagging Options	318
7.4.1.5	MS Options— Advanced	320
7.4.1.6	MS Options — Apply Button	321
7.5	Printing from the Viewer	321
A	Appendix: Single Dish Data Processing	324
A.1	Guidelines for Use of ASAP and SDtasks in CASA	324
A.1.1	Environment Variables	324
A.1.2	Assignment	325
A.1.3	Lists	325
A.1.4	Dictionaries	326
A.1.5	Line Formatting	326
A.2	Single Dish Analysis Tasks	327
A.2.1	SDtask Summaries	330
A.2.1.1	<code>sdaverage</code>	330
A.2.1.2	<code>sdsMOOTH</code>	333
A.2.1.3	<code>sdbaseline</code>	335
A.2.1.4	<code>sdcal</code>	337
A.2.1.5	<code>sdcoadd</code>	342
A.2.1.6	<code>sdfLAG</code>	343

A.2.1.7	<code>sdfit</code>	345
A.2.1.8	<code>sdlist</code>	348
A.2.1.9	<code>sdplot</code>	348
A.2.1.10	<code>sdsave</code>	353
A.2.1.11	<code>sdscale</code>	355
A.2.1.12	<code>sdstat</code>	355
A.2.1.13	<code>sdtpimaging</code>	358
A.2.2	Single Dish Analysis Use Cases With SDTasks	359
A.2.2.1	GBT Position Switched Data Analysis	359
A.2.2.2	Imaging of Total Power Raster Scans	372
A.3	Using The ASAP Toolkit Within CASA	374
A.3.1	Environment Variables	375
A.3.2	Import	376
A.3.3	Scantable Manipulation	378
A.3.3.1	Data Selection	379
A.3.3.2	State Information	379
A.3.3.3	Masks	380
A.3.3.4	Scantable Management	381
A.3.3.5	Scantable Mathematics	381
A.3.3.6	Scantable Save and Export	381
A.3.4	Calibration	382
A.3.4.1	Tsys scaling	382
A.3.4.2	Flux and Temperature Unit Conversion	382
A.3.4.3	Gain-Elevation and Atmospheric Optical Depth Corrections	382
A.3.4.4	Calibration of GBT data	383
A.3.5	Averaging	384
A.3.6	Spectral Smoothing	385
A.3.7	Baseline Fitting	385
A.3.8	Line Fitting	386
A.3.9	Plotting	387
A.3.9.1	ASAP plotter	387
A.3.9.2	Line Catalog	388
A.3.10	Setting/Getting Rest Frequencies	388
A.3.11	Single Dish Spectral Analysis Use Case With ASAP Toolkit	389
A.4	Single Dish Imaging	393
A.4.1	Single Dish Imaging Use Case With ASAP Toolkit	393
A.5	Known Issues, Problems, Deficiencies and Features	395
B	Appendix: Simulation	398
B.1	Simulating ALMA with <code>almasimmos</code>	398
C	Appendix: Obtaining and Installing CASA	400
C.1	Installation Script	400
C.2	Startup	400

D Appendix: Python and CASA	401
D.1 Automatic parentheses	401
D.2 Indentation	402
D.3 Lists and Ranges	402
D.4 Dictionaries	403
D.4.1 Saving and Reading Dictionaries	403
D.5 Control Flow: Conditionals, Loops, and Exceptions	405
D.5.1 Conditionals	405
D.5.2 Loops	407
D.6 System shell access	408
D.6.1 Using the <code>os.system</code> methods	408
D.6.2 Directory Navigation	410
D.6.3 Shell Command and Capture	410
D.7 Logging	412
D.8 History and Searching	412
D.9 Macros	414
D.10 On-line editing	415
D.11 Executing Python scripts	415
D.12 How do I exit from CASA?	416
E Appendix: The Measurement Equation and Calibration	417
E.1 The HBS Measurement Equation	417
E.2 General Calibrator Mechanics	421
F Appendix: Annotated Example Scripts	422
F.1 NGC 5921 — VLA red-shifted HI emission	422
F.1.1 NGC 5921 data summary	445
F.2 Jupiter — VLA continuum polarization	447
F.3 VLA Polarization Calibration	485
G Appendix: CASA Dictionaries	515
G.1 AIPS – CASA dictionary	515
G.2 MIRIAD – CASA dictionary	515
G.3 CLIC – CASA dictionary	515
H Appendix: Writing Tasks in CASA	518
H.1 The XML file	518
H.2 The <code>task_yourtask.py</code> file	522
H.3 Example: The <code>clean</code> task	522
H.3.1 File <code>clean.xml</code>	522
H.3.2 File <code>task_clean.py</code>	540

List of Tables

2.1	Common MS Columns	74
2.2	Commonly accessed MAIN Table columns	75
4.1	Recognized Flux Density Calibrators.	143
G.1	MIRIAD – CASA dictionary	516
G.2	CLIC–CASA dictionary	517

List of Figures

1.1	Screen shot of the default CASA inputs for task <code>clean</code>	50
1.2	The <code>clean</code> inputs after setting values away from their defaults (blue text). Note that some of the boldface ones have opened up new dependent sub-parameters (indented and green).	51
1.3	The <code>clean</code> inputs where one parameter has been set to an invalid value. This is drawn in red to draw attention to the problem. This hapless user probably confused the ' <code>hogbom</code> ' clean algorithm with Harry Potter.	52
1.4	The CASA Logger GUI window under Linux. Note that under MacOSX a stripped down logger will instead appear as a Console.	55
1.5	Using the Search facility in the <code>casalogger</code> . Here we have specified the string ' <code>plotted</code> ' and it has highlighted all instances in green.	56
1.6	Using the <code>casalogger</code> Filter facility. The log output can be sorted by Priority, Time, Origin, and Message. In this example we are filtering by Origin using ' <code>clean</code> ', and it now shows all the log output from the <code>clean</code> task.	57
1.7	CASA Logger - Insert facility: The log output can be augmented by adding notes or comments during the reduction. The file should then be saved to disk to retain these changes.	58
1.8	Different message priority levels as seen in the <code>casalogger</code> window. These can also be Filtered upon.	59
1.9	Flow chart of the data processing operations that a general user will carry out in an end-to-end CASA reduction session.	62
2.1	The contents of a Measurement Set. These tables compose a Measurement Set named <code>ngc5921.demo.ms</code> on disk. This display is obtained by using the File:Open menu in <code>browsetable</code> and left double-clicking on the <code>ngc5921.demo.ms</code> directory.	73

3.1	The <code>plotxy</code> plotter, showing the Jupiter data versus uv-distance. You can see bad data in this plot. The bottom set of buttons on the lower left are: 1,2,3) Home, Back, and Forward . Click to navigate between previously defined views (akin to web navigation). 4) Pan . Click and drag to pan to a new position. 5) Zoom . Click to define a rectangular region for zooming. 6) Subplot Configuration . Click to configure the parameters of the subplot and spaces for the figures. 7) Save . Click to launch a file save dialog box. The upper set of buttons in the lower left are: 1) Mark Region . Press this to begin marking regions (rather than zooming or panning). 2,3,4) Flag, Unflag, Locate . Click on these to flag, unflag, or list the data within the marked regions. 5) Next . Click to move to the next in a series of iterated plots. Finally, the cursor readout is on the bottom right.	99
3.2	The <code>plotxy</code> iteration plot. The first set of plots from the example in § 3.4.3.1 with <code>iteration='antenna'</code> . Each time you press the Next button, you get the next series of plots.	104
3.3	Multi-panel display of visibility versus channel (top), antenna array configuration (bottom left) and the resulting uv coverage (bottom right). The commands to make these three panels respectively are: 1) <code>plotxy('ngc5921.ms', xaxis='channel', datacolumn='data', field='0', subplot=211, plotcolor='', plotsymbol='go')</code> 2) <code>plotxy('ngc5921.ms', xaxis='x', field='0', subplot=223, plotsymbol='r.')</code> , 3) <code>plotxy('ngc5921.ms', xaxis='u', yaxis='v', field='0', subplot=224, plotsymbol='b,' ,fig</code>	108
3.4	Plot of amplitude versus uv distance, before (left) and after (right) flagging two marked regions. The call was: <code>plotxy(vis='ngc5921.ms',xaxis='uvdist', field='1445*')</code>	109
3.5	<code>flagdata</code> : Example showing before and after displays using a selection of one antenna and a range of channels. Note that each invocation of the <code>flagdata</code> task represents a cumulative selection, i.e., running <code>antenna='0'</code> will flag all data with antenna 0, while <code>antenna='0', spw='0:10 15'</code> will flag only those channels on antenna 0.	116
3.6	<code>flagdata</code> : Flagging example using the clip facility.	117
3.7	<code>browsetable</code> : The browser displays the main table within a frame. You can scroll through the data (x=columns of the <code>MAIN</code> table, and y=the rows) or select a specific page or row as desired. By default, 1000 rows of the table are loaded at a time, but you can step through the MS in batches.	119
3.8	<code>browsetable</code> : You can use the tab for <code>Table Keywords</code> to look at other tables within an MS. You can then double-click on a table to view its contents.	120
3.9	<code>browsetable</code> : Viewing the <code>SOURCE</code> table of the MS.	121
4.1	Flow chart of synthesis calibration operations. Not shown are use of table manipulation and plotting tasks <code>accum</code> , <code>plotcal</code> , and <code>smoothcal</code> (see Figure 4.2).	135
4.2	Chart of the table flow during calibration. The parameter names for input or output of the tasks are shown on the connectors. Note that from the output solver through the accumulator only a single calibration type (e.g. ' <code>B</code> ', ' <code>G</code> ') can be smoothed, interpolated or accumulated at a time. The final set of cumulative calibration tables of all types are then input to <code>applycal</code> as shown in Figure 4.1.	138

4.3	Display of the amplitude (upper) and phase (lower) gain solutions for all antennas and polarizations in the <code>ngc5921</code> post- <code>fluxscale</code> table.	170
4.4	Display of the amplitude (upper), phase (middle), and signal-to-noise ratio (lower) of the <code>bandpass</code> 'B' solutions for <code>antenna='0'</code> and both polarizations for <code>ngc5921</code> . Note the falloff of the SNR at the band edges in the lower panel.	172
4.5	Display of the amplitude of the <code>bandpass</code> 'B' solutions. Iteration over antennas was turned on using <code>iteration='antenna'</code> . The first page is shown. The user would use the Next button to advance to the next set of antennas.	173
4.6	The 'amp' of gain solutions for NGC4826 before (top) and after (bottom) smoothing with a 7200 sec <code>smoothtime</code> and <code>smoothtype='mean'</code> . Note that the first solution is in a different <code>spw</code> and on a different source, and is not smoothed together with the subsequent solutions.	175
4.7	The 'phase' of gain solutions for NGC4826 before (top) and after (bottom) 'linear' interpolation onto a 20 sec <code>accumtime</code> grid. The first scan was 3C273 in <code>spw='0'</code> while the calibrator scans on 1331+305 were in <code>spw='1'</code> . The use of <code>spwmap</code> was necessary to transfer the interpolation correctly onto the NGC4826 scans.	178
4.8	The final 'amp' (top) and 'phase' (bottom) of the self-calibration gain solutions for Jupiter. An initial phase calibration on 10s <code>solint</code> was followed by an incremental gain solution on each scan. These were accumulated into the cumulative solution shown here.	181
4.9	The final 'amp' versus 'uvdist' plot of the self-calibrated Jupiter data, as shown in <code>plotxy</code> . The 'RR LL' correlations are selected. No outliers that need flagging are seen.	184
4.10	Use of <code>plotxy</code> to display corrected data (red and blue points) and uv model fit data (green circles).	192
5.1	Close-up of the top of the interactive <code>clean</code> window. Note the boxes at the left (where the <code>iterations</code> , <code>cycles</code> , and <code>threshold</code> can be changed), the buttons that control add/erase, the application of mask to channels, and whether to stop, complete, or continue cleaning, and the row of Mouse-button tool assignment icons.	225
5.2	Screen-shots of the interactive <code>clean</code> window during deconvolution of the VLA 6m Jupiter dataset. We start from the calibrated data, but before any self-calibration. In the initial stage (left), the window pops up and you can see it dominated by a bright source in the center. Next (right), we zoom in and draw a box around this emission. We have also at this stage dismissed the tape deck and Position Tracking parts of the display (§ 7.2.1) as they are not used here. We have also changed the <code>iterations</code> to 30 for this boxed clean. We will now hit the Next Action Continue Cleaning button (the green clockwise arrow) to start cleaning.	233
5.3	We continue in our interactive <code>cleaning</code> of Jupiter from where Figure 5.2 left off. In the first (left) panel, we have cleaned 30 iterations in the region previously marked, and are zoomed in again ready to extend the mask to pick up the newly revealed emission. Next (right), we have used the Polygon tool to redraw the mask around the emission, and are ready to Continue Cleaning for another 100 iterations.	234

5.4	We continue in our interactive <code>cleaning</code> of Jupiter from where Figure 5.3 left off. In the first (left) panel, it has cleaned deeper, and we come back and zoom in to see that our current mask is good and we should clean further. We change <code>npercycl</code> to 500 (from 100) in the box at upper right of the window. In the final panel (right), we see the results after this clean. The residuals are such that we should terminate the <code>clean</code> using the red X button and use our model for self-calibration.	235
5.5	After clean and self-calibration using the intensity image, we arrive at the final polarization image of Jupiter. Shown in the <code>viewer</code> superimposed on the intensity raster is the linear polarization intensity (green contours) and linear polarization B-vectors (vectors). The color of the contours and the sampling and rotation by 90 degrees of the vectors was set in the Display Options panel. A LEL expression was used in the Load Data panel to mask the vectors on the polarized intensity.	236
5.6	Screen-shot of the interactive <code>clean</code> window during deconvolution of the NGC5921 spectral line dataset. Note where we have selected the mask to apply to the <code>Displayed Plane</code> rather than <code>All Channels</code> . We have just used the Polygon tool to draw a mask region around the emission in this channel, which will apply to this channel only.	237
6.1	NGC2403 VLA moment zero (left) and NGC4826 BIMA moment one (right) images as shown in the <code>viewer</code>	278
7.1	The Viewer Display Panel (left) and Data Display Options (right) panels that appear when the <code>viewer</code> is called with the image cube from NGC5921 (<code>viewer('ngc5921.usecase.clean.i</code>). The initial display is of the first channel of the cube.	293
7.2	The Viewer Display Panel (left) and Data Display Options (right) panels that appear when the <code>viewer</code> is called with the NGC5921 Measurement Set (<code>viewer('ngc5921.usecase.ms')</code>).2	294
7.3	The display panel's Main Toolbar appears directly below the menus and contains 'shortcut' buttons for most of the frequently-used menu items.	297
7.4	The ' Mouse Tool ' Bar allows you to assign separate mouse buttons to tools you control with the mouse within the image display area. Initially, zooming, color adjustment, and rectangular regions are assigned to the left, middle and right mouse buttons, respectively.	297
7.5	The Load Data - Viewer panel that appears if you open the <code>viewer</code> without any <code>infile</code> specified, or if you use the <code>Data:Open</code> menu or Open icon. You can see the images and MS available in your current directory, and the options for loading them. 301	301
7.6	The Load Data - Viewer panel as it appears if you select an image. You can see all options are available to load the image as a <code>Raster Image</code> , <code>Contour Map</code> , <code>Vector Map</code> , or <code>Marker Map</code> . In this example, clicking on the <code>Raster Image</code> button would bring up the displays shown in Figure 7.1.	303
7.7	The Basic Settings category of the Data Display Options panel as it appears if you load the image as a <code>Raster Image</code> . This is a zoom-in for the data displayed in Figure 7.1.	304
7.8	Example curves for scaling power cycles.	306

7.9	The Viewer Display Panel (left) and Data Display Options panel (right) after choosing Contour Map from the Load Data panel. The image shown is for channel 11 of the NGC5921 cube, selected using the Animator tape deck, and zoomed in using the tool bar icon. Note the different options in the open Basic Settings category of the Data Display Options panel.	307
7.10	The Viewer Display Panel (left) and Data Display Options panel (right) after overlaying a Contour Map on a Raster Image from the same image cube. The image shown is for channel 11 of the NGC5921 cube, selected using the Animator tape deck, and zoomed in using the tool bar icon. The tab for the contour plot is open in the Data Display Options panel.	308
7.11	The Image Profile panel that appears if you use the Tools:Spectral Profile menu, and then use the rectangle or polygon tool to select a region in the image. You can also use the crosshair to get the profile at a single position in the image. The profile will change to track movements of the region or crosshair if moved by dragging with the mouse.	309
7.12	The Region Manager panel that appears if you select the Tools:Region Manager menu item.	310
7.13	Selecting an image region with the polygon tool.	311
7.14	A multi-panel display set up through the Viewer Canvas Manager	312
7.15	The Load Data - Viewer panel as it appears if you select an MS. The only option available is to load this as a Raster Image . In this example, clicking on the Raster Image button would bring up the displays shown in Figure 7.2.	313
7.16	The MS for NGC4826 BIMA observations has been loaded into the viewer. We see the first of the spw in the Display Panel , and have opened up MS and Visibility Selections in the Data Display Options panel. The display panel raster is not full of visibilties because spw 0 is continuum and was only observed for the first few scans. This is a case where the different spectral windows have different numbers of channels also.	315
7.17	The MS for NGC4826 from Figure 7.16, now with the Display Axes open in the Data Display Options panel. By default, channels are on the Animation Axis and thus in the tapedeck, while spectral window and polarization are on the Display Axes sliders.	317
7.18	The MS for NGC4826, continuing from Figure 7.17. We have now put spectral window on the Animation Axis and used the tapedeck to step to spw 2 , where we see the data from the rest of the scans. Now channels is on a Display Axes slider, which has been dragged to show Channel 33	318
7.19	Setting up to print to a file. The background color has been set to white , the line width to 2, and the print resolution to 600 dpi (for an postscript plot). To make the plot, use the Save button on the Viewer Print Manager panel (positioned in the figure in the upper right) and select a format with the drop-down, or use the Print button to send directly to a printer.	322
A.1	Wiring diagram for the SDtask sdcal . The stages of processing within the task are shown, along with the parameters that control them.	329

A.2	Total power data display using <code>sdtppimaging</code> , with <code>calmode='baseline'</code> . The top panel shows uncalibrated data versus row numbers. The middle panel shows baseline fitting of each scan (only shown here the last scan). The bottom panel shows the calibrated (baseline subtracted) data.	373
A.3	Multi-panel display of the scatable. There are two plots per scan indicating the <code>_psr</code> (reference position data) and the <code>_ps</code> (source data).	390
A.4	Two panel plot of the calibrated spectra. The GBT data has a separate scan for the SOURCE and REFERENCE positions so scans 20,21,22 and 23 result in these two spectra.	391
A.5	Calibrated spectrum with a line at zero (using histograms).	392
A.6	FLS3a HI emission. The display illustrates the visualization of the data cube (left) and the profile display of the cube at the cursor location (right); the Tools menu of the Viewer Display Panel has a Spectral Profile button which brings up this display. By default, it grabs the left-mouse button. Pressing down the button and moving in the display will show the profile variations.	395

Chapter 1

Introduction

This document describes how to calibrate and image interferometric and single-dish radio astronomical data using the CASA (Common Astronomy Software Application) package. CASA is a suite of astronomical data reduction tools and tasks that can be run via the IPython interface to Python. CASA is being developed in order to fulfill the data post-processing requirements of the ALMA and EVLA projects, but also provides basic and advanced capabilities useful for the analysis of data from other radio, millimeter, and submillimeter telescopes.

You have in your hands the **Beta Release** of CASA. This means that there are a number of caveats and limitations for the use of this package. See § 1.1 below for more information, and pay heed to the numerous **BETA ALERTs** placed throughout this cookbook. You can expect regular updates and patches, as well as increasing functionality. But you can also expect interface changes. The goals of this Beta Release are to get the package out into the hands of real users so you can take it for a spin. Please knock it about a bit, but remember it is not a polished, finished product. Beware!

This cookbook is a task-based walk-through of interferometric data reduction and analysis. In CASA, **tasks** represent the more streamlined operations that a typical user would carry out. The idea for having tasks is that they are simple to use, provide a more familiar interface, and are easy to learn for most astronomers who are familiar with radio interferometric data reduction (and hopefully for novice users as well). In CASA, the **tools** provide the full capability of the package, and are the atomic functions that form the basis of data reduction. These tools augment the tasks, or fill in gaps left by tasks that are under development but not yet available. See the **CASA User Reference Manual** for more details on the tools. Note that in most cases, the tasks are Python interface scripts to the tools, but with specific, limited access to them and a standardized interface for parameter setting. The tasks and tools can be used together to carry out more advanced data reduction operations.

Inside the Toolkit:

Throughout this Cookbook, we will occasionally intersperse boxed-off pointers to parts of the toolkit that power users might want to explore.

For the moment, the audience is assumed to have some basic grasp of the fundamentals of synthesis imaging, so details of how a radio interferometer or telescope works and why the data needs to

undergo calibration in order to make synthesis images are left to other documentation — a good place to start might be Synthesis Imaging in Radio Astronomy II (1999, ASP Conference Series Vol. 180, eds. Taylor, Carilli & Perley).

This cookbook is broken down by the main phases of data analysis:

- data import, export, and selection (Chapter 2),
- examination and flagging of data (Chapter 3),
- interferometric calibration (Chapter 4),
- interferometric imaging (Chapter 5),
- image analysis (Chapter 6), and
- data and image visualization (Chapter 7).

BETA ALERT: For the Beta Release, there are also special chapters in the Appendix on

- single dish data analysis (Chapter A), and
- simulation (Chapter B).

These are included for users that will be doing EVLA and ALMA telescope commissioning and software development. They will become part of the main cookbook in later releases.

The general appendices provide more details on what's happening under the hood of CASA, as well as supplementary material on tasks, scripts, and relating CASA to other packages. These appendices include:

- obtaining and installing CASA (Appendix C),
- more details about Python and CASA (Appendix D),
- a discussion of the Hamaker-Bregman-Sault Measurement Equation (Appendix E),
- annotated scripts for typical data reduction cases (Appendix F), and
- CASA dictionaries to AIPS, MIRIAD, and CLIC (Appendix G).
- Writing your own CASA Task (Appendix H).

The CASA User Documentation includes:

- **CASA Synthesis & Single Dish Reduction Cookbook** — this document, a task-based data analysis walk-through and instructions;
- **CASA in-line help** — accessed using `help` in the `casapy` interface;

- The **CASA Toolkit Reference Manual** — details on a specific task or tool does and how to use it.
- The **CASA Task Reference Manual** — the information from the inline help and task documentation, available online in HTML.

The CASA home page can be found at:

<http://casa.nrao.edu>

From there you can find documentation and assistance for the use of the package, including the User Documentation. You will also find information on how to obtain the latest release and receive user support.

1.1 About This Beta Release

Currently, CASA is in the **Beta Release** stage. This means that much, but not all, of the eventual functionality is available. Furthermore, the package is still under development, and some features might change in future releases. This should be taken into account as users begin to learn the package. We will do our best to point out commands, tasks, and parameters that are likely to change underfoot.

Unfortunately, bugs and crashes also come along with the Beta release territory. We will do our best to stamp these out as soon as we find them, but sometimes known bugs will persist until we can find the right time to fix them (like in a task that we know we want to make a big change to next month). See the release notes for the current version for more details. In this cookbook, we will try to point out known pitfalls and workarounds in the **Beta Alert** boxes, or in **BETA ALERT** notes in the text.

Beta Alert!

Boxes like this will bring to your attention some of the features (or lack thereof) in the current Beta release version of CASA.

Not only is the software in Beta Release, but this cookbook is also a living document. You can expect this document, as well as other on-line and in-line user support guides, to be updated regularly. Also, feel free to send us comments and suggestions on the contents of our documentation.

Please check the CASA Home page (<http://casa.nrao.edu>) regularly to look for updates to the release and to the documentation, and to check the list of known problems. You can find the contact information for feedback here also.

We also note here that we are also in the process of commissioning our User Support system for CASA. Thus, we can only support a limited number of official Beta Release Users at this time. See the CASA Home Page for more information on the policies and conditions on obtaining and getting support for this Beta Release.

1.1.1 What's New in Patch 3

This Cookbook version is for Beta Release Patch 3.0 (Dec 2008) or CASA Version 2.3.0 and above. This patch differs from previous versions of CASA in a number of ways:

- New interface changes:
 - The versioning of CASA has changed such that the startup and `casalog.version` now report **Version X.Y.Z** where X=2 for the Beta Release, Y is the Patch number, and Z is the sub-patch release. For example, the December 2008 Patch 3.0 release is Version 2.3.0.
- New data handling features:
 - The `importasdm` task now has better handling of ALMA ATF data (§ 2.2.3).
- New plotting and flagging features:
 - The `plotxy` task now has the `extendflag` parameter and sub-parameters that allow the extension of interactive flagging to data cells beyond those plotted (§ 3.4.6).
- New synthesis calibration features:
 - The `bandtype='BPOLY'` option now has the capability of getting solutions in different sets of spectral windows (§ 4.4.2.3).
- New synthesis imaging features:
 - NEW: `widefield` — a prototype task to make wide-field (e.g. low frequency) images using w-projection and/or faceting. Includes the ability to image multiple flanking fields set up using a box file (§ 5.4).
 - The `clean` task now handles multiple dish sizes for heterogeneous imaging (§ 5.3.16).
 - The `clean` task has been improved in its handling of mosaics (§ 5.3.15).
- New image analysis features:
 - NEW: `imval` — a task that will return the data values in an image at a given pixel or in a specified region (§ 6.8).
 - The `imfit` task has improved reporting of fit results (§ 6.4).
- New viewer features:
 - The `viewer` now includes the ability to Save and Restore the GUI settings via a Data menu item (§ 7.2.2).
 - There is now improved control and appearance of Printing from the `viewer` (§ 7.5).
- New documentation features:
 - There is now an appendix on how to write and include your own CASA tasks, intended for the power-user (§ H).
 - There is now an online **CASA Task Reference Manual**.

1.1.1.1 Changes in Patch 2

These were changes made in July 2008 with Beta Release Patch 2.0–2.2:

- New interface changes:
 - Global parameters (variables) are not changed in task calls (§ 1.3.5.1).
 - Global parameters (variables) are not used if a task is called as a function with one or more arguments specified, e.g. `task(arg1=val1,...)`. Non-specified parameters are defaulted to the task-specific default values (§ 1.3.2).
 - Return values from tasks are used instead of output variables (§ 1.3.3).
- New data handling features:
 - The `concat` task now takes multiple input MS and will combine into a possibly new output MS (§ 2.4).
- New synthesis calibration features:
 - The calibration tasks now include a `combine` which allows control of the scope of solutions (§ 4.4.1.5).
 - The behavior of the `solint` parameter has changed, with `solint=0` now giving per-integration solutions instead of per-scan. This is used in conjunction with `combine` to control solution scope (§ 4.4.1.5).
- New synthesis imaging features:
 - The `clean` task now incorporates the features of old tasks `invert` and `mosaic`, with added capabilities (§ 5.3).
- New image analysis features:
 - Lattice Expression Language (LEL) in the image analysis tasks and tools is now fully 0-based, while previously it was partly 1-based. This is most noticeable in the `immoments` task with the `planes` parameter, and in using the `INDEXIN` LEL function in the `ia` tool methods (§ 6.1.3).
 - NEW: `imfit` — a task to do image-plane Gaussian fitting (§ 6.4).
 - The `immath` task now includes the options to make spectral index, linearly polarized intensity and angle images (§ 6.5).
- New viewer features:
 - The `viewer` now includes a **Region Manager** tool that can save the last box or polygon region to a file. In addition, the pixel coordinates under the cursor are displayed in the Position Tracking panel. (§ 7).

WARNING: Some of these changes will require scripts from Patch 1 or earlier to be changed. In some cases, you may not get an error but will get noticeably different behavior (e.g. from the `solint` changes in Calibration).

1.2 CASA Basics — Information for First-Time Users

This section assumes that CASA has been installed on your LINUX or OSX system. See Appendix C for instructions on how to obtain and install CASA.

1.2.1 Before Starting CASA

If you have done a default installation under Linux using rpms, or on the Mac with the CASA application, then there should be a `sh` script called `casapy` in the `/usr/bin` area which is in your path. This shell will set up its environment and run the version of `casapy` that it points to. If this is how you set up the system, then you need to nothing further and can run `casapy`.

Depending on your setup, there may be other specially built versions available. For example at the NRAO AOC, the “stable build” can be started by running “`casapy-test`”, e.g.

```
/usr/bin/casapy-test
```

On some systems, particularly if you have multiple versions installed, to define environment variables and the `casapy` alias, you will need to run one of the `casainit` shell scripts. The location of the startup scripts for CASA will depend upon where you installed CASA on your system. For a default installation this will likely be in `/usr/lib/casapy/`. For example, at the NRAO AOC, the current release is executed as

```
/usr/bin/casapy
```

and uses the pathname to

```
/usr/lib/casapy/23.0.6654-001
```

Sometimes, you will have multiple non-default versions (for example, various development versions). For example at the NRAO AOC, the “stable build” is in `/home/casa`. Then, to use this version:

```
In bash:  
> . /home/casa/casainit.sh  
or for csh:  
> source /home/casa/casainit.csh
```

depending on what shell you are running (Bourne or [t]csh).

BETA ALERT: If you want to run the `casabrowser` (see § 3.6) outside of the `casapy` shell, then you will need to put the CASA root in your path using one of the above mechanisms.

1.2.1.1 Environment Variables

Before starting up `casapy`, you should set or reset any *environment variables* needed, as CASA will adopt these on startup. For example, the `PAGER` environment variable determines how help is displayed in the CASA terminal window (see § 1.2.8.3). The choices are `less`, `more`, and `cat`.

In `bash`, pick one of

```
PAGER=less
PAGER=more
PAGER=cat
```

followed by

```
export PAGER
```

In `csh` or `tcsh`, pick one of

```
setenv PAGER less
setenv PAGER more
setenv PAGER cat
```

The actions of these are as if you were using the equivalent Unix shell command to view the help material. See § 1.2.8.3 for more information on these choices. We recommend using the `cat` option for most users, as this works smoothly both interactively and in scripts.

BETA ALERT: There is currently no way within CASA to change these environment variables.

1.2.1.2 Where is CASA?

Note that the path to the CASA installation, which contains the scripts and data repository, will also depend upon the installation. With a default installation under Linux this will probably be in

```
/usr/lib/casapy/
```

while in a Mac OSX default install it will likely be an application (in the Applications folder), with the data repository in:

```
/opt/casa/
```

You can find the location after initialized by looking at the `AIPSPATH` environment variable. You can find it within `casapy` by

```
pathname=os.environ.get('AIPSPATH').split()[0]
print pathname
```

1.2.2 Starting CASA

After having run the appropriate casainit script, CASA is started by typing `casapy` on the UNIX command line, e.g.

```
casapy
```

After startup information, you should get an IPython

`CASA <1>`:

command prompt in the xterm window where you started CASA. CASA will take approximately 10 seconds to initialize at startup in a new working directory; subsequent startups are faster. CASA is active when you get a

`CASA <1>`

prompt in the command line interface. You will also see a `logger` GUI appear on your Desktop (usually near the upper left). *Note: Under MacOSX the logger will appear in a Console window.*

You also have the option of starting CASA with various `logger` options (see § 1.4.2.1). For example, if you are running remotely in a terminal window without an X11 connection, or if you just do not want to see the logger GUI, and want the `logger` messages to come to your terminal, do

```
casapy --nologger --log2term
```

See § 1.4.2 for information on the `logger` in general.

1.2.3 Ending CASA

You can exit CASA by typing `quit`. This will bring up the query

```
Do you really want to exit ([y]/n)?
```

to give you a chance in case you did not mean to exit. You can also quit using `%exit` or `CTRL-D`.

If you don't want to see the question "Do you really want to exit [y]/n?", then just type `Exit` or `exit` and CASA will stop right then and there.

1.2.4 What happens if something goes wrong?

BETA ALERT: This is a Beta Release, and there are still ways to cause CASA to crash. Please check the CASA Home Page for Beta Release information including a list of known problems. If you think you have encountered an unknown problem, please consult the CASA HelpDesk (contact information on the CASA Home Page). See also the caveats to this Beta Release (§ 1.1 for pointers to our policy on User Support).

First, always check that your inputs are correct; use the

```
help <taskname>
(§ 1.2.8.2) or

help par.<parameter name>
(§ 1.2.8.4) to review the inputs/output.
```

1.2.5 Aborting CASA execution

If something has gone wrong and you want to stop what is executing, then typing CNTL-C (Control and C keys simultaneously) will usually cleanly abort the application. This will work if you are running a task synchronously. If this does not work on your system, or you are running a task asynchronously (§ 1.3.4) then try CNTL-Z to put the task or shell in the background, and then follow up with a `kill -9 <PID>` where you have found the relevant `casapy` process ID (PID) using `ps` (see § 1.2.6 below).

See § 1.3.2 for more information on running tasks.

If the problem causes CASA to crash, see the next sub-section.

1.2.6 What happens if CASA crashes?

Usually, restarting `casapy` is sufficient to get you going again after a crash takes you out of the Python interface. Note that there may be spawned subprocesses still running, such as the `casaviewer` or the `logger`. These can be dismissed manually in the usual manner. After a crash, there may also be hidden processes. You can find these by listing processes, e.g. in linux:

```
ps -elf | grep casa
```

or on MacOSX (or other BSD Unix):

```
ps -aux | grep casa
```

You can then kill these, for example using the Unix `kill` or `killall` commands. This may be necessary if you are running remotely using `ssh`, as you cannot logout until all your background processes are terminated. For example,

```
killall ipcontroller
```

or

```
killall Python
```

will terminate the most common post-crash zombies.

1.2.7 Python Basics for CASA

Within CASA, you use Python to interact with the system. This does not mean an extensive Python course is necessary - basic interaction with the system (assigning parameters, running tasks) is straightforward. At the same time, the full potential of Python is at the more experienced user's disposal. Some further details about Python, IPython, and the interaction between Python and CASA can be found in Appendix D.

The following are some examples of helpful hints and tricks on making Python work for you in CASA.

1.2.7.1 Variables

Python variables are set using the `<parameter> = <value>` syntax. Python assigns the type dynamically as you set the value, and thus you can easily give it a non-sensical value, e.g.

```
vis = 'ngc5921.ms'
vis = 1
```

The CASA parameter system will check types when you run a task or tool, or more helpfully when you set inputs using `inp` (see below). CASA will check and protect the assignments of the global parameters in its namespace.

Note that Python variable names are case-sensitive:

```
CASA <109>: Foo = 'bar'
CASA <110>: foo = 'Bar'
CASA <111>: foo
  Out[111]: 'Bar'
CASA <112>: Foo
  Out[112]: 'bar'
```

so be careful.

Also note that mis-spelling a variable assignment will not be noticed (as long as it is a valid Python variable name) by the interface. For example, if you wish to set `correlation='RR'` but instead type `corellation='RR'` you will find `correlation` unset and a new `corellation` variable set. Command completion (see § 1.2.8.1) should help you avoid this.

1.2.7.2 Lists and Ranges

Sometimes, you need to give a task a list of indices. If these are consecutive, you can use the Python `range` function to generate this list:

```
CASA <1>: iflist=range(4,8)
CASA <2>: print iflist
```

```
[4, 5, 6, 7]
CASA <3>: iflist=range(4)
CASA <4>: print iflist
[0, 1, 2, 3]
```

See Appendix D.3 for more information.

1.2.7.3 Indexes

As in C, Python indices are 0-based. For example, the first element in a list `antlist` would be `antlist[0]`:

```
CASA <113>: antlist=range(5)
CASA <114>: antlist
Out[114]: [0, 1, 2, 3, 4]
CASA <115>: antlist[0]
Out[115]: 0
CASA <116>: antlist[4]
Out[116]: 4
```

CASA also uses 0-based indexing internally for elements in the Measurement Set (MS – the basic construct that contains visibility and/or single dish data; see Chapter 2). Thus, we will often talk about Field or Antenna “ID”s which will start at 0. For example, the first field in an MS would have `FIELD_ID==0` in the `MSselect` syntax, and can be addressed as be indexed as `field='0'` in most tasks, as well as by name `field='0137+331'` (assuming that's the name of the first field). You will see these indices in the MS summary from the task `listobs`.

1.2.7.4 Indentation

Python pays attention to the indentation of lines, as it uses indentation to determine the level of nesting in loops. Be careful when cutting and pasting: if you get the wrong indentation, then unpredictable things can happen (usually it just gives an error).

See Appendix D.2 for more information.

1.2.7.5 System shell access

If you want to access system commands from a script, use the `os.system` command (§ D.6.1).

In interactive mode, any input line beginning with a ‘!’ character is passed verbatim (minus the ‘!’, of course) to the underlying operating system. Also, several common commands (`ls`, `pwd`, `less`) may be executed with or without the ‘!’, although the `cp` command must use ‘!’ and `cd` must be executed without the ‘!’. For example:

```
CASA <5>: !rm -r mydata.ms
```

Note that if you want to access a Unix environment variable, you will need to prefix with a double \$\$ instead of a single \$ — for example, to print the value of the \$PAGER variable, you would use

```
CASA <6>: !echo $$PAGER
```

See Appendix D.6 for more information.

1.2.7.6 Executing Python scripts

You can execute Python scripts (ASCII text files containing Python or casapy commands) using the `execfile` command. For example, to execute the script contained in the file `myscript.py` (in the current directory), you would type

```
CASA <7>: execfile('myscript.py')
```

or

```
CASA <8>: execfile 'myscript.py'
```

which will invoke the IPython auto-parenthesis feature.

NOTE: in some cases, you can use the IPython `run` command instead, e.g.

```
CASA <9>: run myscript.py
```

In this case, you do not need the quotes around the filename. This is most useful for re-initializing the task parameters, e.g.

```
CASA <10>: run clean.last
```

(see § 1.3.5.7).

See Appendix D.11 for more information.

1.2.8 Getting Help in CASA

1.2.8.1 TAB key

At **any** time, hitting the `<TAB>` key will complete any available commands or variable names and show you a list of the possible completions if there's no unambiguous result. It will also complete filenames in the current directory if no CASA or Python names match.

For example, it can be used to list the available functionality using minimum match; once you have typed enough characters to make the command unique, `<TAB>` will complete it.

```
CASA <15>: cle<TAB>
clean           clean_description      clearcal_check_params
clearplot       clearstat
clean_check_params   clear           clearcal_defaults
clearplot_defaults   clearstat_defaults
clean_defaults    clearcal          clearcal_description
clearplot_description  clearstat_description
```

1.2.8.2 help <taskname>

Basic information on an application, including the parameters used and their defaults, can be obtained by typing `help task` (`pdoc task` and `task?` are equivalent commands with some additional programming information returned). `help task` provides a one line description of the task and then lists all parameters, a brief description of the parameter, the parameter default, an example setting the parameter and any options if there are limited allowed values for the parameter.

```
CASA <45>: help uvcontsub
-----> help(uvcontsub)
Help on function uvcontsub in module uvcontsub:

uvcontsub(vis=None, field=None, spw=None, chans=None, solint=None,
fitorder=None, fitmode=None, splitdata=None, async=None)
    Continuum fitting and subtraction in the uv plane:

A polynomial of the desired order is fit across the specified
channels that define the continuum emission. The data may be
averaged in time to increase the signal to noise. This fit
represents a model of the continuum in all channels.

For fitmode='subtract', the fitted continuum spectrum is
subtracted from all channels and the result (presumably only
line emission) is stored in the CORRECTED_DATA. The
continuum fit is stored in the MODEL_DATA.

For fitmode='model' the continuum model is stored in the
MODEL_DATA; but the CORRECTED_DATA is unaffected.

For fitmode='replace' the continuum model is stored in
the CORRECTED_DATA; this is useful to image the continuum model
result.

Keyword arguments:
vis -- Name of input visibility file
      default: none; example: vis='ngc5921.ms'
field -- Field selection
      default: field = '' means select all fields
      field = 1 # will get field_id=1 (if you give it an
                 integer, it will retrieve the source with that index.
      field = '1328+307' specifies source '1328+307'
```

```

field = '13*' will retrieve '1328+307' and any other fields
      beginning with '13'
spw -- Spectral selection
      default: spw='', means select all spws;
      example: spw='1'
chans -- List of channels to fit for the continuum
      default: (all); example: chans=range(4,7)+range(50,60)
solint -- Averaging time for per-baseline fit (seconds)
      default: -1.0 --> no averaging, fit every integration;
      example: solint=10 --> average to 10s before fitting
fitorder -- Polynomial order for the fit of the continuum
      default: 0 (constant); example: fitorder=1
fitmode -- Use of the continuum fit model
      default: 'subtract'; example: fitmode='replace'
      Options:
      'subtract'-store fitted continuum model in MODEL and
          subtract this continuum from data in CORRECTED to
          produce line-emission in CORRECTED.
      'model'-store fit continuum model in MODEL, but
          do not change data in CORRECTED.
      'replace'-replace CORRECTED with continuum mode fit.
splitdata -- Split out continuum and continuum subtracted line data
      default: 'False'; example: splitdata=True
      The continuum data will be placed in: vis.cont
      The continuum subtracted data will be placed in: vis.contsub
async -- Run task in a separate process (return CASA prompt)
      default: False; example: async=True

```

You can also get the short help for a CASA tool method by typing 'help tool.method'.

```

CASA <46>: help ia.subimage
-----> help(ia.subimage)
Help on built-in function subimage:

subimage(...)
    Create a (sub)image from a region of the image'  :
        outfile
        region
        mask
        dropdeg   = false
        overwrite = false
        list      = true
-----

```

For a full list of keywords associated with the various tools, see the **CASA User Reference Manual**. **BETA ALERT:** The User Reference Manual currently covers only tools, not tasks.

1.2.8.3 help and PAGER

Your PAGER environment variable (§ 1.2.1) determines how help is displayed in the terminal window where you start CASA. If you set your bash environment variable PAGER=less (`setenv PAGER less` in csh) then typing `help <taskname>` will show you the help but the text will vanish and return you to the command line when you are done viewing it. Setting PAGER=more (`setenv PAGER more`) will scroll the help onto your command window and then return you to your prompt (but leaving it on display). Setting PAGER=cat (`setenv PAGER cat`) will give you the more equivalent without some extra formatting baggage and is the recommended choice.

If you have set PAGER=more or PAGER=less, the `help` display will be fine, but the display of 'taskname?' will often have confusing formatting content at the beginning (lots of ESC surrounding the text). This can be remedied by exiting casapy and doing an 'unset PAGER' (`unsetenv PAGER` in [t]csh) at the Unix command line.

You can see the current value of the PAGER environment variable with CASA by typing:

```
!echo $$PAGER
```

(note the double \$\$). This will show what command paging is pointed to.

1.2.8.4 help par.<parameter>

Typing `help par.<parameter>` provides a brief description of a given parameter <parameter>.

```
CASA <46>: help par.robust
Help on function robust in module parameter_dictionary:

robust()
    Brigg's robustness parameter.

Options: -2.0 (close to uniform) to 2.0 (close to natural)
```

1.2.8.5 Python help

Typing `help` at the casapy prompt with no arguments will bring up the native Python help facility, and give you the `help>` prompt for further information; hitting <RETURN> at the help prompt returns you to the CASA prompt.

```
CASA <2>: help
-----> help()

Welcome to Python 2.5!  This is the online help utility.

If this is your first time using Python, you should definitely check out
the tutorial on the Internet at http://www.python.org/doc/tut/.
```

Enter the name of any module, keyword, or topic to get help on writing Python programs and using Python modules. To quit this help utility and return to the interpreter, just type "quit".

To get a list of available modules, keywords, or topics, type "modules", "keywords", or "topics". Each module also comes with a one-line summary of what it does; to list the modules whose summaries contain a given word such as "spam", type "modules spam".

```
help> keywords
```

Here is a list of the Python keywords. Enter any keyword to get more help.

and	else	import	raise
assert	except	in	return
break	exec	is	try
class	finally	lambda	while
continue	for	not	yield
def	from	or	
del	global	pass	
elif	if	print	

```
help>
```

```
# hit <RETURN> to return to CASA prompt
```

You are now leaving help and returning to the Python interpreter.
If you want to ask for help on a particular object directly from the interpreter, you can type "help(object)". Executing "help('string')" has the same effect as typing a particular string at the help> prompt.

Further help in working within the Python shell is given in Appendix D.

1.3 Tasks and Tools in CASA

Originally, CASA consisted of a collection of tools, combined in the so-called toolkit. Since the majority of prospective users is far more familiar with the concept of tasks, an effort is underway to replace most - if not all - toolkit functionality by tasks.

While running CASA, you will have access to and be interacting with tasks, either indirectly by providing parameters to a task, or directly by running a task. Each task has a well defined purpose, and a number of associated parameters, the values of which are to be supplied by the user. Technically speaking, tasks are built on top of tools - when you are running a task, you are running tools in the toolkit, though this should be transparent.

As more tasks are being written, and the functionality of each task is enhanced, there will be less and less reason to run tools in the toolkit. We are working toward a system in which direct access to the underlying toolkit is unnecessary for all standard data processing.

1.3.1 What Tasks are Available?

As mentioned in the introduction, tasks in CASA are python interfaces to the more basic toolkit. Tasks are executed to perform a single job, such as loading, plotting, flagging, calibrating, and imaging the data.

Basic information on tasks, including the parameters used and their defaults, can be obtained by typing `help <taskname>` or `<taskname>?` at the CASA prompt, where `<taskname>` is the name of a given task. As described above in § 1.2.8.2, `help <taskname>` provides a description of the task and then lists all parameters, a brief description of the parameter, the parameter default, an example setting the parameter and any options if there are limited allowed values for the parameter.

To see what tasks are available in CASA, use `tasklist`, e.g.

```
CASA <4>: tasklist()
Available tasks:

Import/Export      Information    Data Editing    Display/Plot
-----            -----          -----          -----
importvla         listcal        flagautocorr  clearplot
(importasdm)      listhistory   flagdata       plotants
importfits        listobs        flagmanager   plotcal
importuvfits     listvis         plotxy        plotxy
exportfits        imhead         viewer
exportuvfits     imstat

Calibration       Imaging        Modelling     Utility
-----            -----          -----          -----
accum             clean          setjy         help task
applycal          deconvolve   uvcontsub    help par.parameter
bandpass          feather        uvmodelfit  taskhelp
(blcal)
ft
gaincal           invert         browsetable
fluxscale         makemask      clearplot
(fringecal)      mosaic         clearstat
clearcal
listcal
smoothcal
polcal
hanningsmooth

Image Analysis    Simulation    Single Dish
-----            -----          -----
imcontsub        (almasimmos) sdaverage
```

imhead	sdbaseline
immath	sdcal
immoments	sdcoadd
imregrid	sdfit
imstat	sdflag
imval	sdlist
(specfit)	sdplot
	sdsave
	sdscale
	sdssmooth
	sdsdtat

The tasks with name in parentheses are experimental.

Typing `taskhelp` provides a one line description of all available tasks.

```
CASA <5>: taskhelp()
```

Available tasks:

accum	: Accumulate incremental calibration solutions into a calibration table
almasisimos	: ALMA mosaic simulation task (prototype):
applycal	: Apply calibrations solutions(s) to data
bandpass	: Calculates a bandpass calibration solution
blcal	: Calculate a baseline-based calibration solution (gain or bandpass)
browsetable	: Browse a table (MS, calibration table, image)
clean	: Deconvolve an image with selected algorithm
clearcal	: Re-initializes the calibration for a visibility data set
clearplot	: Clear the matplotlib plotter and all layers
clearstat	: Clear all read/write locks
concat	: Concatenate two visibility data sets.
deconvolve	: Image based deconvolver
exportfits	: Convert a CASA image to a FITS file
exportuvfits	: Convert a CASA visibility data set to a UVFITS file:
feather	: Feathering: Combine two images using the Fourier Addition
find	: Find string in tasks, task names, parameter names:
flagautocorr	: Flag autocorrelations
flagdata	: All purpose flagging task based on selections
flagmanager	: Enable list, save, restore and delete flag version files.
fluxscale	: Bootstrap the flux density scale from standard calibrators
fringecal	: Calculate a baseline-based fringe-fitting solution (phase, delay, delay-rate); Note: cu
ft	: Insert a source model into the MODEL_DATA column of a visibility set:
gaincal	: Determine temporal gains from calibrator observations
hanningsmooth	: Hanning smooth frequency channel data to remove Gibbs ringing
imcontsub	: Subtracts specified continuum channels from a spectral line data set
imfit	: Fit One Elliptical Gaussian Component on an image region(s)
imhead	: List, get and put image header parameters
immath	: Perform math operations on images
immoments	: Compute moments from an image
importasdm	: Convert an ALMA Science Data Model observation into a CASA visibility file
importfits	: Convert an image FITS file into a CASA image

```

importuvfits      : Convert a UVFITS file to a CASA visibility data set
importvla        : Import VLA archive file(s) to a measurement set
imregrid         : regrid an image onto a template image
imstat           : Displays statistical information from an image or image region
imval            : Get the data value(s) and/or mask value in an image.
invert           : Calculate the dirty image and dirty beam from a visibility set
listcal          : List calibrated antenna gain solutions
listhistory      : List the processing history of a dataset:
listobs          : List data set summary in the logger
listvis          : List measurement set visibilities.
makemask         : Derive a mask image from a cleanbox blc, trc regions
mosaic           : Create a multi-field deconvolved image with selected algorithm
newclean          : Deconvolve an image with selected algorithm
newflagdata      : Flag/Clip data based on selections
oldclean          : Deconvolve an image with selected algorithm
plotants         : Plot the antenna distribution in the local reference frame:
plotcal          : An all-purpose plotter for calibration results
plotxy           : An X-Y plotter/interactive flagger for visibility data.
polcal           : Determine instrumental polarization calibrations
sdaverage        : ASAP SD task: do data selection, calibration, and averaging
sdbaseline       : ASAP SD task: fit/remove a spectral baseline
sdcal            : ASAP SD task: do sdaverage, sdsMOOTH, and sdbaseline in one task
sdcoadd          : ASAP SD task: coadd multiple scantables into one
sdfit             : ASAP SD task: fit a spectral line
sdflag            : ASAP SD spectral flagging task
sdlist            : ASAP SD task: list summary of single dish data
sdplot            : ASAP SD plotting task
sdsave            : ASAP SD task: save the sd spectra in various format
sdscale           : ASAP SD task: scale the sd spectra
sdsmooth          : ASAP SD task: do smoothing of spectra
sdstat            : ASAP SD task: list statistics of spectral region
sdtpimaging      : SD task: do a simple calibration and imaging for total power data
setjy             :
smoothcal        : Smooth calibration solution(s) derived from one or more sources:
(specfit)         : Fit 1-dimentional profile(s) or polynomial(s) to an image or image region
split              :
uvcontsub        : Continuum fitting and subtraction in the uv plane
uvmodelfit       : Fit a single component source model to the uv data
uvsub             : Subtract/add model from/to the corrected visibility data.
viewer            : View an image or visibility data set:
widefield        : Wide-field imaging and deconvolution with selected algorithm

```

Typing `startup` will provide the startup page displayed when entering CASA. For example,

```
CASA <6>: startup()
```

Available tasks:

accum	flagdata	invert	sdflag
applycal	flagmanager	listcal	sdlist

```

bandpass      fluxscale      listhistory    sdplot
browsetable   ft            listtobs       sdsave
clean         gaincal       listvis        sdsscale
clearcal      hanningsmooth makemask       sdsmooth
clearplot     imcontsub     mosaic         sdstat
clearstat     imhead        plotants       setjy
concat        immoments    plotcal        smoothcal
deconvolve    importfits    plotxy         specfit
exportfits    importuvfits sdaverage     split
exportuvfits  importvls    sdbaseline    tget
feather       imregrid     sdcal          uvcontsub
filecatalog   imstat       sdciadd       uvmodelfit
find          imval        sdfit         viewer

```

Additional tasks are available for ALMA commissioning use
 (still alpha code as of Beta 0 release):

```
almasimmos    blcal        fringecal    importasdm
```

Available tools:

```

cb (calibrator)  cp (cal plot)    fg (flagger)
ia (image analysis) im (imager)   me (measures)
mp (MS plot)      ms (MS)        qa (quanta)
sm (simulation)   tb (table)     tp (table plot)
vp (voltage patterns)

pl (pylab functions)
sd (ASAP functions - run asap_init() to import into CASA)

casalogger        - Call up the casalogger (if it goes away)
-----
```

Help :

help taskname	- Full help for task
help par.parametername	- Full help for parameter name
find string	- Find occurrences of string in doc
tasklist	- Task list organized by category
taskhelp	- One line summary of available tasks
toolhelp	- One line summary of available tools
startup	- The start up screen

1.3.2 Running Tasks and Tools

Tools are functions linked to the Python interface which must be called by name with arguments. Tasks have

BETA ALERT:

This is a new behavior in Patch 2. In previous versions global parameters were always used no matter how the task was called.

higher-level capabilities than tools. Tasks require input parameters which maybe be specified when you call the task as a function, or be set as parameters in the interface. A task, like a tool, is a function under Python and may be written in Python, C, or C++ (the CASA toolkit is made up of C++ functions).

There are two distinct ways to run tasks. You can either set the global CASA parameters relevant to the task and tell the task to “go”, or you can call the task as a function with one or more arguments specified. These two invocation methods differ in whether the global parameter values are used or not.

For example,

```
default('plotxy')
vis='ngc5921.ms'
xaxis='channel'
yaxis='amp'
datacolumn='data'
go
```

will execute `plotxy` with the set values for the parameters (see § 1.3.5). Instead of using `go` command (§ 1.3.5.3) to invoke the task, you can also call the task with no arguments, e.g.

```
default('plotxy')
vis='ngc5921.ms'
xaxis='channel'
yaxis='amp'
datacolumn='data'
plotxy()
```

which will also use the global parameter values.

Second, one may call tasks and tools by name with parameters set on the same line. Parameters may be set either as explicit `<parameter>=<value>` arguments, or as a series of comma delimited `<value>`s in the correct order for that task or tool. Note that missing parameters will *use the default values for that task*. For example, the following are equivalent:

```
# Specify parameter names for each keyword input:
plotxy(vis='ngc5921.ms',xaxis='channel',yaxis='amp',datacolumn='data')
# when specifying the parameter name, order doesn't matter, e.g.:
plotxy(xaxis='channel',vis='ngc5921.ms',datacolumn='data',yaxis='amp')
# use parameter order for invoking tasks
plotxy('ngc5921.ms','channel','amp','data')
```

This non-use of globals when calling as a function is so that robust scripts can be written. One need only cut-and-paste the calls and need not worry about the state of the global variables or what has been run previously. It is also more like the standard behavior of function calls in Python and other languages.

Tools can only be called in this second manner by name, with arguments (§ 1.3.6). Tools never use the global parameters and the related mechanisms of `inp` and `go`.

1.3.2.1 Aborting Synchronous Tasks

If you are running CASA tasks synchronously, then you can usually use CNTL-C to abort execution of the task. If this does not work, try CNTL-Z followed by a `kill`. See § 1.2.5 for more on these methods to abort CASA execution.

You may have to quit and restart CASA after an abort, as the internal state can get mixed up.

1.3.3 Getting Return Values

Some tasks and tools return a record (usually a Python dictionary) to the interface. For example, the `imstat` task (§ 6.7) returns a dictionary with the image statistics in it. To catch these return values into a Python variable, you MUST assign that variable to the task call, e.g.

```
xstat = imstat('ngc5921.clean.image')
```

or

```
default('imstat')
imagename = 'ngc5921.clean.image'
xstat = imstat()
```

Note that tools that return values work in the same way (§ 1.3.6).

You can print or use the return value in Python for controlling scripts. For example,

```
CASA <1>: xstat = imstat('ngc5921.clean.image')
CASA <2>: xstat
Out[2]:
{'blc': array([0, 0, 0, 0]),
 'blcf': '15:24:08.404, +04.31.59.181, I, 1.41281e+09Hz',
 'flux': array([ 4.15292207]),
 'max': array([ 0.05240594]),
 'maxpos': array([134, 134, 0, 38]),
 'maxposf': '15:21:53.976, +05.05.29.998, I, 1.41374e+09Hz',
 'mean': array([ 1.62978083e-05]),
 'medabsdevmed': array([ 0.00127287]),
 'median': array([-1.10467618e-05]),
 'min': array([-0.0105249]),
 'minpos': array([160, 1, 0, 30]),
 'minposf': '15:21:27.899, +04.32.14.923, I, 1.41354e+09Hz',
 'npts': array([ 3014656.]),
 'quartile': array([ 0.00254587]),
 'rms': array([ 0.00201818]),
 'sigma': array([ 0.00201811]),
 'sum': array([ 49.1322855]),
 'sumsq': array([ 12.27880404]),
 'trc': array([255, 255, 0, 45]),
```

```
'trcf': '15:19:52.390, +05.35.44.246, I, 1.41391e+09Hz'}
CASA <3>: myrms = xstat['rms'][0]
CASA <4>: print 10.0*myrms
0.0201817648485
```

If you do not catch the return variable, it will be lost

```
imstat('ngc5921.clean.image')
```

or

```
default('imstat')
imagename = 'ngc5921.clean.image'
imstat()
```

and spewed to terminal. Note that `go` will trap and lose the return value, e.g.

```
default('imstat')
imagename = 'ngc5921.clean.image'
go
```

will not dump the return to the terminal either.

NOTE: You cannot currently catch a return value from a task run asynchronously (§ 1.3.4).

BETA ALERT: Before Patch 2, the return values for tasks like `imstat` and `imhead` were put into the global variables (`xstat` and `hdvalue` respectively). This is no longer the case.

1.3.4 Running Tasks Asynchronously

By default, most tasks run synchronously in the foreground. Many tasks, particularly those that can take a long time to execute, have the `async` parameter. This allows the user to send the task to the background for execution.

BETA ALERT: A few tasks, such as the `exportuvfits` and `exportfits` tasks, have `async=True` by default. This is a workaround for a known problem where they can trample on other tasks and tools if they use the default global tools underneath.

1.3.4.1 Monitoring Asynchronous Tasks

BETA ALERT: Currently, this is only available with the `tm` tool. We are working on a `taskmanager` task.

There is a “taskmanager” tool `tm` that allows the user to retrieve the status of, and to abort the execution of, tasks running with `async=True` in the background. There are two methods of interest for the user, `tm.retrieve` and `tm.abort`.

If you run a task with `async=True` then several things will happen. First of all, the task returns a “handle” that is a number used to identify the process. This is printed to the screen, e.g.

```
CASA <5>: inp()
# mosaic :: Calculate a multi-field deconvolved image with selected clean algorithm:
...
async           =      True       #   if True run in the background, prompt is freed

CASA <6>: mosaic()
Connecting to controller: ('127.0.0.1', 60775)
Out[6]: 0
```

where the output value 0 is the handle id.

You can also catch the return value in a variable, e.g.

```
CASA <7>: handle = mosaic()
...
CASA <8>: print handle
1
```

You should also see the usual messages from the task in the logger, with some extra lines of information

```
#####
### Begin Task: mosaic #####
Tue Oct 2 17:58:16 2007    NORMAL ::mosaic:
"""

"Use: "
tm.abort(return_value)    # to abort the asynchronous task
tm.retrieve(return_value) # to retrieve the status
"""

... usual messages here ...

###
## End Task: mosaic ##
#####
"""


```

for the example above.

To show the current state of an asynchronous task, use the `tm.retrieve` method using the handle id as the argument. For example,

BETA ALERT:

You should not use the `go` command to run a task asynchronously, as the “handle” will be swallowed by the Python task wrapper and you will not be able to access it with `tm`. This is also true if you run in a Python script.

```
CASA <9>: tm.retrieve(handle)
Out[9]: {'result': None, 'state': 'pending'}
```

or

```
CASA <10>: tm.retrieve(1)
Out[10]: {'result': None, 'state': 'pending'}
```

which means its still running. You should be seeing output in the `logger` also while the task is running.

When a task is finished, you will see:

```
CASA <11>: tm.retrieve(1)
Out[11]: {'result': None, 'state': 'done'}
```

which indicates completion.

1.3.4.2 Aborting Asynchronous Tasks

To abort a task while it is running in the background, use the `tm.abort` method, again with the task handle id as the argument. For example,

```
CASA <12>: handle = mosaic()
...
CASA <13>: tm.abort(handle)
```

will abort the task if it is running.

If this does not work, try CNTL-Z followed by a `kill -9 <PID>` for the appropriate process ID. See § 1.2.5 for more on these methods to abort CASA execution.

1.3.5 Setting Parameters and Invoking Tasks

One can set parameters for tasks (but currently not for tools) by performing the assignment within the CASA shell and then inspecting them using the `inp` command:

```
CASA <30>: default(plotxy)
CASA <31>: vis = 'ngc5921.ms'
CASA <32>: xaxis = 'channel'
CASA <33>: yaxis = 'amp'
CASA <34>: datacolumn = 'data'
CASA <35>: inp(plotxy)
vis                  = 'ngc5921.ms'      #  Name of input visibility
xaxis                = 'channel'        #  azimuth,elevation,hourangle,baseline,channel,time,u,v,w,uvdis
```

Inside the Toolkit:

In the current version of CASA, you cannot use the task parameter setting features, such as the `inp`, `default`, or `go` commands, for the tools.

```

yaxis          =      'amp'          # azimuth,elevation,hourangle,baseline,amp,pha,u,v,w,uvdist
datacolumn     =      'data'         # data (raw), corrected, model
field          =      ''             # Select data based on field name or index
spw           =      ''             # Select data based on spectral window
selectdata    =      False          # Select a subset of the data - opens selection params
average        =      ''             # Select averaging mode: time or channel
subplot        =      111            # Panel number on display screen (yxn)
overplot       =      False          # Overplot values on current plot (if possible)
showflags      =      False          # Show flagged data
iteration      =      ''             # Plot separate panels by field, antenna, baseline, scan, feed
plotsymbol    =      '.'             # pylab plot symbol
plotcolor      =      'darkcyan'     # pylab plot color
markersize    =      5.0            # Size of plotted marks
linewidth      =      1.0            # Width of plotted lines
connect        =      'none'         # Specifies which points are connected with lines
plotrange     =      [-1, -1, -1, -1] # The range of data to be plotted, can be time values
skipnpoints   =      1               # Plot every nth point
multicolor    =      False          # Plot polarizations and channels in different colors
replacetopplot=      False          # Replace the last plot or not when overplotting
removeoldpanels=      True           # Turn on/of automatic clearing of panels
title          =      ''             # Plot title (above plot)
xlabels        =      ''             # Label for x-axis
ylabels        =      ''             # Label for y-axis
fontsize       =      10.0           # Font size for labels
windowsize    =      1.0            # Window size

```

See § 1.3.5.4 below for more details on the use of the `inputs` command.

All task parameters have **global** scope within CASA: the parameter values are common to all tasks and also at the CASA command line. This allows the convenience of not changing parameters that are shared between tasks but does require care when chaining together sequences of task invocations (to ensure proper values are provided).

If you want to reset the input keywords for a single task, use the `default` command (§ 1.3.5.2). For example, to set the defaults for the `clean` task, type:

```
CASA <12>: default('clean')
```

To inspect a single parameter value just type it at the command line:

```
CASA <16>: alg          # type 'alg' to see the what the algorithm keyword is set to
Out[16]: 'clark'        # CASA tells you it is set to use the Clark algorithm
```

CASA parameters are just Python variables.

Parameters for a given task can be saved by using the `saveinputs` command (see § 1.3.5.5) and restored using the `execfile '<filename>'` command. Note that if the task is successfully executed, then a `<taskname>.last` file is created in the working directory containing the parameter values (see § 1.3.5.7).

We now describe the individual CASA task parameter interface commands and features in more detail.

1.3.5.1 The scope of parameters in CASA

All task parameters have **global** scope within CASA: the parameter values are common to all tasks and also at the CASA command line. This allows the convenience of not changing parameters that are shared between tasks but does require care when chaining together sequences of task invocations (to ensure proper values are provided). Tasks DO NOT change the values of the global parameters, nor does the invocation of tasks using the functional call with arguments change the globals.

This does mean that unless you do an explicit `default` of the task (§ 1.3.5.2), previously set values may be unexpectedly used if you do not inspect the `inp` carefully. For example, good practice is:

```
default('imhead')
imagername = 'ngc5921.usecase.clean.image'
mode = 'list'
imhead()
```

If you supply the task call with arguments, then these will be used for the values of those parameters (see above). However, if some but not all arguments are supplied, then those parameters not given as arguments will default and NOT use the current global values. Thus,

```
imhead('ngc5921.usecase.clean.image', mode='list')
```

will reproduce the above.

Advanced Tip

By default, the scope of CASA parameters is global, as stated here. However, if you call a task as a function with one or more arguments specified, e.g. `task(arg1=val1,...)`, then non-specified parameters will be defaulted and no globals used. This makes scripting more robust. Tasks DO NOT change the value of globals.

1.3.5.2 The `default` Command

Each task has a special set of default parameters defined for its parameters. You can use the `default` command to reset the parameters for a specified task (or the current task as defined by the `taskname` variable) to their default.

Important Note: The `default` command resets the values of the task parameters to a set of “defaults” as specified in the task code. Some defaults are blank strings ‘’ or empty lists [],

others are specific numerical values, strings, or lists. It is important to understand that just setting a string parameter to an empty string '' is not setting it to its default! Some parameters do not have a blank as an allowed value. See the `help` for a particular task to find out its default. If '' is the default or an allowed value, it will say so explicitly.

For example, suppose we have been running CASA on a particular dataset, e.g.

```
CASA <40>: inp clean
-----> inp('clean')
vis          = 'ngc5921.ms'      # Name of input visibility file
imagename    = 'ngc5921'        # Pre-name of output images
mode         = 'mfs'            # Type of selection (mfs, channel, velocity, frequency)
alg          = 'csclclean'      # Algorithm to use (hogbom, clark, csclclean, multiscale)
niter        = 1000             # Number of iterations
...
...
```

and now we wish to switch to a different one. We can reset the parameter values using `default`:

```
CASA <41>: default
-----> default()

CASA <42>: inp
-----> inp()
vis          =      ''          # Name of input visibility file
imagename    =      ''          # Pre-name of output images
mode         = 'mfs'            # Type of selection (mfs, channel, velocity, frequency)
alg          = 'clark'          # Algorithm to use (hogbom, clark, csclclean, multiscale)
niter        = 500              # Number of iterations
...
...
```

It is good practice to use `default` before running a task if you are unsure what state the CASA global variables are in.

BETA ALERT: You currently can only reset ALL of the parameters for a given task to their defaults. In an upcoming update we will allow the `default` command to take a second argument with a specific parameter to default its value.

1.3.5.3 The `go` Command

You can execute a task using the `go` command, either explicitly

```
CASA <44>: go listobs
-----> go(listobs)
Executing: listobs()
...
...
```

or implicitly if `taskname` is defined (e.g. by previous use of `default` or `inp`)

```
CASA <45>: taskname = 'clean'
CASA <46>: go
-----> go()
Executing: clean()
...
```

You can also execute a task simply by typing the taskname.

```
CASA <46>: clean
-----> clean()
Executing: clean()
...
```

The `go` command can also be used to launch a different task without changing the current `taskname`, without disrupting the `inp` process on the current task you are working on. For example

```
default 'gaincal' # set current task to gaincal and default
vis = 'n5921.ms' # set the working ms
...
# set some more parameters
go listobs      # launch listobs w/o chaning current task
inp            # see the inputs for gaincal (not listobs!)
```

BETA ALERT: Doing `go listobs(vis='foo.ms')` will currently change the `taskname`, and will change `vis`, which might not be what is desired.

1.3.5.4 The `inp` Command

You can set the values for the parameters for tasks (but currently not for tools) by performing the assignment within the CASA shell and then inspecting them using the `inp` command. This command can be invoked in any of three ways: via function call `inp('<taskname>')` or `inp(<taskname>)`, without parentheses `inp '<taskname>'` or `inp <taskname>`, or using the current `taskname` variable setting with `inp`. For example,

```
CASA <1>: inp('clean')
...
CASA <2>: inp 'clean'
-----> inp('clean')
...
CASA <3>: inp(clean)
...
CASA <4>: inp clean
-----> inp(clean)
...
CASA <5>: taskname = 'clean'
CASA <6>: inp
-----> inp()
```

all do the same thing.

When you invoke the task inputs via `inp`, you see a list of the parameters, their current values, and a short description of what that parameter does. For example, starting from the default values,

```
CASA <18>: inp('clean')
# clean :: Calculates a deconvolved image with a selected clean algorithm

vis          =      ''    # Name of input visibility file
imagingname  =      ''    # Pre-name of output images
mode         = 'mfs'   # Type of selection (mfs, channel, velocity, frequency)
alg          = 'clark'  # Algorithm to use (hogbom, clark, csclean, multiscale)
niter        = 500     # Number of iterations
gain          = 0.1     # Loop gain for cleaning
threshold    = 0.0     # Flux level to stop cleaning (mJy)
mask          = ['']    # Name of mask image used in cleaning
cleanbox     = []      # clean box regions or file name or 'interactive'
imsize       = [256, 256] # Image size in pixels [nx,ny]; symmetric for single value
cell          = ['1.0arcsec', '1.0arcsec']      # Cell size in arcseconds [x,y]
stokes        = 'I'     # Stokes parameter to image (I,IV,IQU,IQUV)
field         = '0'     # Field name
phasecenter   = ''      # Field Identifier or direction of the image phase center
spw           = ''      # spectral window:channels: ''=>all
weighting     = 'natural' # Weighting to apply to visibilities
uvfilter      = False   # Apply additional filtering/uv tapering of the visibilities
timerange     = ''      # range of time to select from data
restfreq      = ''      # restfrequency to use in image
async         = False   # if True run in the background, prompt is freed
```


Figure 1.1 shows how this will look to you on your terminal. Note that some parameters are in boldface with a gray background. This means that some values for this parameter will cause it to *expand*, revealing new *sub-parameters* to be set.

CASA uses color and font to indicate different properties of parameters and their values:

Parameter and Values in CASA inp

	Text Font	Text Color	Highlight	Indentation	Meaning
Parameters:					
	plain	black	none	none	standard parameter
	bold	black	grey	none	expandable parameter
	plain	green	none	yes	sub-parameter
Values:					
	plain	black	none	none	default value
	plain	blue	none	none	non-default value
	plain	red	none	none	invalid value

Figure 1.2 shows what happens when you set some of the `clean` parameters to non-default values. Some have opened up sub-parameters, which can now be seen and set. Figure 1.3 shows what



The screenshot shows a terminal window titled 'xterm <2>' containing CASA script. The script defines parameters for the 'clean' task. Several parameters are highlighted in red, indicating they have invalid values:

```

CASA <23>: default 'clean'
-----> default('clean')

CASA <24>: inp
-----> inp()
# clean :: Calculates a deconvolved image with a selected clean algorithm

vis          =      ''          # Name of input visibility file
imagename    =      ''          # Pre-name of output images
mode         =      'mfs'       # Type of selection (mfs, channel, velocity, frequency)
alg          =      'clark'     # Algorithm to use (hogbom, clark, csclean, multiscale)
niter        =      500         # Number of iterations
gain          =      0.1         # Loop gain for cleaning
threshold    =      0.0         # Flux level to stop cleaning (mJy)
mask          =      ['']        # Name of mask image used in cleaning
cleanbox     =      []          # clean box regions or file name or 'interactive'
imsize        =      [256, 256]   # Image size in pixels [nx,ny]; symmetric for single value
cell          =      ['1.0arcsec', '1.0arcsec'] # Cell size in arcseconds [x,y]
stokes        =      'I'         # Stokes parameter to image (L,IV,IQU,IQUV)
field         =      '0'         # Field name
phasecenter   =      ''          # Field Identifier or direction of the image phase center
spw          =      ''          # spectral window/channels: '>all'
weighting     =      'natural'   # Weighting to apply to visibilities
uvfilter     =      False        # Apply additional filtering/uv tapering of the visibilities
timerange    =      ''          # range of time to select from data
restfreq     =      ''          # restfrequency to use in image
async         =      False        # if True run in the background, prompt is freed

CASA <25>: ■

```

Figure 1.1: Screen shot of the default CASA inputs for task `clean`.

happens when you set a parameter, in this case `vis` and `mode`, to an invalid value. Its value now appears in red. Reasons for invalidation include incorrect type, an invalid menu choice, or a filename that does not exist. For example, since `vis` expects a filename, it will be invalidated (red) if it is set to a non-string value, or a string that is not the name of a file that can be found. The `mode='happy'` is invalid because its not a supported choice ('`mfs`', '`channel`', '`velocity`', or '`frequency`').

1.3.5.5 The `saveinputs` Command

The `saveinputs` command will save the current values of a given task parameters to a Python (plain ascii) file. It can take up to two arguments, e.g.

```
saveinputs(taskname, outfile)
```

The first is the usual `taskname` parameter. The second is the name for the output Python file. If there is no second argument, for example,

```
saveinputs('plotxy')
```

a file with name `<taskname>.saved` (in this case '`plotxy.saved`') will be created or overwritten if extant. If invoked with no arguments, e.g.

```
saveinputs
```

it will use the current values of the `taskname` variable (as set using `inp <taskname>` or `default <taskname>`). You can also use the `taskname` global parameter explicitly,

```

xterm <2>
CASA <29>: tget clean
-----> tget(clean)
Restored parameters from file clean.last

CASA <30>: inp
-----> inp()
# clean :: Calculates a deconvolved image with a selected clean algorithm

vis           = 'ngc5921.usescase.ms.contsub'          # Name of input visibility file
imagerename   = 'ngc5921.usescase.clean'             # Pre-name of output images
mode         = 'channel'                            # Type of selection (mfs, channel, velocity, frequency)
    nchan       = 46                                # Number of channels to select
    start        = 5                                 # Start channel
    step         = 1                                 # Increment between channels/velocity
    width        = 1                                 # Channel width (value > 1 indicates channel averaging)

alg          = 'clark'                             # Algorithm to use (hogbom, clark, csclean, multiscale)
    niter        = 6000                             # Number of iterations
    gain         = 0.1                               # Loop gain for cleaning
    threshold    = 8.0                               # Flux level to stop cleaning (mJy)
    mask         = ''                                # Name of mask image used in cleaning
cleanbox     = []                                # clean box regions or file name or 'interactive'
    imsize       = [256, 256]                         # Image size in pixels [nx,ny]; symmetric for single value
    cell         = [15.0, 15.0]                       # Cell size in arcseconds [x,y]
    stokes      = 'I'                               # Stokes parameter to image (I,IV,IQU,IQUV)
    field        = '0'                               # Field name
    phasecenter = ''                                # Field Identifier or direction of the image phase center
    spw         = ''                                # spectral window/channels: '>all'
weighting    = 'briggs'                           # Weighting to apply to visibilities
    rmode        = 'norm'                            # Robustness mode (for Briggs weighting)
    robust       = 0.5                             # Briggs robustness parameter
    noise        = '0.0Jy'                           # noise parameter for briggs weighting when rmode='abs'
    npixels     = 0                                 # number of pixels to determine uv-cell size 0=> field of view

uvfilter    = False                             # Apply additional filtering/uv tapering of the visibilities
timerange   = ''                                # range of time to select from data
restfreq    = ''                                # restfrequency to use in image
async        = False                             # if True run in the background, prompt is freed

CASA <31>: ■

```

Figure 1.2: The `clean` inputs after setting values away from their defaults (blue text). Note that some of the boldface ones have opened up new dependent sub-parameters (indented and green).

```
saveinputs(taskname, taskname+'_1.save')
```

For example, starting from default values

```
CASA <1>: default('listobs')
CASA <2>: vis='ngc5921.ms'
CASA <3>: saveinputs
CASA <4>: !more 'listobs.saved'
IPython system call: more 'listobs.saved'
taskname      = "listobs"
vis           = "ngc5921.ms"
verbose       = True
#listobs(vis="ngc5921.ms", verbose=False)
```

To read these back in, use the Python `execfile` command. For example,

```
CASA <5>: execfile('listobs.saved')
```

and we are back.

An example save to a custom named file:

```
CASA <6>: saveinputs('listobs','ngc5921_listobs.par')
```

You can also use the CASA `tget` command (see § 1.3.5.6 below) instead of the Python `execfile` to restore your inputs.

```

CASA <31>: alg='hogwarts'
CASA <32>: inp
-----> inp()
# clean :: Calculates a deconvolved image with a selected clean algorithm
vis           = 'ngc5921.usescase.ms.consub'          # Name of input visibility file
imagename     = 'ngc5921.usescase.clean'            # Pre-name of output images
mode          = 'channel'                           # Type of selection (mfs, channel, velocity, frequency)
nchan         = 46                                 # Number of channels to select
start         = 5                                  # Start channel
step          = 1                                  # Increment between channels/velocity
width         = 1                                  # Channel width (value > 1 indicates channel averaging)

alg           = 'hogwarts'                         # Algorithm to use (hogbom, clark, csclean, multiscale)
niter         = 6000                               # Number of iterations
gain          = 0.1                                # Loop gain for cleaning
threshold     = 8.0                                # Flux level to stop cleaning (mJy)
mask          = ''                                 # Name of mask image used in cleaning
cleanbox      = []                                # clean box regions or file name or 'interactive'
imsize        = [256, 256]                          # Image size in pixels [nx,ny]; symmetric for single value
cell          = [15.0, 15.0]                        # Cell size in arcseconds [x,y]
stokes        = 'I'                                # Stokes parameter to image (I,IV,IQU,IQUV)
field         = '0'                                # Field name
phasecenter   = ''                                # Field Identifier or direction of the image phase center
spw           = ''                                # spectral window/channels: '>all'
weighting     = 'briggs'                           # Weighting to apply to visibilities
rmode         = 'norm'                             # Robustness mode (for Briggs weighting)
robust        = 0.5                                # Briggs robustness parameter
noise         = '0.0Jy'                            # noise parameter for briggs weighting when rmode='abs'
npixels       = 0                                  # number of pixels to determine uv-cell size 0=> field of view

uvfilter      = False                             # Apply additional filtering/uv tapering of the visibilities
timerange    = ''                                # range of time to select from data
restfreq     = ''                                # restfrequency to use in image
async         = False                             # if True run in the background, prompt is freed

CASA <33>: 
```

Figure 1.3: The `clean` inputs where one parameter has been set to an invalid value. This is drawn in red to draw attention to the problem. This hapless user probably confused the '`'hogbom'` clean algorithm with Harry Potter.

1.3.5.6 The `tget` Command

The `tget` command will recover saved values of the inputs of tasks. This is a convenient alternative to using the Python `execfile` command (see above).

Typing `tget` without a taskname will recover the saved values of the inputs for the current task as given in the current value of the `taskname` parameter.

Adding a task name, e.g. `tget <taskname>` will recover values for the specified task. This is done by searching for 1) a `<taskname>.last` file (see § 1.3.5.7 below), then for 2) a `<taskname>.saved` file (see § 1.3.5.5 above), and then executing the Python in these files.

For example,

```

default('clean')      # set current task to clean and default
tget                  # read saved inputs from clean.last (or clean.saved)
inp                  # see these inputs!
tget mosaic          # now get from mosaic.last (or mosaic.saved)
inp                  # task is now mosaic, with recovered inputs

```

1.3.5.7 The `.last` file

Whenever you successfully execute a CASA task, a Python script file called `<taskname>.last` will be written (or over-written) into the current working directory. For example, if you ran the `listobs`

task as detailed above, then

```
CASA <14>: vis = 'ngc5921.ms'

CASA <15>: verbose = True

CASA <16>: listobs()

CASA <17>: !more 'listobs.last'
IPython system call: more listobs.last
taskname      = "listobs"
vis           = "ngc5921.ms"
verbose       = True
#listobs(vis="ngc5921.ms",verbose=False)
```

You can restore the parameter values from the save file using

```
CASA <18>: execfile('listobs.last')
```

or

```
CASA <19>: run listobs.last
```

Note that the `.last` file is generally not created until the task actually finished (successfully), so it is often best to manually create a save file beforehand using the `saveinputs` command if you are running a critical task that you strongly desire to have the inputs saved for.

1.3.6 Tools in CASA

The CASA *toolkit* is the foundation of the functionality in the package, and consists of a suite of functions that are callable from Python. The tools are used by the tasks, and can be used by advanced users to perform operations that are not available through the tasks.

It is beyond the scope of this Cookbook to describe the toolkit in detail. Occasionally, examples will be given that utilize the tools (e.g. § 6.11). In short, tools are always called as functions, with any parameters that are not to be defaulted given as arguments. For example:

```
ia.open('ngc5921.chan21.clean.cleanbox.mask')
ia.calcmask('ngc5921.chan21.clean.cleanbox.mask">0.5','mymask')
ia.summary()
ia.close()
```

uses the `image` tool (`ia`) to turn a clean mask image into an image mask. Tools never use the CASA global parameters.

To find what tools are available, use the `toolhelp` command:

```
CASA <1>: toolhelp()
```

Available tools:

```
at : Juan Pardo ATM library
cb : Calibration utilities
cp : Cal solution plotting utilities
fg : Flagging/Flag management utilities
ia : Image analysis utilities
im : Imaging utilities
me : Measures utilities
ms : MeasurementSet (MS) utilties
mp : MS plotting (data (amp/phase) versus other quantities)
tb : Table utilities (selection, extraction, etc)
tp : Table plotting utilities
qa : Quanta utilities
sm : Simulation utilities
vp : Voltage pattern/primary beam utilties
---
pl : pylab functions (e.g., pl.title, etc)
---
```

You can find much more information about the toolkit in the *CASA User Reference Manual*:

<http://casa.nrao.edu/docs/casaref/CasaRef.html>

1.4 Getting the most out of CASA

There are some other general things you should know about using CASA in order to make things go smoothly during your data reduction.

1.4.1 Your command line history

Your command line history is automatically maintained and stored as `ipython.log` in your local directory . This file can be edited and re-executed as appropriate using the `execfile '<filename>'` feature.

You can also use the “up-arrow” and “down-arrow” keys for command line recall in the `casapy` interface. If you start typing text, and then use “up-arrow”, you will navigate back through commands matching what you typed.

1.4.2 Logging your session

The output from CASA commands is sent to the file `casapy.log`, also in your local directory. Whenever you start up `casapy`, the previous `casapy.log` is renamed (based on the date and time) and a new log file is started.




Figure 1.4: The CASA Logger GUI window under Linux. Note that under MacOSX a stripped down logger will instead appear as a Console.

The output contained in `casapy.log` is also displayed in a separate window using the `casalogger`. Generally, the logger window will be brought up when `casapy` is started. If you do not want the logger GUI to appear, then start `casapy` using the `--nologger` option,

```
casapy --nologger
```

which will run CASA in the terminal window. See § 1.4.2.1 for more startup options.

BETA ALERT: Due to problems with Qt under MacOSX, we had to replace the GUI `qtcasalogger` with a special stripped down one that uses the Mac Console. This still has the important capabilities such as showing the messages and cut/paste. The following description is for the Linux version and thus should mostly be disregarded on OSX. On the Mac, you treat this as just another console window and use the usual mouse and hot-key actions to do what is needed.

The CASA logger window for Linux is shown in Figure 1.4. The main feature is the display area for the log text, which is divided into columns. The columns are:

- **Time** — the time that the message was generated. Note that this will be in local computer time (usually UT) for `casapy` generated messages, and may be different for user generated messages;
- **Priority** — the *Priority Level* (see below) of the message;
- **Origin** — where within CASA the message came from. This is in the format `Task::Tool::Method` (one or more of the fields may be missing depending upon the message);
- **Message** — the actual text.

The `casalogger` GUI has a range of features, which include:




Figure 1.5: Using the Search facility in the casalogger. Here we have specified the string 'plotted' and it has highlighted all instances in green.

- **Search** — search messages by entering text in the Search window and clicking the search icon. The search currently just matches the exact text you type anywhere in the message. See Figure 1.5 for an example.
- **Filter** — a filter to sort by message priority, time, task/tool of origin, and message contents. Enter text in the Filter window and click the filter icon to the right of the window. Use the pull-down at the left of the Filter window to choose what to filter. The matching is for the exact text currently (no regular expressions). See Figure 1.6 for an example.
- **View** — show and hide columns (Time, Priority, Origin, Message) by checking boxes under the **View** menu pull-down. You can also change the font here.
- **Insert Message** — insert additional comments as “notes” in the log. Enter the text into the “Insert Message” box at the bottom of the logger, and click on the Add (+) button, or choose to enter a longer message. The entered message will appear with a priority of “NOTE” with the Origin as your username. See Figure 1.7 for an example.
- **Copy** — left-click on a row, or click-drag a range of rows, or click at the start and shift click at the end to select. Use the Copy button or **Edit** menu Copy to put the selected rows into the clipboard. You can then (usually) paste this where you wish. **BETA ALERT:** this does not work routinely in the current version. You are best off going to the `casapy.log` file if you want to grab text.
- **Open** — **BETA ALERT:** there is an Open function in the **File** menu, and an Open button, but these are “grayed-out” in the beta. Sorry!

Other operations are also possible from the menu or buttons. Mouse “flyover” will reveal the operation of buttons, for example.




Figure 1.6: Using the `casalogger` Filter facility. The log output can be sorted by Priority, Time, Origin, and Message. In this example we are filtering by Origin using '`clean`', and it now shows all the log output from the `clean` task.

1.4.2.1 Starup options for the logger

One can specify logger options at the startup of `casapy` on the command line:

```
casapy <logger option>
```

These options are:

<code>--log2term</code>	<code>==</code> logging message go to terminal
<code>--nologfile</code>	<code>==</code> no <code>casapy.log</code> logfile is produced
<code>--logfile <filename></code>	<code>==</code> use specified name for logfile instead of <code>casapy.log</code>
<code>--nologger</code>	<code>==</code> do not bring up GUI logger (see above)
<code>--nolog</code> (is deprecated use <code>--nologger</code>)	

For example, to not bring up a GUI but send the message to your terminal, do

```
casapy --nologger --log2term
```

while

```
casapy --logfile mynewlogfile.log
```

will start `casapy` with logger messages going to the file `mynewlogfile.log`.




Figure 1.7: CASA Logger - Insert facility: The log output can be augmented by adding notes or comments during the reduction. The file should then be saved to disk to retain these changes.

1.4.2.2 Setting priority levels in the logger

Logger messages are assigned a *Priority Level* when generated within CASA. The current levels of Priority are:

1. **SEVERE** — errors;
2. **WARN** — warnings;
3. **INFO** — basic information every user should be aware of or has requested;
4. **INFO1** — information possibly helpful to the user;
5. **INFO2** — details the power user might want to see;
6. **INFO3** — even more details;
7. **INFO4** — lowest level of non-debugging information;
8. **DEBUGGING** — most “important” debugging messages;
9. **DEBUG1** — more details;
10. **DEBUG2** — lowest level of debugging messages.

The “debugging” levels are intended for the developers use.

There is a threshold for which these messages are written to the `casapy.log` file and are thus visible in the logger. By default, only messages at level **INFO** and above are logged. The user can change the threshold using the `casalog.filter` method. This takes a single string argument of the `level` for the threshold. The `level` sets the lowest priority that will be generated, and all messages of this level or higher will go into the `casapy.log` file.

Inside the Toolkit:

The `casalog` tool can be used to control the logging. In particular, the `casalog.filter` method sets the priority threshold. This tool can also be used to change the output log file, and to post messages into the logger.

Some examples:

```
casalog.filter('INFO')                      # the default
casalog.filter('INFO2')                     # should satisfy even advanced users
casalog.filter('INFO4')                     # all INFOx messages
casalog.filter('DEBUG2')                    # all messages including debugging
```

WARNING: Setting the threshold to **DEBUG2** will put lots of messages in the log!

BETA ALERT: We are transitioning to the new Priority Level system, and not all tasks and tools obey the guidelines uniformly. This will be improved as we progress through the Beta patches. Also, the `casalog` tool is the only way to set the threshold currently.




Figure 1.8: Different message priority levels as seen in the `casalogger` window. These can also be Filtered upon.

1.4.3 Where are my data in CASA?

Interferometric data are filled into a so-called Measurement Set (or MS). In its logical structure, the MS looks like a generalized description of data from any interferometric or single dish telescope. Physically, the MS consists of several tables in a directory on disk.

Tables in CASA are actually directories containing files that are the sub-tables. For example, when you create a MS called `AM675.ms`, then the name of the directory where all the tables are stored will be called `AM675.ms/`. See Chapter 2 for more information on Measurement Set and Data Handling in CASA.

The data that you originally get from a telescope can be put in any directory that is convenient to you. Once you "fill" the data into a measurement set that can be accessed by CASA, it is generally best to keep that MS in the same directory where you started CASA so you can get access to it easily (rather than constantly having to specify a full path name).

When you generate calibration solutions or images (again these are in table format), these will also be written to disk. It is a good idea to keep them in the directory in which you started CASA. Note that when you delete a measurement set, calibration table, or image, you must delete the top level directory, and all underlying directories and files, using the file delete method of the operating system you started CASA from. For example, when running CASA on a Linux system, in order to delete the measurement set named `AM675.ms` type:

```
CASA <5>: !rm -r AM675.ms
```

from within CASA. The `!` tells CASA that a system command follows (see § 1.2.7.5), and the `-r` makes sure that all subdirectories are deleted recursively.

It is convenient to prefix all MS, calibration tables, and output files produced in a run with a common string. For example, one might prefix all files from VLA project AM675 with `AM675`, e.g. `AM675.ms`, `AM675.cal`, `AM675.clean`. Then,

```
CASA <6>: !rm -r AM675*
```

will clean up all of these.

1.4.4 What's in my data?

The actual data is in a large `MAIN` table that is organized in such a way that you can access different parts of the data easily. This table contains a number of "rows", which are effectively a single timestamp for a single spectral window (like an IF from the VLA) and a single baseline (for an interferometer).

There are a number of "columns" in the MS, the most important of which for our purposes is the `DATA` column — this contains the original visibility data from when the MS was created or filled. There are other helpful "scratch" columns which hold useful versions of the data or weights for further processing: the `CORRECTED_DATA` column, which is used to hold calibrated data; the `MODEL_DATA` column, which holds the Fourier inversion of a particular model image; and the `IMAGING_WEIGHT` column which can hold the weights to be used in imaging. The creation and use of the scratch columns is generally done behind the scenes, but you should be aware that they are there (and when they are used). We will occasionally refer to the rows and columns in the MS.

More on the contents of the MS can be found in § 2.1.

1.4.5 Data Selection in CASA

We have tried to make the CASA task interface as uniform as possible. If a given parameter appears in multiple tasks, it should, as far as is possible, mean the same thing and be used in the same way in each. There are groups of parameters that appear in a number of tasks to do the same thing, such as for data selection.

The parameters `field`, `spw`, and `selectdata` (which if `True` expands to a number of sub-parameters) are commonly used in tasks to select data on which to work. These common data selection parameters are described in § 2.5.

1.5 From Loading Data to Images

The subsections below provide a brief overview of the steps you will need to load data into CASA and obtain a final, calibrated image. Each subject is covered in more detail in Chapters 2 through 6.

An end-to-end workflow diagram for CASA data reduction for interferometry data is shown in Figure 1.9. This might help you chart your course through the package. In the following subsections, we will chart a rough course through this process, with the later chapters filling in the individual boxes.

Note that single-dish data reduction (for example with the ALMA single-dish system) follows a similar course. This is detailed in Chapter A.

1.5.1 Loading Data into CASA

The key data and image import tasks are:

- `importuvfits` — import visibility data in UVFITS format (§ 2.2.1);
- `importvla` — import data from VLA that is in *export* format (§ 2.2.2);
- `importasdm` — import data in ALMA ASDM format (§ 2.2.3);
- `importfits` — import a FITS image into a CASA *image* format table (§ 6.10).

These are used to bring in your interferometer data, to be stored as a CASA Measurement set (MS), and any previously made images or models (to be stored as CASA image tables).

The data import tasks will create a MS with a path and name specified by the `vis` parameter. See § 1.4.3 for more information on MS in CASA. The measurement set is the internal data format used by CASA, and conversion from any other native format is necessary for most of the data reduction tasks.

Once data is imported, there are other operations you can use to manipulate the datasets:




Figure 1.9: Flow chart of the data processing operations that a general user will carry out in an end-to-end CASA reduction session.

- `concat` — concatenate a second MS into a given MS (§ 2.4)

Data import, export, concatenation, and selection detailed in Chapter 2.

1.5.1.1 VLA: Filling data from VLA archive format

VLA data in “archive” format are read into CASA from disk using the `importvla` task (see § 2.2.2). This filler supports the new naming conventions of EVLA antennas when incorporated into the old VLA system.

Note that future data from the EVLA in ASDM format will use a different filler. This will be made available in a later release.

1.5.1.2 Filling data from UVFITS format

For UVFITS format, use the `importuvfits` task. A subset of popular flavors of UVFITS (in particular UVFITS as written by AIPS) is supported by the CASA filler. See § 2.2.1 for details.

1.5.1.3 Loading FITS images

For FITS format images, such as those to be used as calibration models, use the `importfits` task. Most, though not all, types of FITS images written by astronomical software packages can be read in.

See § 6.10 for more information.

1.5.1.4 Concatenation of multiple MS

Once you have loaded data into measurement sets on disk, you can use the `concat` task to combine them. Currently, `concat` will add a second MS to an existing MS (not producing a new one). This would be run multiple times if you had more than two sets to combine.

See § 2.4 for details.

1.5.2 Data Examination, Editing, and Flagging

The main data examination and flagging tasks are:

- `listobs` — summarize the contents of a MS (§ 2.3);
- `flagmanager` — save and manage versions of the flagging entries in the measurement set (§ 3.2);
- `flagautocorr` — non-interactive flagging of auto-correlations (§ 3.3);
- `plotxy` — interactive X-Y plotting and flagging of visibility data (§ 3.4);
- `flagdata` — non-interactive flagging (and unflagging) of specified data (§ 3.5);
- `viewer` — the CASA viewer can display (as a raster image) MS data, with some editing capabilities (§ 7).

These tasks allow you to list, plot, and/or flag data in a CASA MS.

There will eventually be tasks for “automatic” flagging to data based upon statistical criteria. Stay tuned.

Examination and editing of synthesis data is described in Chapter 3.

Visualization and editing of an MS using the `casaviewer` is described in Chapter 7.

1.5.2.1 Interactive X-Y Plotting and Flagging

The principal tool for making X-Y plots of visibility data is `plotxy` (see § 3.4). Amplitudes and phases (among other things) can be plotted against several x-axis options.

Interactive flagging (i.e., “see it – flag it”) is possible on the `plotxy` X-Y displays of the data (§ 3.4.5). Since flags are inserted into the measurement set, it is useful to backup (or make a copy) of the current flags before further flagging is done, using `flagmanager` (§ 3.2). Copies of the flag table can also be restored to the MS in this way.

1.5.2.2 Flag the Data Non-interactively

The `flagdata` task (§ 3.5) will flag the visibility data set based on the specified data selections. The `listobs` task (§ 2.3) may be run (e.g. with `verbose=True`) to provide some of the information needed to specify the flagging scope.

1.5.2.3 Viewing and Flagging the MS

The CASA `viewer` can be used to display the data in the MS as a (grayscale or color) raster image. The MS can also be edited. Use of the `viewer` on an MS is detailed in § 7.4.

1.5.3 Calibration

The major calibration tasks are:

- `setjy` — Computes the model visibilities for a specified source given a flux density or model image, knows about standard calibrator sources (§ 4.3.4);
- `bandpass` — Solves for frequency-dependent (bandpass) complex gains (§ 4.4.2);
- `gaincal` — Solves for time-dependent (frequency-independent) complex gains (§ 4.4.3);
- `fluxscale` — Bootstraps the flux density scale from standard calibrators (§ 4.4.4);
- `polcal` — polarization calibration (§ 4.4.5);
- `accum` — Accumulates incremental calibration solutions into a cumulative calibration table (§ 4.5.4);
- `smoothcal` — Smooths calibration solutions derived from one or more sources (§ 4.5.3);
- `applycal` — Applies calculated calibration solutions (§ 4.6.1);
- `clearcal` — Re-initializes calibrated visibility data in a given measurement set (§ 4.6.3);
- `listcal` — Lists calibration solutions (§ 4.5.2);

- `plotcal` — Plots (and optionally flags) calibration solutions (§ 4.5.1);
- `uvcontsub` — carry out uv-plane continuum subtraction for spectral-line data (§ 4.7.4);
- `split` — write out a new (calibrated) MS for specified sources (§ 4.7.1).

During the course of calibration, the user will specify a set of calibrations to pre-apply before solving for a particular type of effect, for example gain or bandpass or polarization. The solutions are stored in a calibration table (subdirectory) which is specified by the user, *not* by the task: care must be taken in naming the table for future use. The user then has the option, as the calibration process proceeds, to accumulate the current state of calibration in a new cumulative table. Finally, the calibration can be applied to the dataset.

Synthesis data calibration is described in detail in Chapter 4.

1.5.3.1 Prior Calibration

The `setjy` task places the Fourier transform of a standard calibration source model in the `MODEL_DATA` column of the measurement set. This can then be used in later calibration tasks. Currently, `setjy` knows the flux density as a function of frequency for several standard VLA flux calibrators, and the value of the flux density can be manually inserted for any other source. If the source is not well-modeled as a point source, then a model image of that source structure can be used (with the total flux density scaled by the values given or calculated above for the flux density). Models are provided for the standard VLA calibrators.

Antenna gain-elevation curves (e.g. for the VLA antennas) and atmospheric optical depth corrections (applied as an elevation-dependent function) may be pre-applied before solving for the bandpass and gains. This is currently done by setting the `gaincurve` and `opacity` parameters in the various calibration solving tasks.

See § 4.3 for more details.

1.5.3.2 Bandpass Calibration

The `bandpass` task calculates a bandpass calibration solution: that is, it solves for gain variations in frequency as well as in time. Since the bandpass (relative gain as a function of frequency) generally varies much more slowly than the changes in overall (mean) gain solved for by `gaintcal`, one generally uses a long time scale when solving for the bandpass. The default 'B' solution mode solves for the gains in frequency slots consisting of channels or averages of channels.

A polynomial fit for the solution (solution type 'BPOLY') may be carried out instead of the default frequency-slot based 'B' solutions. This single solution will span (combine) multiple spectral windows.

Bandpass calibration is discussed in detail in § 4.4.2.

If the gains of the system are changing over the time that the bandpass calibrator is observed, then you may need to do an initial gain calibration (see next step).

1.5.3.3 Gain Calibration

The `gaincal` task determines solutions for the time-based complex antenna gains, for each spectral window, from the specified calibration sources. A solution interval may be specified. The default '`G`' solution mode solved for gains in specified time solution intervals.

A spline fit for the solution (solution type '`GSPLINE`') may be carried out instead of the default time-slot based '`G`' solutions. This single solution will span (combine) multiple spectral windows.

See § 4.4.3 for more on gain calibration.

1.5.3.4 Polarization Calibration

The `polcal` task will solve for any unknown polarization leakage and cross-hand phase terms ('`D`' and '`X`' solutions). The '`D`' leakage solutions will work on sources with no polarization, sources with known (and supplied) polarization, and sources with unknown polarization tracked through a range in parallactic angle on the sky.

The solution for the unknown cross-hand polarization phase difference '`X`' term requires a polarized source with known linear polarization (`Q,U`).

See § 4.4.5 for more on polarization calibration.

1.5.3.5 Examining Calibration Solutions

The `plotcal` task (§ 4.5.1) will plot the solutions in a calibration table. The `xaxis` choices include time (for `gaincal` solutions) and channel (e.g. for `bandpass` calibration). The `plotcal` interface and plotting surface is similar to that in `plotxy`. Eventually, `plotcal` will allow you to flag and unflag calibration solutions in the same way that data can be edited in `plotxy`.

The `listcal` task (§ 4.5.2) will print out the calibration solutions in a specified table.

1.5.3.6 Bootstrapping Flux Calibration

The `fluxscale` task bootstraps the flux density scale from “primary” standard calibrators to the “secondary” calibration sources. Note that the flux density scale must have been previously established on the “primary” calibrator(s), typically using `setjy`, and of course a calibration table containing valid solutions for all calibrators must be available.

See § 4.4.4 for more.

1.5.3.7 Calibration Accumulation

The `accum` task applies an incremental solution, of a given type, from a table to a previous calibration table (of the same type), and writes out a cumulative solution table. Different interpolation schemes may be selected.

A description of this process is given in § 4.5.4.

1.5.3.8 Correcting the Data

The final step in the calibration process, `applycal` may be used to apply several calibration tables (e.g., from `gaincal` or `bandpass`). The corrections are applied to the `DATA` column of the visibility, writing the `CORRECTED_DATA` column which can then be plotted (e.g. in `plotxy`), `split` out as the `DATA` column of a new MS, or imaged (e.g. using `clean`). Any existing corrected data are overwritten.

See § 4.6.1 for details.

1.5.3.9 Splitting the Data

After a suitable calibration is achieved, it may be desirable to create one or more new measurement sets containing the data for selected sources. This can be done using the `split` task (§ 4.7.1).

Further imaging and calibration (e.g. self-calibration) can be carried out on these split Measurement Sets.

1.5.4 Synthesis Imaging

The key synthesis imaging tasks are:

- `clean` — Calculates a deconvolved image based on the visibility data, using one of several `clean` algorithms (§ 5.3);
- `feather` — Combines a single dish and synthesis image in the Fourier plane (§ 5.5).

Most of these tasks are used to take calibrated interferometer data, with the possible addition of a single-dish image, and reconstruct a model image of the sky.

There are several other utility imaging tasks of interest:

- `makemask` — Makes a mask image from a `cleanbox`, a file or list specifying sets of pairs of box corners (§ 5.6);
- `ft` — Fourier transforms the specified model (or component list) and inserts this into the `MODEL_DATA` column of the MS (§ 5.7);
- `deconvolve` — Deconvolve an input image from a provided PSF, using one of several image-plane deconvolution algorithms (§ 5.8).

These are not discussed in this walk-through, see the indicated sections for details.

See Chapter 5 for more on synthesis imaging.

1.5.4.1 Cleaning a single-field image or a mosaic

The CLEAN algorithm is the most popular and widely-studied method for reconstructing a model image based on interferometer data. It iteratively removes at each step a fraction of the flux in the brightest pixel in a defined region of the current “dirty” image, and places this in the model image. The `clean` task implements the CLEAN algorithm for single-field data. The user can choose from a number of options for the particular flavor of CLEAN to use.

Often, the first step in imaging is to make a simple gridded Fourier inversion of the calibrated data to make a “dirty” image. This can then be examined to look for the presence of noticeable emission above the noise, and to assess the quality of the calibration by searching for artifacts in the image. This is done using `clean` with `niter=0`.

The `clean` task can jointly deconvolve mosaics as well as single fields.

See § 5.3 for an in-depth discussion of the `clean` task.

1.5.4.2 Feathering in a Single-Dish image

If you have a single-dish image of the large-scale emission in the field, this can be “feathered” in to the image obtained from the interferometer data. This is carried out using the `feather` tasks as the weighted sum in the uv-plane of the gridded transforms of these two images. While not as accurate as a true joint reconstruction of an image from the synthesis and single-dish data together, it is sufficient for most purposes.

See § 5.5 for details on the use of the `feather` task.

1.5.5 Self Calibration

Once a calibrated dataset is obtained, and a first deconvolved model image is computed, a “self-calibration” loop can be performed. Effectively, the model (not restored) image is passed back to another calibration process (on the target data). This refines the calibration of the target source, which up to this point has had (usually) only external calibration applied. This process follows the regular calibration procedure outlined above.

Any number of self-calibration loops can be performed. As long as the images are improving, it is usually prudent to continue the self-calibration iterations.

This process is described in § 5.9.

1.5.6 Data and Image Analysis

The key data and image analysis tasks are:

- `imhead` — summarize and manipulate the “header” information in a CASA image (§ 6.2);

- `imcontsub` — perform continuum subtraction on a spectral-line image cube (§ 6.3);
- `immath` — perform mathematical operations on or between images (§ 6.5);
- `immoments` — compute the moments of an image cube (§ 6.6);
- `imstat` — calculate statistics on an image or part of an image (§ 6.7);
- `imregrid` — regrid an image onto the coordinate system of another image (§ 6.9);
- `viewer` — there are useful region statistics and image cube plotting capabilities in the viewer (§ 7).

1.5.6.1 What’s in an image?

The `imhead` task will print out a summary of image “header” keywords and values. This task can also be used to retrieve and change the header values.

See § 6.2 for more.

1.5.6.2 Image statistics

The `imstat` task will print image statistics. There are options to restrict this to a box region, and to specified channels and Stokes of the cube. This task will return the statistics in a Python dictionary return variable.

See § 6.7 for more.

1.5.6.3 Moments of an Image Cube

The `immoments` task will compute a “moments” image of an input image cube. A number of options are available, from the traditional true moments (zero, first, second) and variations thereof, to other images such as median, minimum, or maximum along the moment axis.

See § 6.6 for details.

1.5.6.4 Image math

The `immath` task will allow you to form a new image by mathematical combinations of other images (or parts of images). This is a powerful, but tricky, task to use.

See § 6.5 for more.

1.5.6.5 Regridding an Image

It is occasionally necessary to regrid an image onto a new coordinate system. The `imregrid` task can be used to regrid an input image onto the coordinate system of an existing template image, creating a new output image.

See § 6.9 for a description of this task.

1.5.6.6 Displaying Images

To display an image use the `viewer` task. The viewer will display images in raster, contour, or vector form. Blinking and movies are available for spectral-line image cubes. To start the viewer, type:

```
viewer
```

Executing the `viewer` task will bring up two windows: a viewer screen showing the data or image, and a file catalog list. Click on an image or ms from the file catalog list, choose the proper display, and the image should pop up on the screen. Clicking on the wrench tool (second from left on upper left) will obtain the data display options. Most functions are self-documenting.

The viewer can be run outside of casapy by typing `casaviewer`.

See § 7 for more on viewing images.

1.5.7 Getting data and images out of CASA

The key data and image export tasks are:

- `exportuvfits` — export a CASA MS in UVFITS format (§ 2.2.1);
- `exportfits` — export a CASA image table as FITS (§ 6.10).

These tasks can be used to export a CASA MS or image to UVFITS or FITS respectively. See the individual sections referred to above for more on each.

Chapter 2

Visibility Data Import, Export, and Selection

To use CASA to process your data, you first will need to get it into a form that is understood by the package. These are “measurement sets” for synthesis (and single dish) data, and “image tables” for images.

There are a number of tasks used to fill telescope-specific data, to import/export standard formats, to list data contents, and to concatenate multiple datasets. These are:

- `importuvfits` — import visibility data in UVFITS format (§ 2.2.1.1)
- `importvla` — import data from VLA that is in *export* format (§ 2.2.2)
- `importasdm` — import data in ALMA ASDM format (§ 2.2.3)
- `exportuvfits` — export a CASA MS in UVFITS format (§ 2.2.1.2)
- `listobs` — summarize the contents of a MS (§ 2.3)
- `concat` — concatenate two or more MS into a new MS (§ 2.4)

In CASA, there is a standard syntax for selection of data that is employed by multiple tasks. This is described in § 2.5.

There are also tasks for the import and export of image data using FITS:

- `importfits` — import a FITS image into a CASA *image* format table (§ 6.10)
- `exportfits` — export a CASA image table as FITS (§ 6.10)

2.1 CASA Measurement Sets

Data is handled in CASA via the `table` system. In particular, visibility data are stored in a CASA table known as a Measurement Set (MS). Details of the physical and logical MS structure are given below, but for our purposes here an MS is just a construct that contains the data. An MS can also store single dish data (essentially a set of auto-correlations of a 1-element interferometer), though there are also data formats more suitable for single-dish spectra (see § A).

Note that images are handled through special `image` tables, although standard FITS I/O is also supported. Images and `image` data are described in a separate chapter.

Unless your data was previously processed by CASA or software based upon its predecessor `aips++`, you will need to import it into CASA as an MS. Supported formats include some “standard” flavors of UVFITS, the VLA “Export” archive format, and most recently, the ALMA Science Data Model (ASDM) format. These are described below in § 2.2.

Inside the Toolkit:

Measurement sets are handled in the `ms` tool. Import and export methods include `ms.fromfits` and `ms.tofits`.

Once in Measurement Set form, your data can be accessed through various tools and tasks with a common interface. The most important of these is the *data selection interface* (§ 2.5) which allows you to specify the subset of the data on which the tasks and tools will operate.

2.1.1 Under the Hood: Structure of the Measurement Set

It is not necessary that a casual CASA user know the specific details on how the data in the MS is stored and the contents of all the sub-tables. However, we will occasionally refer to specific “columns” of the MS when describing the actions of various tasks, and thus we provide the following synopsis to familiarize the user with the necessary nomenclature. You may skip ahead to subsequent sections if you like!

Inside the Toolkit:

Generic CASA tables are handled in the `tb` tool. You have direct access to keywords, rows and columns of the tables with the methods of this tool.

All CASA data files, including Measurement Sets, are written into the current working directory by default, with each CASA table represented as a separate sub-directory. MS names therefore need only comply with UNIX file or directory naming conventions, and can be referred to from within CASA directly, or via full path names.

An MS consists of a `MAIN` table containing the visibility data. and associated sub-tables containing auxiliary or secondary information. The tables are logical constructs, with contents located in the physical `table.*` files on disk. The `MAIN` table consists of the `table.*` files in the main directory of the ms-file itself, and the other tables are in the respective subdirectories. The various MS tables and sub-tables can be seen by listing the contents of the MS directory itself (e.g. using Unix `ls`), or via the `browsetable` task (§ 3.6).

See Fig 2.1 for an example of the contents of a MS directory. Or, from the casapy prompt,

```
CASA <1>: ls ngc5921.ms
IPython system call: ls -F ngc5921.ms
ANTENNA          POLARIZATION    table.f1      table.f3_TSM1  table.f8
DATA_DESCRIPTION PROCESSOR       table.f10     table.f4      table.f8_TSM1
FEED             SORTED_TABLE   table.f10_TSM1 table.f5      table.f9
FIELD            SOURCE         table.f11     table.f5_TSM1  table.f9_TSM1
FLAG_CMD          SPECTRAL_WINDOW table.f11_TSM1 table.f6      table.info
HISTORY           STATE          table.f2      table.f6_TSM0  table.lock
OBSERVATION       table.dat     table.f2_TSM1  table.f7
POINTING          table.f0       table.f3      table.f7_TSM1
```

Note that the MAIN table information is contained in the `table.*` files in this directory. Each of the sub-table sub-directories contain their own `table.dat` and other files, e.g.

```
CASA <2>: ls ngc5921.ms/SOURCE
IPython system call: ls -F ngc5921.ms/SOURCE
table.dat  table.f0  table.f0i  table.info  table.lock
```




Figure 2.1: The contents of a Measurement Set. These tables compose a Measurement Set named `ngc5921.demo.ms` on disk. This display is obtained by using the **File:Open** menu in `browsetable` and left double-clicking on the `ngc5921.demo.ms` directory.

Each “row” in a table contains entries for a number of specified “columns”. For example, in the **MAIN** table of the MS, the original visibility data is contained in the **DATA** column — each “cell” contains a matrix of observed complex visibilities for that row at a single time stamp, for a single baseline in a single spectral window. The shape of the data matrix is given by the number of channels and the number of correlations (voltage-products) formed by the correlator for an array.

Table 2.1 lists the non-data columns of the **MAIN** table that are most important during a typical data reduction session. Table 2.2 lists the key data columns of the **MAIN** table of an interferometer MS. The MS produced by fillers for specific instruments may insert special columns, such as **ALMA_PHASE_CORR**, **ALMA_NO_PHAS_CORR** and **ALMA_PHAS_CORR_FLAG_ROW** for ALMA data filled using the **importasdm** filler (§ 2.2.3). These columns are visible in **browsetable** and are accessible from the toolkit in the **ms** tool (e.g. the **ms.getdata** method) and from the **tb** “table” tool (e.g. using **tb.getcol**).

Note that when you examine table entries for IDs such as **FIELD_ID** or **DATA_DESC_ID**, you will see 0-based numbers.

Table 2.1: Common columns in the **MAIN** table of the MS.

Parameter	Contents
ANTENNA1	First antenna in baseline
ANTENNA2	Second antenna in baseline
FIELD_ID	Field (source no.) identification
DATA_DESC_ID	Spectral window number, polarization identifier pair (IF no.)
ARRAY_ID	Subarray number
OBSERVATION_ID	Observation identification
POLARIZATION_ID	Polarization identification
SCAN_NUMBER	Scan number
TIME	Integration midpoint time
UVW	UVW coordinates

The MS can contain a number of “scratch” columns, which are used to hold useful versions of other columns such as the data or weights for further processing. The most common scratch columns are:

- **CORRECTED_DATA** — used to hold calibrated data for imaging or display;
- **MODEL_DATA** — holds the Fourier inversion of a particular model image for calibration or imaging;
- **IMAGING_WEIGHT** — holds the gridding weights to be used in imaging.

The creation and use of the scratch columns is generally done behind the scenes, but you should be aware that they are there (and when they are used).

Table 2.2: Commonly accessed MAIN Table data-related columns. Note that the columns `ALMA_PHASE_CORR`, `ALMA_NO_PHAS_CORR` and `ALMA_PHAS_CORR_FLAG_ROW` are specific to ALMA data filled using the `importasdm` filler.

Column	Format	Contents
DATA	Complex(N_c, N_f)	complex visibility data matrix (= <code>ALMA_PHASE_CORR</code> by default)
FLAG	Bool(N_c, N_f)	cumulative data flags
WEIGHT	Float(N_c)	weight for a row
WEIGHT_SPECTRUM	Float(N_c, N_f)	individual weights for a data matrix
ALMA_PHASE_CORR	Complex(N_c, N_f)	on-line phase corrected data (<i>Not in VLA data</i>)
ALMA_NO_PHAS_CORR	Bool(N_c, N_f)	data that has not been phase corrected (<i>Not in VLA data</i>)
ALMA_PHAS_CORR_FLAG_ROW	Bool(N_c, N_f)	flag to use phase-corrected data or not (<i>not in VLA data</i>)
MODEL_DATA	Complex(N_c, N_f)	Scratch: created by calibrator or imager tools
CORRECTED_DATA	Complex(N_c, N_f)	Scratch: created by calibrator or imager tools
IMAGING_WEIGHT	Float(N_c)	Scratch: created by calibrator or imager tools

The most recent specification for the MS is **Aips++ MeasurementSet definition version 2.0** (<http://casa.nrao.edu/Memos/229.html>).

2.2 Data Import and Export

There are a number of tasks available to bring data in various forms into CASA as a Measurement Set:

- UVFITS format can be imported into and exported from CASA (`importuvfits` and `exportuvfits`)
- VLA Archive format data can be imported into CASA (`importvla`)
- ALMA and EVLA Science Data Model format data can be imported into CASA (`importasdm`)

2.2.1 UVFITS Import and Export

The UVFITS format is not exactly a standard, but is a popular archive and transport format nonetheless. CASA supports UVFITS files written by the AIPS FITTP task, and others.

UVFITS is supported for both import and export.

2.2.1.1 Import using importuvfits

To import UVFITS format data into CASA, use the `importuvfits` task:

```
CASA <1>: inp(importuvfits)
fitsfile      =      '' # Name of input UVFITS file
vis          =      '' # Name of output visibility file (MS)
async        =    False # if True run in the background, prompt is freed
```

This is straightforward, since all it does is read in a UVFITS file and convert it as best it can into a MS.

For example:

```
importuvfits(fitsfile='NGC5921.fits',vis='ngc5921.ms')
```

BETA ALERT: We cannot currently fill CARMA data exported via Miriad UVFITS.

2.2.1.2 Export using exportuvfits

The `exportuvfits` task will take a MS and write it out in UVFITS format. The defaults are:

```
# exportuvfits :: Convert a CASA visibility data set (MS) to a UVFITS file

vis      =      '' # Name of input visibility file
fitsfile =      '' # Name of output UVFITS file)
datacolumn = 'corrected' # which data to write (data, corrected, model)
field     =      '' # Field name list
spw       =      '' # Spectral window and channel selection
antenna   =      '' # antenna list to select
time      =      '' # time range selection
nchan     =      -1 # Number of channels to select
start     =      0 # Start channel
width     =      1 # Channel averaging width (value>1 indicates averaging)
writesyscal =    False # Write GC and TY tables
multisource =   True # Write in multi-source format
combinespw =   True # Combine spectral windows (True for AIPS)
writestation =  True # Write station name instead of antenna name
async     =    False # if True run in the background, prompt is freed
```

For example:

```
exportuvfits(vis='ngc5921.split.ms',
            fitsfile='NGC5921.split.fits',
            multisource=False)
```

The MS selection parameters `field`, `spw`, `antenna`, and `timerange` follow the standard selection syntax described in § 2.5.

BETA ALERT: The `nchan`, `start`, and `width` parameters will be superseded by channel selection in `spw`. Currently, there is a `time` parameter rather than `timerange`.

The `datacolumn` parameter chooses which data-containing column of the MS (see § 2.1.1) is to be written out to the UV FITS file. Choices are: '`data`', '`corrected`', and '`model`'.

There are a number of special parameters that control what is written out. These are mostly here for compatibility with AIPS.

The `writesyscal` parameter toggles whether GC and TY extension tables are written. These are important for VLBA data, and for EVLA data. **BETA ALERT:** Not yet available.

The `multisource` parameter determines whether the UV FITS file is a multi-source file or a single-source file, if you have a *single-source* MS or choose only a single source. Note: the difference between a single-source and multi-source UVFITS file here is whether it has a source (SU) table and the source ID in the random parameters. If you select more than one source in `fields`, then the `multisource` parameter will be overridden to be `True` regardless.

The `combinespw` parameter allows combination of all spectral windows at one time. If `True`, then all spectral windows must have the same shape. For AIPS to read an exported file, then set `combinespw=True`.

The `writestation` parameter toggles the writing of the station name instead of antenna name.

2.2.2 VLA: Filling data from archive format (`importvla`)

VLA data in archive format (i.e., as downloaded from the VLA data archive) are read into CASA from disk using the `importvla` task. The inputs are:

```
# importvla :: import VLA archive file(s) to a measurement set:

archivefiles =      ''    # Name of input VLA archive file(s)
vis          =      ''    # Name of output visibility file
bandname     =      ''    # VLA frequency band name: ''=>obtain all bands in archive files
frequencytol = 150000.0 # Frequency shift to define a unique spectral window (Hz)
project      =      ''    # Project name: '' => all projects in file
starttime   =      ''    # start time to search for data
stoptime    =      ''    # end time to search for data
applytsys   =      True  # apply nominal sensitivity scaling to data & weights
autocorr     =     False # import autocorrelations to ms, if set to True
antnamescheme =  'new'  # 'old' or 'new'; 'VA04' or '4' for ant 4
async        =     False
```

The main parameters are `archivefiles` to specify the input VLA Archive format file names, and `vis` to specify the output MS name.

BETA ALERT: The scaling of VLA data both before and after the June 2007 Modcomp-turnoff is fully supported, based on the value of `applytsys`.

The NRAO Archive is located at:

- <https://archive.nrao.edu>

Note that `archivefiles` takes a string or list of strings, as there are often multiple files for a project in the archive.

For example:

```
archivefiles = ['AP314_A950519.xp1', 'AP314_A950519.xp2']
vis = 'NGC7538.ms'
```

The `importvla` task allows selection on the frequency band. Suppose that you have 1.3 cm line observations in K-band and you have copied the archive data files `AP314_A95019.xp*` to your working directory and started `casapy`. Then,

```
default('importvla')
archivefiles = ['AP314_A950519.xp1', 'AP314_A950519.xp2', 'AP314_A950519.xp3']
vis = 'ngc7538.ms'
bandname = 'K'
frequencytol = 10e6
importvla()
```

If the data is located in a different directory on disk, then use the full path name to specify each archive file, e.g.:

```
archivefiles=['/home/rohir2/jmcmulli/ALMATST1/Data/N7538/AP314_A950519.xp1', \
'/home/rohir2/jmcmulli/ALMATST1/Data/N7538/AP314_A950519.xp2', \
'/home/rohir2/jmcmulli/ALMATST1/Data/N7538/AP314_A950519.xp3']
```

Important Note: `importvla` will import the on-line flags (from the VLA system) along with the data. These will be put in the `MAIN` table and thus available to subsequent tasks and tools. If you wish to revert to unflagged data, use `flagmanager` (§ 3.2) to save the flags (if you wish), and then use `flagdata` (§ 3.5) with `mode='manualflag'` and `unflag=True` to toggle off the flags.

The other parameters are:

2.2.2.1 Parameter `applytsys`

The `applytsys` parameter controls whether the nominal sensitivity scaling (based on the measured TSYS, with the weights scaled accordingly using the integration time) is applied to the visibility amplitudes or not. If `True`, then it will be scaled so as to be the same as AIPS `FILLM` (ie. approximately in deciJanskys). Note that post-Modcomp data is in raw correlation coefficient and will be scaled using the TSYS values, while Modcomp-era data had this applied online. In all cases

`importvla` will do the correct thing to data and weights based on an internal flag in the VLA Archive file, either scaling it or unscaling based on your choice for `applytys`.

If `applytys=True` and you see strange behavior in data amplitudes, it may be due to erroneous TSYS values from the online system. You might want to then fill with `applytys=False` and look at the correlation coefficients to see if the behavior is as expected.

2.2.2.2 Parameter bandname

The `bandname` indicates the VLA Frequency band(s) to load, using the traditional bandname codes. These are:

- '4' = 48-96 MHz
- 'P' = 298-345 MHz
- 'L' = 1.15-1.75 GHz
- 'C' = 4.2-5.1 GHz
- 'X' = 6.8-9.6 GHz
- 'U' = 13.5-16.3 GHz
- 'K' = 20.8-25.8 GHz
- 'Q' = 38-51 GHz
- '' = all bands (default)

Note that as the transition from the VLA to EVLA progresses, the actual frequency ranges covered by the bands will expand, and additional bands will be added (namely 'S' from 1-2 GHz and 'A' from 26.4-40 GHz).

2.2.2.3 Parameter frequencytol

The `frequencytol` parameter specifies the frequency separation tolerated when assigning data to spectral windows. The default is `frequencytol=150000` (Hz). For Doppler tracked data, where the sky frequency changes with time, a `frequencytol < 10000` Hz may produce too many unnecessary spectral windows.

2.2.2.4 Parameter project

You can specify a specific `project` name to import from archive files. The default '' will import data from all projects in file(s) `archivefiles`.

For example for VLA Project AL519:

```
project = 'AL519'      # this will work
project = 'al519'       # this will also work
```

while `project='AL0519'` will NOT work (even though that is what queries to the VLA Archive will print it as - sorry!).

2.2.2.5 Parameters starttime and stoptime

You can specify start and stop times for the data, e.g.:

```
starttime = '1970/1/31/00:00:00'
stoptime = '2199/1/31/23:59:59'
```

Note that the blank defaults will load all data fitting other criteria.

2.2.2.6 Parameter autocorr

Note that autocorrelations are filled into the data set if `autocorr=True`. Generally for the VLA, autocorrelation data is not useful, and furthermore the imaging routine will try to image the autocorrelation data (it assumes it is single dish data) which will swamp any real signal. Thus, if you do fill the autocorrelations, you will have to flag them before imaging.

2.2.2.7 Parameter antnamescheme

The `antnamescheme` parameter controls whether `importvla` will try to use a naming scheme where EVLA antennas are prefixed with `EA` (e.g. '`EA16`') and old VLA antennas have names prefixed with `VA` (e.g. '`VA11`'). Our method to detect whether an antenna is EVLA is not yet perfected, and thus unless you require this feature, simply use `antnamescheme='old'`.

2.2.3 ALMA: Filling ALMA Science Data Model (ASDM) observations

The `importasdm` task will fill an ASDM into a CASA visibility data set (MS).

BETA ALERT: Note that ASDM data are not generally available at this time, except for commissioning at the ALMA Test Facility (ATF) and the site. Thus, this filler is in a development stage. Also, currently there are no options for filling selected data (you get the whole data set).

Current inputs are:

```
# importasdm :: Convert an ALMA Science Data Model observation into a CASA visibility file
asdm          = ''      # Name of input asdm directory (on disk)
corr_mode     = 'all'   # Correlation mode on input (e.g. 'ao' 'co' 'ac')
srt           = 'all'   # Spectral resolution type on input (e.g. 'fr' 'ca' 'bw')
time_sampling = 'all'   # Time sampling (INTEGRATION 'i' and/or SUBINTEGRATION 'si')
```

```
ocorr_mode      =  'co'   #  Output correlation mode AUTO_ONLY (ao), CROSS_ONLY (co), or CROSS_AND_AUTO (c)
async          =  False   #  Run task asynchronously
```

For example:

```
CASA <1>: importasdm('/home/basho3/jmcmulli/ASDM/ExecBlock3')

Parameter: asdm is: /home/basho3/jmcmulli/ASDM/ExecBlock3 and has type <type 'str'>.
Taking the dataset /home/basho3/jmcmulli/ASDM/ExecBlock3 as input.
Time spent parsing the XML metadata :1.16 s.
The measurement set will be filled with complex data
About to create a new measurement set '/home/basho3/jmcmulli/ASDM/ExecBlock3.ms'
The dataset has 4 antennas...successfully copied them into the measurement set.
The dataset has 33 spectral windows...successfully copied them into the measurement set.
The dataset has 4 polarizations...successfully copied them into the measurement set.
The dataset has 41 data descriptions...successfully copied them into the measurement set.
The dataset has 125 feeds...successfully copied them into the measurement set.
The dataset has 2 fields...successfully copied them into the measurement set.
The dataset has 0 flags...
The dataset has 0 historys...
The dataset has 1 execBlock(s)...successfully copied them into the measurement set.
The dataset has 12 pointings...successfully copied them into the measurement set.
The dataset has 3 processors...successfully copied them into the measurement set.
The dataset has 72 sources...successfully copied them into the measurement set.
The dataset has 3 states...
The dataset has 132 calDevices...
The dataset has 72 mains...
Processing row # 0 in MainTable
Entree ds getDataCols
About to clear
About to getData
About to new VMSData
Exit from getDataCols
ASDM Main table row #0 transformed into 40 MS Main table rows
Processing row # 1 in MainTable
Entree ds getDataCols
About to clear
About to getData
About to new VMSData
Exit from getDataCols
ASDM Main table row #1 transformed into 40 MS Main table rows
...
ASDM Main table row #71 transformed into 40 MS Main table rows

...successfully copied them into the measurement set.
About to flush and close the measurement set.
Overall time spent in ASDM methods to read/process the ASDM Main table : cpu = 5.31 s.
Overall time spent in AIPS methods to fill the MS Main table : cpu = 1.3
```

2.3 Summarizing your MS (`listobs`)

Once you import your data into a CASA Measurement Set, you can get a summary of the MS contents with the `listobs` task.

The inputs are:

```
vis          =      ''      #  Name of input visibility file (MS)
verbose      =     True      #  Extended summary list of data set in logger
```

The summary will be written to the logger and to the `casapy.log` file. For example, using `verbose=False`:

```
listobs('n5921.ms',False)
```

results in the logger messages:

```
Thu Jul 5 17:20:55 2007      NORMAL ms::summary:

MeasurementSet Name: /home/scamper/CASA/N5921/n5921.ms      MS Version 2

Observer: TEST      Project:
Observation: VLA(28 antennas)

Thu Jul 5 17:20:55 2007      NORMAL ms::summary:
Data records: 22653      Total integration time = 5280 seconds
Observed from 09:19:00 to 10:47:00

Thu Jul 5 17:20:55 2007      NORMAL ms::summary:
Fields: 3
ID  Name      Right Ascension  Declination   Epoch
0   1331+30500002_013:31:08.29      +30.30.32.96  J2000
1   1445+09900002_014:45:16.47      +09.58.36.07  J2000
2   N5921_2      15:22:00.00      +05.04.00.00  J2000

Thu Jul 5 17:20:55 2007      NORMAL ms::summary:
Spectral Windows: (1 unique spectral windows and 1 unique polarization setups)
SpwID #Chans Frame Ch1(MHz)  Resoln(kHz)  TotBW(kHz)  Ref(MHz)  Corrs
0       63    LSRK  1412.68608  24.4140625  1550.19688  1413.44902  RR  LL

Thu Jul 5 17:20:55 2007      NORMAL ms::summary:
Antennas: 27
ID= 0-3: '1'='VLA:N7', '2'='VLA:W1', '3'='VLA:W2', '4'='VLA:E1',
ID= 4-7: '5'='VLA:E3', '6'='VLA:E9', '7'='VLA:E6', '8'='VLA:W8',
ID= 8-11: '9'='VLA:N5', '10'='VLA:W3', '11'='VLA:N4', '12'='VLA:W5',
ID= 12-15: '13'='VLA:N3', '14'='VLA:N1', '15'='VLA:N2', '16'='VLA:E7',
ID= 16-19: '17'='VLA:E8', '18'='VLA:W4', '19'='VLA:E5', '20'='VLA:W9',
ID= 20-24: '21'='VLA:W6', '22'='VLA:E4', '24'='VLA:E2', '25'='VLA:N6',
ID= 25-26: '26'='VLA:N9', '27'='VLA:N8'
```

Thu Jul 5 17:20:55 2007 NORMAL ms::summary:

```
Tables(rows): (-1 = table absent)
  MAIN(22653)
  ANTENNA(28)  DATA_DESCRIPTION(1)  DOPPLER(-1)  FEED(28)  FIELD(3)
  FLAG_CMD(0)  FREQ_OFFSET(-1)  HISTORY(310)  OBSERVATION(1)  POINTING(168)
  POLARIZATION(1)  PROCESSOR(0)  SOURCE(3)  SPECTRAL_WINDOW(1)  STATE(0)
  SYSCAL(-1)  WEATHER(-1)
```

Thu Jul 5 17:20:55 2007 NORMAL ms::summary ""

Thu Jul 5 17:20:55 2007 NORMAL ms::close:
 Readonly measurement set: just detaching from file.

If you choose the (default) `verbose=True` option, there will be more information. For example,

```
listobs('n5921.ms',True)
```

will result in the logger messages:

Thu Jul 5 17:23:55 2007 NORMAL ms::summary:

```
MeasurementSet Name: /home/scamper/CASA/N5921/n5921.ms     MS Version 2
```

```
Observer: TEST     Project:
Observation: VLA
```

Thu Jul 5 17:23:55 2007 NORMAL ms::summary:
 Data records: 22653 Total integration time = 5280 seconds
 Observed from 09:19:00 to 10:47:00

Thu Jul 5 17:23:55 2007 NORMAL ms::summary:

	ObservationID = 0	ArrayID = 0			
Date	Timerange	Scan	FldId	FieldName	SpwIds
13-Apr-1995/09:19:00.0 - 09:24:30.0		1	0	1331+30500002_0	[0]
	09:27:30.0 - 09:29:30.0	2	1	1445+09900002_0	[0]
	09:33:00.0 - 09:48:00.0	3	2	N5921_2	[0]
	09:50:30.0 - 09:51:00.0	4	1	1445+09900002_0	[0]
	10:22:00.0 - 10:23:00.0	5	1	1445+09900002_0	[0]
	10:26:00.0 - 10:43:00.0	6	2	N5921_2	[0]
	10:45:30.0 - 10:47:00.0	7	1	1445+09900002_0	[0]

Thu Jul 5 17:23:55 2007 NORMAL ms::summary:

Fields: 3

ID	Name	Right Ascension	Declination	Epoch
0	1331+30500002_013:31:08.29	+30.30.32.96	J2000	
1	1445+09900002_014:45:16.47	+09.58.36.07	J2000	

```
2      N5921_2          15:22:00.00      +05.04.00.00  J2000
```

Thu Jul 5 17:23:55 2007 NORMAL ms::summary:
 Spectral Windows: (1 unique spectral windows and 1 unique polarization setups)
 SpwID #Chans Frame Ch1(MHz) Resoln(kHz) TotBW(kHz) Ref(MHz) Corrs
 0 63 LSRK 1412.68608 24.4140625 1550.19688 1413.44902 RR LL

Thu Jul 5 17:23:55 2007 NORMAL ms::summary:
 Feeds: 28: printing first row only
 Antenna Spectral Window # Receptors Polarizations
 1 -1 2 [R, L]

Thu Jul 5 17:23:55 2007 NORMAL ms::summary:
 Antennas: 27:

ID	Name	Station	Diam.	Long.	Lat.
0	1	VLA:N7	25.0 m	-107.37.07.2	+33.54.12.9
1	2	VLA:W1	25.0 m	-107.37.05.9	+33.54.00.5
2	3	VLA:W2	25.0 m	-107.37.07.4	+33.54.00.9
3	4	VLA:E1	25.0 m	-107.37.05.7	+33.53.59.2
4	5	VLA:E3	25.0 m	-107.37.02.8	+33.54.00.5
5	6	VLA:E9	25.0 m	-107.36.45.1	+33.53.53.6
6	7	VLA:E6	25.0 m	-107.36.55.6	+33.53.57.7
7	8	VLA:W8	25.0 m	-107.37.21.6	+33.53.53.0
8	9	VLA:N5	25.0 m	-107.37.06.7	+33.54.08.0
9	10	VLA:W3	25.0 m	-107.37.08.9	+33.54.00.1
10	11	VLA:N4	25.0 m	-107.37.06.5	+33.54.06.1
11	12	VLA:W5	25.0 m	-107.37.13.0	+33.53.57.8
12	13	VLA:N3	25.0 m	-107.37.06.3	+33.54.04.8
13	14	VLA:N1	25.0 m	-107.37.06.0	+33.54.01.8
14	15	VLA:N2	25.0 m	-107.37.06.2	+33.54.03.5
15	16	VLA:E7	25.0 m	-107.36.52.4	+33.53.56.5
16	17	VLA:E8	25.0 m	-107.36.48.9	+33.53.55.1
17	18	VLA:W4	25.0 m	-107.37.10.8	+33.53.59.1
18	19	VLA:E5	25.0 m	-107.36.58.4	+33.53.58.8
19	20	VLA:W9	25.0 m	-107.37.25.1	+33.53.51.0
20	21	VLA:W6	25.0 m	-107.37.15.6	+33.53.56.4
21	22	VLA:E4	25.0 m	-107.37.00.8	+33.53.59.7
23	24	VLA:E2	25.0 m	-107.37.04.4	+33.54.01.1
24	25	VLA:N6	25.0 m	-107.37.06.9	+33.54.10.3
25	26	VLA:N9	25.0 m	-107.37.07.8	+33.54.19.0
26	27	VLA:N8	25.0 m	-107.37.07.5	+33.54.15.8
27	28	VLA:W7	25.0 m	-107.37.18.4	+33.53.54.8

Thu Jul 5 17:23:55 2007 NORMAL ms::summary:

Tables:

MAIN	22653 rows
ANTENNA	28 rows
DATA_DESCRIPTION	1 row
DOPPLER	<absent>

```

FEED           28 rows
FIELD          3 rows
FLAG_CMD       <empty>
FREQ_OFFSET    <absent>
HISTORY        310 rows
OBSERVATION    1 row
POINTING       168 rows
POLARIZATION   1 row
PROCESSOR      <empty>
SOURCE          3 rows
SPECTRAL_WINDOW 1 row
STATE           <empty>
SYSCAL          <absent>
WEATHER         <absent>

```

```
Thu Jul 5 17:23:55 2007    NORMAL ms::summary ""
```

```
Thu Jul 5 17:23:55 2007    NORMAL ms::close:
 Readonly measurement set: just detaching from file.
```

The most useful extra information that `verbose=True` gives is the list of the scans in the dataset.

2.4 Concatenating multiple datasets (`concat`)

Once you have your data in the form of CASA Measurement Sets, you can go ahead and process your data using the editing, calibration, and imaging tasks. In some cases, you will most efficiently operate on single MS for a particular session (such as calibration). Other tasks will (eventually) take multiple Measurement Sets as input. For others, it is easiest to combine your multiple data files into one.

If you need to combine multiple datasets, you can use the `concat` task. The default inputs are:

```

# concat :: Concatenate two or more visibility data sets.
vis      =      []    # Name of input visibility files to be concatenated
concatvis =      ''    # Name of output visibility file
freqtol  =      ''    # Frequency tolerance for considering data as the same spwid
dirtol   =      ''    # Direction tolerance for considering data as the same field
async    =  False    # If true the taskname must be started using concat(...)

```

The `vis` parameter will take a list of one or more MS. Usually, this will contain all the MS to combine.

The `concatvis` parameter contains the name of the output MS. If this points to an existing file on disk, then the MS in `vis` will appended to it, otherwise a new MS file is created to contain the concatenated data. Be careful here!

The parameters `freqtol` and `dirtol` control how close together in frequency and angle on the sky spectral windows or field locations need to be before calling them the same.

BETA ALERT: Note that if multiple frequencies or pointings are combined using `freqtol` or `dirtol`, then the data are not changed (ie. not rephased to the single phase center). Use of these parameters is intended to be tolerant of small offsets (e.g. planets tracked which move slightly in J2000 over the course of observations, or combining epochs observed with slightly different positions).

For example:

```
default('concat')
vis = ['n4826_16apr.split.ms', 'n4826_22apr.split.ms']
concatvis = 'n4826_tboth.ms'
freqtol = '50MHz'
concat()
```

combines the two days in `'n4826_16apr.split.ms'` and `'n4826_22apr.split.ms'` into a new output MS called `'n4826_tboth.ms'`.

BETA ALERT: This has changed in Patch 2! Previously, only appended a single MS given in `concatvis` to that in `vis` (somewhat the reverse of what it does now).

2.5 Data Selection

Once in MS form, subsets of the data can be operated on using the tasks and tools. In CASA, there are three common data selection parameters used in the various tasks: `field`, `spw`, and `selectdata`. In addition, the `selectdata` parameter, if set to `True`, will open up a number of other sub-parameters for selection. The selection operation is unified across all the tasks. The available `selectdata` parameters may not be the same in all tasks. But if present, the same parameters mean the same thing and behave in the same manner when used in any task.

Beta Alert!

Data selection is being changed over to this new unified system. In various tasks, you may find relics of the old way, such as `fieldid` or `spwid`.

For example:

```
field      =      ''      # field names or index of calibrators ''==>all
spw        =      ''      # spectral window:channels: ''==>all
selectdata =  False    # Other data selection parameters
```

versus

```
field      =      ''      # field names or index of calibrators ''==>all
spw        =      ''      # spectral window:channels: ''==>all
selectdata =  True     # Other data selection parameters
timerange  =      ''      # time range: ''==>all
uvrange    =      ''      # uv range ''=all
antenna    =      ''      # antenna/baselines: ''==>all
scan       =      ''      # scan numbers: Not yet implemented
```

```
msselect      =      ''      #  Optional data selection (Specialized. but see help)
```

The following are the general syntax rules and descriptions of the individual selection parameters of particular interest for the tasks:

2.5.1 General selection syntax

Most of the selections are effected through the use of selection strings. This sub-section describes the general rules used in constructing and parsing these strings. Note that some selections are done though the use of numbers or lists. There are also parameter-specific rules that are described under each parameter.

All lists of basic selection specification-units are comma separated lists and can be of any length. White-spaces before and after the commas (e.g. '3C286, 3C48, 3C84') are ignored, while white-space within sub-strings is treated as part of the sub-string (e.g. '3C286, VIRGO A, 3C84').

All integers can be of any length (in terms of characters) composed of the characters 0–9. Floating point numbers can be in the standard format (DIGIT.DIGIT, DIGIT., or .DIGIT) or in the mantissa-exponent format (e.g. 1.4e9). Places where only integers make sense (e.g. IDs), if a floating point number is given, only the integer part is used (it is truncated).

Range of numbers (integers or real numbers) can be given in the format 'N0~N1'. For integer ranges, it is expanded into a list of integers starting from N0 (inclusive) to N1 (inclusive). For real numbers, it is used to select all values present for the appropriate parameter in the Measurement Set between N0 and N1 (including the boundaries). Note that the ' ~' character is used rather than the more obvious '-' in order to accommodate hyphens in strings and minus signs in numbers.

Wherever appropriate, units can be specified. The units are used to convert the values given to the units used in the Measurement Set. For ranges, the unit is specified only once (at the end) and applies to both the range boundaries.

2.5.1.1 String Matching

String matching can be done in three ways. Any component of a comma separated list that cannot be parsed as a number, a number range, or a physical quantity is treated as a regular expression or a literal string. If the string does not contain the characters '*', '{', '}' or '?', it is treated as a literal string and used for exact matching. If any of the above mentioned characters are part of the string, they are used as a regular expression. As a result, for most cases, the user does not need to supply any special delimiters for literal strings and/or regular expressions. For example:

```
field = '3'      # match field ID 3 and not select field named "3C286".

field = '3*'     # used as a pattern and matched against field names. If
# names like "3C84", "3C286", "3020+2207" are found,
# all will match. Field ID 3 will not be selected
# (unless of course one of the above mentioned field
```

```
# names also correspond to field ID 3!).  
  
field = '30*' # will match only with "3020+2207" in above set.
```

However if it is required that the string be matched exclusively as a regular expression, it can be supplied within a pair of '/' as delimiters (e.g. '/.+BAND.+/'). A string enclosed within double quotes ('"') is used exclusively for pattern matching (patterns are a simplified form of regular expressions - used in most UNIX commands for string matching). Patterns are internally converted to equivalent regular expressions before matching. See the Unix command "info regex", or visit <http://www.regular-expressions.info>, for details of regular expressions and patterns.

Strings can include any character except the following:

```
', ' ; ' " ' /' NEWLINE
```

(since these are part of the selection syntax). Strings that do not contain any of the characters used to construct regular expressions or patterns are used for exact matches. Although it is highly discouraged to have name in the MS containing the above mentioned reserved characters, if one *does* choose to include the reserved characters as parts of names etc., those names can only be matched against quoted strings (since regular expression and patterns are a super-set of literal strings – i.e., a literal string is also a valid regular expression).

This leaves ''', '*', '{', '}' or '?' as the list of printable character that cannot be part of a name (i.e., a name containing this character can never be matched in a MSSelection expression). These will be treated as pattern-matching even inside double double quotes ('" ""). There is currently no escape mechanism (e.g. via a backslash).

Some examples of strings, regular expressions, and patterns:

- The string 'LBAND' will be used as a literal string for exact match. It will match only the exact string LBAND.
- The wildcarded string '*BAND*' will be used as a string pattern for matching. This will match any string which has the sub-string BAND in it.
- The string '"*BAND*" will also be used as a string pattern, matching any string which has the sub-string BAND in it.
- The string '/.+BAND.+/' will be used as a regular expression. This will also match any string which has the sub-string BAND in it. (the .+ regex operator has the same meaning as the * wildcard operator of patterns).

2.5.2 The field Parameter

The **field** parameter is a string that specifies which field names or ids will be processed in the task or tool. The field selection expression consists of comma separated list of field specifications inside the string.

Field specifications can be literal field names, regular expressions or patterns (see § 2.5.1.1). Those fields for which the entry in the NAME column of the FIELD MS sub-table match the literal field name/regular expression/pattern are selected. If a field name/regular expression/pattern fails to match any field name, the given name/regular expression/pattern are matched against the field code. If still no field is selected, an exception is thrown.

Field specifications can also be given by their integer IDs. IDs can be a single or a range of IDs. Field ID selection can also be done as a boolean expression. For a field specification of the form ' $>ID$ ', all field IDs greater than ID are selected. Similarly for ' $<ID$ ' all field IDs less than the ID are selected.

For example, if the MS has the following observations:

MS summary:

FIELDDID	SPWID	NChan	Pol	NRows	Source Name
0	0	127	RR	10260	0530+135
1	0	127	RR	779139	05582+16320
2	0	127	RR	296190	05309+13319
3	0	127	RR	58266	0319+415
4	0	127	RR	32994	1331+305
5	1	1	RR,RL,LL,RR	23166	KTIP

one might select

```
field = '0~2,KTIP'          # FIELDDID 0,1,2 and field name KTIP
field = '0530+135'          # field 0530+135
field = '05*'                # fields 0530+135,05582+16320,05309+13319
```

2.5.3 The spw Parameter

The `spw` parameter is a string that indicates the specific spectral windows and the channels within them to be used in subsequent processing. Spectral window selection ('`SPWSEL`') can be given as a spectral window integer ID, a list of integer IDs, a spectral window name specified as a literal string (for exact match) or a regular expression or pattern.

The specification can be via frequency ranges or by indexes. A range of frequencies are used to select all spectral windows which contain channels within the given range. Frequencies can be specified with an optional unit — the default unit being `Hz`. Other common choices for radio and mm/sub-mm data are `kHz`, `MHz`, and `GHz`. You will get the entire spectral windows, not just the channels in the specified range. You will need to do channel selection (see below) to do that.

The `spw` can also be selected via comparison for integer IDs. For example, ' $>ID$ ' will select all spectral windows with ID greater than the specified value, while ' $<ID$ ' will select those with ID lesser than the specified value.

BETA ALERT: In the current Beta Release, '<ID' and '>ID' are *inclusive* with the ID specified included in the selection, e.g. `spw='<2'` is equivalent to `spw='0,1,2'` and not `spw='0,1'` as was intended. This will be fixed in an upcoming release.

Spectral window selection using strings follows the standard rules:

```
spw = '1'                      # SPWID 1
spw = '1,3,5'                   # SPWID 1,3,5
spw = '0~3'                     # SPWID 0,1,2,3
spw = '0~3,5'                   # SPWID 0,1,2,3 and 5
spw = '<3,5'                    # SPWID 0,1,2,3 and 5
spw = '*'                       # All spectral windows
spw = '1412~1415MHz'           # Spectral windows containing 1412-1415MHz
```

In some cases, the spectral windows may allow specification by name. For example,

```
spw = '3mmUSB, 3mmLSB'          # choose by names (if available)
```

might be meaningful for the dataset in question.

Note that the order in which multiple `spws` are given may be important for other parameters. For example, the `mode = 'channel'` in `clean` uses the first `spw` as the origin for the channelization of the resulting image cube.

2.5.3.1 Channel selection in the spw parameter

Channel selection can be included in the `spw` string in the form '`SPWSEL:CHANSEL`' where `CHANSEL` is the channel selector. In the end, the spectral selection within a given spectral window comes down to the selection of specific channels. We provide a number of shorthand selection options for this. These `CHANSEL` options include:

Beta Alert!

Not all options are available yet, such as percentages or velocities. Stay tuned!

- *Channel ranges:* '`START~STOP`'
- *Frequency ranges:* '`FSTART~FSTOP`'
- *Velocity ranges:* '`VSTART~VSTOP`' (**not yet available**)
- *Bandwidth percentages:* '`PSTART~PSTOP`' or '`PWIDTH`' (**not yet available**)
- *Channel striding/stepping:* '`START~STOP^STEP`' or '`FSTART~FSTOP^FSTEP`'

The most common selection is via channel ranges '`START~STOP`' or frequency ranges '`FSTART~FSTOP`:

```
spw = '0:13~53'                 # spw 0, channels 13-53, inclusive
spw = '0:1413~1414MHz'          # spw 0, 1413-1414MHz section only
```

All ranges are inclusive, with the channel given by, or containing the frequency or velocity given by, START and STOP plus all channels between included in the selection. You can also select the spectral window via frequency ranges 'FSTART~FSTOP', as described above:

```
spw = '1413~1414MHz:1413~1414MHz'      # channels falling within 1413~1414MHz
spw = '*:1413~1414MHz'                  # does the same thing
```

You can also specify multiple spectral window or channel ranges, e.g.

```
spw = '2:16, 3:32~34'          # spw 2, channel 16 plus spw 3 channels 32-34
spw = '2:1~3;57~63'           # spw 2, channels 1-3 and 57-63
spw = '1~3:10~20'             # spw 1-3, channels 10-20
spw = '*:4~56'                # all spw, channels 4-56
```

Note the use of the wildcard in the last example.

A step can be also be included using '^STEP' as a postfix:

```
spw = '0:10~100^2'            # chans 10,12,14,...,100 of spw 0
spw = ':^4'                   # chans 0,4,8,... of all spw
spw = ':100~150GHz^10GHz'    # closest chans to 100,110,...,150GHz
```

A step in frequency or velocity will pick the channel in which that frequency or velocity falls, or the nearest channel.

2.5.4 The `selectdata` Parameters

The `selectdata` parameter, if set to `True`, will expand the inputs to include a number of sub-parameters, given below and in the individual task descriptions (if different). If `selectdata = False`, then the sub-parameters are treated as blank for selection by the task. The default for `selectdata` is `False`.

The common `selectdata` expanded sub-parameters are:

2.5.4.1 The `antenna` Parameter

The `antenna` selection string is a semi-colon (';') separated list of baseline specifications. A baseline specification is of the form:

- 'ANT1' — Select all baselines including the antenna(s) specified by the selector `ANT1`.
- 'ANT1&' — Select only baselines between the antennas specified by the selector `ANT1`.
- 'ANT1&ANT2' — Select only the cross-correlation baselines between the antennas specified by selector `ANT1` and antennas specified by selector `ANT2`. Thus 'ANT1&' is an abbreviation for 'ANT1&ANT1'.

- '**ANT1&&ANT2**' — Select only auto-correlation and cross-correlation baselines between antennas specified by the selectors **ANT1** and **ANT2**. Note that this is what the default **antenna=''** gives you.
- '**ANT1&&&**' — Select only autocorrelations specified by the selector **ANT1**.

The selectors **ANT1** and **ANT2** are comma-separated lists of antenna integer-IDs or literal antenna names, patterns, or regular expressions. The **ANT** strings are parsed and converted to a list of antenna integer-IDs or IDs of antennas whose name match the given names/pattern/regular expression. Baselines corresponding to all combinations of the elements in lists on either side of ampersand are selected.

Integer IDs can be specified as single values or a range of integers. When items of the list are parsed as literal strings or regular expressions or patterns (see § 2.5.1 for more details on strings). All antenna names that match the given string (exact match)/regular expression/pattern are selected.

The comma is used only as a separator for the list of antenna specifications. The list of baselines specifications is a semi-colon separated list, e.g.

```
antenna = '1~3 & 4~6 ; 10&11'
```

will select baselines between antennas 1,2,3 and 4,5,6 ('1&4', '1&5', ..., '3&6') plus baseline '10&11'.

The wildcard operator ('*') will be the most often used pattern. To make it easy to use, the wildcard (and only this operator) can be used without enclosing it in quotes. For example, the selection

```
antenna = 'VA*'
```

will match all antenna names which have 'VA' as the first 2 characters in the name (irrespective of what follows after these characters).

Some examples:

```
antenna=''          # shows blank autocorr pages
antenna='*&*'      # does not show the autocorrs
antenna='*&&*'    # show both auto and cross-cor (default)
antenna='*&&&'     # shows only autocorrs

antenna='5&*'      # shows non-auto baselines with AN 5

antenna='5,6&&&'  # AN 5 and 6 autocor
antenna='5&&&;6&*' # AN 5 autocor plus cross-cors to AN 6
```

Antenna numbers as names: Needless to say, naming antennas such that the names can also be parsed as a valid token of the syntax is a bad idea. Nevertheless, antenna names that contain any of the reserved characters and/or can be parsed as integers or integer ranges can still be used by enclosing the antenna names in double quotes (' "ANT" '). E.g. the string

```
antenna = '10~15,21,VA22'
```

will expand into an antenna ID list 10,11,12,13,14,15,21,22 (assuming the index of the antenna named 'VA22' is 22). If the antenna with ID index 50 is named '21', the string

```
antenna = '10~15,"21",VA22'
```

will expand into an antenna ID list of 10,11,12,13,14,15,50,22.

Read elsewhere (e.g. `info regex` under Unix) for details of regular expression and patterns.

2.5.4.2 The scan Parameter

The `scan` parameter selects the scan ID numbers of the data. There is currently no naming convention for scans. The scan ID is filled into the MS depending on how the data was obtained, so use this with care.

Examples:

```
scan = '3'                      # scan number 3.
scan = '1~8'                    # scan numbers 1 through 8, inclusive
scan = '1,2,4,6'                # scans 1,2,4,6
scan = '<9'                     # scans <9 (1-8)
```

NOTE: ALMA and VLA/EVLA number scans starting with 1 and not 0. You can see what the numbering is in your MS using the `listobs` task with `verbose=True` (see § 2.3).

2.5.4.3 The timerange Parameter

The time strings in the following (`T0`, `T1` and `dT`) can be specified as `YYYY/MM/DD/HH:MM:SS.FF`. The time fields (i.e., `YYYY`, `MM`, `DD`, `HH`, `MM`, `SS` and `FF`), starting from left to right, may be omitted and they will be replaced by context sensitive defaults as explained below.

Some examples:

1. `timerange='T0~T1'`: Select all time stamps from `T0` to `T1`. For example:

```
timerange = '2007/10/09/00:40:00 ~ 2007/10/09/03:30:00'
```

Note that fields missing in `T0` are replaced by the fields in the time stamp of the first valid row in the MS. For example,

```
timerange = '09/00:40:00 ~ 09/03:30:00'
```

where the `YY/MM/` part of the selection has been defaulted to the start of the MS.

Fields missing in `T1`, such as the date part of the string, are replaced by the corresponding fields of `T0` (after its defaults are set). For example:

```
timerange = '2007/10/09/22:40:00 ~ 03:30:00'
```

does the same thing as above.

2. **timerange='T0':** Select all time stamps that are within an integration time of T0. For example,

```
timerange = '2007/10/09/23:41:00'
```

Integration time is determined from the first valid row (more rigorously, an average integration time should be computed). Default settings for the missing fields of T0 are as in (1).

3. **timerange='T0+dT':** Select all time stamps starting from T0 and ending with time stamp T0+dT. For example,

```
timerange = '23:41:00+01:00:00'
```

picks an hour-long chunk of time.

Defaults of T0 are set as usual. Defaults for dT are set from the time corresponding to MJD=0. Thus, dT is a specification of length of time from the assumed nominal "start of time".

4. **timerange='>T0':** Select all times greater than T0. For example,

```
timerange = '>2007/10/09/23:41:00'
```

Default settings for T0 are as above.

5. **timerange='<T1':** Select all times less than T1. For example,

```
timerange = '<2007/10/09/23:41:00'
```

Default settings for T1 are as above.

An ultra-conservative selection might be:

```
timerange = '1960/01/01/00:00:00~2020/12/31/23:59:59'
```

which would choose all possible data!

2.5.4.4 The `uvrange` Parameter

Rows in the MS can also be selected based on the uv-distance or physical baseline length that the visibilities in each row correspond to. This `uvrange` can be specified in various formats.

The basic building block of uv-distance specification is a valid number with optional units in the format N[UNIT] (the unit in square brackets is optional). We refer to this basic building block as `UVDIST`. The default unit is meter. Units of length (such as '`m`' and '`km`') select physical

baseline distances (independent of wavelength). The other allowed units are in wavelengths (such as 'lambda', 'klambda' and 'Mlambda' and are true uv-plane radii

$$r_{uv} = \sqrt{u^2 + v^2}. \quad (2.1)$$

If only a single UVDIST is specified, all rows, the uv-distance of which exactly matches the given UVDIST, are selected.

UVDIST can be specified as a range in the format '`N0~N1[UNIT]`' (where N0 and N1 are valid numbers). All rows corresponding to uv-distance between N0 and N1 (inclusive) when converted to the specified units are selected.

UVDIST can also be selected via comparison operators. When specified in the format '`>UVDIST`', all visibilities with uv-distances greater than the given UVDIST are selected. Likewise, when specified in the format '`<UVDIST`', all rows with uv-distances less than the given UVDIST are selected.

Any number of above mentioned uv-distance specifications can be given as a comma-separated list.

Examples:

```
uvrange = '100~200km'                      # an annulus in physical baseline length
uvrange = '24~35Mlambda, 40~45Mlambda'      # two annuli in units of mega-wavelengths
uvrange = '< 45klambda'                     # less than 45 kilolambda
uvrange = '> 0lambda'                       # greater than zero length (no auto-corrs)
uvrange = '100km'                           # baselines of length 100km
uvrange = '100klambda'                      # uv-radius 100 kilolambda
```

2.5.4.5 The `msselect` Parameter

More complicated selections within the MS structure are possible using the Table Query Language (TaQL). This is accessed through the `msselect` parameter.

Note that the TaQL syntax does not follow the rules given in § 2.5.1 for our other selection strings. TaQL is explained in more detail in **Aips++ NOTE 199 — Table Query Language** (<http://aips2.nrao.edu/docs/notes/199/199.html>). This will eventually become a CASA document. The specific columns of the MS are given in the most recent MS specification document: **Aips++ NOTE 229 — MeasurementSet definition version 2.0** (<http://aips2.nrao.edu/docs/notes/229/229.html>). This documentation will eventually be updated to the CASA document system.

Most selection can be carried out using the other selection parameters. However, these are merely shortcuts to the underlying TaQL selection. For example, field and spectral window selection can be done using `msselect` rather than through `field` or `spw`:

```
msselect='FIELD_ID == 0'                      # Field id 0 only
msselect='FIELD_ID <= 1'                      # Field id 0 and 1
msselect='FIELD_ID IN [1,2]'                  # Field id 1 and 2
msselect='FIELD_ID==0 && DATA_DESC_ID==3'    # Field id 0 in spw id 3 only
```

BETA ALERT: The `msselect` style parameters will be phased out of the tasks. TaQL selection will still be available in the Toolkit.

Chapter 3

Data Examination and Editing

3.1 Plotting and Flagging Visibility Data in CASA

The tasks available for plotting and flagging of data are:

- `flagmanager` — manage versions of data flags (§ 3.2)
- `flagautocorr` — non-interactive flagging of auto-correlations (§ 3.3)
- `plotxy` — create X-Y plots of data in MS, flag data (§ 3.4)
- `flagdata` — non-interactive flagging of data (§ 3.5)
- `browsetable` — browse data in any CASA table (including a MS) (§ 3.6)

The following sections describe the use of these tasks.

Information on other related operations can be found in:

- `listobs` — list what's in a MS (§ 2.3)
- `selectdata` — general data selection syntax (§ 2.5)
- `viewer` — use the `casaviewer` to display the MS as a raster image, and flag it (§ 7)

3.2 Managing flag versions with `flagmanager`

The `flagmanager` task will allow you to manage different versions of flags in your data. These are stored inside a CASA flagversions table, under the name of the MS `<msname>.flagversions`. For example, for the MS `jupiter6cm.usecase.ms`, there will need to be `jupiter6cm.usecase.ms.flagversions` on disk. This is created on import (by `importvla` or `importuvfits`) or when flagging is first done on an MS without a `.flagversions` (e.g. with `plotxy`).

By default, when the `.flagversions` is created, this directory will contain a `flags.Original` in it containing a copy of the original flags in the `MAIN` table of the MS so that you have a backup. It will also contain a file called `FLAG_VERSION_LIST` that has the information on the various flag versions there.

The inputs for `flagmanager` are:

```
vis           =      ''          #  Name of input visibility file (MS)
mode          =      'list'       #  Flag management operation (list,save,restore,delete)
```

The `mode='list'` option will list the available flagversions from the `<msname>.flagversions` file. For example:

```
CASA <102>: default('flagmanager')
CASA <103>: vis = 'jupiter6cm.usecase.ms'
CASA <104>: mode = 'list'
CASA <105>: flagmanager()
MS : /home/imager-b/smyers/Oct07/jupiter6cm.usecase.ms

main : working copy in main table
Original : Original flags at import into CASA
flagautocorr : flagged autocorr
xyflags : Plotxy flags
```

The `mode` parameter expands the options. For example, if you wish to save the current flagging state of `vis=<msname>`,

```
mode          =      'save'       #  Flag management operation (list,save,restore,delete)
versionname   =      ''          #  Name of flag version (no spaces)
comment       =      ''          #  Short description of flag version
merge         =      'replace'    #  Merge option (replace, and, or)
```

with the output version name specified by `versionname`. For example, the above `xyflags` version was written using:

```
default('flagmanager')
vis = 'jupiter6cm.usecase.ms'
mode = 'save'
versionname = 'xyflags'
comment = 'Plotxy flags'
flagmanager()
```

and you can see that there is now a sub-table in the `flagversions` directory

```
CASA <106>: ls jupiter6cm.usecase.ms.flagversions/
IPython system call: ls -F jupiter6cm.usecase.ms.flagversions/
flags.flagautocorr  flags.Original  flags.xyflags  FLAG_VERSION_LIST
```

It is recommended that you use this facility regularly to save versions during flagging.

You can restore a previously saved set of flags using the `mode='restore'` option:

```
mode          = 'restore'      # Flag management operation (list,save,restore,delete)
versionname   = ''           # Name of flag version (no spaces)
merge         = 'replace'     # Merge option (replace, and, or)
```

The `merge` sub-parameter will control the action. For `merge='replace'`, the flags in `versionname` will replace those in the MAIN table of the MS. For `merge='and'`, only data that is flagged in BOTH the current MAIN table and in `versionname` will be flagged. For `merge='or'`, data flagged in EITHER the MAIN or in `versionname` will be flagged.

The `mode='delete'` option can be used to remove `versionname` from the flagversions:

```
mode          = 'delete'      # Flag management operation (list,save,restore,delete)
versionname   = ''           # Name of flag version (no spaces)
```

3.3 Flagging auto-correlations with flagautocorr

The `flagautocorr` task can be used if all you want to do is to flag the auto-correlations out of the MS. Nominally, this can be done upon filling from the VLA for example, but you may be working from a dataset that still has them.

This task has a single input, the MS file name:

```
vis          = ''           # Name of input visibility file (MS)
```

To use it, just set and go:

```
CASA <90>: vis = 'jupiter6cm.uscenario.ms'
CASA <91>: flagautocorr()
```

Note that the auto-correlations can also be flagged using `flagdata` (§ 3.5) but the `flagautocorr` task is an handy shortcut for this common operation.

3.4 X-Y Plotting and Editing of the Data

The principal way to get X-Y plots of visibility data is using the `plotxy` task. This task also provides editing capability. CASA uses the `matplotlib` plotting library to display its plots. You can find information on `matplotlib` at <http://matplotlib.sourceforge.net/>.

To bring up this plotter use the `plotxy` task. The inputs are:

Inside the Toolkit:

Access to `matplotlib` is also provided through the `pl` tool. See below for a description of the `pl` tool functions.




Figure 3.1: The `plotxy` plotter, showing the Jupiter data versus uv-distance. You can see bad data in this plot. The **bottom set of buttons** on the lower left are: 1,2,3) **Home, Back, and Forward**. Click to navigate between previously defined views (akin to web navigation). 4) **Pan**. Click and drag to pan to a new position. 5) **Zoom**. Click to define a rectangular region for zooming. 6) **Subplot Configuration**. Click to configure the parameters of the subplot and spaces for the figures. 7) **Save**. Click to launch a file save dialog box. The **upper set of buttons in the lower left** are: 1) **Mark Region**. Press this to begin marking regions (rather than zooming or panning). 2,3,4) **Flag, Unflag, Locate**. Click on these to flag, unflag, or list the data within the marked regions. 5) **Next**. Click to move to the next in a series of iterated plots. Finally, the **cursor readout** is on the bottom right.

```
#  plotxy :: X-Y plotter/interactive flagger for visibility data

vis          =      ''    #  Name of input visibility
xaxis        =      'time' #  X-axis: def = 'time': see help for options
yaxis        =      'amp'  #  Y-axis: def = 'amp': see help for options
datacolumn   =      'data' #  data (raw), corrected, model, residual (corrected - model)
```

```

selectdata      =      False   # Other data selection parameters
spw            =      ''      # spectral window:channels: ''==>all, spw='1:5~57'
field          =      ''      # field names or index of calibrators: ''==>all
averagemode    =      'vector' # Select averaging type: vector, scalar
    timebin     =      '0'     # Length of time-interval in seconds to average
    crossscans  =      False   # Have time averaging cross scan boundaries?
    width        =      '1'     # Number of channels to average

extendflag     =      False   # Have flagging extend to other data points?
subplot        =      111    # Panel number on display screen (yxn)
overplot       =      False   # Overplot values on current plot (if possible)
showflags      =      False   # Show flagged data
iteration      =      ''      # Plot separate panels by field, antenna, baseline, scan, feed
plotsymbol     =      '.'     # pylab plot symbol
plotcolor      =      'darkcyan' # pylab plot color
connect        =      'none'  # Specifies which points are connected with lines
multicolor    =      'corr'  # Plot in different colors: Options: none,both,chan,corr
interactive    =      True    # Show plot on gui
figfile        =      ''      # ''= no plot hardcopy, otherwise supply name
plotrange     =      [-1, -1, -1, -1] # The range of data to be plotted (see help for times)
selectplot     =      False   # Select additional plotting options (e.g., fontsize, title,etc)

```

BETA ALERT: The `plotxy` task expects all of the scratch columns to be present in the MS, even if it is not asked to plot the contents. If you get an error to the effect "Invalid Table operation: Table: cannot add a column" then use `clearcal()` to force these columns to be made in the MS. Note that this will clear anything in all scratch columns (in case some were actually there and being used).

Setting `selectdata=True` opens up the selection sub-parameters:

```

selectdata      =      True   # Other data selection parameters
    antenna     =      ''      # antenna/baselines: ''==>all, antenna = '3,VA04'
    timerange   =      ''      # time range: ''==>all
    correlation =      ''      # correlations: default = ''
    scan         =      ''      # scan numbers: Not yet implemented
    feed         =      ''      # multi-feed numbers: Not yet implemented
    array        =      ''      # array numbers: Not yet implemented
    uvrage       =      ''      # uv range''==>all; uvrage = '0~100kl' (default unit=meters)

```

These are described in § 2.5.

Averaging is controlled with the set of parameters

```

averagemode    =      'vector' # Select averaging type: vector, scalar
    timebin     =      '0'     # Length of time-interval in seconds to average
    crossscans  =      False   # Have time averaging cross over scans?
    crossbels   =      False   # Have averaging cross over baselines?
    crossarrays =      False   # Have averaging cross over arrays?
    originalchanid =  True    # Use original channel ids?
    width        =      '1'     # Number of channels to average

```

Note that the `timebin`, `crossscans`, and `width` sub-parameters are always open and available whether `averagemode='vector'` or `'scalar'`. See § 3.4.4 below for more on averaging.

You can extend the flagging beyond the data cell plotted:

```
extendflag      =  True    # Have flagging extend to other data points?
extendcorr     =  ''      # flagging correlation extension type
extendchan     =  ''      # flagging channel extension type
extendspw      =  ''      # flagging spectral window extension type
extendant      =  ''      # flagging antenna extension type
extendtime     =  ''      # flagging time extension type
```

See § 3.4.6 below for more on flag extension.

Setting `selectplot=True` will open up a set of plotting control sub-parameters. These are described in § 3.4.2 below.

The `interactive` and `figfile` parameters allow non-interactive production of hardcopy plots. See § 3.4.7 for more details on saving plots to disk.

The `iteration`, `overplot`, `plotrange`, `plotsymbol`, `showflags` and `subplot` parameters deserve extra explanation, and are described in § 3.4.3 below.

For example:

```
plotxy(vis='jupiter6cm.ms',                      # jupiter 6cm dataset
       xaxis='uvdist',                           # plot uv-distance on x-axis
       yaxis='amp',                             # plot amplitude on y-axis
       field='JUPITER',                         # plot only JUPITER
       selectdata=True,                          # open data selection
       correlation='RR,LL',                     # plot RR and LL correlations
       selectplot=True,                          # open plot controls
       title = 'Jupiter 6cm uncalibrated') # give it a title
```

The plotter resulting from these settings is shown in figure 3.1.

BETA ALERT: The `plotxy` task still has a number of issues. The averaging has been greatly speeded up in this release, but there are cases where the plots will be made incorrectly. In particular, there are problems plotting multiple `spw` at the same time. There are sometimes also cases where data that you have flagged in `plotxy` from averaged data is done so incorrectly. This task is under active development for the next cycle to fix these remaining problems, so users should be aware of this.

3.4.1 GUI Plot Control

You can use the various buttons on the `plotxy` GUI to control its operation – in particular, to determine flagging and unflagging behaviors.

There is a standard row of buttons at the bottom. These include (left to right):

- **Home** — The “house” button (1st on left) returns to the original zoom level.
- **Step** — The left and right arrow buttons (2nd and 3rd from left) step through the zoom settings you’ve visited.
- **Pan** — The “four-arrow button” (4th from left) lets you pan in zoomed plot.
- **Zoom** — The most useful is the “magnifying glass” (5th from the left) which lets you draw a box and zoom in on the plot.
- **Panels** — The “window-thingy” button (second from right) brings up a menu to adjust the panel placement in the plot.
- **Save** — The “disk” button (last on right) saves a .png copy of the plot to a generically named file on disk.

In a row above these, there are a set of other buttons (left to right):

- **Mark Region** — If depressed lets you draw rectangles to mark points in the panels. This is done by left-clicking and dragging the mouse. You can Mark multiple boxes before doing something. Clicking the button again will un-depress it and forget the regions. ESC will remove the last region marked.
- **Flag** — Click this to Flag the points in a marked region.
- **Unflag** — Click this to Unflag any flagged point that would be in that region (even if invisible).
- **Locate** — Print out some information to the logger on points in the marked regions.
- **Next** — Step to the next plot in an iteration.
- **Quit** — Exit `plotcal`, clear the window and detach from the MS.

These buttons are shared with the `plotcal` tool.

3.4.2 The `selectplot` Parameters

These parameters work in concert with the native matplotlib functionality to enable flexible representations of data displays.

Setting `selectplot=True` will open up a set of plotting control sub-parameters:

```
selectplot      =      True   # Select additional plotting options (e.g., fontsize, title,etc)
    markersize   =      5.0    # Size of plotted marks
    linewidth    =      1.0    # Width of plotted lines
    skipnrows    =      1       # Plot every nth point
    newplot      =     False   # Replace the last plot or not when overplotting
    clearpanel   =   'auto'   # Specify if old plots are cleared or not
```

```

title      =      ''    # Plot title (above plot)
xlabels   =      ''    # Label for x-axis
ylabels   =      ''    # Label for y-axis
fontsize  =     10.0  # Font size for labels
windowsize =      1.0  # Window size: not yet implemented

```

The `markersize` parameter will change the size of the plot symbols. Increasing it will help legibility when doing screen shots. Decreasing it can help in congested plots. The `linewidth` parameter will do similar things to the lines.

The `skipnrows` parameter, if set to an integer `n` greater than 1, will allow only every `n`th point to be plotted. It does this, as the name suggests, by skipping over whole rows of the MS, so beware (channels are all within the same row for a given `spw`). Be careful flagging on data where you have skipped points! Note that you can also reduce the number of points plotted via averaging (§ 3.4.4) or channel striding in the `spw` specification (§ 2.5.3).

The `newplot` toggle lets you choose whether or not the last layer plotted is replaced when `overplot=True`, or whether a new layer is added.

The `clearpanel` parameter turns on/off the clearing of plot panels that lie under the current panel layer being plotted. The options are: `'none'` (clear nothing), `'auto'` (automatically clear the plotting area), `'current'` (clear the current plot area only), and `'all'` (clear the whole plot panel).

The `title`, `xlabels`, and `ylabels` parameters can be used to change the plot title and axes labels.

The `fontsize` parameter is useful in order to enlarge the label fonts so as to be visible when making plots for screen capture, or just to improve legibility. Shrinking can help if you have lots of panels on the plot also.

The `windowsize` parameter is supposed to allow adjustments on the window size. **BETA ALERT:** This currently does nothing, unless you set it below 1.0, in which case it will produce an error.

3.4.3 Plot Control Parameters

The `iteration`, `overplot`, `plotrange`, `plotsymbol`, `showflags` and `subplot` parameters deserve extra explanation:

3.4.3.1 iteration

There are currently four iteration options available: `'field'`, `'antenna'`, and `'baseline'`. If one of these options is chosen, the data will be split into separate plot displays for each value of the iteration axis (e.g., for the VLA, the `'antenna'` option will get you 27 displays, one for each antenna).

Inside the Toolkit:

For even more functionality, you can access the `pl` tool directly using Pylab functions that allow one to annotate, alter, or add to any plot displayed in the `matplotlib` plotter (e.g. `plotxy`).

BETA ALERT: There will eventually be 'scan' and 'feed' options also.

An example use of iteration:

```
# choose channel averaging, every 5 channels
plotxy('n5921.ms','channel',subplot=221,iteration='antenna',width='5')
```

The results of this are shown in Figure 3.2. Note that this example combines the use of `width`, `iteration` and `subplot`.




Figure 3.2: The `plotxy` iteration plot. The first set of plots from the example in § 3.4.3.1 with `iteration='antenna'`. Each time you press the **Next** button, you get the next series of plots.

NOTE: If you use `iteration='antenna'` or `'baseline'`, be aware if you have set `antenna` selection. You can also control whether you see auto-correlations or not using the appropriate syntax, e.g. `antenna='*&&*&` or `antenna='*&&&'` (§ 2.5.4.1).

3.4.3.2 overplot

The `overplot` parameter toggles whether the current plot will be overlaid on the previous plot or subplot (via the `subplot` setting, § `section:edit.plot.opt.subplot`) or will overwrite it. The default is `False` and the new plot will replace the old.

The `overplot` parameter interacts with the `newplot` sub-parameter (see § 3.4.2).

See § 3.4.3.5 for an example using `overplot`.

3.4.3.3 plotrange

The `plotrange` parameter can be used to specify the size of the plot. The format is `[xmin, xmax, ymin, ymax]`. The units are those on the plot. For example,

```
plotrange = [-20,100,15,30]
```

Note that if `xmin=xmax` and/or `ymin=ymax`, then the values will be ignored and a best guess will be made to auto-range that axis. **BETA ALERT:** Unfortunately, the units for the time axis must be in Julian Days, which are the plotted values.

3.4.3.4 plotsymbol

The `plotsymbol` parameter defines both the line or symbol for the data being drawn as well as the color; from the matplotlib online documentation (e.g., type `pl.plot?` for help):

The following line styles are supported:

-	: solid line
--	: dashed line
-.	: dash-dot line
:	: dotted line
.	: points
,	: pixels
o	: circle symbols
^	: triangle up symbols
v	: triangle down symbols
<	: triangle left symbols
>	: triangle right symbols
s	: square symbols
+	: plus symbols
x	: cross symbols
D	: diamond symbols
d	: thin diamond symbols
1	: tripod down symbols
2	: tripod up symbols
3	: tripod left symbols
4	: tripod right symbols

```

h      : hexagon symbols
H      : rotated hexagon symbols
p      : pentagon symbols
|      : vertical line symbols
-      : horizontal line symbols
steps : use gnuplot style 'steps' # kwarg only
The following color abbreviations are supported
b    : blue
g    : green
r    : red
c    : cyan
m    : magenta
y    : yellow
k    : black
w    : white
In addition, you can specify colors in many weird and
wonderful ways, including full names 'green', hex strings
'#008000', RGB or RGBA tuples (0,1,0,1) or grayscale
intensities as a string '0.8'.
Line styles and colors are combined in a single format string, as in
'bo' for blue circles.

```

3.4.3.5 showflags

The `showflags` parameter determines whether *only* unflagged data (`showflags=False`) or flagged (`showflags=True`) data is plotted by this execution. The default is `False` and will show only unflagged “good” data.

Note that if you want to plot both unflagged and flagged data, in different colors, then you need to run `plotxy` twice using `overplot` (see § 3.4.3.2) the second time, e.g.

```
> plotxy(vis="myfile", xaxis='uvdist', yaxis='amp' )
> plotxy(vis="myfile", xaxis='uvdist', yaxis='amp', overplot=True, showflags=True )
```

3.4.3.6 subplot

The `subplot` parameter takes three numbers. The first is the number of y panels (stacking vertically), the second is the number of xpanels (stacking horizontally) and the third is the number of the panel you want to draw into. For example, `subplot=212` would draw into the lower of two panels stacked vertically in the figure.

An example use of subplot capability is shown in Fig 3.3. These were drawn with the commands (for the top, bottom left, and bottom right panels respectively):

```
plotxy('n5921.ms','channel',      # plot channels for the n5921.ms data set
       field='0',                  # plot only first field
       datacolumn='corrected',     # plot corrected data
       plotcolor='',               # over-ride default plot color
```

```

plotsymbol='go',
           # use green circles
subplot=211)          # plot to the top of two panels

plotxy('n5921.ms','x',
       field='0',
       datacolumn='corrected',
       subplot=223,
       plotcolor='',
       plotsymbol='r.')      # red dots

plotxy('n5921.ms','u','v',
       field='0',
       datacolumn='corrected',
       subplot=224,
       plotcolor='',
       plotsymbol='b,')      # blue, somewhat larger dots
                           # NOTE: You can change the gridding
                           # and panel size by manipulating
                           # the ny x nx grid.

```

See also § 3.4.3.1 above, and Figure 3.2 for an example of channel averaging using `iteration` and `subplot`.

3.4.4 Averaging in `plotxy`

The averaging parameters and sub-parameters are:

```

averagemode      = 'vector'        # Select averaging type: vector, scalar
timebin          = '0'             # Length of time-interval in seconds to average
crossscans       = False          # Have time averaging cross scan boundaries?
width            = '1'             # Number of channels to average

```

The choice of `averagemode` controls how the amplitudes are calculated in the average. The default mode is '`vector`', where the complex average is formed by averaging the real and imaginary parts of the relevant visibilities. If '`scalar`' is chosen, then the amplitude of the average is formed by a scalar average of the individual visibility amplitudes.

Time averaging is effected by setting the `timebin` parameter to a value larger than the integration time. Currently, `timebin` takes a string containing the averaging time in seconds, e.g.

```
timebin = '60.0'
```

to plot one-minute averages.

Channel averaging is invoked by setting `width` to a value greater than 1. Currently, the averaging `width` is given as a number of channels.




Figure 3.3: Multi-panel display of visibility versus channel (**top**), antenna array configuration (**bottom left**) and the resulting uv coverage (**bottom right**). The commands to make these three panels respectively are: 1) `plotxy('ngc5921.ms', xaxis='channel', datacolumn='data', field='0', subplot=211, plotcolor='', plotsymbol='go')` 2) `plotxy('ngc5921.ms', xaxis='x', field='0', subplot=223, plotsymbol='r.')`, 3) `plotxy('ngc5921.ms', xaxis='u', yaxis='v', field='0', subplot=224, plotsymbol='b', figfile='ngc5921_multiplot.png')`.

By default, the averaging will not cross `scan` boundaries (as set in the import process). However, if `crossscans=True`, then averaging will cross scans.

Note that data taken in different sub-arrays are never averaged together. Likewise, there is no way to plot data averaged over `field`.

3.4.5 Interactive Flagging in plotxy

Interactive flagging, on the principle of “see it — flag it”, is possible on the X-Y display of the data plotted by `plotxy`. The user can use the cursor to mark one or more regions, and then flag, unflag, or list the data that falls in these zones of the display.

There is a row of buttons below the plot in the window. You can punch the **Mark Region** button (which will appear to depress), then mark a region by left-clicking and dragging the mouse (each click and drag will mark an additional region). You can get rid of all your regions by clicking again on the **Mark Region** button (which will appear to un-depress), or you can use the `ESC` key to remove the last box you drew. Once regions are marked, you can then click on one of the other buttons to take action:

1. **Flag** — flag the points in the region(s),
2. **Unflag** — unflag flagged points in the region(s),
3. **Locate** — spew out a list of the points in the region(s) to the logger (Warning: this could be a long list!).

Hint!
In the plotting environments such as `plotxy`, the `ESC` key can be used to remove the last region box drawn.

Whenever you click on a button, that action occurs without forcing a disk-write (unlike previous versions). If you quit `plotxy` and re-enter, you will see your previous edits.




Figure 3.4: Plot of amplitude versus uv distance, before (left) and after (right) flagging two marked regions. The call was: `plotxy(vis='ngc5921.ms',xaxis='uvdist', field='1445*')`.

A table with the name <msname>.flagversions (where vis=<msname>) will be created in the same directory if it does not exist already.

It is recommended that you save important flagging stages using the `flagmanager` task (§ 3.2).

3.4.6 Flag extension in plotxy

Flag extension is controlled using `extendflag=T` and its sub-parameters:

```
extendflag      =  True    # Have flagging extend to other data points?
extendcorr     =  ''      # flagging correlation extension type
extendchan     =  ''      # flagging channel extension type
extendspw      =  ''      # flagging spectral window extension type
extendant      =  ''      # flagging antenna extension type
extendtime     =  ''      # flagging time extension type
```

The use of `extendflag` enables the user to plot a subset of the data and extend the flagging to a wider set.

BETA ALERT: Using the `extendflag` options will greatly slow down the flagging in `plotxy`. You will see a long delay after hitting the **Flag** button, with lots of logger messages as it goes through each flag. Fixing this requires a refactoring of `plotxy` which is underway starting in Patch 4 development.

Setting `extendchan='all'` will extend the flagging to other channels in the same `spw` as the displayed point. For example, if `spw='0:0'` and channel 0 is displayed, then flagging will extend to all channels in spw 0.

The `extendcorr` sub-parameter will extend the flagging beyond the correlations displayed. If `extendcorr='all'`, then all correlations will be flagged, e.g. with RR displayed RR,RL,LR,LL will be flagged. If `extendcorr='half'`, then the extension will be to those correlations in common with that show, e.g. with RR displayed then RR,RL,LR will be flagged.

Setting `extendspw='all'` will extend the flagging to all other `spw` for the selection. Using the same example as above, with `spw='0:0'` displayed, then channel 0 in ALL `spw` will be flagged. Note that use of `extendspw` could result in unintended behavior if the `spw` have different numbers of channels, or if it is used in conjunction with `extendchan`.

WARNING: use of the following options, particularly in conjunction with other flag extensions, may lead to deletion of much more data than desired. Be careful!

Setting `extendant='all'` will extend the flagging to all baselines that have antennas in common with those displayed and marked. For example, if `antenna='1&2'` is shown, then ALL baselines to BOTH antennas 1 and 2 will be flagged. Currently, there is no option to extend the flag to ONLY baselines to the first (or second) antenna in a displayed pair, so it is better to use `flagdata` to remove specific antennas.

Setting `extendtime='all'` will extend the flagging to all times matching the other selection or extension for the data in the marked region.

We recommend that before using the flag extensions, you use `flagmanager` to save a copy of the previous flags. That way, you can revert back if something goes wrong.

3.4.7 Printing from `plotxy`

There are two ways to get hardcopy plots in `plotxy`.

The first is to use the “disk save” icon from the interactive plot GUI to print the current plot. This will bring up a sub-menu GUI that will allow you to choose the filename and format. The allowed formats are `.png` (PNG), `.eps` (EPS), and `svg` (SVG). If you give the filename with a suffix (`.png`, `.eps`, or `svg`) it will make a plot of that type. Otherwise it will put a suffix on depending on the format chosen from the menu.

BETA ALERT: The plot files produced by the EPS option can be large, and the SVG files can be very large. The PNG is the smallest.

The second is to specify a `figfile`. You probably want to disable the GUI using `interactive=False` in this case. The type of plot file that is made will depend upon the filename suffix. The allowed choices are `.png` (PNG), `.eps` (EPS), and `svg` (SVG).

This latter option is most useful from scripts. For example,

```
default('plotxy')
vis = 'ngc5921.ms'
field = '2'
spw = ''
xaxis = 'uvdist'
yaxis = 'amp'
interactive=False
figfile = 'ngc5921.uvplot.amp.png'
plotxy()
```

will plot amplitude versus uv-distance in PNG format. No `plotxy` GUI will appear.

BETA ALERT: if you use this option to print to `figfile` with an `iteration` set, you will only get the first plot.

3.4.8 Exiting `plotxy`

You can use the **Quit** button to clear the plot from the window and detach from the MS. You can also dismiss the window by killing it with the X on the frame, which will also detach the MS.

You can also just leave it alone. The plotter pretty much keeps running in the background even when it looks like it’s done! You can keep doing stuff in the plotter window, which is where the `overplot` parameter comes in. Note that the `plotcal` task (§ 4.5.1) will use the same window, and can also overplot on the same panel.

If you leave `plotxy` running, beware of (for instance) deleting or writing over the MS without stopping. It may work from a memory version of the MS or crash.

3.4.9 Example session using plotxy

The following is an example of interactive plotting and flagging using `plotxy` on the Jupiter 6cm continuum VLA dataset. This is extracted from the script `jupiter6cm_usecase.py` available in the script area.

This assumes that the MS `jupiter6cm.usecase.ms` is on disk with `flagautocorr` already run.

BETA ALERT: Exact syntax may be slightly different in your version as the Beta Release progress.

```
default('plotxy')

vis = 'jupiter6cm.usecase.ms'

# The fields we are interested in: 1331+305,JUPITER,0137+331
selectdata = True

# First we do the primary calibrator
field = '1331+305'

# Plot only the RR and LL for now
correlation = 'RR LL'

# Plot amplitude vs. uvdist
xaxis = 'uvdist'
yaxis = 'amp'
multicolor = 'both'

# The easiest thing is to iterate over antennas
iteration = 'antenna'

plotxy()

# You'll see lots of low points as you step through RR LL RL LR
# A basic clip at 0.75 for RR LL and 0.055 for RL LR will work
# If you want to do this interactively, set
iteration = ''

plotxy()

# You can also use flagdata to do this non-interactively
# (see below)

# Now look at the cross-polar products
correlation = 'RL LR'

plotxy()

#-----
```

```
# Now do calibrator 0137+331
field = '0137+331'
correlation = 'RR LL'
xaxis = 'uvdist'
spw = ''
iteration = ''
antenna = ''

plotxy()

# You'll see a bunch of bad data along the bottom near zero amp
# Draw a box around some of it and use Locate
# Looks like much of it is Antenna 9 (ID=8) in spw=1

xaxis = 'time'
spw = '1'
correlation = ''

# Note that the strings like antenna='9' first try to match the
# NAME which we see in listobs was the number '9' for ID=8.
# So be careful here (why naming antennas as numbers is bad).
antenna = '9'

plotxy()

# YES! the last 4 scans are bad. Box 'em and flag.

# Go back and clean up
xaxis = 'uvdist'
spw = ''
antenna = ''
correlation = 'RR LL'

plotxy()

# Box up the bad low points (basically a clip below 0.52) and flag

# Note that RL,LR are too weak to clip on.

#-----
# Finally, do JUPITER
field = 'JUPITER'
correlation = ''
iteration = ''
xaxis = 'time'

plotxy()

# Here you will see that the final scan at 22:00:00 UT is bad
# Draw a box around it and flag it!
```

```

# Now look at whats left
correlation = 'RR LL'
xaxis = 'uvdist'
spw = '1'
antenna = ''
iteration = 'antenna'

plotxy()

# As you step through, you will see that Antenna 9 (ID=8) is often
# bad in this spw. If you box and do Locate (or remember from
# 0137+331) its probably a bad time.

# The easiest way to kill it:

antenna = '9'
iteration = ''
xaxis = 'time'
correlation = ''

plotxy()

# Draw a box around all points in the last bad scans and flag 'em!

# Now clean up the rest
xaxis = 'uvdist'
correlation = 'RR LL'
antenna = ''
spw = ''

# You will be drawing many tiny boxes, so remember you can
# use the ESC key to get rid of the most recent box if you
# make a mistake.

plotxy()

# Note that the end result is we've flagged lots of points
# in RR and LL. We will rely upon imager to ignore the
# RL LR for points with RR LL flagged!

```

3.5 Non-Interactive Flagging using flagdata

Task `flagdata` will flag the visibility data set based on the specified data selections, most of the information coming from a run of the `listobs` task (with/without `verbose=True`). Currently you can select based on any combination of:

- antennas (`antenna`)

- baselines (`antenna`)
- spectral windows and channels (`spw`)
- correlation types (`correlation`)
- field ids or names (`field`)
- uv-ranges (`uvrange`)
- times (`timerange`) or scan numbers (`scan`)
- antenna arrays (`array`)

and choose to flag, unflag, clip (`setclip` and sub-parameters), and remove the first part of each scan (`setquack`) and/or the autocorrelations (`autocorr`).

The inputs to `flagdata` are:

```
# flagdata :: Flag/Clip data based on selections:

vis          =      ''    # Name of input visibility file
antenna      =      ''    # antenna/baseline
spw          =      ''    # spectral-window/frequency/channel
correlation   =      ''    # Select data based on correlation
field         =      ''    # field names or indices
uvrange       =      ''    # uv range (def=meters)
timerange     =      ''    # time range
scan          =      ''    # scan number
feed          =      ''    # feed number - NOT ENABLED
array         =      ''    # array
mode          = 'manualflag' # Mode (manualflag, autoflag, summary, quack)
    autocorr    =    False  # Flag autocorrelations
    unflag      =    False  # Unflag the data specified
    clipexpr    = 'ABS RR' # Expression to clip on
    clipminmax  =      []   # Range to use for clipping
    clipcolumn   = 'DATA'  # Data column to use for clipping
    clipoutside  =    True   # Clip outside the range, or within it
```

The default flagging `mode` is '`manualflag`'. See § 3.5.1.1 more more on this option.

The `mode='summary'` will print out a summary of the current state of flagging into the `logger`.

The `mode='quack'` will allow dropping of integrations from the beginning of scans. See § 3.5.1.2 for details.

BETA ALERT: the `mode='autoflag'` option is not currently supported.

3.5.1 Flag Antenna/Channels

The following commands give the results shown in Figure 3.5:

```
default{'plotxy'}
plotxy('ngc5921.ms', 'channel', iteration='antenna', subplot=311)
default('flagdata')
flagdata(vis='ngc5921.ms', antenna='0', spw='0:10~15')
default plotxy
plotxy('ngc5921.ms', 'channel', iteration='antenna', subplot=311)
```




Figure 3.5: `flagdata`: Example showing before and after displays using a selection of one antenna and a range of channels. Note that each invocation of the `flagdata` task represents a cumulative selection, i.e., running `antenna='0'` will flag all data with antenna 0, while `antenna='0', spw='0:10~15'` will flag only those channels on antenna 0.

3.5.1.1 Manual flagging and clipping in `flagdata`

For `mode='manualflag'`, manual flagging and clipping is controlled by the sub-parameters:

```
mode          = 'manualflag' # Mode (manualflag, autoflag, summary, quack)
autocorr     = False      # Flag autocorrelations
unflag       = False      # Unflag the data specified
clipexpr    = 'ABS RR'   # Expression to clip on
clipminmax  = []         # Range to use for clipping
clipcolumn  = 'DATA'     # Data column to use for clipping
clipoutside = True       # Clip outside the range, or within it
```

The following commands give the results shown in Figure 3.6:

```
plotxy('ngc5921.ms','uvdist')
flagdata(vis='ngc5921.ms',clipexpr='LL',clipminmax=[0.0,1.6],clipoutside=True)
plotxy('ngc5921.ms','uvdist')
```




Figure 3.6: `flagdata`: Flagging example using the clip facility.

3.5.1.2 Flagging the beginning of scans

You can use the `mode='quack'` option to drop integrations from the beginning of scans (as in the AIPS task QUACK):

```
mode          =      'quack'          #  Mode (manualflag,autoflag,summary,quack)
autocorr      =      False           #  Flag autocorrelations
unflag        =      False           #  Unflag the data specified
quackinterval =      0.0            #  Quack n seconds from scan beginning
```

Note that the time is measured from the first integration in the MS for a given scan, and this is often already flagged by the online system.

For example, assuming the integration time is 3.3 seconds (e.g. for VLA), then

```
mode = 'quack'
quackinterval = 14.0
```

will flag the first 4 integrations in every scan.

3.6 Browse the Data

The **browsetable** task is available for viewing data directly (and handles all CASA tables, including Measurement Sets, calibration tables, and images). This task brings up the CASA Qt **casabrowser**, which is a separate program. You can launch this from outside **casapy**.

The default inputs are:

```
# browsetable :: Browse a table (MS, calibration table, image)

tablename      =      ''      # Name of input table
```

Currently, its single input is the **tablename**, so an example would be:

```
browsetable('ngc5921.ms')
```

For an MS such as this, it will come up with a browser of the **MAIN** table (see Fig 3.7). If you want to look at sub-tables, use the tab **table keywords** along the left side to bring up a panel with the sub-tables listed (Fig 3.8), then choose (left-click) a table and **View:Details** to bring it up (Fig 3.9). You can left-click on a cell in a table to view the contents.

Note that one useful feature is that you can Edit the table and its contents. Use the **Edit table** choice from the **Edit** menu, or click on the **Edit** button. Be careful with this, and make a backup copy of the table before editing!

Use the **Close Tables and Exit** option from the **Files** menu to quit the **casabrowser**.

There are alot of features in the **casabrowser** that are not fully documented here. Feel free to explore the capabilities such as plotting and sorting!

BETA ALERT: You are likely to find that the **casabrowser** needs to get a table lock before proceeding. Use the **clearstat** command to clear the lock status in this case.

3.7 Examples of Data Display and Flagging

```
#####
#                               #
# Display and Flagging Use Case Jupiter 6cm VLA      #
#                               #
# Last Updated STM 2008-03-25 (Beta Patch 1.0)       #
#                               #
#####
```

```
scriptmode = True
prefix='jupiter6cm.usecase'
msfile = prefix + '.ms'
```




Figure 3.7: `browsetable`: The browser displays the main table within a frame. You can scroll through the data (x=columns of the MAIN table, and y=the rows) or select a specific page or row as desired. By default, 1000 rows of the table are loaded at a time, but you can step through the MS in batches.

```
#=====
#
# List a summary of the MS
#
print '--Listobs--'
default('listobs')
vis = msfile

# Don't default this one and make use of the previous setting of
# vis. Remember, the variables are GLOBAL!

print "Use listobs to print verbose summary to logger"

# You may wish to see more detailed information, in this case
# use the verbose = True option
verbose = True

listobs()
```





Figure 3.8: `browsetable`: You can use the tab for Table Keywords to look at other tables within an MS. You can then double-click on a table to view its contents.

```
# You should get in your logger window and in the casapy.log file
# something like:
#
#     Observer: FLUX99      Project:
# Observation: VLA
#
# Data records: 2021424      Total integration time = 85133.2 seconds
# Observed from  23:15:27    to  22:54:20
#
#     ObservationID = 0      ArrayID = 0
#     Date          Timerange            Scan  FldId FieldName      SpwIds
# 15-Apr-1999/23:15:26.7 - 23:16:10.0   1      0 0137+331      [0, 1]
#                                23:38:40.0 - 23:48:00.0   2      1 0813+482      [0, 1]
#                                23:53:40.0 - 23:55:20.0   3      2 0542+498      [0, 1]
# 16-Apr-1999/00:22:10.1 - 00:23:49.9   4      3 0437+296      [0, 1]
#                                00:28:23.3 - 00:30:00.1   5      4 VENUS        [0, 1]
#                                00:48:40.0 - 00:50:20.0   6      1 0813+482      [0, 1]
#                                00:56:13.4 - 00:57:49.9   7      2 0542+498      [0, 1]
#                                01:10:20.1 - 01:11:59.9   8      5 0521+166      [0, 1]
#                                01:23:29.9 - 01:25:00.1   9      3 0437+296      [0, 1]
#                                01:29:33.3 - 01:31:10.0  10     4 VENUS        [0, 1]
```

Figure 3.9: `browsetable`: Viewing the SOURCE table of the MS.

```

#      01:49:50.0 - 01:51:30.0    11      6 1411+522      [0, 1]
#      02:03:00.0 - 02:04:30.0    12      7 1331+305      [0, 1]
#      02:17:30.0 - 02:19:10.0    13      1 0813+482      [0, 1]
#      02:24:20.0 - 02:26:00.0    14      2 0542+498      [0, 1]
#      02:37:49.9 - 02:39:30.0    15      5 0521+166      [0, 1]
#      02:50:50.1 - 02:52:20.1    16      3 0437+296      [0, 1]
#      02:59:20.0 - 03:01:00.0    17      6 1411+522      [0, 1]
#      03:12:30.0 - 03:14:10.0    18      7 1331+305      [0, 1]
#      03:27:53.3 - 03:29:39.9    19      1 0813+482      [0, 1]
#      03:35:00.0 - 03:36:40.0    20      2 0542+498      [0, 1]
#      03:49:50.0 - 03:51:30.1    21      6 1411+522      [0, 1]
#      04:03:10.0 - 04:04:50.0    22      7 1331+305      [0, 1]
#      04:18:49.9 - 04:20:40.0    23      1 0813+482      [0, 1]
#      04:25:56.6 - 04:27:39.9    24      2 0542+498      [0, 1]
#      04:42:49.9 - 04:44:40.0    25      8 MARS          [0, 1]
#      04:56:50.0 - 04:58:30.1    26      6 1411+522      [0, 1]
#      05:24:03.3 - 05:33:39.9    27      7 1331+305      [0, 1]
#      05:48:00.0 - 05:49:49.9    28      1 0813+482      [0, 1]
#      05:58:36.6 - 06:00:30.0    29      8 MARS          [0, 1]
#      06:13:20.1 - 06:14:59.9    30      6 1411+522      [0, 1]
#      06:27:40.0 - 06:29:20.0    31      7 1331+305      [0, 1]
#      06:44:13.4 - 06:46:00.0    32      1 0813+482      [0, 1]
#      06:55:06.6 - 06:57:00.0    33      8 MARS          [0, 1]

```

```

#      07:10:40.0 - 07:12:20.0    34      6 1411+522      [0, 1]
#      07:28:20.0 - 07:30:10.1    35      7 1331+305      [0, 1]
#      07:42:49.9 - 07:44:30.0    36      8 MARS          [0, 1]
#      07:58:43.3 - 08:00:39.9    37      6 1411+522      [0, 1]
#      08:13:30.0 - 08:15:19.9    38      7 1331+305      [0, 1]
#      08:27:53.4 - 08:29:30.0    39      8 MARS          [0, 1]
#      08:42:59.9 - 08:44:50.0    40      6 1411+522      [0, 1]
#      08:57:09.9 - 08:58:50.0    41      7 1331+305      [0, 1]
#      09:13:03.3 - 09:14:50.1    42      9 NGC7027       [0, 1]
#      09:26:59.9 - 09:28:40.0    43      6 1411+522      [0, 1]
#      09:40:33.4 - 09:42:09.9    44      7 1331+305      [0, 1]
#      09:56:19.9 - 09:58:10.0    45      9 NGC7027       [0, 1]
#      10:12:59.9 - 10:14:50.0    46      8 MARS          [0, 1]
#      10:27:09.9 - 10:28:50.0    47      6 1411+522      [0, 1]
#      10:40:30.0 - 10:42:00.0    48      7 1331+305      [0, 1]
#      10:56:10.0 - 10:57:50.0    49      9 NGC7027       [0, 1]
#      11:28:30.0 - 11:35:30.0    50      10 NEPTUNE      [0, 1]
#      11:48:20.0 - 11:50:10.0    51      6 1411+522      [0, 1]
#      12:01:36.7 - 12:03:10.0    52      7 1331+305      [0, 1]
#      12:35:33.3 - 12:37:40.0    53      11 URANUS       [0, 1]
#      12:46:30.0 - 12:48:10.0    54      10 NEPTUNE      [0, 1]
#      13:00:29.9 - 13:02:10.0    55      6 1411+522      [0, 1]
#      13:15:23.3 - 13:17:10.1    56      9 NGC7027       [0, 1]
#      13:33:43.3 - 13:35:40.0    57      11 URANUS       [0, 1]
#      13:44:30.0 - 13:46:10.0    58      10 NEPTUNE      [0, 1]
#      14:00:46.7 - 14:01:39.9    59      0 0137+331      [0, 1]
#      14:10:40.0 - 14:12:09.9    60      12 JUPITER      [0, 1]
#      14:24:06.6 - 14:25:40.1    61      11 URANUS       [0, 1]
#      14:34:30.0 - 14:36:10.1    62      10 NEPTUNE      [0, 1]
#      14:59:13.4 - 15:00:00.0    63      0 0137+331      [0, 1]
#      15:09:03.3 - 15:10:40.1    64      12 JUPITER      [0, 1]
#      15:24:30.0 - 15:26:20.1    65      9 NGC7027       [0, 1]
#      15:40:10.0 - 15:45:00.0    66      11 URANUS       [0, 1]
#      15:53:50.0 - 15:55:20.0    67      10 NEPTUNE      [0, 1]
#      16:18:53.4 - 16:19:49.9    68      0 0137+331      [0, 1]
#      16:29:10.1 - 16:30:49.9    69      12 JUPITER      [0, 1]
#      16:42:53.4 - 16:44:30.0    70      11 URANUS       [0, 1]
#      16:54:53.4 - 16:56:40.0    71      9 NGC7027       [0, 1]
#      17:23:06.6 - 17:30:40.0    72      2 0542+498      [0, 1]
#      17:41:50.0 - 17:43:20.0    73      3 0437+296      [0, 1]
#      17:55:36.7 - 17:57:39.9    74      4 VENUS         [0, 1]
#      18:19:23.3 - 18:20:09.9    75      0 0137+331      [0, 1]
#      18:30:23.3 - 18:32:00.0    76      12 JUPITER      [0, 1]
#      18:44:49.9 - 18:46:30.0    77      9 NGC7027       [0, 1]
#      18:59:13.3 - 19:00:59.9    78      2 0542+498      [0, 1]
#      19:19:10.0 - 19:21:20.1    79      5 0521+166      [0, 1]
#      19:32:50.1 - 19:34:29.9    80      3 0437+296      [0, 1]
#      19:39:03.3 - 19:40:40.1    81      4 VENUS         [0, 1]
#      20:08:06.7 - 20:08:59.9    82      0 0137+331      [0, 1]
#      20:18:10.0 - 20:19:50.0    83      12 JUPITER      [0, 1]
#      20:33:53.3 - 20:35:40.1    84      1 0813+482      [0, 1]

```

```

#          20:40:59.9 - 20:42:40.0    85      2 0542+498      [0, 1]
#          21:00:16.6 - 21:02:20.1    86      5 0521+166      [0, 1]
#          21:13:53.4 - 21:15:29.9    87      3 0437+296      [0, 1]
#          21:20:43.4 - 21:22:30.0    88      4 VENUS        [0, 1]
#          21:47:26.7 - 21:48:20.1    89      0 0137+331      [0, 1]
#          21:57:30.0 - 21:59:10.0    90      12 JUPITER      [0, 1]
#          22:12:13.3 - 22:14:00.1    91      2 0542+498      [0, 1]
#          22:28:33.3 - 22:30:19.9    92      4 VENUS        [0, 1]
#          22:53:33.3 - 22:54:19.9    93      0 0137+331      [0, 1]
#
# Fields: 13
#   ID  Name       Right Ascension  Declination  Epoch
#   0   0137+331   01:37:41.30    +33.09.35.13 J2000
#   1   0813+482   08:13:36.05    +48.13.02.26 J2000
#   2   0542+498   05:42:36.14    +49.51.07.23 J2000
#   3   0437+296   04:37:04.17    +29.40.15.14 J2000
#   4   VENUS      04:06:54.11    +22.30.35.91 J2000
#   5   0521+166   05:21:09.89    +16.38.22.05 J2000
#   6   1411+522   14:11:20.65    +52.12.09.14 J2000
#   7   1331+305   13:31:08.29    +30.30.32.96 J2000
#   8   MARS       14:21:41.37    -12.21.49.45 J2000
#   9   NGC7027    21:07:01.59    +42.14.10.19 J2000
#   10  NEPTUNE    20:26:01.14    -18.54.54.21 J2000
#   11  URANUS    21:15:42.83    -16.35.05.59 J2000
#   12  JUPITER    00:55:34.04    +04.45.44.71 J2000
#
# Spectral Windows: (2 unique spectral windows and 1 unique polarization setups)
#   SpwID #Chans Frame Ch1(MHz)  Resoln(kHz) TotBW(kHz) Ref(MHz)  Corrs
#   0       1   TOPO  4885.1     50000      50000    4885.1    RR RL LR LL
#   1       1   TOPO  4835.1     50000      50000    4835.1    RR RL LR LL
#
# Feeds: 28: printing first row only
#   Antenna  Spectral Window  # Receptors  Polarizations
#   1         -1              2            [           R, L]
#
# Antennas: 27:
#   ID  Name  Station  Diam.  Long.  Lat.
#   0   1    VLA:W9  25.0 m  -107.37.25.1 +33.53.51.0
#   1   2    VLA:N9  25.0 m  -107.37.07.8 +33.54.19.0
#   2   3    VLA:N3  25.0 m  -107.37.06.3 +33.54.04.8
#   3   4    VLA:N5  25.0 m  -107.37.06.7 +33.54.08.0
#   4   5    VLA:N2  25.0 m  -107.37.06.2 +33.54.03.5
#   5   6    VLA:E1  25.0 m  -107.37.05.7 +33.53.59.2
#   6   7    VLA:E2  25.0 m  -107.37.04.4 +33.54.01.1
#   7   8    VLA:N8  25.0 m  -107.37.07.5 +33.54.15.8
#   8   9    VLA:E8  25.0 m  -107.36.48.9 +33.53.55.1
#   9   10   VLA:W3  25.0 m  -107.37.08.9 +33.54.00.1
#  10  11   VLA:N1  25.0 m  -107.37.06.0 +33.54.01.8
#  11  12   VLA:E6  25.0 m  -107.36.55.6 +33.53.57.7
#  12  13   VLA:W7  25.0 m  -107.37.18.4 +33.53.54.8
#  13  14   VLA:E4  25.0 m  -107.37.00.8 +33.53.59.7

```

```

# 14 15 VLA:N7 25.0 m -107.37.07.2 +33.54.12.9
# 15 16 VLA:W4 25.0 m -107.37.10.8 +33.53.59.1
# 16 17 VLA:W5 25.0 m -107.37.13.0 +33.53.57.8
# 17 18 VLA:N6 25.0 m -107.37.06.9 +33.54.10.3
# 18 19 VLA:E7 25.0 m -107.36.52.4 +33.53.56.5
# 19 20 VLA:E9 25.0 m -107.36.45.1 +33.53.53.6
# 21 22 VLA:W8 25.0 m -107.37.21.6 +33.53.53.0
# 22 23 VLA:W6 25.0 m -107.37.15.6 +33.53.56.4
# 23 24 VLA:W1 25.0 m -107.37.05.9 +33.54.00.5
# 24 25 VLA:W2 25.0 m -107.37.07.4 +33.54.00.9
# 25 26 VLA:E5 25.0 m -107.36.58.4 +33.53.58.8
# 26 27 VLA:N4 25.0 m -107.37.06.5 +33.54.06.1
# 27 28 VLA:E3 25.0 m -107.37.02.8 +33.54.00.5
#
# Tables:
# MAIN 2021424 rows
# ANTENNA 28 rows
# DATA_DESCRIPTION 2 rows
# DOPPLER <absent>
# FEED 28 rows
# FIELD 13 rows
# FLAG_CMD <empty>
# FREQ_OFFSET <absent>
# HISTORY 7058 rows
# OBSERVATION 1 row
# POINTING 2604 rows
# POLARIZATION 1 row
# PROCESSOR <empty>
# SOURCE <empty> (see FIELD)
# SPECTRAL_WINDOW 2 rows
# STATE <empty>
# SYSCAL <absent>
# WEATHER <absent>

#
#=====
# Data Examination and Flagging
#=====
#
# Get rid of the autocorrelations from the MS
#
print '--Flagautocorr--'

print "Use flagautocorr to zap auto-correlations"
print "Not strictly necessary but here for completeness"

# Don't default this one either

flagautocorr()

#

```

```
#=====
#  
# Use Flagmanager to save a copy of the flags  
#  
print '--Flagmanager--'  
default('flagmanager')  
  
print "Use flagmanager to save these new flags"  
print "These go in the .flagversions sub-dir"  
  
vis = msfile  
  
# Save a copy of the MAIN table flags  
  
mode = 'save'  
versionname = 'flagautocorr'  
comment = 'flagged autocorr'  
merge = 'replace'  
  
flagmanager()  
  
# If you look in the 'jupiter6cm.usecase.ms.flagversions/  
# you'll see flags.flagautocorr there along with the  
# flags.Original that importuvfits made for you  
# Or use  
  
mode = 'list'  
  
print "Now use flagmanager to list flag versions"  
  
flagmanager()  
  
# In the logger you will see something like:  
#  
# MS : /home/sandrock2/smyers/Testing2/Aug07/jupiter6cm.usecase.ms  
#  
# main : working copy in main table  
# Original : Original flags at import into CASA  
# flagautocorr : flagged autocorr  
# See logger for flag versions for this file  
  
#  
#=====
```

```
vis = msfile

# The fields we are interested in: 1331+305, JUPITER, 0137+331
selectdata = True

# First we do the primary calibrator
field = '1331+305'

# Plot only the RR and LL for now
correlation = 'RR LL'

# Plot amplitude vs. uvdist
xaxis = 'uvdist'
yaxis = 'amp'
multicolor = 'both'

# Use the field name as the title
selectplot = True
title = field+"  "

# The easiest thing is to iterate over antennas
iteration = 'antenna'

plotxy()

print ""
print "-----"
print "Plotxy"
print "Showing 1331+305 with iteration='antenna' "
print "Use Next button to step through antennas"
print "You see some low-level crud that you want to clip out"

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

# You'll see lots of low points as you step through RR LL RL LR
# A basic clip at 0.75 for RR LL and 0.055 for RL LR will work
# If you want to do this interactively, set
iteration = ''

plotxy()

print ""
print "-----"
print "Now showing RR LL for all antennas"
print "Use MarkRegion then draw boxes around points to flag"
print "You can use ESC to drop last drawn box"
print "When happy with boxes, hit Flag to flag"
print "You can repeat as necessary"
```

```
# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

# You can also use flagdata to do this non-interactively
# (see below)

# Now look at the cross-polar products
correlation = 'RL LR'

plotxy()

print ""
print "-----"
print "Looking at RL LR"
print "Now flag the bad data here"

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

#-----
# Now do calibrator 0137+331
field = '0137+331'
correlation = 'RR LL'
xaxis = 'uvdist'
spw = ''
iteration = ''
antenna = ''

title = field+"  "

plotxy()

# You'll see a bunch of bad data along the bottom near zero amp
# Draw a box around some of it and use Locate
# Looks like much of it is Antenna 9 (ID=8) in spw=1

print ""
print "-----"
print "Plotting 0137+331 RR LL all antennas"
print "You see bad data along bottom"
print "Mark a box around a bit of it and hit Locate"
print "Look in logger to see what it is"
print "You see much is Antenna 9 (ID=8) in spw 1"

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

xaxis = 'time'
```

```
spw = '1'
correlation = ''

# Note that the strings like antenna='9' first try to match the
# NAME which we see in listobs was the number '9' for ID=8.
# So be careful here (why naming antennas as numbers is bad).
antenna = '9'

plotxy()

# YES! the last 4 scans are bad. Box 'em and flag.

print ""
print "-----"
print "Plotting vs. time antenna='9' and spw='1' "
print "Box up last 4 scans which are bad and Flag"

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

# Go back and clean up
xaxis = 'uvdist'
spw = ''
antenna = ''
correlation = 'RR LL'

plotxy()

# Box up the bad low points (basically a clip below 0.52) and flag

# Note that RL,LR are too weak to clip on.

print ""
print "-----"
print "Back to all data"
print "Clean up remaining bad points"

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

#-----
# Finally, do JUPITER
field = 'JUPITER'
correlation = 'RR LL'
iteration = ''
xaxis = 'uvdist'

title = field+" "
```

```
plotxy()

# Here you will see that the final scan at 22:00:00 UT is bad
# Draw a box around it and flag it!

print ""
print "-----"
print "Now plot JUPITER versus uvdist"
print "Lots of bad stuff near bottom"
print "Lets go and find it - try Locate"
print "Looks like lots of different antennas but at same time"

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

correlation = ''
xaxis = 'time'

plotxy()

# Here you will see that the final scan at 22:00:00 UT is bad
# Draw a box around it and flag it!

print ""
print "-----"
print "Now plotting vs. time"
print "See bad scan at end - flag it!"

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

# Now look at whats left
correlation = 'RR LL'
xaxis = 'uvdist'
spw = '1'
antenna = ''
iteration = 'antenna'

plotxy()

# As you step through, you will see that Antenna 9 (ID=8) is often
# bad in this spw. If you box and do Locate (or remember from
# 0137+331) its probably a bad time.

print ""
print "-----"
print "Step through antennas with Next"
print "See bad Antenna 9 (ID 8) as in 0137+331"
```

```
# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

# The easiest way to kill it:

antenna = '9'
iteration = ''
xaxis = 'time'
correlation = ''

plotxy()

# Draw a box around all points in the last bad scans and flag 'em!

print ""
print "-----"
print "Now plotting vs. time antenna 9 spw 1"
print "Box up the bad scans and Flag"

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

# Now clean up the rest
xaxis = 'uvdist'
correlation = 'RR LL'
antenna = ''
spw = ''

# You will be drawing many tiny boxes, so remember you can
# use the ESC key to get rid of the most recent box if you
# make a mistake.

plotxy()

# Note that the end result is we've flagged lots of points
# in RR and LL. We will rely upon imager to ignore the
# RL LR for points with RR LL flagged!

print ""
print "-----"
print "Back to uvdist plot, see remaining bad data"
print "You can draw little boxes around the outliers and Flag"
print "Depends how patient you are in drawing boxes!"
print "Could also use Locate to find where they come from"

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')
```

```
print "Done with plotxy!"  
  
#  
#=====  
#  
# Use Flagmanager to save a copy of the flags so far  
#  
print '--Flagmanager--'  
default('flagmanager')  
  
print "Now will use flagmanager to save a copy of the flags we just made"  
print "These are named xyflags"  
  
vis = msfile  
mode = 'save'  
versionname = 'xyflags'  
comment = 'Plotxy flags'  
merge = 'replace'  
  
flagmanager()  
  
#  
#=====  
#  
# You can use Flagdata to explicitly clip the data also  
#  
print '--Flagdata--'  
default('flagdata')  
  
print "As a demonstration show how to clip the data with flagdata"  
print "Note we had already flagged many of these interactively"  
  
vis = msfile  
  
# Set some clipping regions  
mode = 'manualflag'  
clipcolumn = 'DATA'  
clipoutside = False  
  
# Clip calibrators  
field = '1331+305'  
clipexpr = 'ABS RR'  
clipminmax = [0.0,0.75]  
flagdata()  
  
clipexpr = 'ABS LL'  
clipminmax = [0.0,0.75]  
flagdata()  
  
clipexpr = 'ABS RL'  
clipminmax = [0.0,0.055]
```

```
flagdata()

clipexpr = 'ABS LR'
clipminmax = [0.0,0.055]
flagdata()

field = '0137+331'
clipexpr = 'ABS RR'
clipminmax = [0.0,0.55]
flagdata()

clipexpr = 'ABS LL'
clipminmax = [0.0,0.55]
flagdata()

# You can also do the antenna edits on 0137+331 and JUPITER
# with flagdata

# Done with flagging

=====
#
# Use Flagmanager to list all saved versions
#
print '--Flagmanager--'
default('flagmanager')

print "Now will use flagmanager to list all the versions we saved"

vis = msfile
mode = 'list'

flagmanager()

#=====
=====
```

Chapter 4

Synthesis Calibration

This chapter explains how to calibrate interferometer data within the CASA task system. Calibration is the process of determining the complex correction factors that must be applied to each visibility in order to make them as close as possible to what an idealized interferometer would measure, such that when the data is imaged an accurate picture of the sky is obtained. This is not an arbitrary process, and there is a philosophy behind the CASA calibration methodology (see § 4.2.1 for more on this). For the most part, calibration in CASA using the tasks is not too different than calibration in other packages such as AIPS or Miriad, so the user should not be alarmed by cosmetic differences such as task and parameter names!

Inside the Toolkit:

The workhorse for synthesis calibration is the `cb` tool.

4.1 Calibration Tasks

The standard set of `calibration` tasks are:

- `accum` — Accumulate incremental calibration solutions into a cumulative cal table (§ 4.5.4),
- `applycal` — Apply calculated calibration solutions (§ 4.6.1),
- `bandpass` — B calibration solving; supports pre-apply of other calibrations (§ 4.4.2),
- `clearcal` — Re-initialize visibility data set calibration data (§ 4.6.3),
- `fluxscale` — Bootstrap the flux density scale from standard calibration sources (§ 4.4.4),
- `gaincal` — G calibration solving; supports pre-apply of other calibrations (§ 4.4.3),
- `listcal` — list calibration solutions (§ 4.5.2),
- `plotcal` — Plot calibration solutions (§ 4.5.1),
- `polcal` — polarization calibration (§ 4.4.5),

- **setjy** — Compute the model visibility for a specified source flux density (§ 4.3.4),
- **smoothcal** — Smooth calibration solutions derived from one or more sources (§ 4.5.3),
- **split** — Write out new MS containing calibrated data from a subset of the original MS (§ 4.7.1).

There are some development versions of calibration and utility tasks that are recently added to the Beta Release suite:

- **hanningsmooth** — apply a Hanning smoothing filter to spectral-line uv data (§ 4.7.2),
- **uvcontsub** — uv-plane continuum fitting and subtraction (§ 4.7.4),
- **uvsub** — subtract the transform of a model image from the uv data (§ 4.7.3).

These are not yet full-featured, and may have only rudimentary controls and options.

Finally, there are also more advanced and experimental calibration tasks available in this release:

- **blcal** — *baseline-based* gain or bandpass calibration; supports pre-apply of other calibrations (§ 4.4.6),
- **fringecal** — *Experimental: baseline-based* fringe-fitting calibration solving; supports pre-apply of other calibrations (§ 4.4.7),
- **uvmodelfit** — fit a component source model to the uv data (§ 4.7.5).

The following sections outline the use of these tasks in standard calibration processes.

Information on other useful tasks and parameter setting can be found in:

- **listobs** — list what is in a MS (§ 2.3),
- **plotxy** — X-Y plotting and editing (§ 3.4),
- **flagdata** — non-interactive data flagging (§ 3.5),
- data selection — general data selection syntax (§ 2.5).

4.2 The Calibration Process — Outline and Philosophy

A work-flow diagram for CASA calibration of interferometry data is shown in Figure 4.1. This should help you chart your course through the complex set of calibration steps. In the following sections, we will detail the steps themselves and explain how to run the necessary tasks and tools.

This can be broken down into a number of discrete phases:




Figure 4.1: Flow chart of synthesis calibration operations. Not shown are use of table manipulation and plotting tasks `accum`, `plotcal`, and `smoothcal` (see Figure 4.2).

- **Prior Calibration** — set up previously known calibration quantities that need to be pre-applied, such as the flux density of calibrators, antenna gain-elevation curves, and atmospheric models. Use the `setjy` task (§ 4.3.4), and set the `gaincurve` (§ 4.3.2) and `opacity` (§ 4.3.3) parameters in subsequent tasks;
- **Bandpass Calibration** — solve for the relative gain of the system over the frequency channels in the dataset (if needed), having pre-applied the prior calibration. Use the `bandpass` task (§ 4.4.2);
- **Gain Calibration** — solve for the gain variations of the system as a function of time, having pre-applied the bandpass (if needed) and prior calibration. Use the `gaincal` task (§ 4.4.3);
- **Polarization Calibration** — solve for any unknown polarization leakage terms. **BETA ALERT:** Polarization Calibration tasks are now available as of Beta Release Patch 1 (§ 4.4.5);
- **Establish Flux Density Scale** — if only some of the calibrators have known flux densities, then rescale gain solutions and derive flux densities of secondary calibrators. Use the `fluxscale` task (§ 4.4.4);
- **Manipulate, Accumulate, and Iterate** — if necessary, accumulate different calibration solutions (tables), smooth, and interpolate/extrapolate onto different sources, bands, and times. Use the `accum` (§ 4.5.4) and `smoothcal` (§ 4.5.3) tasks;
- **Examine Calibration** — at any point, you can (and should) use `plotcal` (§ 4.5.1) and/or `listcal` (§ 4.5.2) to look at the calibration tables that you have created;
- **Apply Calibration to the Data** — this can be forced explicitly by using the `applycal` task (§ 4.6.1), and can be undone using `clearcal` (§ 4.6.3);
- **Post-Calibration Activities** — this includes the determination and subtraction of continuum signal from line data, the splitting of data-sets into subsets (usually single-source), and other operations (such as model-fitting). Use the `uvcontsub` (§ 4.7.4), `split` (§ 4.7.1), and `uvmodelfit` (§ 4.7.5) tasks.

The flow chart and the above list are in a suggested order. However, the actual order in which you will carry out these operations is somewhat fluid, and will be determined by the specific data-reduction use cases you are following. For example, you may need to do an initial **Gain Calibration** on your bandpass calibrator before moving to the **Bandpass Calibration** stage. Or perhaps the polarization leakage calibration will be known from prior service observations, and can be applied as a constituent of Prior Calibration.

4.2.1 The Philosophy of Calibration in CASA

Calibration is not an arbitrary process, and there is a methodology that has been developed to carry out synthesis calibration and an algebra to describe the various corruptions that data might be subject to: the Hamaker-Bregman-Sault Measurement Equation (ME), described in Appendix E. The user need not worry about the details of this mathematics as the CASA software does that for

you. Anyway, its just matrix algebra, and your familiar scalar methods of calibration (such as in AIPS) are encompassed in this more general approach.

There are a number of “physical” components to calibration in CASA:

- **data** — in the form of the Measurement Set (§ 2.1). The MS includes a number of columns that can hold calibrated data, model information, and weights;
- **calibration tables** — these are in the form of standard CASA tables, and hold the calibration solutions (or parameterizations thereof);
- **task parameters** — sometimes the calibration information is in the form of CASA task parameters that tell the calibration tasks to turn on or off various features, contain important values (such as flux densities), or list what should be done to the data.

At its most basic level, Calibration in CASA is the process of taking “uncalibrated” **data**, setting up the operation of calibration tasks using **parameters**, solving for new calibration **tables**, and then applying the calibration tables to form “calibrated” **data**. Iteration can occur as necessary, with the insertion of other non-calibration steps (e.g. “self-calibration” via imaging).

4.2.2 Keeping Track of Calibration Tables

The calibration tables are the currency that is exchanged between the calibration tasks. The “solver” tasks (`gaincal`, `bandpass`, `blcal`, `fringecal`) take in the MS (which may have a calibration model in the `MODEL_DATA` column from `setjy` or `ft`) and previous calibration tables, and will output an “incremental” calibration table (it increments the previous calibration, if any). This table can then be smoothed using `smoothcal` if desired.

You can accumulate the incremental calibration onto previous calibration tables with `accum`, which will then output a cumulative calibration table. This task will also interpolate onto a different time scale. See § 4.5.4 for more on accumulation and interpolation.

Figure 4.2 graphs the flow of these tables through the sequence

```
solve    =>    smooth    =>    accumulate
```

Note that this sequence applied to separate *types* of tables (e.g. ‘B’, ‘G’) although tables of other types can be previous calibration input to the solver.

The final set of cumulative calibration tables is what is applied to the data using `applycal`. You will have to keep track of which tables are the intermediate incremental tables, and which are cumulative, and which were previous to certain steps so that they can also be previous to later steps until accumulation. This can be a confusing business, and it will help if you adopt a consistent table naming scheme (see Figure 4.2) for an example naming scheme).




Figure 4.2: Chart of the table flow during calibration. The parameter names for input or output of the tasks are shown on the connectors. Note that from the output solver through the accumulator only a single calibration type (e.g. 'B', 'G') can be smoothed, interpolated or accumulated at a time. The final set of cumulative calibration tables of all types are then input to `applycal` as shown in Figure 4.1.

4.2.3 The Calibration of VLA data in CASA

CASA supports the calibration of VLA data that is imported from the Archive through the `importvla` task. See § 2.2.2 for more information.

BETA ALERT: Data taken both before and after the Modcomp turn-off in late June 2007 will be handled automatically by `importvla`. You do not need to set special parameters to do so, and it will obey the scaling specified by `applytsys`.

You can also import VLA data in UVFITS format with the `importuvfits` task (§ 2.2.1.1). However, in this case, you must be careful during calibration in that some prior or previous calibrations (see below) may or may not have been done in AIPS and applied (or not) before export.

For example, the default settings of AIPS `FILLM` will apply VLA gaincurve and approximate (weather-based) atmospheric optical depth corrections when it generates the extension table `CL 1`. If the data is exported immediately using `FITTP`, then this table is included in the `UVFITS` file. However, CASA is not able to read or use the AIPS `SN` or `CL` tables, so that prior calibration information is lost and must be applied during calibration here (ie. using `gaincurve=True` and setting the `opacity` parameter).

On the other hand, if you apply calibration in AIPS by using the `SPLIT` or `SPLAT` tasks to apply the `CL` tables before exporting with `FITTP`, then this calibration will be in the data itself. In this case, you do not want to re-apply these calibrations when processing in CASA.

4.3 Preparing for Calibration

There are a number of “a priori” calibration quantities that may need to be applied to the data before further calibration is carried out. These include

- **system temperature correction** — turn correlation coefficient into correlated flux density (necessary for some telescopes),
- **gain curves** — antenna gain-elevation dependence,
- **atmospheric optical depth** — attenuation of the signal by the atmosphere, correcting for its elevation dependence.
- **flux density models** — establish the flux density scale using “standard” calibrator sources, with models for resolved calibrators,

These are pre-determined effects and should be applied (if known) before solving for other calibration terms. If unknown, then they will need to be solved for as one of the standard calibration types (gain or bandpass).

We now deal with these in turn.

4.3.1 System Temperature Correction

Some telescopes, including the EVLA and the VLBA, record the visibilities in the form of raw *correlation coefficient* with weights proportional to the number of bits correlated. The correlation coefficient is the fraction of the total signal that is correlated, and thus multiplication by the system temperature and the antenna gain (in Jy/K) will produce visibilities with units of correlated flux density. Note that the old VLA system did this initial calibration on-line, and ALMA will also provide some level of on-line calibration (TBD).

BETA ALERT: There is as yet no mechanism available in `importvla` or in the calibration tasks to use the system temperature information provided by the VLA/EVLA on-line system to calibrate EVLA or VLBA data in raw form. This includes VLA data taken after the Modcomp turn-over

in late June 2007. You may pass the data through AIPS first. You can also just forge ahead with standard calibration. The drawback to this is that short-term changes in T_{sys} which are not tracked by calibrator observations or self-calibration will remain in the data.

4.3.2 Antenna Gain-Elevation Curve Calibration

Large antennas (such as the 25-meter antennas used in the VLA and VLBA) have a forward gain and efficiency that changes with elevation. Gain curve calibration involves compensating for the effects of elevation on the amplitude of the received signals at each antenna. Antennas are not absolutely rigid, and so their effective collecting area and net surface accuracy vary with elevation as gravity deforms the surface. This calibration is especially important at higher frequencies where the deformations represent a greater fraction of the observing wavelength. By design, this effect is usually minimized (i.e., gain maximized) for elevations between 45 and 60 degrees, with the gain decreasing at higher and lower elevations. Gain curves are most often described as 2nd- or 3rd-order polynomials in zenith angle.

Gain curve calibration has been implemented in CASA for the VLA (only), with gain curve polynomial coefficients available directly from the CASA data repository. To make gain curve corrections for VLA data, set `gaincurve=True` for any of the calibration tasks.

BETA ALERT: The `gaincurve` parameter must be supplied to any calibration task that allows pre-application of the prior calibration (e.g. `bandpass`, `gaincal`, `applycal`). This should be done consistently through the calibration process. In future updates we will likely move to a separate task to calibrate the gain curve.

For example, to pre-apply the `gaincurve` during gain calibration:

```
gaincal('data.ms', 'cal.G0', gaincurve=True, solint=0., refant=11)
```

NOTE: Set `gaincurve=False` if you are not using VLA data.

The gain curve will be calculated per timestamp. Upon execution of a calibration task (e.g., `gaincal`, `bandpass`, `applycal`, etc.), the gain curve data appropriate to the observing frequencies will be automatically retrieved from the data repository and applied.

BETA ALERT: Currently, gain-curves for VLA are built into the CASA system and this is what is applied when `gaincurve=True`. Therefore, the application of the gain-curves, if `gaincurve=True`, is allowed only if the VLA is set as the telescope of observation in the MS, otherwise an error will be generated. Set `gaincurve=False` if you are not using VLA data. A general mechanism for incorporating `gaincurve` information for other arrays will be made available in future releases. Also note that the VLA gain-curves are the most recent ones (that are also supplied in AIPS). Caution should be used in applying these `gaincurve` corrections to VLA data taken before 2001, as antenna changes were poorly tracked previous to this time. We will include gain curves for EVLA antennas when those are measured and become available.

4.3.3 Atmospheric Optical Depth Correction

The troposphere is not completely transparent. At high radio frequencies (>15 GHz), water vapor and molecular oxygen begin to have a substantial effect on radio observations. According to the physics of radiative transmission, the effect is threefold. First, radio waves from astronomical sources are absorbed (and therefore attenuated) before reaching the antenna. Second, since a good absorber is also a good emitter, significant noise-like power will be added to the overall system noise. Finally, the optical path length through the troposphere introduces a time-dependent phase error. In all cases, the effects become worse at lower elevations due to the increased air mass through which the antenna is looking. In CASA, the opacity correction described here compensates only for the first of these effects, tropospheric attenuation, using a plane-parallel approximation for the troposphere to estimate the elevation dependence.

Opacity corrections are a component of calibration type 'T'. To make opacity corrections in CASA, an estimate of the zenith opacity is required (see observatory-specific chapters for how to measure zenith opacity). This is then supplied to the `opacity` parameter in the calibration tasks.

BETA ALERT: The `opacity` parameter must be supplied to any calibration task that allows pre-application of the prior calibration (e.g. `bandpass`, `gaincal`, `applycal`). This should be done consistently through the calibration process. In future updates we will likely move to a separate task to calibrate the atmospheric optical depth.

For example, if the zenith optical depth is 0.1 nepers, then use the following parameters:

```
gaincal('data.ms', 'cal.G0', solint=0., refant=11, opacity=0.1)
```

The calibration task in this example will apply an elevation-dependent opacity correction (scaled to 0.1 nepers at the zenith for all antennas for this example) calculated at each scan (`solint=0`). Set `solint=-1` instead to get a solution every timestamp.

BETA ALERT: Currently, you can only supply a single value of `opacity`, which will then be pre-applied to whatever calibration task that you set it in. Generalizations to antenna- and time-dependent opacities, including derivation (from weather information) and solving (directly from the visibility data) capabilities, will be made available in the future.

If you do not have an externally supplied value for `opacity`, for example from a VLA tip procedure, then you should either use an average value for the telescope, or leave it at zero and hope that your gain calibration compensates (e.g. that your calibrator is at the same elevation as your target at approximately the same time. As noted above, there are no facilities yet to estimate this from the data (e.g. by plotting TANT vs. elevation).

Below, we give instructions for determining `opacity` for VLA observations where tip-curve data is available. It is beyond the scope of this cookbook to provide information for other telescopes.

4.3.3.1 Determining opacity corrections for VLA data

For VLA data, zenith opacity can be measured at the frequency and during the time observations are made using a VLA tipping scan in the observe file. Historical tipping data are available at:

<http://www.vla.nrao.edu/astro/calib/tipper>

Choose a year, and click Go to get a list of all tipping scans that have been made for that year.

If a tipping scan was made for your observation, then select the appropriate file. Go to the bottom of the page and click on the button that says Press here to continue.. The results of the tipping scan will be displayed. Go to the section called 'Overall Fit Summary' to find the fit quality and the fitted zenith opacity in percent. If the zenith opacity is reported as 6%, then the actual zenith optical depth value is opacity=0.060 for gaincal and other calibration tasks.

If there were no tipping scans made for your observation, then look for others made in the same band around the same time and weather conditions. If nothing is available here, then at K and Q bands you might consider using an average value (e.g. 6% in reasonable weather). See the VLA memo

<http://www.vla.nrao.edu/memos/test/232/232.pdf>

for more on the atmospheric optical depth correction at the VLA, including plots of the seasonal variations.

4.3.4 Setting the Flux Density Scale using (setjy)

When solving for visibility-plane calibration, CASA calibration applications compare the observed DATA column with the MODEL_DATA column. The first time that an imaging or calibration task is executed for a given MS, the MODEL_DATA column is created and initialized with unit point source flux density visibilities (unpolarized) for all sources (e.g. AMP=1, phase=0°). The setjy task is then used to set the proper flux density for flux calibrators. For sources that are recognized flux calibrators (listed in Table 4.1), setjy will calculate the flux densities, Fourier transform the data and write the results to the MODEL_DATA column. For the VLA, the default source models are customarily point sources defined by the Baars or Perley-Taylor flux density scales, or point sources of unit flux density if the flux density is unknown. The MODEL_DATA column can also be filled with a model generated from an image of the source (e.g. the Fourier transform of an image generated after initial calibration of the data).

The inputs for setjy are:

```
# setjy :: Place flux density of sources in the measurement set:

vis          =      ''      # Name of input visibility file
field        =      ''      # Field name list or field ids list
spw          =      ''      # Spectral window identifier (list)
modimage     =      ''      # Model image name
fluxdensity  =      -1      # Specified flux density [I,Q,U,V]
standard     = 'Perley-Taylor 99'    # Flux density standard
```

Table 4.1:

3C Name	B1950 Name	J2000 Name
3C286	1328+307	1331+305
3C48	0134+329	0137+331
3C147	0538+498	0542+498
3C138	0518+165	0521+166
—	1934-638	—
3C295	1409+524	1411+522

By default the `setjy` task will cycle through all fields and spectral windows, setting the flux density either to 1 Jy (unpolarized), or if the source is recognized as one of the calibrators in the above table, to the flux density (assumed unpolarized) appropriate to the observing frequency. For example, to run `setjy` on a measurement set called `data.ms`:

```
setjy(vis='data.ms')          # This will set all fields and spectral windows
```

BETA ALERT: At this time, all that `setjy` does is to fill the `MODEL_DATA` column of the MS with the Fourier transform of a source model. The `ft` task (§ 5.7) will do the same thing, although it does not offer the options for flux rescaling that `setjy` does. Note also that currently `setjy` will not transform a full-Stokes model image such that all polarizations are filled correct. You need to use `ft` for this.

To limit this operation to certain fields and spectral windows, use the `field` and/or `spw` parameters, which take the usual data selection strings (§ 2.5). For example, to set the flux density of the first field (all spectral windows)

```
setjy(vis='data.ms',field='0')
```

or to set the flux density of the second field in spectral window 17

```
setjy(vis='data.ms',field='1',spw='17')
```

The full-polarization flux density (I,Q,U,V) may also be explicitly provided:

```
setjy(vis='data.ms',
      field='1',spw='16',           # Run setjy on field id 1, spw id 17
      fluxdensity=[3.5,0.2,0.13,0.0]) # and set I,Q,U,V explicitly
```

Note: The `setjy` (or `ft`) operation is different than the antenna gain-elevation and atmospheric opacity Prior Calibrations (§ 4.3.2–4.3.3) in that it is applied to (and carried with) the MS itself, rather than via other tables or parameters to the subsequent tasks. It is more like the `Tsys` correction (§ 4.3.1) in this regard.

4.3.4.1 Using Calibration Models for Resolved Sources

If the flux density calibrator is resolved at the observing frequency, the point source model generated by `setjy` will not be appropriate. If available, a model image of the resolved source at the observing frequency may be used to generate the appropriate visibilities using the `modimage` parameter (or in older versions explicitly with the `ft` task). To use this, provide `modimage` with the path to the model image. Remember, if you just give the file name, it will assume that it is in the current working directory. It is

Otherwise, you may need to use the `uvrange` selection (§ 4.4.1.2) in the calibration solving tasks to exclude the baselines where the resolution effect is significant. There is not hard and fast rule for this, though you should consider this if your calibrator is shows a drop of more than 10% on the longest baselines (use `plotxy`, § 3.4, to look at this). You may need to do `antenna` selection also, if it is heavily resolved and there are few good baselines to the outer antennas. Note that `uvrange` may also be needed to exclude the short baselines on some calibrators that have extended flux not accounted for in the model. **Note:** the calibrator guides for the specific telescopes usually indicate appropriate min and max for `uvrange`. For example, see the *VLA Calibration Manual* at:

```
http://www.vla.nrao.edu/astro/calib/manual/
```

for details on the use of standard calibrators for the VLA.

Model images for some flux density calibrators are provided with CASA:

- Red Hat Linux RPMs (RHE4, Fedora 6): located in `/usr/lib/casapy/data/nrao/VLA/CalModels`
- MAC OSX .dmg: located in `/opt/casa/data/nrao/VLA/CalModels`
- NRAO-AOC stable: `/home/casa/data/nrao/VLA/CalModels`
- NRAO-AOC daily: `/home/ballista/casa/daily/data/nrao/VLA/CalModels`

e.g., these are found in the `data/nrao/VLA/CalModels` sub-directory of the CASA installation. For example, just point to the repository copy, e.g.

```
modimage = '/usr/lib/casapy/data/nrao/VLA/CalModels/3C48_C.im'
```

or if you like, you can copy the ones you wish to use to your working directory.

The models available are:

```
3C138_C.im/ 3C138_Q.im/ 3C147_K.im/ 3C286_C.im/ 3C286_Q.im/ 3C48_C.im/ 3C48_Q.im/
3C138_K.im/ 3C138_U.im/ 3C147_Q.im/ 3C286_K.im/ 3C286_U.im/ 3C48_K.im/ 3C48_U.im/
3C138_L.im/ 3C138_X.im/ 3C147_U.im/ 3C286_L.im/ 3C286_X.im/ 3C48_L.im/ 3C48_X.im/
```

These are all un-reconvolved images of AIPS CC lists, properly scaled to the Perley-Taylor 1999 flux density for the frequencies at which they were observed.

It is important that the model image *not* be one convolved with a finite beam; it must have units of Jy/pixel (not Jy/beam).

Note that `setjy` will rescale the flux in the models for known sources (e.g. those in Table 4.1) to match those it would have calculated. It will thus extrapolate the flux out of the frequency band of the model image to whatever spectral windows in the MS are specified (but will use the structure of the source in the model image).

BETA ALERT: The reference position in the `modimage` is currently used by `setjy` when it does the Fourier transform, thus differences from the positions for the calibrator in the MS will show up as phase gradients in the uv-plane. If your model image position is significantly different but you don't want this to affect your calibration, then you can doctor either the image header using `imhead` (§ 6.2) or in the MS (using the `ms` tool) as appropriate. In an upcoming Beta patch we will put in a toggle to use or ignore the position of the `modimage`. Note that this will not affect the flux scaling (only put in erroneous model phases); in any event small position differences, such as those arising by changing epoch from B1950 to J2000 using `regridimage` (§ 6.9), will be inconsequential to the calibration.

This illustrates the use of `uvrange` for a slightly resolved calibrator:

```
# Import the data
importvla(archivefiles='AS776_A031015.xp2', vis='ngc7538_XBAND.ms',
           freqtol=10000000.0, bandname='X')

# Flag the ACs
flagautocorr('ngc7538_XBAND.ms')

# METHOD 1: Use point source model for 3C48, plus uvrage in solve

# Use point source model for 3C48
setjy(vis='ngc7538_XBAND.ms',field='0');

# Limit 3C48 (fieldid=0) solutions to uvrage = 0-40 klambda
gaincal(vis='ngc7538_XBAND.ms', caltable='cal.G', field='0',
        solint=60.0, refant='10', selectdata=True, uvrage='0~40klambda',
        append=False, gaincurve=False, opacity=0.0)

# Append phase-calibrator's solutions (no uvrage) to the same table
gaincal(vis='ngc7538_XBAND.ms', caltable='cal.G', field='2',
        solint=60.0, refant='10', selectdata=True, uvrage='',
        append=True, gaincurve=False, opacity=0.0)

# Fluxscale
fluxscale(vis='ngc7538_XBAND.ms', caltable='cal.G', reference=['0137+331'],
           transfer=['2230+697'], fluxtable='cal.Gflx', append=False)
```

while the following illustrates the use of of a model:

```

# METHOD 2: use a resolved model copied from the data repository
#   for 3C48, and no uvrangle
# (NB: detailed freq-dep flux scaling TBD)

# Copy the model image 3C48_X.im to the working directory first!

setjy(vis='ngc7538_XBAND.ms', field='0', modimage='3C48_X.im')

# Solutions on both calibrators with no uvrangle
gaincal(vis='ngc7538_XBAND.ms', caltable='cal.G2', field='0,2',
        solint=60.0, refant='10',
        append=False, gaincurve=False, opacity=0.0)

# Fluxscale
fluxscale(vis='ngc7538_XBAND.ms', caltable='cal.G2', reference=['0137+331'],
           transfer=['2230+697'], fluxtable='cal.G2flx', append=False)

# Both methods give 2230 flux densities ~0.7 Jy, in good agreement with
#   AIPS

```

4.3.5 Other *a priori* Calibrations and Corrections

Other *a priori* calibrations will be added to the **calibrator** (cb) tool in the near future. These will include antenna-position (phase) corrections, system temperature normalization (amplitude) corrections, tropospheric phase corrections derived from Water Vapor Radiometry (WVR) measurements, instrumental line-length corrections, etc. Where appropriate, solving capabilities for these effects will also be added.

4.4 Solving for Calibration — Bandpass, Gain, Polarization

These tasks actually solve for the unknown calibration parameters, placing the results in a calibration table. They take as input an MS, and a number of parameters that specify any prior calibration or previous calibration tables to pre-apply before computing the solution. These are placed in the proper sequence of the Measurement Equation automatically.

We first discuss the parameters that are in common between many of the calibration tasks. Then we describe each solver in turn.

4.4.1 Common Calibration Solver Parameters

There are a number of parameters that are in common between the calibration “solver” tasks. These also appear in some of the other calibration manipulation and application tasks.

4.4.1.1 Parameters for Specification : vis and caltable

The input measurement set and output table are controlled by the following parameters:

```
vis      =      ''    #  Name of input visibility file
caltable =      ''    #  Name of output calibration table
```

The MS name is input in **vis**. If it is highlighted red in the inputs (§ 1.3.5.4) then it does not exist, and the task will not execute. Check the name and path in this case.

The output table name is placed in **caltable**. Be sure to give a unique name to the output table, or be careful. If the table exists, then what happens next will depend on the task and the values of other parameters (e.g. § 4.4.1.6). The task may not execute giving a warning that the table already exists, or will go ahead and overwrite the solutions in that table, or append them. Be careful.

4.4.1.2 Selection: field, spw, and selectdata

Selection is controlled by the parameters:

```
field      =      ''    #  field names or index of calibrators: ''==>all
spw        =      ''    #  spectral window:channels: ''==>all
selectdata = False   #  Other data selection parameters
```

Field and spectral window selection are so often used, that we have made these standard parameters **field** and **spw** respectively.

The **selectdata** parameter expands as usual, uncovering other selection sub-parameters:

```
selectdata = True    #  Other data selection parameters
timerange  =      ''    #  time range: ''==>all
uvrange    =      ''    #  uv range''==>all
antenna    =      ''    #  antenna/baselines: ''==>all
scan       =      ''    #  scan numbers: Not yet implemented
msselect   =      ''    #  Optional data selection (Specialized. but see help)
```

Note that if **selectdata=False** these parameters are not used when the task is executed, even if set underneath.

The most common **selectdata** parameter to use is **uvrange**, which can be used to exclude longer baselines if the calibrator is resolved, or short baselines of the calibrator contains extended flux not accounted for in the model (e.g. § 4.3.4.1).

See § 2.5 for more on the selection parameters.

4.4.1.3 Prior Calibration and Correction: `parang`, `gaincurve` and `opacity`

These parameters control the on-the-fly application of various calibration or effect-based corrections prior to the solving process.

The `parang` parameter turns on the application of the antenna-based parallactic angle correction ('P') in the measurement equation. This is necessary for polarization calibration and imaging, or for cases where the parallactic angles are different for geographically spaced antennas (e.g. VLBI). For dealing with only the parallel-hand corrections (e.g. RR, LL, XX, YY) for a co-located array (e.g. the VLA or ALMA), you can set `parang=False` and save some computational effort. Otherwise, set `parang=True` to apply this correction.

There are two control parameters for applying Prior Calibration:

```
gaincurve      =      False    #  Apply VLA antenna gain curve correction
opacity        =      0.0     #  Opacity correction to apply (nepers)
```

See § 4.3 for more on **Prior Calibration**.

4.4.1.4 Previous Calibration: `gaintable`, `gainfield`, `interp` and `spwmap`

Calibration tables that have already been determined can also be applied before solving for the new table:

```
gaintable      =      ''    #  Prior gain calibration table(s) to apply
gainfield      =      ''    #  Field selection on prior gaintable(s)
interp         =      ''    #  Interpolation mode (in time) for prior gaintable(s)
spwmap         =      []    #  Spectral window mapping for each gaintable (see help)
```

This is controlled by the `gaintable` parameter, which takes a string or list of strings giving one or more calibration tables to pre-apply. For example,

```
gaintable = ['ngc5921.bcal', 'ngc5921.gcal']
```

specifies two tables, in this case bandpass and gain calibration tables respectively.

The other parameters key off `gaintable`, taking single values or lists, with an entry for each table in `gaintable`. The order is given by that in `gaintable`.

The `gainfield` parameter specifies which fields from the respective `gaintable` to use to apply. This is a list, with each entry a string or list of strings. The default '' for an entry means to use all in that table. For example,

```
gaintable = ['ngc5921.bcal', 'ngc5921.gcal']
gainfield = [ '1331+305', ['1331+305', '1445+099'] ]
```

or using indices

```
gainfield = [ '0', ['0','1'] ]
```

to specify the field '1331+305' from the table 'ngc5921.bcal' and fields '1331+305' and '1445+099' from the second table 'ngc5921.gcal'. We could also have wildcarded the selection, e.g.

```
gainfield = [ '0', '*' ]
```

taking all fields from the second table. And of course we could have used the default

```
gainfield = [ '0', '' ]
```

or even

```
gainfield = [ '0' ]
```

which is to take all.

The `interp` parameter chooses the interpolation scheme to be used when pre-applying the solution in the tables. This interpolation is (currently) only in time. The choices are currently '`nearest`', '`linear`', and '`aipslin`':

- '`nearest`' just picks the entry nearest in time to the visibility in question;
- '`linear`' interpolation calibrates each datum with calibration phases and amplitudes linearly interpolated from neighboring time values. In the case of phase, this mode will assume that phase jumps greater than 180° between neighboring points indicate a cycle slip, and the interpolated value will follow this change in cycle accordingly;
- '`aipslin`' emulates the classic AIPS interpolation mode with linearly interpolated amplitudes and phases derived from interpolation of the complex calibration values. While this method avoids having to track cycle slips (which is unstable for solutions with very low SNR), it will yield a phase interpolation which becomes increasingly non-linear as the spanned phase difference increases. The non-linearity mimics the behavior of `interp='nearest'` as the spanned phase difference approaches 180° (the phase of the interpolated complex calibration value initially changes very slowly, then rapidly jumps to the second value at the midpoint of the interval).

If the uncalibrated phase is changing rapidly, a '`nearest`' interpolation is not desirable. Usually, `interp='linear'` is the best choice. For example,

```
interp = [ 'nearest', 'linear' ]
```

uses nearest "interpolation" on the first table, and linear on the second.

The `spwmap` parameter sets the spectral window combinations to form for the `gaintable(s)`. This is a list, or a list of lists, of integers giving the `spw` IDs to map. There is one list for each table in `gaintable`, with an entry for each ID in the MS. For example,

```
spwmap=[0,0,1,1]          # apply from spw=0 to 0,1 and 1 to 2,3
```

for an MS with `spw=0,1,2,3`. For multiple `gaintable`, use lists of lists, e.g.

```
spwmap=[ [0,0,1,1], [0,1,0,1] ] # 2nd table spw=0 to 0,2 and 1 to 1,3
```

BETA ALERT: This scheme for mapping the pre-apply tables is not particularly elegant, particularly for `spwmap`. This may change in the future.

4.4.1.5 Solving: `solint`, `combine`, `refant`, and `minsnr`

The parameters controlling common aspects of the solution are:

```
solint      =      'inf'    # Solution interval
combine     =      ''       # Data axes which to combine for solve (scan, spw, and/or field)
refant      =      ''       # Reference antenna name: ''=no explicit reference
minsnr      =      0.0     # Reject solutions below this SNR: 0==>no rejection
```

The solution interval is given by `solint`. If given a number without a unit, this is in seconds. The special values `'inf'` and `-1` specify an “infinite” solution interval encompassing the entire dataset, while `'int'` or zero specify a solution every integration. You can use time quanta in the string, e.g. `solint='1m'` and `solint='60s'` both specify solution intervals of one minute. Note that `solint` interacts with `combine` to determine whether the solutions cross scan or field boundaries.

The parameter controlling the scope of the solution is `combine`. For the default `combine=''` solutions will break at scan, field, and spw boundaries. Specification of any of these in `combine` will extend the solutions over the boundaries (up to the `solint`). For example, `combine='spw'` will combine spectral windows together for solving, while `combine='scan'` will cross scans. Thus, to do scan-based solutions (single solution for each scan), set

```
solint = 'inf'
combine = ''

while
```

```
solint = 'inf'
combine = 'scan'
```

will make a single solution for the entire dataset (for a given field and spw). You can specify multiple choices for combination:

```
combine = 'scan,spw'
```

for example.

The reference antenna is specified by the `refant` parameter. This useful to “lock” the solutions with time, effectively rotating (after solving) the phase of the gain solution for the reference antenna to be zero (the exact effect depends on the type of solution). You can also run without a reference antenna, but in this case the solutions will float with time, with a phase that rotates around with the relative weights of the antennas in the solution (its more or less like setting the weighted sum of the antenna phases to zero). It is usually prudent to select an antenna in the center of the array that is known to be particularly stable, as any gain jumps or wanders in the `refant` will be transferred to the other antenna solutions.

The minimum signal-to-noise ratio allowed for an acceptable solution is specified in the `minsnr` parameter. **BETA ALERT:** Not all calibration tasks have this parameter.

4.4.1.6 Action: `append` and `solnorm`

The following parameters control some things that happen after solutions are obtained:

```
solnorm      =      False   #  Normalize solution amplitudes post-solve.
append       =      False   #  Append solutions to (existing) table.  False will overwrite.
```

The `solnorm` parameter toggles on the option to normalize the solution amplitudes after the solutions are obtained. The exact effect of this depends upon the type of solution. Not all tasks include this parameter.

One should be aware when using `solnorm` that if this is done in the last stage of a chain of calibration, then the part of the calibration that is “normalized” away will be lost. It is best to use this in early stages (for example in a first bandpass calibration) so that later stages (such as final gain calibration) can absorb the lost normalization scaling. It is not strictly necessary to use `solnorm=True` at all, but is sometimes helpful if you want to have a normalized bandpass for example.

The `append` parameter, if set to `True`, will append the solutions from this run to existing solutions in `caltable`. Of course, this only matters if the table already exists. If `append=False` and `caltable` exists, it will overwrite.

4.4.2 Spectral Bandpass Calibration (`bandpass`)

For channelized data, it is often desirable to solve for the gain variations in frequency as well as in time. Variation in frequency arises as a result of non-uniform filter passbands or other dispersive effects in signal transmission. It is usually the case that these frequency-dependent effects vary on timescales much longer than the time-dependent effects handled by the gain types 'G' and 'T'. Thus, it makes sense to solve for them as a separate term: 'B', using the `bandpass` task.

The inputs to `bandpass` are:

```
# bandpass :: Calculate a bandpass solution

vis          =      ''      # Nome of input visibility file
caltable     =      ''      # Name of output gain calibration table
field        =      ''      # Select field using field id(s) or field name(s)
spw          =      ''      # Select spectral window/channels
selectdata   =    False    # Other data selection parameters
solint       =    'inf'   # Solution interval
combine      =    'scan'  # Data axes which to combine for solve (scan, spw, and/or field)
refant       =      ''      # Reference antenna name
solnorm      =    False    # Normalize average solution amplitudes to 1.0
bandtype     =    'B'      # Type of bandpass solution (B or BPOLY)
append       =    False    # Append solutions to the (existing) table
gaintable    =    ['']    # Gain calibration table(s) to apply on the fly
gainfield    =    ['']    # Select a subset of calibrators from gaintable(s)
interp       =    ['']    # Interpolation mode (in time) to use for each gaintable
spwmap       =    []      # Spectral windows combinations to form for gaintables(s)
gaincurve   =    False    # Apply internal VLA antenna gain curve correction
opacity      =    0.0     # Opacity correction to apply (nepers)
parang       =    False    # Apply parallactic angle correction
async        =    False    # if True run in the background, prompt is freed
```

Many of these parameters are in common with the other calibration tasks and are described above in § 4.4.1.

The `bandtype` parameter selects the type of solution used for the bandpass. The choices are '`B`' and '`BPOLY`'. The former solves for a complex gain in each channel in the selected part of the MS. See § 4.4.2.2 for more on '`B`'. The latter uses a polynomial as a function of channel to fit the bandpass, and expands further to reveal a number of sub-parameters See § 4.4.2.3 for more on '`BPOLY`'.

It is usually best to solve for the bandpass in channel data before solving for the gain as a function of time. However, if the gains of the bandpass calibrator observations are fluctuating over the timerange of those observations, then it can be helpful to first solve for the gains of that source with `gaincal` , and input these to `bandpass` via `gaintable`. See more below on this strategy.

We now describe the issue of bandpass normalization, followed by a description of the options `bandtype='B'` and `bandtype='BPOLY'`.

4.4.2.1 Bandpass Normalization

The `solnorm` parameter (§ 4.4.1.6) deserves more explanation in the context of the bandpass. Most users are used to seeing a normalized bandpass, where the vector sum of the antenna-based channel gains sums to unity amplitude and zero phase. The toggle `solnorm=True` allows this. However, the parts of the bandpass solution normalized away will be still left in the data, and thus you should not use `solnorm=True` if the `bandpass` calibration is the end of your calibration sequence (e.g. you have already done all the gain calibration you want to). Note that setting `solnorm=True` will NOT rescale any previous calibration tables that the user may have supplied in `gaintable`.

You can safely use `solnorm=True` if you do the bandpass first (perhaps after a throw-away initial gain calibration) as we suggest above in § 4.2, as later gain calibration stages will deal with this remaining calibration term. This does have the benefit of isolating the overall (channel independent) gains to the following `gaincal` stage. It is also recommended for the case where you have multiple scans on possibly different bandpass calibrators. It may also be preferred when applying the bandpass before doing `gaincal` and then `fluxscale` (§ 4.4.4), as significant variation of bandpass among antennas could otherwise enter the gain solution and make (probably subtle) adjustments to the flux scale.

We finally note that `solnorm=False` at the bandpass step in the calibration chain will in the end produce the correct results. It only means that there will be a part of what we usually think of the gain calibration inside the bandpass solution, particularly if `bandpass` is run as the first step.

4.4.2.2 B solutions

Calibration type 'B' differs from 'G' only in that it is determined for each channel in each spectral window. It is possible to solve for it as a function of time, but it is most efficient to keep the 'B' solving timescale as long as possible, and use 'G' or 'T' for rapid frequency-independent time-scale variations.

The 'B' solutions are limited by the signal-to-noise ratio available per channel, which may be quite small. It is therefore important that the data be coherent over the time-range of the 'B' solutions. As a result, 'B' solutions are almost always preceded by an initial 'G' or 'T' solve using `gaincal` (§ 4.4.3). In turn, if the 'B' solution improves the frequency domain coherence significantly, a 'G' or 'T' solution following it will be better than the original.

For example, to solve for a 'B' bandpass using a single short scan on the calibrator, then

```
default('bandpass')

vis = 'n5921.ms'
caltable = 'n5921.bcal'
gaintable = ''                      # No gain tables yet
gainfield = ''
interp = ''
field = '0'                           # Calibrator 1331+305 = 3C286 (FIELD_ID 0)
spw = ''                             # all channels
selectdata = False                   # No other selection
gaincurve = False                    # No gaincurve at L-band
opacity = 0.0                         # No troposphere
bandtype = 'B'                       # standard time-binned B (rather than BPOLY)
solint = 'inf'                       # set solution interval arbitrarily long
refant = '15'                         # ref antenna 15 (=VLA:N2) (ID 14)

bandpass()
```

On the other hand, we might have a number of scans on the bandpass calibrator spread over time, but we want a single bandpass solution. In this case, we could solve for and then pre-apply an initial gain calibration, and let the bandpass solution cross scans:

```

gaintable = 'n5921.init.gcal'      # Our previously determined G table
gainfield = '0'
interp = 'linear'                  # Do linear interpolation
solint = 'inf'                     # One interval over dataset
combine = 'scan'                   # Solution crosses scans

spw = '0:4~59'                    # channels 4-59 of spw 0

```

Note that we obtained a bandpass solution for all channels in the MS. If explicit channel selection is desired, for example some channels are useless and can be avoided entirely (e.g. edge channels or those dominated by Gibbs ringing), then `spw` can be set to select only these channels, e.g.

`spw = '0:4~59'` # channels 4-59 of spw 0

This is not so critical for 'B' solutions as for 'BPOLY', as each channel is solved for independently, and poor solutions can be dropped.

If you have multiple time solutions, then these will be applied using whatever interpolation scheme is specified in later tasks.

BETA ALERT: The 'B' solutions will allow you to use multiple `fields`, but in this case `bandpass` will produce different solutions for each source. i.e. you cannot average in time across different fields. Note that this currently provides a safety net of sorts because you should not average across fields unless the phase has already been corrected (e.g. in an initial `gaintcal`). In the future it will be possible to do this but then 'BPOLY' caveat below will then hold for 'B' solutions obtained using this option as well in the multiple field case.

4.4.2.3 BPOLY solutions

For some observations, it may be the case that the SNR per channel is insufficient to obtain a usable per-channel 'B' solution. In this case it is desirable to solve instead for a best-fit functional form for each antenna using the `bandtype='BPOLY'` solver. The 'BPOLY' solver naturally enough fits (Chebychev) polynomials to the amplitude and phase of the calibrator visibilities as a function of frequency. Unlike ordinary 'B', a single common 'BPOLY' solution will be determined for all spectral windows specified (or implicit) in the selection. As such, it is usually most meaningful to select individual spectral windows for 'BPOLY' solves, unless groups of adjacent spectral windows are known *a priori* to share a single continuous bandpass response over their combined frequency range (e.g., PdBI data).

The 'BPOLY' solver requires a number of unique sub-parameters:

```

bandtype      =      'BPOLY'    # Type of bandpass solution (B or BPOLY)
degamp        =          3    # Polynomial degree for BPOLY amplitude solution
degphase       =          3    # Polynomial degree for BPOLY phase solution
visnorm       =     False    # Normalize data prior to BPOLY solution
maskcenter    =          0    # Number of channels in BPOLY to avoid in center of band
maskedge      =          0    # Percent of channels in BPOLY to avoid at each band edge

```

The `degamp` and `degphase` parameters indicate the polynomial degree desired for the amplitude and phase solutions. The `maskcenter` parameter is used to indicate the number of channels in the center of the band to avoid passing to the solution (e.g., to avoid Gibbs ringing in central channels for PdBI data). The `maskedge` drops beginning and end channels. The `visnorm` parameter turns on normalization before the solution is obtained (rather than after for `solnorm`).

BETA ALERT: Note that currently, 'BPOLY' solutions cannot be solved for in a time-dependent manner. Furthermore, `bandpass` will allow you to use multiple `fields`, but will determine a single solution for all specified fields. If you want to use more than one field in the solution it is prudent to use an initial `gaincal` and use this table as an input to `bandpass` because in general the phase towards two (widely separated) sources will not be sufficiently similar to combine them. If you do not include amplitude in the initial `gaincal`, you probably want to set `visnorm=True` also to take out the amplitude normalization change. Note also in the case of multiple `fields`, that the 'BPOLY' solution will be labeled with the field ID of the first `field` used in the 'BPOLY' solution, so if for example you point `plotcal` at the name or ID of one of the other fields used in the solution, `plotcal` does not plot.

For example, to solve for a 'BPOLY' (5th order in amplitude, 7th order in phase), using data from field 2, with `G` corrections pre-applied:

```
bandpass(vis='data.ms',           # input data set
        caltable='cal.BPOLY',      #
        spw='0:2~56',             # Use channels 3-57 (avoid end channels)
        field='0',                # Select bandpass calibrator (field 0)
        bandtype='BPOLY',          # Select bandpass polynomials
        degamp=5,                 # 5th order amp
        degphase=7,                # 7th order phase
        gaintable='cal.G',         # Pre-apply gain solutions derived previously
        refant='14')               #
```

Note that all available spectral windows will be used to obtain a single solution spanning them all. If separate solutions for each spectral window are desired, solve for each separately, e.g., if there are 3 spectral windows (0,1,2):

```
bandpass(vis='data.ms',
        caltable='cal.BPOLY.0',
        spw='0:2~56',
        field='0',
        bandtype='BPOLY',
        degamp=5,
        degphase=7,
        gaintable='cal.G',
        refant='14')

bandpass(vis='data.ms',
        caltable='cal.BPOLY.1',
        spw='1:2~56',
        bandtype='BPOLY',
        degamp=5,
```

```

    degphase=7,
    gaintable='cal.G',
    refant='14')

bandpass(vis='data.ms',
          caltable='cal.BPOLY.2',
          spw='2:2~56',
          field='0',
          bandtype='BPOLY',
          degamp=5,
          degphase=7,
          gaintable='cal.G',
          refant='14')

```

Each solution is stored in a separate table. As a result, subsequent calibration operations may also be undertaken for each spectral window separately, or all the tables included in `gaintable` during later operations.

BETA ALERT: Once you do a separate `bandpass` run for different fields (making separate tables, you will need to continue keeping the calibration for these fields separate (in `gaincal` etc.) as they cannot be currently recombined later. Because of this complication, we recommend doing `bandpass` with '`BPOLY`' on a single field only at this time.

4.4.3 Complex Gain Calibration (`gaincal`)

The fundamental calibration to be done on your interferometer data is to calibrate the antenna-based gains as a function of time in the various frequency channels and polarizations. Some of these calibrations are known beforehand ("a priori") and others must be determined from observations of calibrators, or from observations of the target itself ("self-calibration").

It is best to have removed a (slowly-varying) "bandpass" from the frequency channels by solving for the bandpass (see above). Thus, the `bandpass` calibration table would be input to `gaincal` via the `gaintable` parameter (see below).

The `gaincal` task has the following inputs:

```
# gaincal :: Determine temporal gains from calibrator observations:

vis      =      ''   # Nome of input visibility file
caltable =      ''   # Name of output gain calibration table
field    =      ''   # Select field using field id(s) or field name(s)
spw      =      ''   # Select spectral window/channels
selectdata = False  # Other data selection parameters
solint   = 'inf'   # Solution interval (see help)
combine  =      ''   # Data axes which to combine for solve (scan, spw, and/or field)
preavg   = -1.0    # Pre-averaging interval (sec)
refant   =      ''   # Reference antenna name
minsnr   = 0.0     # Reject solutions below this SNR
solnorm  = False   # Normalize average solution amplitudes to 1.0 (G, T only)
```

```

gaintype      =      'G'      # Type of gain solution (G, T, or GSPLINE)
calmode       =      'ap'     # Type of solution" ('ap', 'p', 'a')
append        =      False    # Append solutions to the (existing) table
gaintable     =      ['']     # Gain calibration table(s) to apply on the fly
gainfield     =      ['']     # Select a subset of calibrators from gaintable(s)
interp         =      ['']     # Interpolation mode (in time) to use for each gaintable
spwmap         =      []      # Spectral windows combinations to form for gaintables(s)
gaincurve     =      False    # Apply internal VLA antenna gain curve correction
opacity        =      0.0     # Opacity correction to apply (nepers)
parang        =      False    # Apply parallactic angle correction
async          =      False    #

```

Data selection is done through the standard `field`, `spw` and `selectdata` expandable sub-parameters (see § 2.5). The bulk of the other parameters are the standard solver parameters. See § 4.4.1 above for a description of these.

The `gaintype` parameter selects the type of gain solution to compute. The choices are '`T`', '`G`', and '`GSPLINE`'. The '`G`' and '`T`' options solve for independent complex gains in each solution interval (classic AIPS style), with '`T`' enforcing a single polarization-independent gain for each co-polar correlation (e.g. `RR` and `LL`, or `XX` and `YY`) and '`G`' having independent gains for these. See § 4.4.3.1 for a more detailed description of '`G`' solutions, and § 4.4.3.2 for more on '`T`'. The '`GSPLINE`' fits cubic splines to the gain as a function of time. See § 4.4.3.3 for more on this option.

4.4.3.1 Polarization-dependent Gain (G)

Systematic time-dependent complex gain errors are almost always the dominant calibration effect, and a solution for them is almost always necessary before proceeding with any other calibration. Traditionally, this calibration type has been a catch-all for a variety of similar effects, including: the relative amplitude and phase gain for each antenna, phase and amplitude drifts in the electronics of each antenna, amplitude response as a function of elevation (gain curve), and tropospheric amplitude and phase effects. In CASA, it is possible to handle many of these effects separately, as available information and circumstances warrant, but it is still possible to solve for the net effect using calibration type G.

Generally speaking, type G can represent any per-spectral window multiplicative polarization- and time-dependent complex gain effect downstream of the polarizers. (Polarization *independent* effects *upstream* of the polarizers may also be treated with G.) Multi-channel data (per spectral window) will be averaged in frequency before solving (use calibration type B to solve for frequency-dependent effects within each spectral window).

To solve for G on, say, fields 1 & 2, on a 90s timescale, and apply, e.g., gain curve corrections:

```

gaincal('data.ms',
        caltable='cal.G',           # Write solutions to disk file 'cal.G'
        field='0,1',                # Restrict field selection
        solint=90.0,                 # Solve for phase and amp on a 90s timescale
        gaincurve=True               # Note: gaincurve=False by default
        refant=3)                   #

```

```
plotcal('cal.G','amp')          # Inspect solutions
```

These G solution will be referenced to antenna 4. Choose a well-behaved antenna that is located near the center of the array for the reference antenna. For non-polarization datasets, reference antennas need not be specified although you can if you want. If no reference antenna is specified, an effective phase reference that is an average over the data will be calculated and used. For data that requires polarization calibration, you must choose a reference antenna that has a constant phase difference between the right and left polarizations (e.g. no phase jumps or drifts). If no reference antenna (or a poor one) is specified, the phase reference may have jumps in the R–L phase, and the resulting polarization angle response will vary during the observation, thus corrupting the polarization imaging.

To apply this solution to the calibrators and the target source (field 2, say):

```
applycal('data.ms',
    field='0,1,2',           # Restrict field selection (cals + src)
    opacity=0.0,             # Don't apply opacity correction
    gaintable='cal.G')       # Apply G solutions and correct data
                            # (written to the CORRECTED_DATA column)
                            # Note: calwt=True by default
plotxy('data.ms',xaxis='channel',datacolumn='data',subplot=211)
plotxy('data.ms',xaxis='channel',datacolumn='corrected',subplot=212)
```

4.4.3.2 Polarization-independent Gain (T)

At high frequencies, it is often the case that the most rapid time-dependent gain errors are introduced by the troposphere, and are polarization-independent. It is therefore unnecessary to solve for separate time-dependent solutions for both polarizations, as is the case for 'G'. Calibration type 'T' is available to calibrate such tropospheric effects, differing from 'G' only in that a single common solution for both polarizations is determined. In cases where only one polarization is observed, type 'T' is adequate to describe the time-dependent complex multiplicative gain calibration.

In the following example, we assume we have a 'G' solution obtained on a longish timescale (longer than a few minutes, say), and we want a residual 'T' solution to track the polarization-independent variations on a very short timescale:

```
gaincal('data.ms',          # Visibility dataset
    caltable='cal.T',        # Specify output table name
    gaintype='T',            # Solve for T
    field='0,1',              # Restrict data selection to calibrators
    solint=3.0,               # Obtain solutions on a 3s timescale
    gaintable='cal120.G')     # Pre-apply prior G solution
```

For dual-polarization observations, it will always be necessary to obtain a 'G' solution to account for differences and drifts between the polarizations (which traverse different electronics), but solutions

for rapidly varying polarization-independent effects such as those introduced by the troposphere will be optimized by using 'T'. Note that 'T' can be used in this way for self-calibration purposes, too.

4.4.3.3 GSPLINE solutions

At high radio frequencies, where tropospheric phase fluctuates rapidly, it is often the case that there is insufficient signal-to-noise ratio to obtain robust 'G' or 'T' solutions on timescales short enough to track the variation. In this case it is desirable to solve for a best-fit functional form for each antenna using the 'GSPLINE' solver. This fits a time-series of cubic B-splines to the phase and/or amplitude of the calibrator visibilities.

BETA ALERT: Unlike ordinary 'G', a single common 'GSPLINE' solution will be determined from data for all selected spectral windows and fields specified in the MS selection parameters, and the resulting solution will be applicable to any field or spectral window in the same Measurement Set. This behavior is similar to that of the 'BPOLY' in `bandpass`. If you do want separate spectral window solutions, then you will have to do separate runs of `gaincal`. An important consequence of this is that all fields used to obtain a 'GSPLINE' amplitude solution must have models with accurate relative flux densities. Use of incorrect relative flux densities will introduce spurious variations in the 'GSPLINE' amplitude solution.

The 'GSPLINE' solver requires a number of unique additional parameters, compared to ordinary 'G' and 'T' solving. The sub-parameters are:

```
gaintype      = 'GSPLINE'    # Type of solution (G, T, or GSPLINE)
splineftime  = 3600.0       # Spline (smooth) timescale (sec), default=1 hours
npointaver   = 3             # Points to average for phase wrap (okay)
phasewrap    = 180           # Wrap phase when greater than this (okay)
```

The duration of each spline segment is controlled by `splineftime`. The actual `splineftime` will be adjusted such that an integral number of equal-length spline segments will fit within the overall range of data.

Phase splines require that cycle ambiguities be resolved prior to the fit; this operation is controlled by `npointaver` and `phasewrap`. The `npointaver` parameter controls how many contiguous points in the time-series are used to predict the cycle ambiguity of the next point in the time-series, and `phasewrap` sets the threshold phase jump (in degrees) that would indicate a cycle slip. Large values of `npointaver` improve the SNR of the cycle estimate, but tend to frustrate ambiguity detection if the phase rates are large. The `phasewrap` parameter may be adjusted to influence when cycles are detected. Generally speaking, large values ($> 180^\circ$) are useful when SNR is high and phase rates are low. Smaller values for `phasewrap` can force cycle slip detection when low SNR conspires to obscure the jump, but the algorithm becomes significantly less robust. More robust algorithms for phase-tracking are under development (including fringe-fitting).

For example, to solve for 'GSPLINE' phase and amplitudes, with splines of duration 600 seconds,

```
gaincal('data.ms',
```

```

caltable='cal.spline.ap',
gaintype='GSPLINE'      # Solve for GSPLINE
calmode='ap'             # Solve for amp & phase
field='0,1',              # Restrict data selection to calibrators
splinetime=600.)         # Set spline timescale to 10min

```

BETA ALERT: The 'GSPLINE' solutions can not yet be used in `fluxscale`. You should do at least some 'G' amplitude solutions to establish the flux scale, then do 'GSPLINE' in phase before or after to fix up the short timescale variations. Note that the "phase tracking" algorithm in 'GSPLINE' needs some improvement.

4.4.4 Establishing the Flux Density Scale (`fluxscale`)

The 'G' or 'T' solutions obtained from calibrators for which the flux density was unknown and assumed to be 1 Jansky are correct in a time- and antenna- relative sense, but are mis-scaled by a factor equal to the inverse of the square root of the true flux density. This scaling can be corrected by enforcing the constraint that mean gain amplitudes determined from calibrators of unknown flux density should be the same as determined from those with known flux densities. The `fluxscale` task exists for this purpose.

The inputs for `fluxscale` are:

```

# fluxscale :: Bootstrap the flux density scale from standard calibrators
vis      =      ''    # Name of input visibility file
caltable =      ''    # Name of input calibration table
fluxtable =      ''    # Name of output, flux-scaled calibration table
reference =      ''    # Reference field name(s) (transfer flux scale FROM)
transfer  =      ''    # Transfer field name(s) (transfer flux scale TO), '' -> all
append    =    False   # Append solutions?
refspwmap = [-1]    # Scale across spectral window boundaries. See help fluxscale

```

Before running `fluxscale`, one must have first run `setjy` for the `reference` sources and run a `gaincal` on both `reference` and `transfer` fields. After running `fluxscale` the output `fluxtable` `caltable` will have been scaled such that the correct scaling will be applied to the `transfer` sources.

For example, given a 'G' table, e.g. 'cal.G', containing solutions for a flux density calibrator (in this case '3C286') and for one or more gain calibrator sources with unknown flux densities (in this example '0234+285' and '0323+022'):

```

fluxscale(vis='data.ms',
          caltable='cal.G',           # Select input table
          fluxtable= 'cal.Gflux',     # Write scaled solutions to cal.Gflux
          reference='3C286',          # 3C286 = flux calibrator
          transfer='0234+258, 0323+022') # Select calibrators to scale

```

The output table, 'cal.Gflux', contains solutions that are properly scaled for all calibrators.

Note that the assertion that the gain solutions are independent of the calibrator includes the assumption that the gain amplitudes are strictly not systematically time dependent. While synthesis antennas are designed as much as possible to achieve this goal, in practice, a number of effects conspire to frustrate it. When relevant, it is advisable to pre-apply `gaincurve` and `opacity` corrections when solving for the '`G`' solutions that will be flux-scaled (see § 4.3 and § 4.4.1.3). When the '`G`' solutions are essentially constant for each calibrator separately, the `fluxscale` operation is likely to be robust.

The `fluxscale` task can be executed on either '`G`' or '`T`' solutions, but it should only be used on one of these types if solutions exist for both and one was solved relative to the other (use `fluxscale` only on the first of the two).

BETA ALERT: The '`GSPLINE`' option is not yet supported in `fluxscale` (see § 4.4.3.3).

If the `reference` and `transfer` fields were observed in different spectral windows, the `refspwmap` parameter may be used to achieve the scaling calculation across spectral window boundaries.

The `refspwmap` parameter functions similarly to the standard `spwmap` parameter (§ 4.4.1.4), and takes a list of indices indicating the spectral window mapping for the reference fields, such that `refspwmap[i]=j` means that reference field amplitudes from spectral window `j` will be used for spectral window `i`.

Note: You should be careful when you have a dataset with spectral windows with different bandwidths, and you have observed the calibrators differently in the different `spw`. The flux-scaling will probably be different in windows with different bandwidths.

For example,

```
fluxscale(vis='data.ms',
          caltable='cal.G',
          fluxtable= 'cal.Gflux',
          reference='3C286',
          transfer='0234+258,0323+022',
          refspwmap=[0,0,0])
```

Select input table
Write scaled solutions to cal.Gflux
3C286 = flux calibrator
Select calibrators to scale
Use spwid 0 scaling for spwids 1 & 2

will use `spw=0` to scale the others, while in

```
fluxscale(vis='data.ms',
          caltable='cal.G',
          fluxtable= 'cal.Gflux',
          reference='3C286',
          transfer='0234+285, 0323+022',
          refspwmap=[0,0,1,1])
```

Select input table
Write scaled solutions to cal.Gflux
3C286 = flux calibrator,
select calibrators to scale,
select spwids for scaling,

the reference amplitudes from spectral window 0 will be used for spectral windows 0 and 1 and reference amplitudes from spectral window 2 will be used for spectral windows 2 and 3.

4.4.4.1 Using Resolved Calibrators

If the flux density calibrator is resolved, the assumption that it is a point source will cause solutions on outlying antennas to be biased in amplitude. In turn, the `fluxscale` step will be biased on these antennas as well. In general, it is best to use model for the calibrator, but if such a model is not available, it is important to limit the solution on the flux density calibrator to only the subset of antennas that have baselines short enough that the point-source assumption is valid. This can be done by using `antenna` and `uvrange` selection when solving for the flux density calibrator. For example, if antennas 1 through 8 are the antennas among which the baselines are short enough that the point-source assumption is valid, and we want to be sure to limit the solutions to the use of baselines shorter than 15000 wavelengths, then we can assemble properly scaled solutions for the other calibrator as follows (note: specifying both an antenna and a `uvrange` constraint prevents inclusion of antennas with only a small number of baselines within the specified `uvrange` from being included in the solution; such antennas will have poorly constrained solutions):

As an example, we first solve for gain solutions for the flux density calibrator (3C286 observed in field 0) using a subset of antennas

```
gaincal(vis='data.ms',
       caltable='cal.G',          # write solutions to cal.G
       field='0',                 # Select the flux density calibrator
       selectdata=True,            # Expand other selectors
       antenna='0~7',              # antennas 0-7,
       uvrage='0~15klambda',      # limit uvrage to 0-15klambda
       solint=90)                  # on 90s timescales, write solutions
                                    # to table called cal.G
```

Now solve for other calibrator (0234+285 in field 1) using all antennas (implicitly) and append these solutions to the same table

```
gaincal(vis='data.ms',
       caltable='cal.G',          # write solutions to cal.G
       field='1',
       solint=90,
       append=T)                  # Set up to write to the same table
```

Finally, run `fluxscale` to adjust scaling

```
fluxscale(vis='data.ms',
          caltable='cal.G',        # Input table with unscaled cal solutions
          fluxtable='cal.Gflux',   # Write scaled solutions to cal.Gflux
          reference='3C286',       # Use 3c286 as ref with limited uvrage
          transfer='0234+285')    # Transfer scaling to 0234+285
```

The `fluxscale` calculation will be performed using only the antennas common to both fields, but the result will be applied to all antennas on the transfer field. Note that one can nominally get by only with the `uvrange` selection, but you may find that you get strange effects from some antennas only having visibilities to a subset of the baselines and thus causing problems in the solving.

4.4.5 Instrumental Polarization Calibration (D,X)

BETA ALERT: The `polcal` task is now available as of Beta Patch 1. It is still undergoing extensive testing, and only basic capabilities are currently provided.

The inputs to `polcal` are:

```
# polcal :: Determine instrumental polarization from calibrator observations
vis          =      ''    # Nome of input visibility file
caltable     =      ''    # Name of output gain calibration table
field        =      ''    # Select field using field id(s) or field name(s)
spw          =      ''    # Select spectral window/channels
selectdata   =     False  # Other data selection parameters
solint       =    'inf'  # Solution interval
combine      =    'scan'  # Data axes which to combine for solve (scan, spw, and/or field)
preavg      =   300.0   # Pre-averaging interval (sec)
refant       =      ''    # Reference antenna name
minsnr      =    0.0    # Reject solutions below this SNR
poltype     =    'D+QU'  # Type of instrumental polarization solution (see help)
append       =     False  # Append solutions to the (existing) table
gaintable   =      []    # Gain calibration table(s) to apply
gainfield   =      []    # Select a subset of calibrators from gaintable(s)
interp       =      []    # Interpolation mode (in time) to use for each gaintable
spwmap      =      []    # Spectral windows combinations to form for gaintables(s)
gaincurve   =     False  # Apply internal VLA antenna gain curve correction
opacity      =    0.0    # Opacity correction to apply (nepers)
async        =     False
```

The `polcal` task uses many of the standard calibration parameters as described above in § 4.4.1.

The key parameter controlling `polcal` is `poltype`. The choices are:

'D' — Solve for instrumental polarization (leakage D-terms), using the transform of an IQU model in `MODEL_DATA`; requires no parallactic angle coverage, but if the source polarization is non-zero, the gain calibration must have the correct R-L phase registration. (Note: this is unlikely, so just use 'D+X' to let the position angle registration float.) This will produce a calibration table of type **D**.

'D+X' — Solve for instrumental polarization D-terms and the polarization position angle correction, using the transform of an IQU model in `MODEL_DATA`; this mode requires at least 2 distinct parallactic angles to separate the net instrumental polarization and the PA. This will produce a calibration table of type 'D'. **BETA ALERT:** no table of type 'X' will be produced, so you must follow this by a run of `polcal` with `polmode='X'` (see below).

'D+QU' — Solve for instrumental polarization and source $Q + iU$; requires at least 3 distinct parallactic angles to separate the net instrumental polarization from the source Q and U. Effectively sets the polarization PA to the value if the R-L phase difference were 0° . This will produce a calibration table of type 'D'.

'X' — Solve only for the position angle correction; best to use this after getting the D-terms from one of the above modes. Requires the observation of a calibrator with known $Q + iU$ (or at least known U/Q). This will produce a calibration table of type '**X**'.

There are channelized solution modes for the above options. For example, substitute '**Df**' for '**D**' in the '**D***' modes described above to get a channelized D-term solution. **BETA ALERT:** '**X**' solutions are currently always frequency-independent.

BETA ALERT: `polcal` will obtain a separate D-term solution for each `field` supplied to it. This limitation will be relaxed in the future, enabling more sensitive solutions, as well as flexibilities like solving for '**D+X**' using a single scan each of two or more position angle calibrators.

4.4.5.1 Heuristics and Strategies for Polarization Calibration

Fundamentally, with good ordinary gain (and bandpass, if relevant) calibration already in hand, good polarization calibration must deliver both the instrumental polarization and position angle calibration. An unpolarized source can deliver only the first of these, but does not require parallactic angle coverage. A polarized source can only deliver the position angle calibration also if its polarization is known a priori. Sources that are polarized, but with unknown polarization, must always be observed with sufficient parallactic angle coverage, where "sufficient" is determined by SNR and the details of the solving mode.

These principles are stated assuming the instrumental polarization solution is solved using the "linear approximation" where cross-terms in more than a single product of the instrumental or source polarizations are ignored in the Measurement Equation (see § E). A general non-linearized solution, with sufficient SNR, may enable some relaxation of the requirements indicated here.

For instrumental polarization calibration, there are 3 types of calibrator choice:

CASA Polarization Calibration Modes

Cal Polarization	Parallactic Angles	MODEL_DATA	polmode	Result
unpolarized	any	set $Q = U = 0$	'D' or 'Df'	D-terms only
known non-zero	2+ scans	set Q, U	'D+X' or 'Df+X'	D-terms and PA
unknown	3+ scans	ignored	'D+QU' or 'Df+QU'	D-terms and source

Note that the parallactic angle ranges spanned by the scans in the modes that require this should be large enough to give good separation between the components of the solution. In practice, 60° is a good target.

Each of these solutions should be followed with a '**X**' solution on a source with known polarization position angle (and correct $Q + iU$ in MODEL_DATA). **BETA ALERT:** `polmode='D+X'` will soon deliver this automatically.

The `polcal` task will solve for the '**D**' or '**X**' terms using the model visibilities that are in the MODEL_DATA column of the MS. Calibration of the parallel hands must have already been carried out using `gaincal` and/or `bandpass` in order to align the phases over time and frequency. This

calibration need not have been applied and can be supplied through the `gaintable` parameters, but any cal-tables to be used in `polcal` must agree (e.g. have been derived from) the data in the `DATA` column and the model visibilities in the `MODEL_DATA` column of the MS. Thus, for example, one would not use the cal-table produced by `fluxscale` as the rescaled amplitudes would no longer agree with the contents of `MODEL_DATA`.

Be careful when using resolved calibrators for polarization calibration. A particular problem is if the structure in Q and U is offset from that in I. Use of a point model, or a resolved model for I but point models for Q and U, can lead to errors in the '`X`' calibration. Use of a `uvrange` will help here. The use of a full-Stokes model with the correct polarization is the only way to ensure a correct calibration if these offsets are large.

4.4.5.2 A Polarization Calibration Example

In the following example, we do a standard '`D+QU`' solution on the bright source BLLac (2202+422) which has been tracked through a range in parallactic angle:

```
default('polcal')
vis = 'polcal_20080224.cband.all.ms'
caltable = 'polcal_20080224.cband.all.pcal'
field = '2202+422'
spw =
solint = 'inf'
combine = 'scan'
preavg = 300.0
refant = 'VA15'
minsnr = 3
poltype = 'D+QU'
gaintable = 'polcal_20080224.cband.all.gcal'
gainfield =
polcal()
```

This assumes `setjy` and `gaincal` have already been run. Note that the original gain-calibration table is used in `gaintable` so that what is in the `MODEL_DATA` column is in agreement with what is in the `gaintable`, rather than using the table resulting from `fluxscale`.

A bit later on, we need to set the R-L phase using a scan on 3C48 (0137+331):

```
default('polcal')
vis = 'polcal_20080224.cband.all.ms'
caltable = 'polcal_20080224.cband.all.polx'
field = '0137+331'
refant = 'VA15'
minsnr = 3
poltype = 'X'
gaintable = ['polcal_20080224.cband.all.gcal', 'polcal_20080224.cband.all.pcal']
polcal()
```

If, on the other hand, we had a scan on an unpolarized bright source, for example 3C84 (0319+415), we could use this to calibrate the leakages:

```
default('polcal')
vis = 'polcal_20080224.cband.all.ms'
caltable = 'polcal_20080224.cband.all_3c84.pcal'
field = '0319+415'
refant = 'VA15'
poltype = 'D'
gaintable = 'polcal_20080224.cband.all.gcal'
polcal()
```

We would then do the 'X' calibration as before (but using this D-table in `gaintable`).

A full processing example for continuum polarimetry can be found in § F.3.

4.4.6 Baseline-based Calibration (`blcal`)

BETA ALERT: The `blcal` task has not had extensive testing, and is included as part of our support for the ALMA and EVLA commissioning efforts.

You can use the `blcal` task to solve for baseline-dependent (non-closing) errors. **WARNING:** this is in general a very dangerous thing to do, since baseline-dependent errors once introduced are difficult to remove. You must be sure you have an excellent model for the source (better than the magnitude of the baseline-dependent errors).

The inputs are:

```
# blcal :: Calculate a baseline-based calibration solution (gain or bandpass)

vis = '' # Nome of input visibility file
caltable = '' # Name of output gain calibration table
field = '' # Select field using field id(s) or field name(s)
spw = '' # Select spectral window/channels
selectdata = False # Other data selection parameters
solint = 'inf' # Solution interval
combine = 'scan' # Data axes which to combine for solve (scan, spw, and/or field)
freqdep = False # Solve for frequency dependent solutions
gaintable = [''] # Gain calibration table(s) to apply on the fly
gainfield = [''] # Select a subset of calibrators from gaintable(s)
interp = [''] # Interpolation mode (in time) to use for each gaintable
spwmap = [] # Spectral windows combinations to form for gaintables(s)
gaincurve = False # Apply internal VLA antenna gain curve correction
opacity = 0.0 # Opacity correction to apply (nepers)
parang = False # Apply parallactic angle correction
async = False
```

The `freqdep` parameter controls whether `blcal` solves for “gain” (`freqdep=True`) or “bandpass” (`freqdep=False`) style calibration.

Other parameters are the same as in other calibration tasks. These common calibration parameters are described in § 4.4.1.

4.4.7 EXPERIMENTAL: Fringe Fitting (fringecal)

BETA ALERT: The `fringecal` task has not had extensive testing, and is included as part of our support for the ALMA commissioning effort.

The `fringecal` task provides the capability for solving for *baseline-based* phase, phase-delay, and delay-rate terms in the gains (G-type). This is not full antenna-based “fringe-fitting” as is commonly used in VLBI. The main use is to calibrate ALMA or EVLA commissioning data where the delays may be improperly set, and to test “fringe” solutions as a way for dealing with non-dispersive atmospheric terms.

The inputs are:

```
# fringecal :: BL-based fringe-fitting solution:

vis          =      ''    # Name of input visibility file (MS)
caltable     =      ''    # Name of output bandpass calibration table
field        =      ''    # Select data based on field name or index
spw          =      ''    # Select data based on spectral window
selectdata   =     False  # Activate data selection details
gaincurve    =     False  # Apply VLA antenna gain curve correction
opacity      =      0.0   # Opacity correction to apply (nepers)
gaintable    =      ''    # Gain calibration solutions to apply
gainfield    =      ''    # 
solint       =      0.0   # Solution interval (sec)
refant       =      ''    # Reference antenna
async        =     False  # if True run in the background, prompt is freed
```

All of the `fringecal` parameters are common calibration parameters as described in § 4.4.1.

BETA ALERT: This task has not been updated to use the new standard `solint` and `combine` syntax. Also note that `plotcal` cannot currently display ‘delay’ or `delayrate` solutions from `fringecal`.

4.5 Plotting and Manipulating Calibration Tables

At some point, the user should examine (plotting or listing) the calibration solutions. Calibration tables can also be manipulated in various ways, such as by interpolating between times (and sources), smoothing of solutions, and accumulating various separate calibrations into a single table.

4.5.1 Plotting Calibration Solutions (plotcal)

The `plotcal` task is available for examining solutions of all of the basic solvable types (G, T, B, D, M, MF, K). The inputs are:

```
# plotcal :: An all-purpose plotter for calibration results:

caltable      =      ''      # Name of input calibration table
xaxis         =      ''      # Value to plot along x axis (time,chan,amp,phase,real,imag,snr)
yaxis         =      ''      # Value to plot along y axis (amp,phase,real,imag,snr)
poln          =      ''      # Polarization to plot (RL,R,L,XY,X,Y,/)

field         =      ''      # Field names or index: ''=all, '3C286,P1321*', '0~3'
antenna       =      ''      # Antenna selection. E.g., antenna='3~5'
spw           =      ''      # Spectral window: ''=all, '0,1' means spw 0 and 1
timerange     =      ''      # Time selection ''=all
subplot        =      111    # Panel number on display screen (yxn)
overplot       =      False   # Overplot solutions on existing display
clearpanel    =      'Auto'  # Specify if old plots are cleared or not
iteration      =      ''      # Iterate on antenna,time,spw,field
plotrange     =      []      # plot axes ranges: [xmin,xmax,ymin,ymax]
showflags      =      False   # If true, show flags
plotsymbol    =      '.'     # pylab plot symbol
plotcolor      =      'blue'  # initial plotting color
markersize    =      5.0    # size of plot symbols
fontsize       =      10.0   # size of label font
showgui        =      True    # Show plot on gui
figfile        =      ''      # ''= no plot hardcopy, otherwise supply name
```

BETA ALERT: Currently, `plotcal` needs to know the MS from which `caltable` was derived to get indexing information. It does this using the name stored inside the table, which does not include the full path, but assumes the MS is in the cwd. Thus if you are using a MS in a directory other than the current one, it will not find it. You need to change directories using `cd` in IPython (or `os.chdir()` inside a script) to the MS location.

The controls for the `plotcal` window are the same as for `plotxy` (see § 3.4.1).

The `xaxis` and `yaxis` plot options available are:

- `'amp'` — amplitude,
- `'phase'` — phase,
- `'real'` – the real part,
- `'imag'` — the imaginary part,
- `'snr'` – the signal-to-noise ratio,

of the calibration solutions that are in the `caltable`. The `xaxis` choices also include `'time'` and `'channel'` which will be used as the sensible defaults (if `xaxis=''`) for gain and bandpass solutions respectively.

The `poln` parameter determines what polarization or combination of polarization is being plotted. The `poln='RL'` plots both R and L polarizations on the same plot. The respective XY options

do equivalent things. The `poln='/'` option plots amplitude ratios or phase differences between whatever polarizations are in the MS (R and L. or X and Y).

The `field`, `spw`, and `antenna` selection parameters are available to obtain plots of subsets of solutions. The syntax for selection is given in § 2.5.

The `subplot` parameter is particularly helpful in making multi-panel plots. The format is `subplot=yxn` where `yxn` is an integer with digit `y` representing the number of plots in the y-axis, digit `x` the number of panels along the x-axis, and digit `n` giving the location of the plot in the panel array (where `n = 1, ..., xy`, in order upper left to right, then down). See § 3.4.3.6 for more details on this option.

The `iteration` parameter allows you to select an identifier to iterate over when producing multi-panel plots. The choices for `iteration` are: '`antenna`', '`time`', '`spw`', '`field`'. For example, if per-antenna solution plots are desired, use `iteration='antenna'`. You can then use `subplot` to specify the number of plots to appear on each page. In this case, set the `n` to 1 for `subplot=yxn`. Use the **Next** button on the `plotcal` window to advance to the next set of plots. Note that if there is more than one timestamp in a '`B`' table, the user will be queried to interactively advance the plot to each timestamp, or if `multiplot=True`, the antennas plots will be cycled through for each timestamp in turn. Note that `iteration` can take more than one iteration choice (as a single string containing a comma-separated list of the options). **BETA ALERT:** the iteration order is fixed (independent of the order specified in the `iteration` string), for example:

```
iteration = 'antenna, time, field'
iteration = 'time, antenna, field'
```

will both iterate over each field (fastest) then time (next) and antenna (slowest). The order is:

```
iteration = 'antenna, time, field, spw'
```

from the slowest (outer loop) to fastest (inner loop).

The `markersize` and `fontsize` parameters are especially helpful in making the dot and label sizes appropriate for the plot being made. The screen shots in this section used this feature to make the plots more readable in the cookbook. Adjusting the `fontsize` can be tricky on multi-panel plots, as the labels can run together if too large. You can also help yourself by manually resizing the Plotter window to get better aspect ratios on the plots.

BETA ALERT: Unfortunately, `plotcal` has many of the same problems that `plotxy` does, as they use similar code underneath. An overhaul is underway, so stay tuned.

4.5.1.1 Examples for `plotcal`

For example, to plot amplitude or phase as a function of time for '`G`' solutions (after rescaling by `fluxscale` for the NGC5921 “usecase” data (see § 4.8.1 below, and Appendix F.1),

```
default('plotcal')
fontsize = 14.0      # Make labels larger
```

```

markersize = 10.0    # Make dots bigger

caltable = 'ngc5921.usecase.fluxscale'
yaxis = 'amp'
subplot = 211
plotcal()

yaxis = 'phase'
subplot = 212
plotcal()

```

The results are shown in Figure 4.3. This makes use of the `subplot` option to make multi-panel displays.




Figure 4.3: Display of the amplitude (upper) and phase (lower) gain solutions for all antennas and polarizations in the `ngc5921` post-fluxscale table.

Similarly, to plot amplitude or phase as a function of channel for 'B' solutions for NGC5921:

```

default('plotcal')
fontsize = 14.0      # Make labels larger
markersize = 10.0    # Make dots bigger

caltable = 'ngc5921.usescase.bcal'
antenna = '1'
yaxis = 'amp'
subplot = 311
plotcal()

yaxis = 'phase'
subplot = 312
plotcal()

yaxis = 'snr'
subplot = 313
plotcal()

```

The results are shown in Figure 4.4. This stacks three panels with amplitude, phase, and signal-to-noise ratio. We have picked `antenna='1'` to show.

For example, to show 6 plots per page of 'B' amplitudes on a 3×2 grid:

```

default('plotcal')
fontsize = 12.0      # Make labels just large enough
markersize = 10.0    # Make dots bigger

caltable = 'ngc5921.usescase.bcal'
yaxis = 'amp'
subplot = 231
iteration = 'antenna'

plotcal()

```

See Figure 4.5 for this example. This uses the `iteration` parameter.

BETA ALERT: Note that `plotcal` cannot currently display 'delay' or `delayrate` solutions from `fringecal`.

4.5.2 Listing calibration solutions with (`listcal`)

The `listcal` task will list the solutions in a specified calibration table.

The inputs are:

```

# listcal :: List data set summary in the logger:

vis      =      ''    # Name of input visibility file (MS)
caltable =      ''    # Input calibration table to list

```




Figure 4.4: Display of the amplitude (upper), phase (middle), and signal-to-noise ratio (lower) of the bandpass 'B' solutions for `antenna='0'` and both polarizations for `ngc5921`. Note the falloff of the SNR at the band edges in the lower panel.

```

field      =      ''    # Select data based on field name or index
antenna   =      ''    # Select data based on antenna name or index
spw       =      ''    # Spectral window, channel to list
listfile   =      ''    # Disk file to write, else to terminal
pagerows   =      0     # Rows listed per page
async     =     False

```

An example listing is:

```
Listing CalTable: jupiter6cm.usecase.split.ms.smoothcal2  (G Jones)
-----
```

```

SpwId = 0,  channel = 0.
Time           Field        Ant       :   Amp      Phase      Amp      Phase

```




Figure 4.5: Display of the amplitude of the bandpass 'B' solutions. Iteration over antennas was turned on using `iteration='antenna'`. The first page is shown. The user would use the `Next` button to advance to the next set of antennas.

1999/04/16/14:10:43.5	'JUPITER'	'1'	:	1.016	-11.5	1.016	-9.2
		'2'	:	1.013	-5.3	0.993	-3.1
		'3'	:	0.993	-0.8	0.990	-5.1
		'4'	:	0.997	-10.7	0.999	-8.3
		'5'	:	0.985	-2.7	0.988	-4.0
		'6'	:	1.005	-8.4	1.009	-5.3
		'7'	:	0.894	-8.7	0.897	-6.8
		'8'	:	1.001	-0.1	0.992	-0.7
		'9'	:	0.989	-12.4	0.992	-13.5
		'10'	:	1.000F	-4.2F	1.000F	-3.2F
		'11'	:	0.896	-0.0	0.890	-0.0
		'12'	:	0.996	-10.6	0.996	-4.2
		'13'	:	1.009	-8.4	1.011	-6.1

'14'	:	0.993	-17.6	0.994	-16.1
'15'	:	1.002	-0.8	1.002	-1.1
'16'	:	1.010	-9.9	1.012	-8.6
'17'	:	1.014	-8.0	1.017	-7.1
'18'	:	0.998	-3.0	1.005	-1.0
'19'	:	0.997	-39.1	0.994	-38.9
'20'	:	0.984	-5.7	0.986	3.0
'21'	:	1.000F	-4.2F	1.000F	-3.2F
'22'	:	1.003	-11.8	1.004	-10.4
'23'	:	1.007	-13.8	1.009	-11.7
'24'	:	1.000F	-4.2F	1.000F	-3.2F
'25'	:	1.000F	-4.2F	1.000F	-3.2F
'26'	:	0.992	3.7	1.000	-0.2
'27'	:	0.994	-5.6	0.991	-4.3
'28'	:	0.993	-10.7	0.997	-3.8

BETA ALERT: It is likely that the format of this listing will change to better present it to the user.

4.5.3 Calibration Smoothing (smoothcal)

The `smoothcal` task will smooth calibration solutions (most usefully G or T) over a longer time interval to reduce noise and outliers. The inputs are:

```
# smoothcal :: Smooth calibration solution(s) derived from one or more sources:

vis      =      ''    # Name of input visibility file
tablein  =      ''    # Input calibration table
caltable =      ''    # Output calibration table
field    =      ''    # Field name list
smoothtype = 'median' # Smoothing filter to use
smoothtime =   60.0   # Smoothing time (sec)
async    = False    # if True run in the background, prompt is freed
```

The smoothing will use the `smoothtime` and `smoothtype` parameters to determine the new data points which will replace the previous points on the same time sampling grid as for the `tablein` solutions. The currently supported `smoothtype` options:

- '`mean`' — use the mean of the points within the window defined by `smoothtime` (a "boxcar" average),
- '`median`' — use the median of the points within the window defined by `smoothtime` (most useful when many points lie in the interval).

Note that `smoothtime` defines the width of the time window that is used for the smoothing.




Figure 4.6: The ‘amp’ of gain solutions for NGC4826 before (top) and after (bottom) smoothing with a 7200 sec `smoothtime` and `smoothtype='mean'`. Note that the first solution is in a different `spw` and on a different source, and is not smoothed together with the subsequent solutions.

BETA ALERT: Note that `smoothcal` currently smooths by `field` and `spw`, and thus you cannot smooth solutions from different sources or bands together into one solution.

An example using the `smoothcal` task to smooth an existing table:

```
smoothcal('n4826_16apr.ms',
    tablein='n4826_16apr.gcal',
    caltable='n4826_16apr.smoothcal',
    smoothtime=7200.,
    smoothtype='mean')

# Plot up before and after tables
plotcal('n4826_16apr.gcal','','amp',antenna='1',subplot=211)
plotcal('n4826_16apr.smoothcal','','amp',antenna='1',subplot=212)
```

This example uses 2 hours (7200 sec) for the smoothing time and `smoothtype='mean'`. The `plotcal` results are shown in Figure 4.6.

4.5.4 Calibration Interpolation and Accumulation (`accum`)

The `accum` task is used to interpolate calibration solutions onto a different time grid, and to *accumulate* incremental calibrations into a *cumulative* calibration table.

Its inputs are:

```
# accum :: Accumulate incremental calibration solutions

vis          =      ''    # Name of input visibility file
tablein      =      ''    # Input (cumulative) calibration table; use '' on first run
    accumtime = 1.0   # Timescale on which to create cumulative table

incrtable    =      ''    # Input incremental calibration table to add
caltable     =      ''    # Output (cumulative) calibration table
field        =      ''    # List of field names to process from tablein.
calfield     =      ''    # List of field names to use from incrtable.
interp       = 'linear' # Interpolation mode to use for resampling incrtable solutions
spwmap       = [-1]    # Spectral window combinations to apply
```

The *mapping* implied here is

```
tablein + incrtable => caltable
```

(mathematically the cal solutions are multiplied as complex numbers as per the Measurement Equation). The `tablein` is optional (see below). You must specify an `incrtable` and a `caltable`.

The `tablein` parameter is used to specify the existing cumulative calibration table to which an incremental table is to be applied. Initially, no such table exists, and if `tablein=''`, then `accum` will generate one from scratch (on-the-fly), using the timescale (in seconds) specified by the sub-parameter `accumtime`. These nominal solutions will be unit-amplitude, zero-phase calibration, ready to be adjusted by accumulation according to the settings of other parameters. When `accumtime` is negative (the default), the table name specified in `tablein` must exist and will be used. If `tablein` is specified, then the entries in that table will be used.

The `incrtable` parameter is used to specify the incremental table that should be applied to `tablein`. The calibration type of `incrtable` sets the type assumed in the operation, so `tablein` (if specified) must be of the same type. If it is not, `accum` will exit with an error message. (Certain combinations of types and subtypes will be supported by `accum` in the future.)

The `caltable` parameter is used to specify the name of the output table to write. If un-specified (''), then `tablein` will be overwritten. Use this feature with care, since an error here will require building up the cumulative table from the most recent distinct version (if any).

The `field` parameter specifies those field names in `tablein` to which the incremental solution should be applied. The solutions for other fields will be passed to `caltable` unaltered. If the

cumulative table was created from scratch in this run of accumulate, then the solutions for these other fields will be unit-amplitude, zero-phase, as described above.

The `calfld` parameter is used to specify the fields to select from `incrtable` to use when applying to `tablein`. Together, use of `field` and `calfld` permit completely flexible combinations of calibration accumulation with respect to fields. Multiple runs of `accum` can be used to generate a single table with many combinations. In future, a '`self`' mode will be enabled that will simplify the accumulation of field-specific solutions.

The `spwmap` parameter gives the mapping of the spectral windows in the `incrtable` onto those in `tablein` and `caltable`. The syntax is described in § 4.4.1.4.

The `interp` parameter controls the method used for interpolation. The options are (currently): '`nearest`', '`linear`', and '`aipslin`'. These are described in § 4.4.1.4. For most purposes, the '`linear`' option should suffice.

We now describe the two uses of `accum`.

4.5.4.1 Interpolation using (`accum`)

Calibration solutions (most notably G or T) can be interpolated onto the timestamps of the science target observations using `accum`.

The following example uses `accum` to interpolate an existing table onto a new time grid:

```
accum(vis='n4826_16apr.ms',
      tablein='',
      accumtime=20.0,
      incrtable='n4826_16apr.gcal',
      caltable='n4826_16apr.20s.gcal',
      interp='linear',
      spwmap=[0,1,1,1,1,1])

plotcal('n4826_16apr.gcal','','phase',antenna='1',subplot=211)
plotcal('n4826_16apr.20s.gcal','','phase',antenna='1',subplot=212)
```

See Figure 4.7 for the `plotcal` results. The data used in this example is BIMA data (single polarization YY) where the calibrators were observed in single continuum spectral windows (`spw='0,1'`) and the target NGC4826 was observed in 64-channel line windows (`spw='2,3,4,5'`). Thus, it is necessary to use `spwmap=[0,1,1,1,1,1]` to map the bandpass calibrator in `spw='0'` onto itself, and the phase calibrator in `spw='1'` onto the target source in `spw='2,3,4,5'`.

4.5.4.2 Incremental Calibration using (`accum`)

It is occasionally desirable to solve for and apply calibration incrementally. This is the case when a calibration table of a certain type already exists (from a previous solve), a solution *of the same type* and incremental *relative to the first* is required, and it is not possible or convenient to recover the cumulative solution by a single solve.




Figure 4.7: The ‘phase’ of gain solutions for NGC4826 before (top) and after (bottom) ‘linear’ interpolation onto a 20 sec `accumtime` grid. The first scan was 3C273 in `spw='0'` while the calibrator scans on 1331+305 were in `spw='1'`. The use of `spwmap` was necessary to transfer the interpolation correctly onto the NGC4826 scans.

Much of the time, it is, in fact, possible to recover the cumulative solution. This is because the equation describing the solution for the incremental solution (using the original solution), and that describing the solution for their product are fundamentally the same equation—the cumulative solution, if unique, must always be the same no matter what initial solution is. One circumstance where an incremental solution is necessary is the case of *phase-only* self-calibration relative to a full amplitude and phase calibration already obtained (from a different field).

For example, a phase-only ‘G’ self-calibration on a target source may be desired to tweak the full amplitude and phase ‘G’ calibration already obtained from a calibrator. The initial calibration (from the calibrator) contains amplitude information, and so must be carried forward, yet the phase-only solution itself cannot (by definition) recover this information, as a full amplitude and phase self-calibration would. In this case, the initial solution must be applied while solving for the

phase-only solution, then the two solutions combined to form a cumulative calibration embodying the net effect of both. In terms of the Measurement Equation, the net calibration is the product of the initial and incremental solutions.

Cumulative calibration tables also provide a means of generating carefully interpolated calibration, on variable user-defined timescales, that can be examined prior to application to the data with `applycal`. The solutions for different fields and/or spectral windows can be interpolated in different ways, with all solutions stored in the same table.

The only difference between incremental and cumulative calibration tables is that incremental tables are generated directly from the calibration solving tasks (`gaincal`, `bandpass`, etc), and cumulative tables are generated from other cumulative and incremental tables via `accum`. In all other respects (internal format, application to data with `applycal`, plotting with `plotcal`, etc.), they are the same, and therefore interchangeable. Thus, accumulate and cumulative calibration tables need only be used when circumstances require it.

Other Packages:

The analog of `accum` in classic AIPS is the use of CLCAL to combine a series of (incremental) SN calibration tables to form successive (cumulative) CL calibration tables. AIPS SN/CL tables are the analog of 'G' tables in CASA.

The `accum` task represents a generalization on the classic AIPS CLCAL (see sidebox) model of cumulative calibration in that its application is not limited to accumulation of 'G' solutions. In principle, any basic calibration type can be accumulated (onto itself), as long as the result of the accumulation (matrix product) is of the same type. This is true of all the basic types, except 'D'. Accumulation is currently supported for 'B', 'G', and 'T', and, in future, 'F' (ionospheric Faraday rotation), delay-rate, and perhaps others. Accumulation of certain specialized types (e.g., 'GSPLINE', 'TOPAC', etc.) onto the basic types will be supported in the near future. The treatment of various calibration from ancillary data (e.g., system temperatures, weather data, WVR, etc.), as they become available, will also make use of accumulate to achieve the net calibration.

Note that accumulation only makes sense if treatment of a uniquely incremental solution is required (as described above), or if a careful interpolation or sampling of a solution is desired. In all other cases, re-solving for the type in question will suffice to form the net calibration of that type. For example, the product of an existing 'G' solution and an amplitude and phase 'G' self-cal (solved with the existing solution applied), is equivalent to full amplitude and phase 'G' self-cal (with no prior solution applied), as long as the timescale of this solution is at least as short as that of the existing solution.

One obvious application is to calibrate the amplitudes and phases on different timescales during self-calibration. Here is an example, using the Jupiter VLA 6m continuum imaging example (see § 4.8.2 below):

```
# Put clean model into MODEL_DATA column
ft(vis='jupiter6cm.usescase.split.ms',
    model='jupiter6cm.usescase.clean1.model')

# Phase only self-cal on 10s timescales
gaincal(vis='jupiter6cm.usescase.split.ms',
        calsetable='jupiter6cm.usescase.phasecal1',
```

```

gaintype='G',
calmode='p',
refant='6',
solint=10.0,
minsnr=1.0)

# Plot up solution phase and SNR
plotcal('jupiter6cm.usecase.phasecal1','','phase',antenna='1',subplot=211)
plotcal('jupiter6cm.usecase.phasecal1','','snr',antenna='1',subplot=212)

# Amplitude and phase self-cal on scans
gaincal(vis='jupiter6cm.usecase.split.ms',
        caltable='jupiter6cm.usecase.scancal1',
        gaintable='jupiter6cm.usecase.phasecal1',
        gaintype='G',
        calmode='ap',
        refant='6',
        solint='inf',
        minsnr=1.0)

# Plot up solution amp and SNR
plotcal('jupiter6cm.usecase.scancal1','','amp',antenna='1',subplot=211)
plotcal('jupiter6cm.usecase.scancal1','','snr',antenna='1',subplot=212)

# Now accumulate these - they will be on the 10s grid
accum(vis='jupiter6cm.usecase.split.ms',
       tablein='jupiter6cm.usecase.phasecal1',
       incrtable='jupiter6cm.usecase.scancal1',
       caltable='jupiter6cm.usecase.selfcal1',
       interp='linear')

# Plot this up
plotcal('jupiter6cm.usecase.selfcal1','','amp',antenna='1',subplot=211)
plotcal('jupiter6cm.usecase.selfcal1','','phase',antenna='1',subplot=212)

```

The final plot is shown in Figure 4.8

BETA ALERT: Only interpolation is offered in `accum`, no smoothing (as in `smoothcal`).

4.6 Application of Calibration to the Data

After the calibration solutions are computed and written to one or more calibration tables, one then needs to apply them to the data.

4.6.1 Application of Calibration (`applycal`)

After all relevant calibration types have been determined, they must be applied to the target source(s) before splitting off to a new MS or before imaging. This is currently done by explicitly




Figure 4.8: The final 'amp' (top) and 'phase' (bottom) of the self-calibration gain solutions for Jupiter. An initial phase calibration on 10s `soltint` was followed by an incremental gain solution on each scan. These were accumulated into the cumulative solution shown here.

taking the data in the `DATA` column in the `MAIN` table of the MS, applying the relevant calibration tables, and creating the `CORRECTED_DATA` scratch column. The original `DATA` column is untouched.

The `applycal` task does this. The inputs are:

```
# applycal :: Apply calibration solution(s) to data

vis          =      ''    # Name of input visibility file
field        =      ''    # Names or indices of data fields to apply calibration ''==>all
spw          =      ''    # spectral window:channels: ''==>all
selectdata   =     False  # Other data selection parameters
gaintable   =      ''    # List of calibration table(s) to apply
gainfield   =      ''    # Field selection for each gaintable
interp       =      ''    # Interpolation mode (in time) for each gaintable
```

```

spwmap      =      []    # Spectral window mapping for each gaintable (see help)
gaincurve   =     False  # Apply VLA antenna gain curve correction
opacity      =     0.0   # Opacity correction to apply (nepers)
parang       =     False  # Apply the parallactic angle correction
calwt        =     True   # Apply calibration also to the WEIGHTS
async        =     False  # if True run in the background, prompt is freed

```

As in other tasks, setting `selectdata=True` will open up the other selection sub-parameters (see § 2.5). Many of the other parameters are the common calibration parameters that are described in § 4.4.1.

The single non-standard parameter is the `calwt` option to toggle the ability to scale the visibility weights by the inverse of the products of the scale factors applied to the amplitude of the antenna gains (for the pair of antennas of a given visibility). This should in *almost all cases* be set to its default (`True`). The weights should reflect the inverse noise variance of the visibility, and errors in amplitude are usually also in the weights.

For `applycal`, the list of final cumulative tables is given in `gaintable`. In this case you will have run `accum` if you have done incremental calibration for any of the types, such as '`G`'. You can also feed `gaintable` the full sets and rely on use of `gainfield`, `interp` and `spwmap` to do the correct interpolation and transfer. It is often more convenient to go through accumulation of each type with `accum` as described above (see § 4.5.4.2), as this makes it easier to keep track of the sequence of incremental calibration as it is solved and applied. You can also do any required smoothing of tables using `smoothcal` (§ 4.5.3), as this is not yet available in `accum` or `applycal`.

If you are not doing polarization calibration or imaging, then you can set `parang=False` to make the calculations faster. If you are applying polarization calibration, or wish to make polarization images, then set `parang=True` so that the parallactic angle rotation is applied to the appropriate correlations. Currently, you must do this in `applycal` as this cannot be done on-the-fly in `clean` or `mosaic`. See § 4.4.1.3 for more on `parang`.

For example, to apply the final bandpass and flux-scaled gain calibration tables solutions to the NGC5921 data:

```

default('applycal')

vis='ngc5921.usecase.ms'

# We want to correct the calibrators using themselves
# and transfer from 1445+099 to itself and the target N5921

# Start with the fluxscale/gain and bandpass tables
gaintable=['ngc5921.usecase.fluxscale','ngc5921.usecase.bcal']

# pick the 1445+099 (field 1) out of the gain table for transfer
# use all of the bandpass table
gainfield = ['1','*']

# interpolation using linear for gain, nearest for bandpass
interp = ['linear','nearest']

```

```

# only one spw, do not need mapping
spwmap = []

# all channels, no other selection
spw = ''
selectdata = False

# no prior calibration
gaincurve = False
opacity = 0.0

# select the fields for 1445+099 and N5921 (fields 1 and 2)
field = '1,2'

applycal()

# Now for completeness apply 1331+305 (field 0) to itself

field = '0'
gainfield = ['0', '*']

applycal()

# The CORRECTED_DATA column now contains the calibrated visibilities

```

In another example, we apply the final cumulative self-calibration of the Jupiter continuum data obtained in the example of § 4.5.4.2:

```

applycal(vis='jupiter6cm.usecase.split.ms',
         gaintable='jupiter6cm.usecase.selfcall1',
         selectdata=False)

```

Again, it is important to remember the relative nature of each calibration term. A term solved for in the presence of others is, in effect, residual to the others, and so must be used in combination with them (or new versions of them) in subsequent processing. At the same time, it is important to avoid isolating the same calibration effects in more than one term, e.g., by solving for both ' G ' and ' T ' separately (without applying the other), and then using them together.

It is always a good idea to examine the corrected data after calibration (using `plotxy` to compare the raw ('`data`') and corrected ('`corrected`') visibilities), as we describe next.

4.6.2 Examine the Calibrated Data

Once the source data is calibrated using `applycal`, you should examine the *uv* data and flag anything that looks bad. If you find source data that has not been flanked by calibration scans, delete it (it will not be calibrated).

For example, to look at the calibrated Jupiter data in the last example given in the previous section:

```
plotxy('jupiter6cm.usecase.split.ms','uvdist','amp','corrected',
       selectdata=True,correlation='RR LL',fontsize = 14.0)
```

will show the CORRECTED_DATA column. See Figure 4.9.




Figure 4.9: The final 'amp' versus 'uvdist' plot of the self-calibrated Jupiter data, as shown in `plotxy`. The 'RR LL' correlations are selected. No outliers that need flagging are seen.

See § 3.4 for a description of how to display and edit data using `plotxy`, and § 7.4 for use of the `viewer` to visualize and edit a Measurement Set.

4.6.3 Resetting the Applied Calibration using (`clearcal`)

The `applycal` task will set the CORRECTED_DATA column. The `clearcal` task will reset it to be the same as the DATA column. This may or may not be what you really want to do — nominally you will rerun `applycal` to get new calibration if you have changed the tables or want to apply them differently.

There is only a single input to `clearcal`:

```
# clearcal :: Re-initializes calibration for an ms
vis           =      ''          # Name of input visibility file
```

Note: `clearcal` also resets the `MODEL_DATA` column to (1,0) for all fields and spectral windows.

4.7 Other Calibration and UV-Plane Analysis Options

4.7.1 Splitting out Calibrated uv data (`split`)

The `split` task will apply calibration and output a new sub-MS containing a specified list of sources (usually a single source). The inputs are:

```
# split :: Create a visibility subset from an existing visibility set:
vis           =      ''          # Name of input visibility file
outputvis    =      ''          # Name of output visibility file
field         =      ''          # Field name list
spw           =      ''          # Spectral window identifier
width         =      1           # number of channel to average to form one output channel
antenna       =      ''          # Antenna selection
timebin       =      '-1s'        # time averaging of data
timerange     =      ''          # time range for subset of data
datacolumn    =      'corrected' # which column to split (data, corrected, model)
async         =      False        # if True run in the background, prompt is freed
```

Usually you will run `split` with `datacolumn='corrected'` as previous operations (e.g. `applycal`) will have placed the calibrated data in the `CORRECTED_DATA` column of the MS.

For example, to split out 46 channels (5-50) from `spw 1` of our NGC5921 calibrated dataset:

```
split(vis='ngc5921.usecase.ms',
      outputvis='ngc5921.split.ms',
      field='2',                                # Output NGC5921 data (field 2)
      spw='0:5~50',                             # Select 46 chans from spw 0
      datacolumn='corrected')                   # Take the calibrated data column
```

4.7.1.1 Averaging in `split` (EXPERIMENTAL)

BETA ALERT: The averaging in `split` is still problematic. In some known cases the time averaging produces incorrect results. Channel averaging seems to work, but needs more testing. User beware!

Time and channel averaging are now available using the `timebin` and `width` parameters.

The `timebin` parameter give the averaging time. It takes a quantity, e.g.

```
timebin = '30s'
```

The `width` parameter defines the number of channels to average to form a given output channel. This can be specified globally for all `spw`, e.g.

```
width = 5
```

or specified per `spw`, e.g.

```
width = [2,3]
```

to average 2 channels of 1st spectral window selected and 3 in the second one.

BETA ALERT: The ability to average channels in both time and channel simultaneously is not yet available. Also, if you average time and channel through sequential runs of `split`, you must average in time first.

4.7.2 Hanning smoothing of uv data (`hanningsmooth`)

The `hanningsmooth` task will apply Hanning smoothing to a spectral line uv data set. It will be applied to the data in the `DATA` column of the input MS and it writes the Hanning smoothed data into the `CORRECTED_DATA` column of that same MS.

Hanning smoothing replaces the contents of channel i with a weighted sum of the contents of a number of channels surrounding channel i . In its current form, only channels $i-1$, i , and $i+1$ participate, with weights 0.25, 0.50, and 0.25 respectively, but we intend to extend the kernel size in future releases. A typical use for Hanning smoothing is to remove Gibbs ringing.

The inputs are:

```
# hanningsmooth :: Hanning smooth frequency channel data
vis           = 'ngc5921.split.ms'      # Name of input visibility file (MS)
async         =      False
```

In many cases the data to be smoothed are in the `CORRECTED_DATA` column of the MS; in that case, run `split` first to copy the contents of the `CORRECTED_DATA` column of the input MS to the `DATA` column of the output MS. Then run `hanningsmooth` on the newly created MS.

After hanning smoothing, the contents of the first and last channel of each visibility are undefined; `hanningsmooth` will therefore flag the first and last channel.

BETA ALERT: We intend to make the kernel size a user supplied parameter. In the longer term we intend to offer other varieties of spectral smoothing as well.

4.7.3 Model subtraction from uv data (uvsub)

The `uvsub` task will subtract the value in the `MODEL` column from that in the `CORRECTED_DATA` column in the input MS and store the result in that same `CORRECTED_DATA` column.

The reverse operation is achieved by specifying `reverse = True`: in that case `uvsub` will add the value in the `MODEL` column to that in the `CORRECTED_DATA` column in the input MS and store the result in that same `CORRECTED_DATA` column.

The inputs are:

```
# uvsub :: Subtract/add model from/to the corrected visibility data.

vis      =      ''    # Name of input visibility file (MS)
reverse  =      False  # reverse the operation (add rather than subtract)
async    =      False
```

For example:

```
uvsub('ngc5921.split.ms')
```

BETA ALERT: Currently, `uvsub` operates on the scratch columns in the MS `vis`. Eventually we will provide the option to handle these columns behind the scenes and to write out a new MS.

4.7.4 UV-Plane Continuum Subtraction (uvcontsub)

At this point, consider whether you are likely to need continuum subtraction. If there is significant continuum emission present in what is intended as a spectral line observation, continuum subtraction may be desirable. You can estimate and subtract continuum emission in the *uv*-plane prior to imaging or wait and subtract an estimate of it in the image-plane. Note that neither method is ideal, and the choice depends primarily upon the distribution and strength of the continuum emission. Subtraction in the *uv*-plane is desirable if continuum emission dominates the source, since deconvolution of the line emission will be more robust if not subject to errors in deconvolution of the brighter continuum. There is also a performance benefit since the continuum is probably the same in each channel of the observation, and it is desirable to avoid duplication of effort. However, the main drawback of subtraction in the *uv*-plane is that it is only strictly correct for the phase center, since without the Fourier transform, the visibilities only describe the phase center. Thus, *uv*-plane continuum subtraction will be increasingly poor for emission distributed further from the phase center. If the continuum emission is relatively weak, it is usually adequate to subtract it in the image plane; this is described in the Image Analysis section of this cookbook. Here, we describe how to do continuum subtraction in the *uv*-plane.

The *uv*-plane continuum subtraction is performed by the `uvcontsub` task. First, determine which channels in your data cube do not have line emission, perhaps by forming a preliminary image as described in the next chapter. This image will also help you decide whether or not you need to come back and do *uv*-plane continuum subtraction at all.

The inputs to `uvcontsub` are:

```
# uvcontsub :: Continuum fitting and subtraction in the uv plane
vis      =      ''    # Nome of input visibility file
field    =      ''    # Select field using field id(s) or field name(s)
fitspw   =      ''    # Spectral window/channel selection for fitting the continuum
spw      =      ''    # Spectral window selection for subtraction/export
solint   =  'int'  # Continuum fit timescale
fitorder =      0    # Polynomial order for the fit
fitmode   = 'subtract' # Use of continuum fit (subtract,replace,model)
splitdata = False   # Split out continuum, continuum-subtracted data
async    = False   #
```

For each baseline, and over the timescale specified in `solint`, `uvcontsub` will provide a simple linear fit to the real and imaginary parts of the (continuum-only) channels specified in `fitspw` (using the standard `spw` selection syntax), and then subtract this model from all channels specified in `spw`, or from all channels in spectral windows of `fitspw` if `spw=''`. **BETA ALERT:** The fits are currently done independently in the spectral windows specified in `fitspw`, and thus overlapping channels in different `spw` will be corrected only with the fits from their respective `fitspw`.

Usually, one would set `solint='int'` which does no averaging and fits each integration. However, if the continuum emission comes from a small region around the phase center, then you can set `solint` larger (as long as it is shorter than the timescale for changes in the visibility function of the continuum). If your scans are short enough you can also use scan averaging `solint='inf'`. Be warned, setting `solint` too large will introduce “time smearing” in the estimated continuum and thus not properly subtracting emission not at the phase center.

Running `uvcontsub` with `fitmode='subtract'` will replace the `CORRECTED_DATA` column in the MS with continuum-subtracted line data and the `MODEL_DATA` column with the continuum model. You can use `fitmode='replace'` to replace the `CORRECTED_DATA` column with the continuum model; however, it is probably better to use `fitmode='subtract'` and then use `split` to select the `MODEL_DATA` and form a dataset appropriate for forming an image of the estimated continuum. Note that a continuum image formed from this model will only be strictly correct near the phase center, for the reasons described above.

The `splitdata` parameter can be used to have `uvcontsub` write out split MS for both the continuum-subtracted data and the continuum. It will leave the input MS in the state as if `fitmode='subtract'` was used. Note that the entire channel range of the MS will be written out (not just the channels specified in `spw` that have had the subtraction), so follow up with a `split` if you want to further restrict the output channel range. If `splitdata=True`, then `uvcontsub` will make two output MS with names `<input msname>.contsub` and `<input msname>.cont`. **BETA ALERT:** be sure to run with `fitmode='subtract'` if setting `splitdata=True`.

Note that it is currently the case that `uvcontsub` will overwrite the `CORRECTED_DATA` column. Therefore, it is desirable to first `split` the relevant corrected data into a new Measurement Set. If you run `uvcontsub` on the original dataset, you will have to re-apply the calibration as described in the previous chapter.

So, the recommended procedure is as follows:

- Finish calibration as described in the previous chapter.

- Use `split` to form a separate dataset.
- Use the `invert` or `clean` task on the `split` result to form an exploratory image that is useful for determining the line-free channels.
- Use `uvcontsub` with `mode='subtract'` to subtract the continuum from the `CORRECTED_DATA` in the MS, and write the continuum model in the `MODEL_DATA` column. Set `splitdata=True` to have it automatically split out continuum-subtracted and continuum datasets, else do this manually.
- Image the line-only emission with the `clean` task.
- If an image of the estimated continuum is desired, and you did not use `splitdata=True`, then run `split` again (on the `uvcontsub`'d dataset), and select the `MODEL_DATA`; then run `clean` to image it.

For example, we perform uv-plane continuum subtraction on our NGC5921 dataset:

```
# Want to use channels 4-6 and 50-59 for continuum
uvcontsub(vis='ngc5921.usecase.ms',
          field='N5921*',
          spw='',                      # all spw (only 0 in this data)
          fitspw='0:4~7;50~59',        # channels 4-6 and 50-59
          solint='inf',                # scans are short enough
          fitorder=0                  # mean only
          fitmode='subtract',          # uv-plane subtraction
          splitdata=True)             # split the data for us

# You will see it made two new MS:
# ngc5921.usecase.ms.cont
# ngc5921.usecase.ms.consub
```

4.7.5 UV-Plane Model Fitting (`uvmodelfit`)

It is often desirable to fit simple analytic source component models directly to visibility data. Such fitting has its origins in early interferometry, especially VLBI, where arrays consisted of only a few antennas and the calibration and deconvolution problems were poorly constrained. These methods overcame the calibration uncertainties by fitting the models to calibration-independent closure quantities and the deconvolution problem by drastically limiting the number of free parameters required to describe the visibilities. Today, even with larger and better calibrated arrays, it is still desirable to use visibility model fitting in order to extract geometric properties such as the positions and sizes of discrete components in radio sources. Fits for physically meaningful component shapes such as disks, rings, and optically thin spheres, though idealized, enable connecting source geometry directly to the physics of the emission regions.

Visibility model fitting is carried out by the `uvmodelfit` task. The inputs are:

```
# uvmodelfit :: Fit a single component source model to the uv data:

vis      =      ''    # Name of input visibility file
field    =      ''    # field name or index
spw      =      ''    # spectral window
selectdata = False   # Activate data selection details
niter    =      5    # Number of fitting iterations to execute
comptype = 'P'     # Component type (P=pt source,G=ell. gauss,D=ell. disk)
sourcepar = [1, 0, 0] # Starting guess (flux,xoff,yoff,bmajaxrat,bpa)
varypar  =      []    # Which parameters can vary in fit
outfile   =      ''    # Optional output component list table
async     = False   # if True run in the background, prompt is freed
```

BETA ALERT: This task currently only fits a single component.

The user specifies the number of non-linear solution iterations (`niter`), the component type (`comptype`), an initial guess for the component parameters (`sourcepar`), and optionally, a vector of Booleans selecting which component parameters should be allowed to vary (`fixpar`), and a filename in which to store a CASA componentlist for use in other applications (`file`). Allowed `comptypes` are currently point 'P' or Gaussian 'G'.

The function returns a vector containing the resulting parameter list. This vector can be edited at the command line, and specified as input (`sourcepar`) for another round of fitting.

The `sourcepar` parameter is currently the only way to specify the starting parameters for the fit. For points, there are three parameters: I (total flux density), and relative direction (RA, Dec) offsets (in arcsec) from the observation's phase center. For Gaussians, there are three additional parameters: the Gaussian's semi-major axis width (arcsec), the aspect ratio, and position angle (degrees). It should be understood that the quality of the result is very sensitive to the starting parameters provided by the user. If this first guess is not sufficiently close to the global χ^2 minimum, the algorithm will happily converge to an incorrect local minimum. In fact, the χ^2 surface, as a function of the component's relative direction parameters, has a shape very much like the inverse of the absolute value of the dirty image of the field. Any peak in this image (positive or negative) corresponds to a local χ^2 minimum that could conceivable capture the fit. It is the user's responsibility to ensure that the correct minimum does the capturing.

Currently, `uvmodelfit` relies on the likelihood that the source is very near the phase center (within a beamwidth) and/or the user's savvy in specifying the starting parameters. This fairly serious constraint will soon be relieved somewhat by enabling a rudimentary form of uv-plane weighting to increase the likelihood that the starting guess is on a slope in the correct χ^2 valley.

Improvements in the works for visibility model fitting include:

- User-specifiable uv-plane weighting
- Additional component shapes, including elliptical disks, rings, and optically thin spheroids.
- Optional calibration pre-application

- Multiple components. The handling of more than one component depends mostly on efficient means of managing the list itself (not easy in command line options), which are currently under development.
- Combined component and calibration fitting.

Example (see Figure 4.10):

```

#
# Note: It's best to channel average the data if many channels
# before running a modelfit
#
split('ngc5921.ms','1445+099_avg.ms',
       datacolumn='corrected',field='1445*',width='63')

# Initial guess is that it's close to the phase center
# and has a flux of 2.0 (a priori we know it's 2.47)
uvmodelfit('1445+099_avg.ms',           # use averaged data
            niter=5,                  # Do 5 iterations
            comptype='P',             # P=Point source, G=Gaussian, D=Disk
            sourcepar=[2.0,.1,.1],    # Source parameters for a point source
            spw='0',                 #
            outfile='gcal.cl')       # Output component list file

# Output looks like:
There are 19656 - 3 = 19653 degrees of freedom.
iter=0: reduced chi2=0.0418509: I=2, dir=[0.1, 0.1] arcsec
iter=1: reduced chi2=0.003382: I=2.48614, dir=[-0.020069, -0.0268826] arcsec
iter=2: reduced chi2=0.00338012: I=2.48614, dir=[0.00323428, -0.00232235] arcsec
iter=3: reduced chi2=0.00338012: I=2.48614, dir=[0.00325324, -0.00228963] arcsec
iter=4: reduced chi2=0.00338012: I=2.48614, dir=[0.00325324, -0.00228963] arcsec
iter=5: reduced chi2=0.00338012: I=2.48614, dir=[0.00325324, -0.00228963] arcsec
If data weights are arbitrarily scaled, the following formal errors
will be underestimated by at least a factor sqrt(reduced chi2). If
the fit is systematically poor, the errors are much worse.
I = 2.48614 +/- 0.0176859
x = 0.00325324 +/- 0.163019 arcsec
y = -0.00228963 +/- 0.174458 arcsec
Writing componentlist to file: /home/sandrock/smyers/Testing/Patch2/N5921/gcal.cl

# Fourier transform the component list into MODEL_DATA column of the MS
ft('1445+099_avg.ms', complist='gcal.cl')

# Plot data versus uv distance
plotxy('1445+099_avg.ms', xaxis='uvdist', datacolumn='corrected')

# Specify green circles for model data (overplotted)
plotxy('1445+099_avg.ms', xaxis='uvdist', datacolumn='model',
       overplot=True, plotsymbol='go')

```




Figure 4.10: Use of `plotxy` to display corrected data (red and blue points) and uv model fit data (green circles).

4.8 Examples of Calibration

Here are two examples of calibration.

BETA ALERT: Note that the syntax has been changing recently and these may get out of date quickly!

4.8.1 Spectral Line Calibration for NGC5921

The following is an example calibration using the NGC5921 VLA observations as the demonstration. This uses the CASA tasks as of the Beta Release. This data is available with the CASA release and so you can try this yourself.

The full NGC5921 example script can be found in Appendix F.1.

```
#####
# Calibration Script for NGC 5921
#
# Updated      STM 2008-03-25 (Beta Patch 1.0)
# Updated      STM 2008-06-11 (Beta Patch 2.0)
#
# Filenames will have the <prefix> = 'ngc5921.usecase'
#
# Input Data          Process          Output Data
#
# NGC5921.fits --> importuvfits --> <prefix>.ms    +
# (1.4GHz,           |                  <prefix>.ms.flagversions
#   63 sp chan,     v
#   D-array)        listobs    --> casapy.log
#                   |
#                   v
#                   flagautocorr
#                   |
#                   v
#                   setjy
#                   |
#                   v
#                   bandpass   --> <prefix>.bcal
#                   |
#                   v
#                   gaincal   --> <prefix>.gcal
#                   |
#                   v
#                   fluxscale  --> <prefix>.fluxscale
#                   |
#                   v
#                   applycal   --> <prefix>.ms
#                   |
#                   v
#                   split      --> <prefix>.cal.split.ms
#                   |
#                   v
#                   split      --> <prefix>.src.split.ms
#                   |
#                   v
#                   exportuvfits --> <prefix>.split.uvfits
#                   |
#                   v
#                   uvcontsub   --> <prefix>.ms.cont +
#                   |                  <prefix>.ms.contsub
#                   v
#####
#
# Set up some useful variables
# The prefix to use for all output files
```

```
prefix='ngc5921.usecase'

# The MS filename is assumed to be ngc5921.usecase.ms and
# already imported
msfile = prefix + '.ms'

# Use task importuvfits to make an ms.
#
# Note that there will be a ngc5921.usecase.ms.flagversions
# in addition to ngc5921.usecase.ms with the data.
#
#=====
#
# List a summary of the MS
#
print '--Listobs--'

# Don't default this one and make use of the previous setting of
# vis. Remember, the variables are GLOBAL!

# You may wish to see more detailed information, like the scans.
# In this case use the verbose = True option
verbose = True

listobs()

# You should get in your logger window and in the casapy.log file
# something like:
#
# MeasurementSet Name: /home/sandrock2/smyers/Testing2/Sep07/ngc5921.usecase.ms
# MS Version 2
#
# Observer: TEST      Project:
# Observation: VLA
#
# Data records: 22653      Total integration time = 5280 seconds
# Observed from 09:19:00 to 10:47:00
#
# ObservationID = 0      ArrayID = 0
# Date      Timerange          Scan  FldId FieldName      SpwIds
# 13-Apr-1995/09:19:00.0 - 09:24:30.0    1      0 1331+30500002_0 [0]
#                      09:27:30.0 - 09:29:30.0    2      1 1445+09900002_0 [0]
#                      09:33:00.0 - 09:48:00.0    3      2 N5921_2        [0]
#                      09:50:30.0 - 09:51:00.0    4      1 1445+09900002_0 [0]
#                      10:22:00.0 - 10:23:00.0   5      1 1445+09900002_0 [0]
#                      10:26:00.0 - 10:43:00.0   6      2 N5921_2        [0]
#                      10:45:30.0 - 10:47:00.0   7      1 1445+09900002_0 [0]
#
# Fields: 3
# ID  Code Name          Right Ascension  Declination  Epoch
# 0    C    1331+30500002_013:31:08.29      +30.30.32.96 J2000
```

```

#   1     A    1445+09900002_014:45:16.47      +09.58.36.07  J2000
#   2           N5921_2        15:22:00.00      +05.04.00.00  J2000
#
# Spectral Windows: (1 unique spectral windows and 1 unique polarization setups)
#   SpwID #Chans Frame Ch1(MHz)  Resoln(kHz) TotBW(kHz) Ref(MHz) Corrs
#   0       63 LSRK  1412.68608  24.4140625  1550.19688  1413.44902 RR LL
#
# Feeds: 28: printing first row only
#   Antenna  Spectral Window  # Receptors  Polarizations
#   1          -1            2             [          R, L]
#
# Antennas: 27:
#   ID  Name  Station  Diam.  Long.  Lat.
#   0   1    VLA:N7  25.0 m  -107.37.07.2 +33.54.12.9
#   1   2    VLA:W1  25.0 m  -107.37.05.9 +33.54.00.5
#   2   3    VLA:W2  25.0 m  -107.37.07.4 +33.54.00.9
#   3   4    VLA:E1  25.0 m  -107.37.05.7 +33.53.59.2
#   4   5    VLA:E3  25.0 m  -107.37.02.8 +33.54.00.5
#   5   6    VLA:E9  25.0 m  -107.36.45.1 +33.53.53.6
#   6   7    VLA:E6  25.0 m  -107.36.55.6 +33.53.57.7
#   7   8    VLA:W8  25.0 m  -107.37.21.6 +33.53.53.0
#   8   9    VLA:N5  25.0 m  -107.37.06.7 +33.54.08.0
#   9   10   VLA:W3  25.0 m  -107.37.08.9 +33.54.00.1
#  10  11   VLA:N4  25.0 m  -107.37.06.5 +33.54.06.1
#  11  12   VLA:W5  25.0 m  -107.37.13.0 +33.53.57.8
#  12  13   VLA:N3  25.0 m  -107.37.06.3 +33.54.04.8
#  13  14   VLA:N1  25.0 m  -107.37.06.0 +33.54.01.8
#  14  15   VLA:N2  25.0 m  -107.37.06.2 +33.54.03.5
#  15  16   VLA:E7  25.0 m  -107.36.52.4 +33.53.56.5
#  16  17   VLA:E8  25.0 m  -107.36.48.9 +33.53.55.1
#  17  18   VLA:W4  25.0 m  -107.37.10.8 +33.53.59.1
#  18  19   VLA:E5  25.0 m  -107.36.58.4 +33.53.58.8
#  19  20   VLA:W9  25.0 m  -107.37.25.1 +33.53.51.0
#  20  21   VLA:W6  25.0 m  -107.37.15.6 +33.53.56.4
#  21  22   VLA:E4  25.0 m  -107.37.00.8 +33.53.59.7
#  23  24   VLA:E2  25.0 m  -107.37.04.4 +33.54.01.1
#  24  25   VLA:N6  25.0 m  -107.37.06.9 +33.54.10.3
#  25  26   VLA:N9  25.0 m  -107.37.07.8 +33.54.19.0
#  26  27   VLA:N8  25.0 m  -107.37.07.5 +33.54.15.8
#  27  28   VLA:W7  25.0 m  -107.37.18.4 +33.53.54.8
#
# Tables:
#   MAIN                  22653 rows
#   ANTENNA                28 rows
#   DATA_DESCRIPTION         1 row
#   DOPPLER                <absent>
#   FEED                   28 rows
#   FIELD                   3 rows
#   FLAG_CMD                <empty>
#   FREQ_OFFSET              <absent>
#   HISTORY                 273 rows

```

```

#      OBSERVATION          1 row
#      POINTING            168 rows
#      POLARIZATION         1 row
#      PROCESSOR           <empty>
#      SOURCE               3 rows
#      SPECTRAL_WINDOW      1 row
#      STATE                <empty>
#      SYSCAL              <absent>
#      WEATHER              <absent>
#
#
#=====
#
# Get rid of the autocorrelations from the MS
#
print '--Flagautocorr--'

# Don't default this one either, there is only one parameter (vis)

flagautocorr()

#
#=====
#
# Set the fluxes of the primary calibrator(s)
#
print '--Setjy--'
default('setjy')

vis = msfile

#
# 1331+305 = 3C286 is our primary calibrator
# Use the wildcard on the end of the source name
# since the field names in the MS have inherited the
# AIPS qualifiers
field = '1331+305*'

# This is 1.4GHz D-config and 1331+305 is sufficiently unresolved
# that we dont need a model image. For higher frequencies
# (particularly in A and B config) you would want to use one.
modimage = ''

# Setjy knows about this source so we dont need anything more

setjy()

#
# You should see something like this in the logger and casapy.log file:
#
# 1331+30500002_0  spwid= 0  [I=14.76, Q=0, U=0, V=0] Jy, (Perley-Taylor 99)

```

```
#  
# So its using 14.76Jy as the flux of 1331+305 in the single Spectral Window  
# in this MS.  
#  
#======  
#  
# Bandpass calibration  
#  
print '--Bandpass--'  
default('bandpass')  
  
# We can first do the bandpass on the single 5min scan on 1331+305  
# At 1.4GHz phase stability should be sufficient to do this without  
# a first (rough) gain calibration. This will give us the relative  
# antenna gain as a function of frequency.  
  
vis = msfile  
  
# set the name for the output bandpass caltable  
btable = prefix + '.bcal'  
caltable = btable  
  
# No gain tables yet  
gaintable = ''  
gainfield = ''  
interp = ''  
  
# Use flux calibrator 1331+305 = 3C286 (FIELD_ID 0) as bandpass calibrator  
field = '0'  
# all channels  
spw = ''  
# No other selection  
selectdata = False  
  
# In this band we do not need a-priori corrections for  
# antenna gain-elevation curve or atmospheric opacity  
# (at 8GHz and above you would want these)  
gaincurve = False  
opacity = 0.0  
  
# Choose bandpass solution type  
# Pick standard time-binned B (rather than BPOLY)  
bandtype = 'B'  
  
# set solution interval arbitrarily long (get single bpss)  
solint = 'inf'  
combine = 'scan'  
  
# reference antenna Name 15 (15=VLA:N2) (Id 14)  
refant = '15'
```

```
bandpass()

#
#=====
#
# Use plotcal to examine the bandpass solutions
#
print '--Plotcal (bandpass)--'
default('plotcal')

caltable = btable
field = '0'

# No GUI for this script
showgui = False
# If you want to do this interactively and iterate over antenna, set
#iteration = 'antenna'
#showgui = True

# Set up 2x1 panels - upper panel amp vs. channel
subplot = 211
yaxis = 'amp'
# No output file yet (wait to plot next panel)
plotcal()
#
# Set up 2x1 panels - lower panel phase vs. channel
subplot = 212
yaxis = 'phase'
# Now send final plot to file in PNG format (via .png suffix)
figfile = caltable + '.plotcal.png'
plotcal()
#
# Note the rolloff in the start and end channels. Looks like
# channels 6-56 (out of 0-62) are the best

#=====
#
# Gain calibration
#
print '--Gaincal--'
default('gaincal')

# Armed with the bandpass, we now solve for the
# time-dependent antenna gains

vis = msfile

# set the name for the output gain caltable
gtable = prefix + '.gcal'
caltable = gtable
```

```
# Use our previously determined bandpass
# Note this will automatically be applied to all sources
# not just the one used to determine the bandpass
gaintable = btable
gainfield = ''

# Use nearest (there is only one bandpass entry)
interp = 'nearest'

# Gain calibrators are 1331+305 and 1445+099 (FIELD_ID 0 and 1)
field = '0,1'

# We have only a single spectral window (SPW 0)
# Choose 51 channels 6-56 out of the 63
# to avoid end effects.
# Channel selection is done inside spw
spw = '0:6~56'

# No other selection
selectdata = False

# In this band we do not need a-priori corrections for
# antenna gain-elevation curve or atmospheric opacity
# (at 8GHz and above you would want these)
gaincurve = False
opacity = 0.0

# scan-based G solutions for both amplitude and phase
gaintype = 'G'
solint = 'inf'
combine = ''
calmode = 'ap'

# minimum SNR allowed
minsnr = 1.0

# reference antenna 15 (15=VLA:N2)
refant = '15'

gaincal()

#
#=====
#
# Bootstrap flux scale
#
print '--Fluxscale--'
default('fluxscale')

vis = msfile
```

```
# set the name for the output rescaled caltable
ftable = prefix + '.fluxscale'
fluxtable = ftable

# point to our first gain cal table
caltable = gtable

# we will be using 1331+305 (the source we did setjy on) as
# our flux standard reference - note its extended name as in
# the FIELD table summary above (it has a VLA seq number appended)
reference = '1331*'

# we want to transfer the flux to our other gain cal source 1445+099
transfer = '1445*'

fluxscale()

# In the logger you should see something like:
# Flux density for 1445+09900002_0 in SpW=0 is:
#     2.48576 +/- 0.00123122 (SNR = 2018.94, nAnt= 27)

# If you run plotcal() on the tablein = 'ngc5921.usecase.fluxscale'
# you will see now it has brought the amplitudes in line between
# the first scan on 1331+305 and the others on 1445+099

#
#=====
#
# Now use plotcal to examine the gain solutions
#
print '--Plotcal (fluxscaled gains)--'
default('plotcal')

caltable = ftable
field = '0,1'

# No GUI for this script
showgui = False
# If you want to do this interactively and iterate over antenna, set
#iteration = 'antenna'
#showgui = True

# Set up 2x1 panels - upper panel amp vs. time
subplot = 211
yaxis = 'amp'
# No output file yet (wait to plot next panel)
plotcal()
#
# Set up 2x1 panels - lower panel phase vs. time
subplot = 212
yaxis = 'phase'
```

```
# Now send final plot to file in PNG format (via .png suffix)
figfile = caltable + '.plotcal.png'
plotcal()
#
# The amp and phase coherence looks good

=====
#
# Apply our calibration solutions to the data
# (This will put calibrated data into the CORRECTED_DATA column)
#
print '--ApplyCal--'
default('applycal')

vis = msfile

# We want to correct the calibrators using themselves
# and transfer from 1445+099 to itself and the target N5921

# Start with the fluxscale/gain and bandpass tables
gaintable = [ftable,btable]

# pick the 1445+099 out of the gain table for transfer
# use all of the bandpass table
gainfield = ['1','*']

# interpolation using linear for gain, nearest for bandpass
interp = ['linear','nearest']

# only one spw, do not need mapping
spwmap = []

# all channels
spw = ''
selectdata = False

# as before
gaincurve = False
opacity = 0.0

# select the fields for 1445+099 and N5921
field = '1,2'

applycal()

# Now for completeness apply 1331+305 to itself

field = '0'
gainfield = ['0','*']

# The CORRECTED_DATA column now contains the calibrated visibilities
```

```
applycal()

#
#=====
#
# Now use plotxy to plot the calibrated target data (before contsub)
#
print '--Plotxy (NGC5921)--'
default('plotxy')

vis = msfile

field = '2'
# Edge channels are bad
spw = '0:4~59'

# Time average across scans
timebin = '86000.'
crossscans = True

# No GUI for this script
interactive = False

# Set up 2x1 panels - upper panel amp vs. channel
subplot = 211
xaxis = 'channel'
yaxis = 'amp'
datacolumn = 'corrected'
# No output file yet (wait to plot next panel)
plotxy()
#
# Set up 2x1 panels - lower panel phase vs. time
subplot = 212
yaxis = 'phase'
datacolumn = 'corrected'
# Now send final plot to file in PNG format (via .png suffix)
figfile = vis + '.plotxy.png'
plotxy()

#=====
#
# Split the gain calibrator data, then the target
#
print '--Split 1445+099 Data--'
default('split')

vis = msfile

# We first want to write out the corrected data for the calibrator
```

```
# Make an output vis file
calsplitms = prefix + '.cal.split.ms'
outputvis = calsplitms

# Select the 1445+099 field, all chans
field = '1445*'
spw = ''

# pick off the CORRECTED_DATA column
datacolumn = 'corrected'

split()

#
# Now split NGC5921 data (before continuum subtraction)
#
print '--Split NGC5921 Data--'

splitms = prefix + '.src.split.ms'
outputvis = splitms

# Pick off N5921
field = 'N5921*'

split()

=====
#
# Export the NGC5921 data as UVFITS
# Start with the split file.
#
print '--Export UVFITS--'
default('exportuvfits')

srcuvfits = prefix + '.split.uvfits'

vis = splitms
fitsfile = srcuvfits

# Since this is a split dataset, the calibrated data is
# in the DATA column already.
datacolumn = 'data'

# Write as a multisource UVFITS (with SU table)
# even though it will have only one field in it
multisource = True

# Run asynchronously so as not to interfere with other tasks
# (BETA: also avoids crash on next importuvfits)
async = True
```

```
exportuvfits()

#=====
#
# UV-plane continuum subtraction on the target
# (this will update the CORRECTED_DATA column)
#
print '--UV Continuum Subtract--'
default('uvcontsub')

vis = msfile

# Pick off N5921
field = 'N5921*'

# Use channels 4-6 and 50-59 for continuum
fitspw = '0:4~6;50~59'
# Apply to all of spw 0
spw = '0'

# Averaging time (none)
solint = 0.0

# Fit only a mean level
fitorder = 0

# Do the uv-plane subtraction
fitmode = 'subtract'

# Let it split out the data automatically for us
splitdata = True

uvcontsub()

# You will see it made two new MS:
# ngc5921.usecase.ms.cont
# ngc5921.usecase.ms.contsub

srcsplitsms = msfile + '.contsub'

# Note that ngc5921.usecase.ms.contsub contains the uv-subtracted
# visibilities (in its DATA column), and ngc5921.usecase.ms.cont
# the pseudo-continuum visibilities (as fit).

# The original ngc5921.usecase.ms now contains the uv-continuum
# subtracted vis in its CORRECTED_DATA column and the continuum
# in its MODEL_DATA column as per the fitmode='subtract'

#=====
```

4.8.2 Continuum Calibration of Jupiter

The following is an example of continuum calibration on the Jupiter 6cm VLA dataset. This assumes you have already imported and flagged the data, and have the ms file `jupiter6cm.usecase.ms` on disk in your working directory. See § 3.7.

The full Jupiter example script can be found in Appendix F.2.

```
#####
# Calibration Script for Jupiter 6cm VLA
#
# Updated STM 2008-03-25 (Beta Patch 1.0)
# Updated STM 2008-06-11 (Beta Patch 2.0)
#
#####

prefix='jupiter6cm.usecase'
msfile = prefix + '.ms'

#
#=====
# Calibration
#=====
#
# Set the fluxes of the primary calibrator(s)
#
print '--SetJy--'
default('setJy')

vis = msfile

#
# 1331+305 = 3C286 is our primary calibrator
field = '1331+305'

# SetJy knows about this source so we dont need anything more

setJy()

#
# You should see something like this in the logger and casapy.log file:
#
# 1331+305 spwid= 0 [I=7.462, Q=0, U=0, V=0] Jy, (Perley-Taylor 99)
# 1331+305 spwid= 1 [I=7.51, Q=0, U=0, V=0] Jy, (Perley-Taylor 99)
#
#=====
```

```
# Initial gain calibration
#
print '--Gaincal--'
default('gaincal')

vis = msfile

# set the name for the output gain caltable
gtable = prefix + '.gcal'
caltable = gtable

# Gain calibrators are 1331+305 and 0137+331 (FIELD_ID 7 and 0)
# We have 2 IFs (SPW 0,1) with one channel each

# selection is via the field and spw strings
field = '1331+305,0137+331'
spw = ''

# a-priori calibration application
# atmospheric optical depth (turn off)
gaincurve = True
opacity = 0.0

# scan-based G solutions for both amplitude and phase
gaintype = 'G'
solint = 'inf'
combine = ''
calmode = 'ap'

# reference antenna 11 (11=VLA:N1)
refant = '11'

# minimum SNR 3
minsnr = 3

gaincal()

#
#=====
#
# Bootstrap flux scale
#
print '--Fluxscale--'
default('fluxscale')

vis = msfile

# set the name for the output rescaled caltable
ftable = prefix + '.fluxscale'
fluxtable = ftable
```

```
# point to our first gain cal table
caltable = gtable

# we will be using 1331+305 (the source we did setjy on) as
# our flux standard reference
reference = '1331+305'

# we want to transfer the flux to our other gain cal source 0137+331
# to bring its gain amplitudes in line with the absolute scale
transfer = '0137+331'

fluxscale()

# You should see in the logger something like:
#Flux density for 0137+331 in SpW=0 is:
#    5.42575 +/- 0.00285011 (SNR = 1903.7, nAnt= 27)
#Flux density for 0137+331 in SpW=1 is:
#    5.46569 +/- 0.00301326 (SNR = 1813.88, nAnt= 27)

#=====
#
# Interpolate the gains onto Jupiter (and others)
#
print '--Accum--'
default('accum')

vis = msfile

tablein = ''
incrtable = ftable
calfield = '1331+305, 0137+331'

# set the name for the output interpolated caltable
atable = prefix + '.accum'
caltable = atable

# linear interpolation
interp = 'linear'

# make 10s entries
accumtime = 10.0

accum()

#=====
#
# Correct the data
# (This will put calibrated data into the CORRECTED_DATA column)
#
print '--ApplyCal--'
default('applycal')
```

```
vis = msfile

# Start with the interpolated fluxscale/gain table
bptable = ''
gaintable = atable

# Since we did gaincurve=True in gaincal, we need it here also
gaincurve = True
opacity=0.0

# select the fields
field = '1331+305,0137+331,JUPITER'
spw = ''
selectdata = False

# do not need to select subset since we did accum
# (note that correct only does 'nearest' interp)
gainfield = ''

applycal()

#
#=====
#
# Now split the Jupiter target data
#
print '--Split Jupiter--'
default('split')

vis = msfile

# Now we write out the corrected data for the calibrator

# Make an output vis file
srcsplitms = prefix + '.split.ms'
outputvis = srcsplitms

# Select the Jupiter field
field = 'JUPITER'
spw = ''

# pick off the CORRECTED_DATA column
datacolumn = 'corrected'

split()

#=====
#
# Export the Jupiter data as UVFITS
# Start with the split file.
```

```
#  
print '--Export UVFITS--'  
default('exportuvfits')  
  
srcuvfits = prefix + '.split.uvfits'  
  
vis = srcsplits  
fitsfile = srcuvfits  
  
# Since this is a split dataset, the calibrated data is  
# in the DATA column already.  
datacolumn = 'data'  
  
# Write as a multisource UVFITS (with SU table)  
# even though it will have only one field in it  
multisource = True  
  
# Run asynchronously so as not to interfere with other tasks  
# (BETA: also avoids crash on next importuvfits)  
async = True  
  
exportuvfits()  
  
=====
```

Chapter 5

Synthesis Imaging

This chapter describes how to make and deconvolve images starting from calibrated interferometric data, possibly supplemented with single-dish data or an image made from single-dish data. This data must be available in CASA (see § 2 on importing data). See § 4 for information on calibrating synthesis data. In the following sections, the user will learn how to make various types of images from synthesis data, reconstruct images of the sky using the available deconvolution techniques, include single-dish information in the imaging process, and to prepare to use the results of imaging for improvement of the calibration process (“self-calibration”).

Inside the Toolkit:

The `im` tool handles synthesis imaging operations.

5.1 Imaging Tasks Overview

The current imaging and deconvolution tasks are:

- `clean` — calculate a deconvolved image with a selected clean algorithm, including mosaicing, or make a dirty image (§ 5.3)
- `feather` — combine a single dish and synthesis image in the Fourier plane (§ 5.5)
- `deconvolve` — image-plane only deconvolution based on the dirty image and beam, using one of several algorithms (§ 5.8)
- `widefield` — a prototype task to create and deconvolve a wide-field image using w-projection and/or faceting (§ 5.4)

There are also tasks that help you set up the imaging or interface imaging with calibration:

- `makemask` - create “cleanbox” deconvolution regions (§ 5.6)

- **ft** - Fourier transform the specified model (or component list) and insert the source model into the MODEL column of a visibility set (§ 5.7)

The full “tool kit” that allows expert-level imaging must still be used if you do not find enough functionality within the tasks above.

Information on other useful tasks and parameter setting can be found in:

- **listobs** — list whats in a MS (§ 2.3),
- **split**— Write out new MS containing calibrated data from a subset of the original MS (§ section:cal.split),
- data selection — general data selection syntax (§ 2.5).
- **viewer** — image display including region statistics and image cube slice and profile capabilities (§ 7)

5.2 Common Imaging Task Parameters

We now describe some parameters are common to the imaging tasks. These should behave the same way in any imaging task that they are found in. These are in alphabetical order.

BETA ALERT: There are still a subset of data selection parameters used in the imaging tasks: `field`, `spw`, `timerange`. In a later patch, we will use the standard data selection set (§ 2.9).

Inside the Toolkit:

The `im.setimage` method is used to set many of the common image parameters. The `im.advise` method gives helpful advice for setting up for imaging.

5.2.1 Parameter `cell`

The `cell` parameter defines the pixel size in the x and y axes for the output image. If given as floats or integers, this is the cell size in arc seconds, e.g.

```
cell=[0.5,0.5]
```

make $0.5''$ pixels. You can also give the cell size in *quantities*, e.g.

```
cell=['1arcmin', '1arcmin']
```

If a single value is given, then square pixels of that size are assumed.

5.2.2 Parameter field

The `field` parameter selects the field indexes or names to be used in imaging. Unless you are making a mosaic, this is usually a single index or name:

```
field = '0'           # First field (index 0)
field = '1331+305'   # 3c286
field = '*'          # all fields in dataset
```

The syntax for `field` selection is given in § 2.5.2.

5.2.3 Parameter imagename

The value of the `imagename` parameter is used as the root name of the output image. Depending on the particular task and the options chosen, one or more images with names built from that root will be created. For example, the `clean` task run with `imagename='ngc5921'` a series of output images with names `ngc5921.clean`, `ngc5921.residual`, and `ngc5921.model` will be created.

If an image with that name already exists, it will in general be overwritten. Beware using names of existing images however. If the `clean` is run using an `imagename` where `<imagename>.residual` and `<imagename>.model` already exist then `clean` will continue starting from these (effectively restarting from the end of the previous `clean`). Thus, if multiple runs of `clean` are run consecutively with the same `imagename`, then the cleaning is incremental (as in the `difmap` package).

5.2.4 Parameter imsize

The image size in numbers of pixels on the x and y axes is set by `imsize`. For example,

```
imsize = [288, 288]
```

makes a square image 288 pixels on a side. If a single value is given, then a square image of that dimension is made. This need not be a power of two, but for optimal performance should be a “composite” number divisible only by 2 and also 3 and/or 5. Note that in the example above $288 = 2^5 \cdot 3^2$.

BETA ALERT: You will be warned if you give a non-composite `imsize` and it will suggest the nearest appropriate value. But it will continue cleaning so you may have to abort if you want to make use of this suggestion. This restriction will be lifted in the future when we migrate to a better FFTW engine.

5.2.5 Parameter mode

The `mode` parameter defines how the frequency channels in the synthesis MS are mapped onto the image. The allowed values are: `mfs`, `channel`, `velocity`, `frequency`. The `mode` parameter is expandable, with some options uncovering a number of sub-parameters, depending upon its value.

5.2.5.1 Mode mfs

The default `mode='mfs'` emulates multi-frequency synthesis in that each visibility-channel datum k with baseline vector \mathbf{B}_k at wavelength λ_k is gridded into the uv-plane at $\mathbf{u}_k = \mathbf{B}_k/\lambda_k$. The result is a single image plane, regardless of how many channels are in the input dataset. This image plane is at the frequency given by the midpoint between the highest and lowest frequency channels in the input `spw(s)`. Currently, there is no way to choose the center frequency of the output image plane independently.

5.2.5.2 Mode channel

If `mode='channel'` is chosen, then an image cube will be created. This is an expandable parameter, with dependent parameters:

```
mode      = 'channel'  # Type of selection (mfs, channel, velocity, frequency)
nchan    =          1  # Number of channels (planes) in output image
start    =          0  # first input channel to use
width    =          1  # Number of input channels to average
```

The channelization of the resulting image is determined by the channelization in the first MS of `vis` of the first `spw` specified (the “reference `spw`”). The actual channels to be gridded and used in the clean are selected via the `spw` parameter as usual. The resulting image cube will have `nchan` channels spaced evenly in frequency. The first output channel will be located at the frequency of channel `start` in the (first) reference `spw`. If `width > 1`, then input MS channels with centers within a frequency range given by $(\text{width} + 1)/2$ times the reference `spw` spacing will be gridded together (as in `mode = 'mfs'` above) into the channels of the output image cube. The output channel spacing is thus given by `width` channels in the reference `spw` of the MS. Channels in `spw` beyond the first are mapped into the nearest output image channel within half a channel (if any). Image channels that lie outside the MS frequency range or have no data mapped to them will be blank in the output image, but will be in the cube.

See the example in § 5.10.1 for using the ‘channel’ mode to image a spectral-line cube. In this case, we use:

```
mode      = 'channel'
nchan    =      46
start    =      5
width    =      1
```

which will produce a 46-channel cube starting with channel 5 of the MS with the same channel width as the MS.

5.2.5.3 Mode frequency

For `mode='frequency'`, an output image cube is created with `nchan` channels spaced evenly in frequency.

```

mode      = 'frequency'    # Type of selection (mfs, channel, velocity, frequency)
nchan    =      1          # Number of channels (planes) in output image
start    =  '1.4GHz'       # Frequency of first image channel: e.g. '1.4GHz'
width    =  '10kHz'        # Image channel width in frequency units: e.g '1.0kHz'

```

The frequency of the first output channel is given by `start` and spacing by `step`. The sign of `width` determines whether the output channels ascend or descend in frequency. Output channels have a width also given by `step`. Data from the input MS with centers that lie within one-half an input channel overlap of the frequency range of $\pm \text{step}/2$ centered on the output channels are gridded together.

Using the NGC5921 dataset as an example:

```

mode      = 'frequency'
nchan    =      21
start    = '1412.830MHz'
width    =  '50kHz'

```

would produce a 21-channel output cube with 50 kHz wide channels rather than the default channelization of the MS (24.4 kHz).

BETA ALERT: In Patch 3 and earlier, it will current grid each channel of the input MS to the nearest image plane, or two if it lies on or close to the border between two planes in frequency or velocity. Thus if you choose to make an image with the channelization non-integral multiples of the MS channel width, you will see effects in the image cube where some planes have higher or lower noise than others depending on how many input channels went into the plane. We will fix this behavior and use true interpolation in future releases. In the meantime we suggest you use `mode='channel'` or be careful with the choice of `start` and `width`.

5.2.5.4 Mode velocity

If `mode='velocity'` is chosen, then an output image cube with `nchan` channels will be created, with channels spaced evenly in velocity. Parameters are:

```

mode      = 'velocity'    # Type of selection (mfs, channel, velocity, frequency)
nchan    =      1          # Number of channels (planes) in output image
start    =  '0.0km/s'     # Velocity of first image channel: e.g '0.0km/s'
width    =  '1km/s'        # image channel width in velocity units: e.g '-1.0km/s'

```

The velocity of the first output channel is given by `start` and spacing by `width`. Note that the velocity frame is given by the rest frequency in the MS header, which can be overridden by the `restfreq` parameter. Averaging is as in `mode='frequency'`.

Again, using the NGC5921 dataset as an example:

```

mode      = 'velocity'
nchan    =      21
start    = '1383.0km/s'
width    =   '10km/s'

```

Note that in this case the velocity axis runs forward, as opposed to the default channelization for 'channel' or 'frequency'.

BETA ALERT: Note that the velocities are expressed in the LSRK frame. This is not currently selectable.

BETA ALERT: In Patch 3 and earlier, it will current grid each channel of the input MS to the nearest image plane, or two if it lies on or close to the border between two planes in frequency or velocity. Thus if you choose to make an image with the channelization non-integral multiples of the MS channel width, you will see effects in the image cube where some planes have higher or lower noise than others depending on how many input channels went into the plane. We will fix this behavior and use true interpolation in future releases. In the meantime we suggest you use `mode='channel'` or be careful with the choice of `start` and `width`.

5.2.6 Parameter phascenter

The `phascenter` parameter indicates which of the field IDs should be used to define the phase center of the mosaic image, or what that phase center is in RA and Dec. The default action is to use the first one given in the `field` list.

For example:

```

phascenter='5'          # field 5 in multi-src ms
phascenter='J2000 19h30m00 -40d00m00' # specify position

```

Note that the format for angles prefers to use `hm` for RA/time units and `dm` for Dec/Angle units as separators. The colon `::` separator is interpreted as RA/time even if its used for the Dec, so be careful not to copy/paste from other sources.

5.2.7 Parameter restfreq

The value of the `restfreq` parameter, if set, will over-ride the rest frequency in the header of the first input MS to define the velocity frame of the output image.

5.2.8 Parameter spw

The `spw` parameter selects the spectral windows that will be used to form the image, and possibly a subset of channels within these windows.

The `spw` parameter is a string with an integer, list of integers, or a range, e.g.

```
spw = '1'          # select spw 1
spw = '0,1,2,3'    # select spw 0,1,2,3
spw = '0~3'        # same thing using ranges
```

You can select channels in the same string with a : separator, for example

```
spw = '1:10~30'      # select channels 10-30 of spw 1
spw = '0:5~55,3:5;6;7' # chans 5-55 of spw 0 and 5,6,7 of spw 3
```

This uses the standard syntax for `spw` selection is given in § 2.5.3. See that section for more options.

Note that the order in which multiple `spws` are given is important for `mode = 'channel'`, as this defines the origin for the channelization of the resulting image.

5.2.9 Parameter `stokes`

The `stokes` parameter specifies the Stokes parameters for the resulting images. Note that forming Stokes Q and U images requires the presence of cross-hand polarizations (e.g. RL and LR for circularly polarized systems such as the VLA) in the data. Stokes V requires both parallel hands (RR and :LL) for circularly polarized systems or the cross-hands (XY and YX) for linearly polarized systems such as ALMA and ATCA.

This parameter is specified as a string of up to four letters (IQUV). For example,

```
stokes = 'I'          # Intensity only
stokes = 'IQU'        # Intensity and linear polarization
stokes = 'IV'         # Intensity and circular polarization
stokes = 'IQUV'       # All Stokes imaging
```

are common choices. () The output image will have planes (along the “polarization axis”) corresponding to the chosen Stokes parameters.

If the `stokes` parameter is being input to deconvolution tasks such as `clean`, then with the exception of `psfmode='hogbom'` (see § 5.3.1) the chosen Stokes images will be deconvolved jointly rather than sequentially as in AIPS.

BETA ALERT: The `stokes = 'QU'` for linear polarization only is not currently an option. There is also no option to make single polarization product (e.g. separate RR and LL, or XX and YY) images from data with dual polarizations available. You currently would have to make `stokes='I'` images from data with a single polarization product (e.g. RR or LL) split out.

5.2.10 Parameter `uvfilter`

This controls the radial weighting of visibilities in the uv-plane (see § 5.2.11 below) through the multiplication of the visibilities by the Fourier transform of an elliptical Gaussian. This is itself a Gaussian, and thus the visibilities are “tapered” with weights decreasing as a function of uv-radius.

The `uvfilter` parameter expands the menu upon setting `uvfilter=True` to reveal the following sub-parameters:

```

uvfilter      =      True   #  Apply additional filtering/uv tapering of the visibilities
uvfilterbmaj =      1.0   #  Major axis of filter (arcseconds)
uvfilterbmin =      1.0   #  Minor axis of filter (arcseconds)
uvfilterbpa  =      0.0   #  Position angle of filter (degrees)

```

The sub-parameters specify the size and orientation of this Gaussian in the image plane (in arcseconds). Note that since this filter effectively *multiplies* the intrinsic visibility weights, the resulting image will not have a PSF given by the size of the filter, but a PSF given by its intrinsic size convolved by the filter. Thus you should end up with a synthesized beam of size equal to the quadratic sum of the original beam and the filter.

BETA ALERT: We will soon give the option of specifying the filter/taper in uv-units (e.g. kilo-lambda or meters).

5.2.11 Parameter weighting

In order to image your data, we must have a map from the visibilities to the image. Part of that map, which is effectively a convolution, is the weights by which each visibility is multiplied before gridding. The first factor in the weighting is the “noise” in that visibility, represented by the data weights in the MS (which is calibrated along with the visibility data). The weighting function can also depend upon the uv locus of that visibility (e.g. a “taper” to change resolution). This is actually controlled by the `uvfilter` parameter (see § 5.2.10). The weighting matrix also includes the convolution kernel that distributes that visibility onto the uv-plane during gridding before Fourier transforming to make the image of the sky. This depends upon the density of visibilities in the uv-plane (e.g. “natural”, “uniform”, “robust” weighting).

Inside the Toolkit:

The `im.weight` method has more weighting options than available in the imaging tasks. See the **User Reference Manual** for more information on imaging weights.

The user has control over all of these.

BETA ALERT: You can find a weighting description in the online User Reference Manual at:

<http://casa.nrao.edu/docs/casaref/imager.weight.html>

The `weighting` parameter expands the menu to include various sub-parameters depending upon the mode chosen:

5.2.11.1 ‘natural’ weighting

For `weighting='natural'`, visibilities are weighted only by the data weights, which are calculated during filling and calibration and should be equal to the inverse noise variance on that visibility. Imaging weight w_i of sample i is given by

$$w_i = \omega_i = \frac{1}{\sigma_k^2} \quad (5.1)$$

where the data weight ω_i is determined from σ_i is the rms noise on visibility i . When data is gridded into the same uv-cell for imaging, the weights are summed, and thus a higher uv density results in higher imaging weights. No sub-parameters are linked to this mode choice. It is the default imaging weight mode, and it should produce “optimum” image with the lowest noise (highest signal-to-noise ratio). Note that this generally produces images with the poorest angular resolution, since the density of visibilities falls radially in the uv-plane

5.2.11.2 ‘uniform’ weighting

For `weighting = ‘uniform’`, the data weights are calculated as in ‘natural’ weighting. The data is then gridded to a number of cells in the uv-plane, and after all data is gridded the uv-cells are re-weighted to have “uniform” imaging weights. This pumps up the influence on the image of data with low weights (they are multiplied up to be the same as for the highest weighted data), which sharpens resolution and reduces the sidelobe level in the field-of-view, but increases the rms image noise. No sub-parameters are linked to this mode choice.

For uniform weighting, we first grid the inverse variance ω_i for all selected data onto a grid with uv cell-size given by $2/FOV$ where FOV is the specified field of view (defaults to the image field of view). This forms the gridded weights W_k . The weight of the i -th sample is then:

$$w_i = \frac{\omega_i}{W_k}. \quad (5.2)$$

5.2.11.3 ‘superuniform’ weighting

The `weighting = ‘superuniform’` mode is similar to the ‘uniform’ weighting mode but there is now an additional `npixels` sub-parameter that specifies a change to the number of cells on a side (with respect to uniform weighting) to define a uv-plane patch for the weighting renormalization. If `npixels=0` you get uniform weighting.

5.2.11.4 ‘radial’ weighting

The `weighting = ‘radial’` mode is a seldom-used option that increases the weight by the radius in the uv-plane, ie.

$$w_i = \omega_i \cdot \sqrt{u_i^2 + v_i^2}. \quad (5.3)$$

Technically, I would call that an inverse uv-taper since it depends on uv-coordinates and not on the data per-se. Its effect is to reduce the rms sidelobes for an east-west synthesis array. This option has limited utility.

5.2.11.5 ‘briggs’ weighting

The `weighting = ‘briggs’` mode is an implementation of the flexible weighting scheme developed by Dan Briggs in his PhD thesis. See:

<http://www.aoc.nrao.edu/dissertations/dbriggs/>

This choice brings up the sub-parameters:

```
weighting      = 'briggs'   # Weighting to apply to visibilities
robust        =      0.0    # Briggs robustness parameter
npixels       =      0     # number of pixels to determine uv-cell size 0=> field of view
```

The actual weighting scheme used is:

$$w_i = \frac{\omega_i}{1 + W_k f^2} \quad (5.4)$$

where W_k is defined as in `uniform` and `superuniform` weighting, and

$$f^2 = \frac{(5 * 10^{-R})^2}{\frac{\sum_k W_k^2}{\sum_i \omega_i}} \quad (5.5)$$

and R is the robust parameter.

The key parameter is the `robust` parameter, which sets R in the Briggs equations. The scaling of R is such that $R = 0$ gives a good trade-off between resolution and sensitivity. The `robust R` takes value between -2.0 (close to uniform weighting) to 2.0 (close to natural).

Superuniform weighting can be combined with Briggs weighting using the `npixels` sub-parameter. This works as in '`superuniform`' weighting (§ 5.2.11.3).

5.2.11.6 '`briggsabs`' weighting

For `weighting='briggsabs'`, a slightly different Briggs weighting is used, with

$$w_i = \frac{\omega_i}{W_k R^2 + 2\sigma_R^2} \quad (5.6)$$

where R is the robust parameter and σ_R is the `noise` parameter.

This choice brings up the sub-parameters:

```
weighting      = 'briggsabs'   # Weighting to apply to visibilities
robust        =      0.0      # Briggs robustness parameter
noise         = '0.0Jy'       # noise parameter for briggs weighting when rmode='abs'
npixels       =      0       # number of pixels to determine uv-cell size 0=> field of view
```

Otherwise, this works as `weighting='briggs'` above (§ 5.2.11.5).

5.2.12 Parameter vis

The value of the `vis` parameter is either the name of a single MS, or a list of strings containing the names of multiple MSs, that should be processed to produce the image. The MS referred to by the first name in the list (if more than one) is used to determine properties of the image such as channelization and rest frequency.

For example,

```
vis = 'ngc5921.ms'
```

set a single input MS, while

```
vis = ['ngc5921_day1.ms', 'ngc5921_day2.ms', 'ngc5921_day3.ms']
```

points to three separate measurement sets that will be gridded together to form the image. This means that you do not have to concatenate datasets, for example from different configurations, before imaging.

5.2.13 Primary beams in imaging

The CASA imaging task and tools use primary beams based on models for each observatory's antenna types. In addition to different antenna diameters, different functions may be used.

The voltage patterns are based on the following antenna primary beams, based on the `TELESCOPE_NAME` keyword in the `OBSERVATION` table:

VLA — Airy disk fitted to measurement. Note that a R/L beam squint is also included with feed dependent angle;

ALMA — Airy disk for 12m dish with a blockage of 1m;

ATA — Airy disk for 6m dish;

ATCA — polynomial fitted to measurement of main lobe;

BIMA, HATCREEK — Gaussian with halfwidth of $\lambda/2D$;

CARMA — the BIMA or OVRO patterns as appropriate;

GBT — polynomial fitted to measurement of main lobe;

GMRT — VLA Airy disk scaled to 45.0m;

IRAMPDB — Airy disk for dish of 15m with a blockage of 1m;

NRAO12M — VLA beam scaled to 12m;

OVRO — VLA Airy disk scaled to 10.4m;

Beta Alert!

Multi-MS handling is not percolated to the tasks yet, as we are still working on this. Use single MS only.

SMA — Spheroidal function fit to FWHM;

WSRT — polynomial fitted to measurement of main lobe;

If the telescope name is unknown, or is CARMA or ALMA, then the `DISH_DIAMETER` in the `ANTENNA` table is used with a scaled VLA pattern. **BETA ALERT:** Currently this generic beam is only implemented for `imagermode='mosaic'` in `clean`, but in the future will be enabled for all cases.

Note that for the purposes of mosaicing in `clean`, the primary beams that are Airy or spheroidal are best-behaved (see § 5.3.15).

5.3 Deconvolution using CLEAN (`clean`)

To create an image and then deconvolve it with the CLEAN algorithm, use the `clean` task. This task will work for single-field data, or for multi-field mosaics (§ 5.3.15). **BETA ALERT:** There is now an experimental feature to image data taken with “heterogeneous” arrays with non-identical dish sizes (§ 5.3.16).

The `clean` task uses many of the common imaging parameters. These are described above in § 5.2. There are also a number of parameters specific to `clean`. These are listed and described below.

The default inputs to `clean` are:

```
# clean :: Calculates a deconvolved image with a selected clean algorithm

vis      =      '' # name of input visibility file (MS)
imagingname =      '' # Pre-name of output images
field    =      '' # Field Name
spw      =      '' # Spectral windows:channels: '' is all
selectdata = False # Other data selection parameters
mode     = 'mfs' # Type of selection (mfs, channel, velocity, frequency)
niter    = 500 # Maximum number of iterations
gain     = 0.1 # Loop gain for cleaning
threshold = '0.0mJy' # Flux level to stop cleaning. Must include units
psfmode   = 'clark' # method of PSF calculation to use during minor cycles
imagermode =      '' # Use csclean or mosaic. If '', use psfmode
multiscale = [] # set deconvolution scales (pixels)
interactive = False # use interactive clean (with GUI viewer)
mask     = [] # cleanbox(es), mask image(s), and/or region(s)
imsize   = [256, 256] # x and y image size in pixels
cell     = ['1.0arcsec', '1.0arcsec'] # x and y cell size. default unit arcsec
phasecenter =      '' # Image phase center: position or field index
restfreq  =      '' # rest frequency to assign to image (see help)
stokes    = 'I' # Stokes params to image (eg I,IV, QU,IQUV)
weighting  = 'natural' # Weighting to apply to visibilities
uvtaper   = False # Apply additional uv tapering of visibilities.
modelimage =      '' # Name of model image(s) to initialize cleaning
restoringbeam = [''] # Output Gaussian restoring beam for CLEAN image
```

```
pbcov      = False   # Output primary beam-corrected image
minpb      = 0.1     # Minimum PB level to use
async      = False
```

The mode, psfmode, imagermode, and weighting parameters open up other sub-parameters. These are detailed in the common imaging task parameters section (§ 5.2).

A typical setup for `clean` on the NGC5921 dataset, after setting parameter values, might look like:

```
vis          = 'ngc5921.usescase.ms.consub' # Name of input visibility file
imagename    = 'ngc5921.usescase.clean' # Pre-name of output images
field        = '0'      # Field Name
spw          = ''       # Spectral windows:channels: '' is all
selectdata   = False    # Other data selection parameters
mode         = 'channel' # Type of selection (mfs, channel, velocity, frequency)
    nchan     = 46      # Number of channels (planes) in output image
    start     = 5       # first input channel to use
    width     = 1       # Number of input channels to average

niter        = 6000    # Maximum number of iterations
gain         = 0.1     # Loop gain for cleaning
threshold    = 8.0     # Flux level to stop cleaning. Must include units
psfmode      = 'clark' # method of PSF calculation to use during minor cycles
imagermode   = ''      # Use csclean or mosaic, or image-plane only if ''
multiscale   = []      # set deconvolution scales (pixels)
interactive  = False   # use interactive clean (with GUI viewer)
mask         = [108, 108, 148, 148] # cleanbox(es), mask image(s), and/or region(s)
imsize        = [256, 256] # x and y image size in pixels
cell          = [15.0, 15.0] # x and y cell size. default unit arcsec
phasecenter  = ''      # Image phase center: position or field index
restfreq     = ''      # rest frequency to assign to image (see help)
stokes        = 'I'     # Stokes params to image (eg I,IV, QU,IQUV)
weighting     = 'briggs' # Weighting to apply to visibilities
    robust    = 0.5    # Briggs robustness parameter
    npixels   = 0      # uv-cell size in pixels 0=> field of view

uv taper     = False   # Apply additional uv tapering of visibilities.
modelimage   = ''      # Name of model image(s) to initialize cleaning
restoringbeam= ['']   # Output Gaussian restoring beam for CLEAN image
pbcov       = False   # Output primary beam-corrected image
minpb       = 0.1     # Minimum PB level to use
async       = False
```

An example of the `clean` task to create a continuum image from many channels is given below:

```
clean(vis='ggtau.1mm.split.ms', # Use data in ggtau.1mm.split.ms
      imagename='ggtau.1mm',   # Name output images 'ggtau.1mm.*' on disk
      psfmode='clark',         # Use the Clark CLEAN algorithm
      imagermode='',           # Do not mosaic or use csclean
      mask='',                 # Do not use clean box or mask
```

```

niter=500, gain=0.1,      # Iterate 500 times using gain of 0.1
mode='mfs',               # multi-frequency synthesis (combine channels)
spw='0~2:2~57',          # Combine channels from 3 spectral windows
field='0',                #
stokes='I',               # Image stokes I polarization
weighting='briggs',        # Use Briggs robust weighting
rmode='norm', robust=0.5,  #   with robustness parameter of 0.5
cell=[0.1,0.1],           # Using 0.1 arcsec pixels
imsize=[256,256])         # Set image size = 256x256 pixels

```

This example will clean the entire inner quarter of the primary beam. However, if you want to limit the region over which you allow the algorithm to find clean components then you can make a deconvolution region (or mask). To create a deconvolution mask, use the `makemask` task and input that mask as a keyword into the task above.

Or you can set up a simple `cleanbox` region. To do this, make a first cut at the image and clean the inner quarter. Then use the `viewer` to look at the image and get an idea of where the emission is located. You can use the `viewer adjustment` panel to view the image in pixel coordinates and read out the pixel locations of your cursor.

Inside the Toolkit:

The `im.clean` method is used for CLEANing data. There are a number of methods used to set up the clean, including `im.setoptions`.

Then, you can use those pixel read-outs you just go to define a clean box region where you specify the bottom-left-corner (`blc`) x & y and top-right-corner x& y locations. For example, say you have a continuum source near the center of your image between `blcx`, `blcy`, `trcx`, `trcy` = 80, 80, 120, 120. Then to use this region:

```
cleanbox=[80,80,120,120]    # Set the deconvolution region as a simple box in the center.
```

The following are the `clean` specific parameters and their allowed values, followed by a description of carrying out interactive cleaning.

5.3.1 Parameter `psfmode`

The `psfmode` parameter chooses the “algorithm” that will be used to calculate the synthesized beam for use during the minor cycles in the image plane. The value types are strings. Allowed choices are '`clark`' (default) and '`hogbom`'.

5.3.1.1 The `clark` algorithm

In the '`clark`' algorithm, the cleaning is split into minor and major cycles. In the minor cycles only the brightest points are cleaned, using a subset of the point spread function. In the major cycle, the points thus found are subtracted correctly by using an FFT-based convolution. This algorithm is reasonably fast. Also, for polarization imaging, Clark searches for the peak in $I^2 + Q^2 + U^2 + V^2$.

5.3.1.2 The hogbom algorithm

The `hogbom` algorithm is the “Classic” image-plane CLEAN, where model pixels are found iteratively by searching for the peak. Each point is subtracted from the full residual image using the shifted and scaled point spread function. In general, this is not a good choice for most imaging problems (`clark` or `csclean` are preferred) as it does not calculate the residuals accurately. But in some cases, with poor uv-coverage and/or a PSF with bad sidelobes, the Hogbom algorithm will do better as it uses a smaller beam patch. For polarization cleaning, Hogbom searches for clean peak in I , Q , U , and V independently.

5.3.2 The multiscale parameter

BETA ALERT: The `multiscale` option is currently under development and should be used with caution and be considered as an “experimental” algorithm. The multi-scale CLEAN method is known to need careful tuning in order to properly converge. However, currently the only control for `multiscale` in the `clean` task is the setting of the `scales`.

To activate multi-scale mode, specify a non-blank list of scales in the `multiscale` parameter. e.g.

```
multiscale = [0,3,10,30]      # Four scales including point sources
```

These are given in numbers of pixels, and specify FWHM of the Gaussians used to compute the filtered images.

Setting the `multiscale` parameter to a non-empty list opens up the sub-parameter:

```
multiscale      = [0, 3, 10, 30]      # set deconvolution scales (pixels)
negcomponent   =         -1          # Stop if largest scale finds this many neg components
```

The `negcomponent` sub-parameter is here to set the point at which the clean terminates because of negative components. For `negcomponent > 0`, component search will cease when this number of negative components are found at the largest scale. If `negcomponent = -1` then component search will continue even if the largest component is negative.

The CASA multi-scale algorithm uses “Multi-scale CLEAN” to deconvolve using delta-functions and circular Gaussians as the basis functions for the model, instead of just delta-functions or pixels as in the other clean algorithms. This algorithm is still in the experimental stage, mostly because we are working on better algorithms for setting the scales for the Gaussians. The sizes of the Gaussians are set using the `scales` sub-parameter.

We are working on defining a better algorithm for scale setting. In the toolkit, there is an `nscale` argument which sets scales

$$\theta_i = \theta_{bmin} 10^{(i-N/2)/2} \quad (5.7)$$

where $N = \text{nscales}$ and θ_{bmin} is the fitted FWHM of the minor axis of the CLEAN beam.

Inside the Toolkit:

The `im.setscales` method sets the `point_sources` multi-scale Gaussian widths. In addition to choosing a list of sizes in pixels, you can just pick a number of scales and get a geometric series of sizes.

5.3.3 Parameter gain

The `gain` parameter sets the fraction of the flux density in the residual image that is removed and placed into the clean model at each minor cycle iteration. The default value is `gain = 0.1` and is suitable for a wide-range of imaging problems. Setting it to a smaller gain per cycle, such as `gain = 0.05`, can sometimes help when cleaning images with lots of diffuse emission. Larger values, up to `gain=1`, are probably too aggressive and are not recommended.




Figure 5.1: Close-up of the top of the interactive `clean` window. Note the boxes at the left (where the `iterations`, `cycles`, and `threshold` can be changed), the buttons that control add/erase, the application of mask to channels, and whether to stop, complete, or continue cleaning, and the row of Mouse-button tool assignment icons.

5.3.4 Parameter imagermode

This choose the mode of operation of `clean`, either as single-field deconvolution using image-plane major and minor cycles only (`imagermode=''`), single-field deconvolution using Cotton-Schwab (CS) residual visibilities for major cycles (`imagermode='csclean'`), or multi-field mosaics using CS major cycles (`imagermode='mosaic'`).

In the default mode (`imagermode=''`), the major and minor clean cycles work off of the gridded FFT dirty image, with residuals updated using the PSF calculation algorithm set by the `psfmode` parameter (§ 5.3.1). This method is not recommended for high dynamic range or high fidelity imaging applications, but can be significantly faster than CS clean. Note that for this option only, if `mask=''` (no mask or box set) then it will clean the inner quarter of the image by default.

The `csclean` choice specifies the Cotton-Schwab algorithm. This opens up the sub-parameters

```
imagermode      = 'csclean'  # Use csclean or mosaic.  If '', use psfmode
cyclefactor    =        1.5  # Change depth in between of csclean cycle
```

```
cyclespeedup = -1 # Cycle threshold doubles in this number of iterations
```

These options are explained below. In the CS mode, cleaning is split into minor and major cycles. For each field, a minor cycle is performed using the PSF algorithm specified in `psfmode` (§ 5.3.1). At major-cycle breakpoints, the points thus found are subtracted from the original visibilities. A fast variant does a convolution using a FFT. This will be faster for large numbers of visibilities. If you want to be extra careful, double the image size from that used for the Clark clean and set a mask to clean only the inner quarter or less (this is not done by default). This is probably the best choice for high-fidelity deconvolution of images without lots of large-scale structure.

Note that when using the Cotton-Schwab algorithm with a `threshold` (§ 5.3.12), there may be strange behavior when you hit the threshold with a major cycle. In particular, it may be above threshold again at the start of the next major cycle. This is particularly noticeable when cleaning a cube, where different channels will hit the threshold at different times.

BETA ALERT: You will see a warning message in the logger, similar to this:

```
Zero Pixels selected with a Flux limit of 0.000551377 and a maximum Residual of 0.00751239
```

whenever it finds 0 pixels above the threshold. This is normal, and not a problem, if you've specified a non-zero threshold. On the other hand, if you get this warning with the threshold set to the default of '0Jy', then you should look carefully at your inputs or your data, since this usually means that the masking is bad.

The option `imagermode='mosaic'` is for multi-field mosaics. This choice opens up the sub-parameters

```
imagermode      = 'mosaic'   # Use csclean or mosaic.  If '', use psfmode
mosweight       = False      # Individually weight the fields of the mosaic
ftmachine       = 'mosaic'   # Gridding method for the image
scaletype       = 'SAULT'    # Controls scaling of pixels in the image plane.
cyclefactor     = 1.5        # change depth in between of csclean cycle
cyclespeedup   = -1         # Cycle threshold doubles in this number of iteration
```

These options are explained below.

5.3.4.1 Sub-parameter `cyclefactor`

This sub-parameter is activated for `imagermode='csclean'` and '`'mosaic'`.

The `cyclefactor` parameter allows the user to change the threshold at which the deconvolution cycle will stop and then degrid and subtract the model from the visibilities to form the residual. This is with respect to the breaks between minor and major cycles that the `clean` part would

Inside the Toolkit:

The `im.setmfcontrol` method sets the parameters that control the cycles and primary beam used in mosaicing.

normally force. Larger values force a major cycle more often.

This parameter in effect controls the threshold used by CLEAN to test whether a major cycle break and reconciliation occurs:

```
cycle threshold = cyclefactor * max sidelobe * max residual
```

If your uv-coverage results in a poor PSF, then you should reconcile often (a `cyclefactor` of 4 or 5); For reasonable PSFs, use `cyclefactor` in the range 1.5 to 2.0. For good PSFs, or for faster cleaning at the expense of some fidelity, we recommend trying a lower value, e.g. `cyclefactor = 0.25`, which at least in some of our mosaicing tests led to a speedup of around a factor of two with little change in residuals.

5.3.4.2 Sub-parameter `cyclespeedup`

This sub-parameter is activated for `imagermode='csclean'` and '`mosaic`'.

The `cyclespeedup` parameter allows the user to let `clean` to raise the threshold at which a major cycle is forced if it is not converging to that threshold. To do this, set `cyclespeedup` to an integer number of iterations at which if the threshold is not reached, the threshold will be doubled. See `cyclefactor` above for more details. By default this is turned off (`cyclespeedup = -1`). In our tests, a value like `cyclespeedup = 50` has been used successfully.

5.3.4.3 Sub-parameter `ftmachine`

This sub-parameter is activated for `imagermode='mosaic'`.

The `ftmachine` parameter controls the gridding method and kernel to be used to make the image. A string value type is expected. Choices are: '`ft`', '`sd`', '`both`', or '`mosaic`' (the default).

The '`ft`' option uses the standard gridding kernel (as used in `clean`).

The '`sd`' option forces gridding as in single-dish data.

For combining single-dish and interferometer MS in the imaging, the '`both`' option will allow `clean` to choose the '`ft`' or '`sd`' machines as appropriate for the data.

The '`mosaic`' option (the default) uses the Fourier transform of the primary beam (the aperture cross-correlation function in the uv-plane) as the gridding kernel. This allows the data from the multiple fields to be gridded down to a single uv-plane, with a significant speed-up in performance in most (non-memory limited) cases. The effect of this extra convolution is an additional multiplication (apodization) by the primary beam in the image plane. This can be corrected for, but does result in an image with optimal signal to noise ratio across it.

Inside the Toolkit:

The `im.setoptions` method sets the parameters relevant to mosaic imaging, such as the `ftmachine`.

The primary beams used in CASA are described in § 5.2.13.

BETA ALERT: Note that making a non-square image (e.g. using unequal values in `imsize`) for `ftmachine='mosaic'` will grid the data into a uv-plane with correspondingly non-square cells. This has not been extensively tested, and may result in undesired image artifacts. We recommend that the user make square mosaic images when possible.

5.3.4.4 Sub-parameter `mosweight`

If `mosweight=True` then individual mosaic fields will receive independent weights, which will give optimum signal to noise ratio.

If `mosweight=False` then the data will be weighted so that the signal-to-noise ratio is as uniform as possible across the mosaic image.

5.3.4.5 Sub-parameter `scaletype`

The `scaletype` parameter controls weighting of pixels in the image plane. This sub-parameter is activated for `imagermode='mosaic'`.

The default `scaletype='PBCOR'` scales the image to have the correct flux scale across it (out to the beam level cutoff `minpb`). This means that the noise level will vary across the image, being increased by the inverse of the weighted primary beam responses that are used to rescale the fluxes.

This option should be used with care, particularly if your data has very different exposure times (and hence intrinsic noise levels) between the mosaic fields.

If `scaletype='SAULT'` then the image will be scaled so as to have constant noise across it. This means that the point source response function varies across the image attenuated by the weighted primary beam(s). However, this response is output in the `.flux` image and can be later used to correct this.

Note that this scaling as a function of position in the image occurs after the weighting of mosaic fields specified by `mosweight` and implied by the gridding weights (`ftmachine` and `weighting`).

Inside the Toolkit:

The `im.setmfcontrol` method gives more options for controlling the primary beam and noise across the image.

5.3.4.6 The threshold revisited

For mosaics, the specification of the threshold is not straightforward, as it is in the single field case. This is because the different fields can be observed to different depths, and get different weights in the mosaic. For efficiency, `clean` does its component search on a weighted and scaled version of the sky.

For `ftmachine='ft'`, the minor cycles of the deconvolution are performed on an image that has been weighted to have constant noise, as in 'SAULT' weighting (see § 5.3.4.5). This is equivalent

to making a dirty mosaic by coadding dirty images made from the individual pointings with a sum of the mosaic contributions to a given pixel weighted by so as to give constant noise across the image. This means that the flux scale can vary across the mosaic depending on the effective noise (higher weighted regions have lower noise, and thus will have higher “fluxes” in the ’SAULT’ map). Effectively, the flux scale that threshold applies to is that at the center of the highest-weighted mosaic field, with higher-noise regions down-scaled accordingly. Compared to the true sky, this image has a factor of the PB, plus a scaling map (returned in the .flux image). You will preferentially find components in the low-noise regions near mosaic centers.

When `ftmachine='mosaic'`, the underlying deconvolution is performed on a constant signal-to-noise image. This is equivalent to a dirty mosaic that is formed by coadding dirty images made from the individual fields after apodizing each by the PB function. Thus compared to the true sky, this has a factor of the PB² in it. You will thus preferentially find components in the centers of the mosaic fields (even more so than in the ’ft’ mosaics).

Both these cases should have the same flux scale in the centers of the lowest-noise pointings in the mosaic. This is where the `threshold` units match those in the image being used in the minor cycle.

BETA ALERT: This is fairly complicated, and we are working on explaining this better and possibly making this more straightforward to specify.

5.3.5 Parameter interactive

If `interactive=True` is set, then an interactive window will appear at various “cycle” stages while you clean, so you can set and change mask regions. These breakpoints are controlled by the `npercycle` sub-parameter which sets the number of iterations of clean before stopping.

```
interactive      =      True    #  use interactive clean (with GUI viewer)
npercycle      =      100    #  Number of iterations before interactive prompt
```

BETA ALERT: `npercycle` is currently the only way to control the breakpoints in interactive clean.

See the example of interactive cleaning in § 5.3.13.

5.3.6 Parameter mask

The `mask` parameter takes a list of elements, each of which can be a list of coordinates specifying a box, or a string pointing to the name of a cleanbox file, mask image, or region file. These are used by CLEAN to define a region to search for components.

Note that for `imagermode=''` (§ 5.3.4) the default with `mask=''` is to restrict `clean` to the inner quarter of the image.

5.3.6.1 Setting clean boxes

If `mask` is given a list, these are taken to be pixel coordinates for the `blc` and `trc` (bottom-left and top-right corners) of one or more rectangular boxes. For example,

```
cleanbox = [110,110,150,145, 180,70,190,80]
```

defines two boxes.

5.3.6.2 Using clean box files

You can provide `mask` a string with the name of an ASCII file containing the BLC, TRC of the boxes with one box per line. Each line should contain five numbers

```
<fieldindex> <blc-x> <blc-y> <trc-x> <trc-y>
```

with whitespace separators. Currently the `<fieldindex>` is ignored.

Here is an example `cleanbox` file:

```
CASA <21>: !cat mycleanbox.txt
IPython system call: cat mycleanbox.txt
1 108 108 148 148
2 160 160 180 180
```

NOTE: In future patches we will include options for the specification of circular and polygonal regions in the `cleanbox` file, as well as the use of world coordinates (not just pixel) and control of plane ranges for the boxes. For now, use the `mask` mechanism for more complicated CLEAN regions.

5.3.6.3 Using clean mask images

You can give the `mask` parameter a string containing the name of a mask image to be used for CLEAN to search for components. You can use the `makemask` task to construct this mask, or use one made using `interactive=True` (§ 5.3.5).

5.3.6.4 Using region files

You can give the `mask` parameter a string pointing to a file that describes a *region*. This region file can be generated in the `viewer` (§ 7).

5.3.7 Parameter `minpb`

The `minpb` parameter sets the level down to which the primary beam (or more correctly the voltage patterns in the array) can go and have a given pixel included in the image. This is important as it defines where the edge of the visible image or mosaic is. The default is 0.1 or equivalent to the 10% response level. If there is a lot of emission near the edge, then set this lower if you want to be able to clean it out.

5.3.8 Parameter `modelimage`

The `modelimage` parameter specifies the name(s) of one or more input starting image(s) to use to calculate the first residual before cleaning. These are used in addition to any image with a name defaulting from the `imagername` root (e.g. on a restart). The output model will contain this model plus clean components found during deconvolution.

If the units of the image are Jy/pixel, then this is treated as a model image.

If the units of the image are Jy/beam or Jy per solid angle, then this is treated as a “single-dish” image and rescaled by the resolution (in the ‘beam’ image header keyword). Inclusion of the SD image here is superior to feathering it in later. See § 5.5 for more information on feathering.

5.3.9 Parameter `niter`

The `niter` parameter sets the maximum total number of minor-cycle CLEAN iterations to be performed during this run of `clean`. If restarting from a previous state, it will carry on from where it was. Note that the `threshold` parameter can cause the CLEAN to be terminated before the requested number of iterations is reached.

5.3.10 Parameter `pbcor`

The `pbcor` parameter controls whether the final `.image` is scaled to correct for the Primary Beam of the array or not.

If `pbcor=False` (the default), then no such scaling is done and the image is in whatever “raw” scaling used by the `imagermode` algorithm underneath. For single-field cleaning with `imagermode=''` or `'csclean'`, this is the standard constant-noise image. If `imagermode='mosaic'`, then this is the ‘SAULT’ scaled image (regardless of what `scaletype` is set to).

If `pbcor=True`, then at the end of deconvolution and imaging the “raw” image is rescaled by dividing by the noise and PB correction image. This is what is output by `clean` as the `.flux` image.

Note that regardless of what you set `pbcor` to, you can recover the other option using `immath` (§ 6.5) to either multiply or divide by the `.flux` image.

5.3.11 Parameter `restoringbeam`

The `restoringbeam` parameter allows the user to set a specific Gaussian restoring beam to make the final restored `.image` from the final `.model` and residuals.

If `restoringbeam=''` (the default), then the restoring beam is calculated by fitting to the PSF (e.g. the `.psf` image). For a mosaic, this is at the center of the field closest to the `phasecenter`.

To specify a restoring beam, provide `restoringbeam` a list of [`bmaj`, `bmin`, `bpa`] which are the parameters of an elliptical Gaussian. The default units are in arc-seconds for `bmaj`, `bmin` components and degrees for the `bpa` component.

For example,

```
restoringbeam=['10arcsec']          # circular Gaussian FWHM 10"
restoringbeam=['10.0','5.0','45.0deg'] # 10"x5" at PA=45 degrees
```

5.3.12 Parameter `threshold`

The `threshold` parameter instructs `clean` to terminate when the maximum (absolute?) residual reaches this level or below. Note that it may not reach this residual level due to the value of the `niter` parameter which may cause it to terminate early.

If `threshold` is given a floating-point number, then this is the threshold in milli-Jansky.

You can also supply a flux density *quanta* to `threshold`, e.g.

```
threshold = '8.0mJy'
threshold = '0.008Jy'
```

(these do the same thing).

5.3.13 Example — Interactive Cleaning

If `interactive=True` is set, then an interactive window will appear at various “cycle” stages while you clean, so you can set and change mask regions. These breakpoints are controlled by the `npercycle` sub-parameter which sets the number of iterations of `clean` before stopping.

The window controls are fairly self-explanatory. It is basically a form of the `viewer`. A close-up of the controls are shown in Figure 5.1, and an example can be found in Figures 5.2–5.4. You assign one of the drawing functions (rectangle or polygon, default is rectangle) to the right-mouse button (usually), then use it to mark out regions on the image. Zoom in if necessary (standard with the left-mouse button assignment). Double-click inside the marked region to add it to the mask. If you want to reduce the mask, click the **Erase** radio button (rather than **Add**), then mark and select as normal. When finished setting or changing your mask, click the green clockwise arrow “Continue Cleaning” Next Action button. If you want to finish your clean with no more changes to the mask,




Figure 5.2: Screen-shots of the interactive `clean` window during deconvolution of the VLA 6m Jupiter dataset. We start from the calibrated data, but before any self-calibration. In the initial stage (left), the window pops up and you can see it dominated by a bright source in the center. Next (right), we zoom in and draw a box around this emission. We have also at this stage dismissed the tape deck and Position Tracking parts of the display (§ 7.2.1) as they are not used here. We have also changed the `iterations` to 30 for this boxed clean. We will now hit the Next Action **Continue Cleaning** button (the green clockwise arrow) to start cleaning.

hit the blue right arrow “Apply mask edits and proceed with non-interactive clean” button. If you want to terminate the clean, click the red X “Stop deconvolving now” button.

While stopped in an interactive step, you can change a number of control parameters in the boxes provided at the left of the menu bar. The main use of this is to control how many `iterations` before the next breakpoint (initially set to `npercycle`), how many cycles before completion (initially equal to `niter/npercycle`), and to change the `threshold` for ending cleaning. Typically, the user would start with a relatively small number of iterations (50 or 100) to clean the bright emission in tight mask regions, and then increase this as you get deeper and the masking covers more of the emission region. For extended sources, you may end up needing to clean a large number of components (10000 or more) and thus it is useful to set `niter` to a large number to begin with — you can always terminate the clean interactively when you think it is done. Note that if you change `iterations` you may also want to change `cycles` or your clean may terminate before you

expect it to.




Figure 5.3: We continue in our interactive `cleaning` of Jupiter from where Figure 5.2 left off. In the first (left) panel, we have cleaned 30 iterations in the region previously marked, and are zoomed in again ready to extend the mask to pick up the newly revealed emission. Next (right), we have used the Polygon tool to redraw the mask around the emission, and are ready to **Continue Cleaning** for another 100 iterations.

For strangely shaped emission regions, you may find using the polygon region marking tool (the second from the right in the button assignment toolbar) the most useful.

See the example of cleaning and self-calibrating the Jupiter 6cm continuum data given below in § 5.10.2. The sequence of cleaning starting with the “raw” externally calibrated data is shown in Figures 5.2 – 5.4.

The final result of all this cleaning for Jupiter is shown in Figure 5.5. The `viewer` (§ 7) was used to overplot the polarized intensity contours and linear polarization vectors calculated using `immath` (§ 6.5) on the total intensity. See the following chapters on how to make the most of your imaging results.

For spectral cube images you can use the tapedeck to move through the channels. You also use the panel with radio buttons for choosing whether the mask you draw applies to the `Displayed Plane` or to `All Channels`. See Figure 5.6 for an example. Note that currently the `Displayed Plane` option is set by default. This toggle is unimportant for single-channel images or `mode='mfs'`.




Figure 5.4: We continue in our interactive `clean` of Jupiter from where Figure 5.3 left off. In the first (left) panel, it has cleaned deeper, and we come back and zoom in to see that our current mask is good and we should clean further. We change `npercycle` to 500 (from 100) in the box at upper right of the window. In the final panel (right), we see the results after this clean. The residuals are such that we should terminate the `clean` using the red X button and use our model for self-calibration.

Advanced Tip: Note that while in interactive `clean`, you are using the `viewer`. Thus, you have the ability to open and register other images in order to help you set up the clean mask. For example, if you have a previously cleaned image of a complex source or mosaic that you wish to use to guide the placement of boxes or polygons, just use the **Open** button or menu item to bring in that image, which will be visible and registered on top of your dirty residual image that you are cleaning on. You can then draw masks as usual, which will be stored in the mask layer as before. Note you can blink between the new and dirty image, change the colormap and/or contrast, and carry out other standard viewer operations. See § 7 for more on the use of the `viewer`.

BETA ALERT: Currently, interactive spectral line cleaning is done globally over the cube, with halts for interaction after searching all channels for the requested `npercycle` total iterations. It is more convenient for the user to treat the channels in order, cleaning each in turn before moving on. This will be implemented in an upcoming update.




Figure 5.5: After clean and self-calibration using the intensity image, we arrive at the final polarization image of Jupiter. Shown in the viewer superimposed on the intensity raster is the linear polarization intensity (green contours) and linear polarization B-vectors (vectors). The color of the contours and the sampling and rotation by 90 degrees of the vectors was set in the Display Options panel. A LEL expression was used in the Load Data panel to mask the vectors on the polarized intensity.

5.3.14 Example — Mosaicing

An example of a simple mosaicic `clean` call is shown below:

```
clean(vis='n4826_tboth.ms',
      imagnename='tmosaic',
      mode='channel',
      nchan=30,start=46,           # Make the output cube 30 chan
      width=4,                   # start with 46 of spw 0, avg by 4 chans
      spw='0~2',
      field='0~6',
      cell=[1.,1.],
```




Figure 5.6: Screen-shot of the interactive `clean` window during deconvolution of the NGC5921 spectral line dataset. Note where we have selected the mask to apply to the `Displayed Plane` rather than `All Channels`. We have just used the Polygon tool to draw a mask region around the emission in this channel, which will apply to this channel only.

```
imsize=[256,256],
stokes='I',
psfmode='clark',
niter=500,
imagermode='mosaic',
scaletype='SAULT',
```

```
cyclefactor=0.1)
```

5.3.15 Mosaic imaging

The `clean` task contains the capability to image multiple pointing centers together into a single “mosaic” image. This ability is controlled by setting `imagermode='mosaic'` (§ 5.3.4).

The key parameter that controls how `clean` produces the mosaic is the `ftmachine` sub-parameter (§ 5.3.4.3). For `ftmachine='ft'`, `clean` will perform a weighted combination of the images produced by transforming each mosaic pointing separately. This can be slow, as the individual sub-images must be recombined in the image plane. **NOTE:** this option is preferred for data taken with sub-optimal mosaic sampling (e.g. fields too far apart, on a sparse irregular pattern, etc.).

The primary beams used in CASA are described in § 5.2.13.

If `ftmachine='ft'`, then the data are gridded onto a single uv-plane which is then transformed to produce the single output image. This is accomplished by using a gridding kernel that approximates the transform of the primary beam pattern.

BETA ALERT: In order to avoid aliasing artifacts for `ftmachine='mosaic'` in the mosaic image, due to the discrete sampling of the mosaic pattern on the sky, you should make an image in which the desired unmasked part of the image (above `minpb`) lies within the inner quarter. In other words, make an image twice as big as necessary to encompass the mosaic.

It is also important to choose an appropriate `phasecenter` for your output mosaic image (§ `section:im.pars.phasecenter`).

5.3.16 Heterogeneous imaging

The `clean` task and underlying tools can now handle cases where there are multiple dish sizes, and thus voltage patterns and primary beams, in the array. This is effected by using the dish sizes stored in the `ANTENNA` sub-table of the MS. Depending on how the data was written and imported into CASA, the user may have to manually edit this table to insert the correct dish sizes (e.g. using `browsetable` or the `tb` table tool).

BETA ALERT: This feature is new in Patch 3, and has not been extensively tested. Currently, this works only for an MS where the `OBSERVATORY` keyword is CARMA, ALMA, or is unknown. You must set `imagermode='mosaic'` with `ftmachine='mosaic'`, even when imaging a single field, to use this feature. This will be improved, and made easier to set and use, in future releases.

5.4 Wide-field imaging and deconvolution (`widefield`)

When imaging sufficiently large angular regions, the sky can no longer be treated as a two-dimensional plane and the use of the standard `clean` task will produce distortions around sources

that become increasingly severe with increasing distance from the phase center. In this case, one must use a “wide-field” imaging algorithm such as w-projection or faceting.

When is wide-field imaging needed? It depends on the expected dynamic range the image. In order to keep the phase error associated with the sky/array curvature less than about 5° (good to about 500:1 dynamic range), use the following table, suitably scaled, for guidance:

Maximum Radius of Image Before `widefield` is Needed
Assuming 5 deg phase error and 35-km Baseline

Wavelength	Radius of image
6 cm	1.4 arcmin
20 cm	2.6 arcmin
90 cm	5.3 arcmin

$$\text{Radius of image} \sim \text{SQRT}(\text{Wavelength} * \text{phase error} / \text{Maximum baseline})$$

(arcmin)	(cm)	(deg)	(km)
----------	------	-------	------

If a relatively small image is being made, but there are outliers sources beyond the above limits, then `widefield` should also be used.

The task `widefield` has been introduced for this purpose. This is currently a prototype task that can be used to make and deconvolve a wide-field image (e.g. from low frequency data). It contains most, but not all, of the flexibility of `clean`. The w-term is handled using a combination of w-projection and faceting. Besides making large area undistorted images, `widefield` can be used to outlying fields to image isolated regions (e.g. containing bright confusing sources) distant from the field center.

The inputs for `widefield` are:

```
# widefield :: Wide-field imaging and deconvolution with selected algorithm
vis          =      []      # name of input visibility file
imaginefile =      ''      # Pre-name of output images
outlierfile =      ''      # Text file with image names, sizes, centers
field        =      ''      # Field Name
spw          =      ''      # Spectral windows:channels: '' is all
selectdata   =     False    # Other data selection parameters
mode         =     'mfs'   # Type of selection (mfs, channel, velocity, frequency)
niter        =      500    # Maximum number of iterations
gain         =      0.1    # Loop gain for cleaning
threshold    =     '0.0Jy' # Flux level to stop cleaning. Must include units
psfmode      =     'clark' # Algorithm to use (clark, hogbom)
ftmachine   =     'wproject' # Gridding method for the image (wproject, ft)
wprojplanes =      256    # Number of planes to use in w-convolution function
facets       =       1     # Number of facets along each axis in main image only

multiscale   =      []      # set deconvolution scales (pixels), default: single scale
interactive  =     False   # use interactive clean (with GUI viewer)
mask         =      []      # cleanbox(es), mask image(s), and/or region(s)
imsize       = [256, 256] # Image size in pixels (nx,ny), symmetric for single value
```

```

cell          = ['1.0arcsec', '1.0arcsec'] # The image cell size in arcseconds [x,y].
phasename     = ''      # Field Identifier or direction of the image phase center
restfreq      = ''      # rest frequency to assign to image (see help)
stokes         = 'I'    # Stokes params to image (I,IV,QU,IQUV,RR,LL,XX,YY,RRL,XXYY)
weighting       = 'natural' # Weighting to apply to visibilities
cyclefactor    = 1.5    # Change the threshold at which the deconvolution cycle will stop,
                      # degrid, and subtract from the visibilities.
cyclespeedup   = -1     # Cycle threshold doubles in this number of iterations
uv taper       = False   # Apply additional uv tapering of visibilities.
restoringbeam  = ['']    # Output Gaussian restoring beam for CLEAN image
async          = False   # If true the taskname must be started using widefield(...)

```

Most of the parameters are similar to `clean` and should be reviewed there. Specialized parameters for `widefield` are as follows:

The task `widefield` can be used in two major modes: First, the w-projection mode as chosen with `fpmachine` deals with the w-term (the phase associated with the sky/array curvature) internally. Secondly, the image can be broken into many facets, each small enough so that the w-term is not significant. These two basic methods can be combined, and are discussed below in § 5.4.1.

When using `widefield`, the position and image size of each image must be specified. This can be done in two ways. The first method uses input from a text file `outlierfile`. For example:

```

vis          = 'wfield.ms'    # name of input visibility file
imagine     = 'wf'           # Pre-name of output images
outlierfile = 'setup.txt'   # Text file with image names, sizes, centers
imsize       = [256, 256]     # Image size in pixels (nx,ny), symmetric for single value
cell         = '1.0arcsec'    # The image cell size in arcseconds [x,y].
phasecenter  = ''            # Field Identifier or direction of the image phase center

```

The `cell` is identical for all fields, and `imsize` and `phasecenter` are not used. The output image names will be `wf.main`, `wf.out1`, etc.

The file `outlierfile="setup.txt"` is an AIPS-style field file used to locate outlier fields. For example:

```

C main 2048 2048 13 27 20.98    43 26 28.0 # Main field with image size and phase center
C out1 128 128 13 30 52.158    43 23 08.00 # First outlier field specification
      etc

```

will make a big main image with outliers. The C in column 1 must be present, although it is not presently used.

The alternative input, needing no additional outlier file, versus `imsize` plus `phasecenter`: is:

```

vis          = 'wfield.ms'    # name of input visibility file
imagine     = 'wf'           # Pre-name of output images
outlierfile = 'image_setup.txt' # Text file with image names, sizes, centers
imsize       = [2048, 2048, 128, 128] # Image size in pixels (nx,ny)
cell         = '1.0arcsec'    # The image cell size in arcseconds [x,y].
phasecenter  = ['J2000 13h27m20.98 43d26m28.0', 'J2000 13h30m52.158 43d23m08.00']

```

The other parameters are described in `clean`, and multi-scale cleaning is available. Mosaicing and MEM is not yet included in `widefield`.

5.4.1 ftmachine modes for widefield

The crucial part of `widefield` is the parameters under `ftmachine`. The three types of use are: (1) w-projection only; (2) facets only; (3) w-projection with facets.

5.4.1.1 pure w-projection

The “pure” w-projection mode is invoked using `ftmachine='wproject'`:

```
ftmachine      = 'wproject'   # Gridding method for the image (wproject, ft)
wprojplanes =       64   # Number of planes to use in wprojection convolution function
facets        =       1   # Number of facets along each axis in main image only
```

A reasonable value for `wprojplanes` is equal to $n_w = B_{max}(\text{ink}\lambda) \times \text{imagewidth}(\text{inarcmin}^2)/600$, with a minimum value of $n_w = 16$. The w-projection algorithm is much faster than using facetting, but it does consume a lot of memory. On most 32-bit machines with 1 or 2 Mbytes of memory, images larger than about 4000×4000 cannot be made.

5.4.1.2 faceting only

Faceting only mode will break the image into many small parts. This is invoked using `ftmachine='ft'`:

```
ftmachine      = 'ft'    # Gridding method for the image (wproject, ft)
facets        =       7   # Number of facets along each axis in main image only
```

In this example the image is broken into 49 (7×7) facets.

A reasonable value of facets is such that the image width of each facet does not need the w-term correction. The computation method with pure facetting is slow, so that wprojection is recommended

5.4.1.3 combination of w-projection and facetting

You can also use a combination of wprojection and facetting with `ftmachine='wproject'`:

```
ftmachine      = 'wproject'   # Gridding method for the image (wproject, ft)
wprojplanes =       32   # Number of planes to use in wprojection convolution function
facets        =       3   # Number of facets along each axis in main image only
```

This hybrid method allows for a smaller number of `wprojplanes` in order to try to conserve memory if the image size approached the memory limit of the computer. However, there is a large penalty in execution time.

5.5 Combined Single Dish and Interferometric Imaging (feather)

The term “feathering” is used in radio imaging to describe how to combine or “feather” two images together by forming a weighted sum of their Fourier transforms in the (gridded) uv-plane. Intermediate size scales are down-weighted to give interferometer resolution while preserving single-dish total flux density.

The feathering technique does the following:

1. The single-dish and interferometer images are Fourier transformed.
2. The beam from the single-dish image is Fourier transformed ($FTSDB(u, v)$).
3. The Fourier transform of the interferometer image is multiplied by $(1 - FTSDB(u, v))$. This basically down weights the shorter spacing data from the interferometer image.
4. The Fourier transform of the single-dish image is scaled by the volume ratio of the interferometer restoring beam to the single dish beam.
5. The results from 3 and 4 are added and Fourier transformed back to the image plane.

The term feathering derives from the tapering or down-weighting of the data in this technique; the overlapping, shorter spacing data from the deconvolved interferometer image is weighted down compared to the single dish image while the overlapping, longer spacing data from the single-dish are weighted down compared to the interferometer image.

Other Packages:

The `feather` task is analogous to the AIPS `IMERG` task and the MIRIAD `immerge` task with option '`feather`'.

The tapering uses the transform of the low resolution point spread function. This can be specified as an input image or the appropriate telescope beam for the single-dish. The point spread function for a single dish image may also be calculated using `clean`.

Advice: Note that if you are feathering large images, be advised to have the number of pixels along the X and Y axes to be composite numbers and definitely not prime numbers. In general FFTs work much faster on even and composite numbers. You may use subimage function of the image tool to trim the number of pixels to something desirable.

The inputs for `feather` are:

```
imagename      =      ''      #  Name of output feathered image
highres        =      ''      #  Name of high resolution (synthesis) image
lowres         =      ''      #  Name of low resolution (single dish) image
```

Note that the only inputs are for images. Note that `feather` does not do any deconvolution but combines presumably deconvolved images after the fact.

Starting with a cleaned synthesis image and a low resolution image from a single dish telescope, the following example shows how they can be feathered:

```
feather(imagename='feather.im',      # Create an image called feather.im
        highres='synth.im',       # The synthesis image is called synth.im
        owres='single_dish.im'    # The SD image is called single_dish.im
)
```

Note that the single dish image must have a well-defined beam shape and the correct flux units for a model image (Jy/beam instead of Jy/pixel) so use the tasks `imhead` and `immath` first to convert if needed.

5.6 Making Deconvolution Masks (`makemask`)

For most careful imaging, you will want to restrict the region over which you allow CLEAN components to be found. To do this, you can create a 'deconvolution region' or 'mask' image using the `makemask` task. This is useful if you have a complicated region over which you want to clean and it will take many clean boxes to specify.

The parameter inputs for `makemask` are:

```
# makemask :: Derive a mask image from a cleanbox and set of imaging parameters:

cleanbox      =      []      # Clean box file or regions
vis           =      ''      # Name of input visibility file (if no input image)
imagename     =      ''      # Name of output mask images
mode          =      'mfs'   # Type of selection (mfs, channel, velocity)
imsize        = [256, 256] # Image size in spatial pixels [x,y]
cell          = [1, 1]    # Cell size in arcseconds
phasecenter   =      ''      # Field identifier or direction of the phase center
stokes        =      'I'     # Stokes parameter to image (I,IV,IQU,IQUV)
field         =      '0'     # Field ids list to use in mosaic
spw           =      '0'     # Spectral window identifier (0-based)
```

The majority of the parameters are the standard imaging parameters (§ 5.2). The `cleanbox` parameter uses the syntax for cleanboxes as in the `clean` parameter `mask` (see § 5.3.6), with the option for '`interactive`' also. The `imagename` parameter specifies the name for the output mask image.

You can use the `viewer` to figure out the cleanbox blc-trc x-y settings, make the mask image, and then bring it into the viewer as a contour image over your deconvolved image to compare exactly where your mask regions are relative to the actual emission. In this example, create a mask from many cleanbox regions specified in a file on disk (`cleanboxes.txt`) containing

```
1 80 80 120 120
2 20 40 24 38
3 70 42 75 66
```

where each line specifies the field index and the blc x-y and trc x-y positions of that cleanbox. For example, in `casapy`, you can do this easily:

```
CASA <29>: !cat > cleanboxes.txt
IPython system call: cat > cleanboxes.txt
1 80 80 120 120
2 20 40 24 38
3 70 42 75 66
<CNTL-D>
CASA <30>: !cat cleanboxes.txt
IPython system call: cat cleanboxes.txt
1 80 80 120 120
2 20 40 24 38
3 70 42 75 66
```

Then, in CASA,

```
makemask(vis='source.ms',
         imagename='source.mask',
         cleanbox='cleanboxes.txt',
         mode='mfs',                      # make a multi-frequency synthesis map (combine channels)
         imsize=[200,200])                 # Set image size = 200x200 pixels
         cell=[0.1,0.1],                   # Using 0.1 arcsec pixels
         spw='0,1,2',                     # Combine channels from 3 spectral windows
         field='0',                        # Use the first field in this split dataset
         stokes='I')                      # Image stokes I polarization
```

This task will then create a mask image that has the 3 cleanboxes specified in the `cleanboxes.txt` file.

You can also specify the `cleanbox` as a list (of lists) of blc,trc pairs (4 vertices), e.g.

```
cleanbox = [[80, 80, 120, 120], [20, 40, 24, 38], [70, 42, 75, 66]]
```

is equivalent to the `cleanboxes.txt` given above. Likewise,

```
cleanbox = [80, 80, 120, 120]
```

puts in a single cleanbox.

Note that you must specify a visibility dataset and create the image properties so the mask image will have the same dimensions as the image you want to actually clean.

BETA ALERT: Eventually we will add functionality to deal with the creation of non-rectangular regions and with multi-plane masks. There is also no `cleanbox='interactive'` version currently available. You have to run `clean` with `cleanbox='interactive'` to generate a mask graphically.

5.7 Transforming an Image Model (ft)

The `ft` task will Fourier transform an image and insert the resulting model into the `MODEL_DATA` column of a Measurement Set. You can also convert a CLEAN component list to a model and insert that into the `MODEL_DATA` column. The MS `MODEL_DATA` column is used, for example, to hold the model for calibration purposes in the tasks and toolkit. This is especially useful if you have a resolved calibrator and you want to start with a model of the source before you derive accurate gain solutions. This is also helpful for self-calibration (see § 5.9 below).

The inputs for `ft` are:

```
vis          =      ''    # Name of input visibility file
fieldid     =      0    # Field index identifier
field        =      ''    # Field name list
model        =      ''    # Name of input model image
complist    =      ''    # Name of component list
incremental =      False # Add to the existing MODEL_DATA column?
```

An example of how to do this:

```
ft(vis='n75.ms',
   field='1328',
   model='1328.model.image')      # Start with the visibility dataset n75.ms
                                  # Select field name '1328+307' (minimum match)
                                  # Name of the model image you have already
```

This task will Fourier transform the model image and insert the resulting model in the `MODEL_DATA` column of the rows of the MS corresponding to the source 1328+307.

Note that after `clean`, the transform of the final model is left in the `MODEL_DATA` column so you can go directly to a self-calibration step without explicitly using `ft`.

5.8 Image-plane deconvolution (deconvolve)

If you have only an image (obtained from some telescope) and an image of its point spread function, then you can attempt a simple image-plane deconvolution. Note that for interferometer data, full uv-plane deconvolution using `clean` or similar algorithm is superior!

The default inputs for `deconvolve` are:

```
# deconvolve :: Deconvolving a point spread function from an image

imagename  =      ''    # Name of image to deconvolve
model      =      ''    # Name of output image to which deconvolved components are stored
psf        =      ''    # Name of psf or gaussian parameters if psf is assumed gaussian
alg        =      'clark' # Deconvolution algorithm to use
niter      =      10    # number of iteration to use in deconvolution process
gain       =      0.1   # CLEAN gain parameter
```

Inside the Toolkit:

The `im.ft` method does what the `ft` task does. Its main use is setting the `MODEL_DATA` column in the MS so that the `cb` tool can use it for subsequent calibration.

```

threshold = '0.0Jy' # level below which sources will not be deconvolved
mask = '' # Name of image that has mask to limit region of deconvolution
async = False # if True run in the background, prompt is freed

```

The algorithm (`alg`) options are: '`clark`', '`hogbom`', '`multiscale`' or '`mem`'. The '`multiscale`' and '`mem`' options will open the usual set of sub-parameters for these methods.

5.9 Self-Calibration

Once you have a model image or set of model components reconstructed from your data using one of the deconvolution techniques described above, you can use it to refine your calibration. This is called *self-calibration* as it uses the data to determine its own calibration (rather than observations of special calibration sources).

In principle, self-calibration is no different than the calibration process we described earlier (§ 4). In effect, you alternate between calibration and imaging cycles, refining the calibration and the model as you go. The trick is you have to be careful, as defects in early stages of the calibration can get into the model, and thus prevent the calibration from improving. In practice, it is best to not clean very deeply early on, so that the CLEAN model contains correct components only.

One important thing to keep in mind is that the self-calibration relies upon having the most recent Fourier transform of the model in the `MODEL_DATA` column of the MS. This is indeed the case if you follow the imaging (using `clean`) directly by the self-calibration. If you have done something strange in between and have lost or overwritten the `MODEL_DATA` column (for example done some extra cleaning that you do not want to keep), then use the `ft` task (see § 5.7 above), which fills the `MODEL_DATA` column with the Fourier transform of the specified model or model image.

Likewise, during self-calibration (once you have a new calibration solution) the imaging part relies upon having the `CORRECTED_DATA` column contain the self-calibrated data. This is done with the `applycal` task (§ 4.6.1).

The `clearcal` command can be used during the self-calibration if you need to clear the `CORRECTED_DATA` column and revert to the original `DATA`. If you need to restore the `CORRECTED_DATA` to any previous stage in the self-calibration, use `applycal` again with the appropriate calibration tables.

BETA ALERT: In later patches we will change the tasks so that users need not worry what is contained in the MS scratch columns and how to fill them. CASA will handle that underneath for you!

For now, we refer the user back to the calibration chapter for a reminder on how to run the calibration tasks.

See the example of cleaning and self-calibrating the Jupiter 6cm continuum data given below in § 5.10.2.

5.10 Examples of Imaging

Here are two examples of imaging.

BETA ALERT: Note that the syntax has been changing recently and these may get out of date quickly!

5.10.1 Spectral Line Imaging with NGC5921

The following is an example use of `clean` on the NGC5921 VLA data that we calibrated in the previous Chapter (§ 4.8.1). This assumes you have already run that script and have all of the defined variable in your session, as well as the split calibrated ms files on disk.

The full NGC5921 example script can be found in Appendix F.1.

```
#####
# Imaging Script for NGC 5921
#
# Updated      STM 2008-06-11 (Beta Patch 2.0)
#
#          uvcontsub    --> <prefix>.ms.cont +
#                      |           <prefix>.ms.contsub
#                      v
#          clean      --> <prefix>.clean.image +
#                      |           <prefix>.clean.model +
#                      |           <prefix>.clean.residual
#                      v
#          exportfits   --> <prefix>.clean.fits
#                      |
#                      v
#####
#
# Set up some useful variables
# The prefix to use for all output files
prefix='ngc5921.usecase'

# The split MS filename
msfile = prefix + '.split.ms'

=====
#
# Done with calibration
# Now clean an image cube of N5921
#
print '--Clean--'
default('clean')

# Pick up our split source continuum-subtracted data
```

```
vis = srcsplitsms

# Make an image root file name
imname = prefix + '.clean'
imagename = imname

# Set up the output image cube
mode = 'channel'
nchan = 46
start = 5
width = 1

# This is a single-source MS with one spw
field = '0'
spw = ''

# Standard gain factor 0.1
gain = 0.1

# Set the output image size and cell size (arcsec)
imsize = [256,256]

# Do a simple Clark clean
psfmode = 'clark'

# If desired, you can do a Cotton-Schwab clean
# but will have only marginal improvement for this data
#imagermode='csclean'
imagermode=''

# Pixel size 15 arcsec for this data (1/3 of 45" beam)
# VLA D-config L-band
cell = [15.,15.]

# Fix maximum number of iterations
niter = 6000

# Also set flux residual threshold (in mJy)
threshold=8.0

# Set up the weighting
# Use Briggs weighting (a moderate value, on the uniform side)
weighting = 'briggs'
robust = 0.5

# Set a cleanbox +/-20 pixels around the center 128,128
mask = [108,108,148,148]

# If you don't want any clean box, then
#mask=''
#
```

```
# But if you had a cleanbox saved in a file, e.g. "regionfile.txt"
# you could use it:
#mask='regionfile.txt'
#
# and if you wanted to use interactive clean
#interactive=True

clean()

# Should find stuff in the logger like:
#
# Fitted beam used in restoration: 51.5643 by 45.6021 (arcsec)
#     at pa 14.5411 (deg)
#
# It will have made the images:
# -----
# ngc5921.usecase.clean.image
# ngc5921.usecase.clean.model
# ngc5921.usecase.clean.residual
# ngc5921.usecase.clean.boxclean.mask

clnimage = imname+'.image'

=====
#
# Done with imaging
# Now view the image cube of N5921
#
#print '--View image--'
#viewer(clnimage,'image')

=====
#
# Export the Final CLEAN Image as FITS
#
print '--Final Export CLEAN FITS--'
default('exportfits')

clnfits = prefix + '.clean.fits'

imagename = clnimage
fitsimage = clnfits

# Run asynchronously so as not to interfere with other tasks
# (BETA: also avoids crash on next importfits)
async = True

exportfits()

=====
```

5.10.2 Continuum Imaging of Jupiter

The following is an example use of interactive `clean` and self-calibration on the Jupiter 6cm VLA dataset. This assumes you have already flagged, calibrated, and split out that data and are ready to image, as well as having the split calibrated ms file `jupiter6cm.usecase.split.ms` on disk in your working directory. See § 4.8.2.

In this script, notice the different self-calibrations that were done each cycle, and how they gradually improved the image.

The full Jupiter example script can be found in Appendix F.2.

```
#####
# Imaging/Self-Calibration Script for Jupiter 6cm VLA
#
# Last Updated STM 2008-03-25 (Beta Patch 1.0)
#
#####

# Some variables defined
prefix='jupiter6cm.usecase'
srcsplits = prefix + '.split.ms'

#
#=====
# FIRST CLEAN / SELFCAL CYCLE
#=====
#
# Now clean an image of Jupiter
#
print '--Clean 1--'
default('clean')

# Pick up our split source data
vis = srcsplits

# Make an image root file name
imname1 = prefix + '.clean1'
imagename = imname1

# Set up the output continuum image (single plane mfs)
mode = 'mfs'
stokes = 'I'

# NOTE: current version field='' doesnt work
field = '*'

# Combine all spw
spw = ''
```

```
# This is D-config VLA 6cm (4.85GHz) obs
# Check the observational status summary
# Primary beam FWHM = 45'/f_GHz = 557"
# Synthesized beam FWHM = 14"
# RMS in 10min (600s) = 0.06 mJy (thats now, but close enough)

# Set the output image size and cell size (arcsec)
# 4" will give 3.5x oversampling
# 280 pix will cover to 2xPrimaryBeam
# clean will say to use 288 (a composite integer) for efficiency
clnalg = 'clark'
# if you want CS Clean
#clnmode = 'csclean'
clnmode = ''

clnimsize = [288,288]
clncell = [4.,4.]

psfmode = clnalg
imagermode = clnmode
imsize = clnimsize
cell = clncell

# NOTE: will eventually have an imadvise task to give you this
# information

# Standard gain factor 0.1
gain = 0.1

# Fix maximum number of iterations
niter = 10000

# Also set flux residual threshold (0.04 mJy)
# From our listobs:
# Total integration time = 85133.2 seconds
# With rms of 0.06 mJy in 600s ==> rms = 0.005 mJy
# Set to 10x thermal rms
threshold=0.05

# Note - we can change niter and threshold interactively
# during clean

# Set up the weighting
# Use Briggs weighting (a moderate value, on the uniform side)
weighting = 'briggs'
robust = 0.5

# No clean mask or box
mask = ''
```

```
# Use interactive clean mode
interactive=True

# Moderate number of iter per interactive cycle
npercycle = 100

clean()

# When the interactive clean window comes up, use the right-mouse
# to draw rectangles around obvious emission double-right-clicking
# inside them to add to the flag region. You can also assign the
# right-mouse to polygon region drawing by right-clicking on the
# polygon drawing icon in the toolbar. When you are happy with
# the region, click 'Done Flagging' and it will go and clean another
# 100 iterations. When done, click 'Stop'.

# Set up variables
clnimage1 = imname1+'.image'
clnmodel1 = imname1+'.model'
clnresid1 = imname1+'.residual'
clnmask1 = imname1+'.clean_interactive.mask'

#
#-----
#
# Look at this in viewer
viewer(clnimage1,'image')

# You can use the right-mouse to draw a box in the lower right
# corner of the image away from emission, the double-click inside
# to bring up statistics. Use the right-mouse to grab this box
# and move it up over Jupiter and double-click again. You should
# see stuff like this in the terminal:
#
# jupiter6cm.usecase.clean1.image      (Jy/beam)
#
# n          Std Dev      RMS        Mean      Variance      Sum
# 4712       0.003914    0.003927   0.0003205  1.532e-05   1.510
#
# Flux       Med |Dev|  IntQtlRng   Median     Min        Max
# 0.09417    0.002646    0.005294   0.0001885  -0.01125    0.01503
#
#
# On Jupiter:
#
# n          Std Dev      RMS        Mean      Variance      Sum
# 3640       0.1007      0.1027     0.02023    0.01015     73.63
#
# Flux       Med |Dev|  IntQtlRng   Median     Min        Max
# 4.592      0.003239    0.007120   0.0001329  -0.01396    1.060
#
```

```
# Estimated dynamic range = 1.060 / 0.003927 = 270 (poor)
#
# Note that the exact numbers you get will depend on how deep you
# take the interactive clean and how you draw the box for the stats.
#
#-----
#
# Self-cal using clean model
#
# Note: clean will have left FT of model in the MODEL_DATA column
# If you've done something in between, can use the ft task to
# do this manually.
#
print '--SelfCal 1--'
default('gaincal')

vis = srcsplitms

# New gain table
selfcaltab1 = srcsplitms + '.selfcal1'
caltable = selfcaltab1

# Don't need a-priori cals
selectdata = False
gaincurve = False
opacity = 0.0

# This choice seemed to work
refant = '11'

# Lets do phase-only first time around
gaintype = 'G'
calmode = 'p'

# Do scan-based solutions with SNR>3
solint = 'inf'
combine = ''
minsnr = 3.0

# Do not need to normalize (let gains float)
solnorm = False

gaincal()

#
#-----
#
# Correct the data (no need for interpolation this stage)
#
print '--ApplyCal--'
default('applycal')
```

```
vis = srcsplitms

gaintable = selfcaltab1

gaincurve = False
opacity = 0.0
field = ''
spw = ''
selectdata = False

calwt = True

applycal()

# Self-cal is now in CORRECTED_DATA column of split ms
#
#=====
# SECOND CLEAN / SELFCAL CYCLE
#=====
#
print '--Clean 2--'
default('clean')

vis = srcsplitms

imname2 = prefix + '.clean2'
imagername = imname2

field = '*'
spw = ''
mode = 'mfs'
gain = 0.1
niter = 10000
threshold=0.04

psfmode = clnalg
imagermode = clnmode
imsize = clnimsize
cell = clncell

weighting = 'briggs'
robust = 0.5

cleanbox = 'interactive'
npercycle = 100

clean()

# Set up variables
clnimage2 = imname2+'.image'
```

```

clnmodel2 = imname2+'.model'
clnresid2 = imname2+'.residual'
clnmask2  = imname2+'.clean_interactive.mask'

#
#-----
#
# Look at this in viewer
viewer(clnimage2,'image')

# jupiter6cm.usecase.clean2.image      (Jy/beam)
#
# n          Std Dev     RMS        Mean       Variance    Sum
# 5236      0.001389   0.001390   3.244e-05  1.930e-06  0.1699
#
# Flux      Med |Dev| IntQtlRng Median      Min        Max
# 0.01060   0.0009064  0.001823   -1.884e-05 -0.004015  0.004892
#
#
# On Jupiter:
#
# n          Std Dev     RMS        Mean       Variance    Sum
# 5304      0.08512    0.08629    0.01418    0.007245   75.21
#
# Flux      Med |Dev| IntQtlRng Median      Min        Max
# 4.695    0.0008142   0.001657   0.0001557  -0.004526  1.076
#
# Estimated dynamic range = 1.076 / 0.001389 = 775 (better)
#
# Note that the exact numbers you get will depend on how deep you
# take the interactive clean and how you draw the box for the stats.
#
#-----
#
# Next self-cal cycle
#
print '--SelfCal 2--'
default('gaincal')

vis = srcsplitsms

selfcaltab2 = srcsplitsms + '.selfcal2'
caltable = selfcaltab2

selectdata = False
gaincurve = False
opacity = 0.0
refant = '11'

# This time amp+phase on 10s timescales SNR>1
gaintype = 'G'

```

```
calmode = 'ap'
solint = 10.0
minsnr = 1.0
solnorm = False

gaincal()

#
# It is useful to put this up in plotcal
#
#-----
#
print '--PlotCal--'
default('plotcal')

tablein = selfcaltab2
multiplot = True
yaxis = 'amp'

plotcal()

# Use the Next button to iterate over antennas

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

yaxis = 'phase'

plotcal()

#
# You can see it is not too noisy.
#
# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

# Lets do some smoothing anyway.
#
#-----
#
# Smooth calibration solutions
#
print '--Smooth--'
default('smoothcal')

vis = srcsplitsms

tablein = selfcaltab2
```

```
smoothcaltab2 = srcsplitms + '.smoothcal2'
caltable = smoothcaltab2

# Do a 30s boxcar average
smoothtype = 'mean'
smoothtime = 30.0

smoothcal()

# If you put into plotcal you'll see the results
# For example, you can grab the inputs from the last
# time you ran plotcal, set the new tablename, and plot!
#run plotcal.last
#tablein = smoothcaltab2
#plotcal()

#
#-----
#
# Correct the data
#
print '--ApplyCal--'
default('applycal')

vis = srcsplitms

gaintable = smoothcaltab2

gaincurve = False
opacity = 0.0
field = ''
spw = ''
selectdata = False
calwt = True

applycal()

#
#=====
# THIRD CLEAN / SELFCAL CYCLE
#=====
#
print '--Clean 3--'
default('clean')

vis = srcsplitms

imname3 = prefix + '.clean3'
imagename = imname3

field = '*'  

```

```

spw = ''
mode = 'mfs'
gain = 0.1
niter = 10000
threshold=0.04

psfmode = clnalg
imagermode = clnmode
imsize = clnimsize
cell = clncell

weighting = 'briggs'
robust = 0.5

cleanbox = 'interactive'
npercycle = 100

clean()

# Cleans alot deeper
# You can change the npercycle to larger numbers
# (like 250 or so) as you get deeper also.

# Set up variables
clnimage3 = imname3+'.image'
clnmodel3 = imname3+'.model'
clnresid3 = imname3+'.residual'
clnmask3 = imname3+'.clean_interactive.mask'

#
#-----
#
# Look at this in viewer
viewer(clnimage3,'image')

# jupiter6cm.usecase.clean3.image      (Jy/beam)
#
# n          Std Dev       RMS        Mean      Variance     Sum
# 5848       0.001015    0.001015   -4.036e-06  1.029e-06  -0.02360
#
# Flux      Med |Dev| IntQtlRng Median      Min       Max
# -0.001470  0.0006728  0.001347   8.245e-06  -0.003260  0.003542
#
#
# On Jupiter:
#
# n          Std Dev       RMS        Mean      Variance     Sum
# 6003       0.08012     0.08107    0.01245    0.006419    74.72
#
# Flux      Med |Dev| IntQtlRng Median      Min       Max
# 4.653      0.0006676  0.001383   -1.892e-06  -0.002842  1.076

```

```
#  
# Estimated dynamic range = 1.076 / 0.001015 = 1060 (even better!)  
#  
# Note that the exact numbers you get will depend on how deep you  
# take the interactive clean and how you draw the box for the stats.  
#  
# Greg Taylor got 1600:1 so we still have some ways to go  
# This will probably take several more careful self-cal cycles.  
  
# Set up final variables  
clnimage = clnimage3  
clnmodel = clnmodel3  
clnresid = clnresid3  
clnmask = clnmask3  
  
#=====  
#  
# Export the Final CLEAN Image as FITS  
#  
print '--Final Export CLEAN FITS--'  
default('exportfits')  
  
clnfits = prefix + '.clean.fits'  
  
imagename = clnimage  
fitsimage = clnfits  
  
# Run asynchronously so as not to interfere with other tasks  
# (BETA: also avoids crash on next importfits)  
async = True  
  
exportfits()  
  
#=====  
#  
# Export the Final Self-Calibrated Jupiter data as UVFITS  
#  
print '--Final Export UVFITS--'  
default('exportuvfits')  
  
caluvfits = prefix + '.selfcal.uvfits'  
  
vis = srcsplitsms  
fitsfile = caluvfits  
  
# The self-calibrated data is in the CORRECTED_DATA column  
datacolumn = 'corrected'  
  
# Write as a multisource UVFITS (with SU table)  
# even though it will have only one field in it  
multisource = True
```

```
# Run asynchronously so as not to interfere with other tasks
# (BETA: also avoids crash on next importuvfits)
async = True

exportuvfits()

#=====
```

Chapter 6

Image Analysis

Once data has been calibrated (and imaged in the case of synthesis data), the resulting image or image cube must be displayed or analyzed in order to extract quantitative information, such as statistics or moment images. In addition, there need to be facilities for the coordinate conversion of images for direct comparison. We have assembled a skeleton of image analysis tasks for this release. Many more are still under development.

The image analysis tasks are:

- **imhead** — summarize and manipulate the “header” information in a CASA image (§ 6.2)
- **imcontsub** — perform continuum subtraction on a spectral-line image cube (§ 6.3)
- **imfit** — image plane Gaussian component fitting (§ 6.4)
- **immath** — perform mathematical operations on or between images (§ 6.5)
- **immoments** — compute the moments of an image cube (§ 6.6)
- **imstat** — calculate statistics on an image or part of an image (§ 6.7)
- **imval** — extract the data and mask values from a pixel or region of an image (§ 6.8)
- **imregrid** — regrid an image onto the coordinate system of another image (§ 6.9)
- **importfits** — import a FITS image into a CASA *image* format table (§ 6.10.2)
- **exportfits** — write out an image in FITS format (§ 6.10.1)

There are other tasks which are useful during image analysis. These include:

Inside the Toolkit:

Image analysis is handled in the **ia** tool. Many options exist there, including region statistics and image math. See § 6.11 below for more information.

- **viewer** — there are useful region statistics and image cube slice and profile capabilities in the viewer (§ 7)

We also give some examples of using the CASA Toolkit to aid in image analysis (§ 6.11).

6.1 Common Image Analysis Task Parameters

We now describe some sets of parameters are common to the image analysis. These should behave the same way in any of the tasks described in this section that they are found in.

6.1.1 Region Selection (box)

Region selection in the image analysis tasks is controlled by a set of parameters that allow you to specify regions of an image.

Currently, the only available region selection is using the **box** parameter

```
box      =      ''    # Select one or more box regions

#       string containing blcx,bcly,trcx,trcy

#       A box region in the directional portion of an image.
#       The directional portion of an image are the axes for right
#       ascension and declination, for example. Boxes are specified
#       by their bottom-left corner (blc) and top-right corner (trc)
#       as follows: blcx, blcy, trcx, trcy;
#       ONLY pixel values acceptable at this time.
#       Default: none (all);
#       Example: box='0,0,50,50'
#       Example: box='[10,20,30,40];[100,100,150,150]',
```

To get help on **box**, see the in-line help

```
help(par.box)
```

6.1.2 Plane Selection (chans, stokes)

The channel, frequency, or velocity plane(s) of the image is chosen using the **chans** parameter:

```
chans      =      ''    # Select the channel(spectral) range

#       string containing channel range

#       immath, imstat, and imcontsub - takes a string listing
```

```

#      of channel numbers, velocity, and/or frequency
#      numbers, much like the spw parameter
#      Only channel numbers acceptable at this time.
#      Default: none (all);
#      Example: chans='3~20'
#                  chans="0,3,4,8"
#                  chans="3~20,50,51"

```

The polarization plane(s) of the image is chosen with the **stokes** parameter:

```

stokes      =      ''    # Stokes params to image (I,IV,IQU,IQUV)

#      string containing Stokes selections

#      Stokes parameters to image, may or may not be separated
#      by commas but best if you use commas.
#      Default: none (all); Example: stokes='IQUV';
#      Example:stokes='I,Q'
#      Options: 'I','Q','U','V',
#                  'RR','RL','LR','LL',
#                  'XX','YX','XY','YY',...

```

To get help on these parameters, see the in-line help

```

help(par.chans)
help(par.stokes)

```

Sometimes, as in the **immoments** task, the channel/plane selection is generalized to work on more than one axis type. In this case, the **planes** parameter is used. This behaves like **chans** in syntax.

6.1.3 Lattice Expressions (expr)

Lattice expressions are strings that describe operations on a set of input images to form an output image. These strings use the *Lattice Expression Language* (LEL). LEL syntax is described in detail in AIPS++ Note 223

<http://aips2.nrao.edu/docs/notes/223/223.html>

BETA ALERT: This document was written in the context of glish-based AIPS++ and is not yet updated to CASA syntax (see below).

The **expr** string contains the LEL expression:

```

expr      =      ''    # Mathematical expression using images

#      string containing LEL expression

```

```

#      A mathematical expression, with image file names.
#      image file names must be enclosed in double quotes ("")
#      Default: none
#      Example: expr='min("image2.im")+(2*max("image1.im"))'
#
#      Available functions in the expr and mask parameters:
#      PI(), E(), SIN(), SINH(), ASIN(), COS(), COSH(), TAN(), TANH(),
#      ATAN(), EXP(), LOG(), LOG10(), POW(), SQRT(), COMPLEX(), CONJ()
#      REAL(), IMAG(), ABS(), ARG(), PHASE(), AMPLITUDE(), MIN(), MAX()
#      ROUND(), ISGN(), FLOOR(), CEIL(), REBIN(), SPECTRALINDEX(), PA(),
#      IIF(), INDEXIN(), REPLACE(), ...

```

For examples using LEL `expr`, see § 6.5.1 below.

BETA ALERT: As of Patch 2, LEL expressions use 0-based indices.

6.1.4 Masks (`mask`)

The `mask` string contains a LEL expression (see § 6.1.3 above). This string can be an on-the-fly (OTF) mask expression or refer to an image pixel mask.

```

mask      =      ''    # Mask to be applied to the images

#      string containing LEL expression

#      Name of mask applied to each image in the calculation
#      Default '' means no mask;
#      Example: mask='ngc5921.clean.cleanbox.mask">0.5'
#                  mask='mask(ngc5921.clean.cleanbox.mask)'

```

Note that the mask file supplied in the `mask` parameter must have the same shape, same number of axes and same axes length, as the images supplied in the `expr` parameter, with one exception. The mask may be missing some of the axes — if this is the case then the mask will be expanded along these axes to become the same shape.

For examples using `mask`, see § 6.5.2 below.

6.2 Image Header Manipulation (`imhead`)

To summarize and change keywords and values in the “header” of your image, use the `imhead` task. Its inputs are:

```

# imhead :: Lists, gets and puts image header parameters
imagename      =      ''    # Name of input image file
mode           =  'summary'  # Options: get, put, summary, list, stats
async          =      False

```

The `mode` parameter controls the operation of `imhead`.

Setting `mode='summary'` will print out a summary of the image properties and the header to the logger.

Setting `mode='list'` prints out a list of the header keywords and values to the terminal.

The `mode='get'` allows the user to retrieve the current value for a specified keyword `hditem`:

```
mode      =      'get'  # imhead options: get, put, summary, and list
hditem   =      ''    # Header item to get or set
```

Note that to catch this value, you need to assign it to a Python variable:

```
# Using the functional call method
myvalue = imhead('ngc5921.clean.image', mode='get', hditem='beam')
# Using globals
default('imhead')
imagename = 'ngc5921.clean.image'
mode = 'get'
hditem = 'beam'
myvalue = imhead()
```

See § 1.3.3 for more on return values.

BETA ALERT: This has changed in Patch 2.0. In previous versions `hdvalue` was an output variable for `mode='get'`.

The `mode='put'` allows the user to replace the current value for a given keyword `hditem` with that specified in `hdvalue`. There are two sub-parameters that are opened by this option:

```
mode      =      'put'  # imhead options: get, put, summary, and list
hditem   =      ''    # Header item to get or set
hdvalue  =      ''    # Value to set Header Item (hditem) to
```

WARNING: Be careful when using `mode='put'`. This task does no checking on whether the values you specify (e.g. for the axes types) are valid, and you can render your image invalid. Make sure you know what you are doing when using this option!

6.2.1 Examples for `imhead`

For example,

```
CASA <1>: imhead('ngc5921.usecase.clean.image', 'summary')
Summary information is listed in logger
```

prints in the logger:

```
Opened image ngc5921.usecase.clean.image
```

```
Image name      : ngc5921.usecase.clean.image
Object name     :
Image type      : PagedImage
Image quantity   : Intensity
Pixel mask(s)    : None
Region(s)       : None
Image units     : Jy/beam
Restoring Beam  : 51.5254 arcsec, 45.5987 arcsec, 14.6417 deg
```

```
Direction reference : J2000
Spectral reference  : LSRK
Velocity type       : RADIO
Rest frequency      : 1.42041e+09 Hz
Pointing center     : 15:22:00.000000 +05.04.00.000000
Telescope          : VLA
Observer            : TEST
Date observation    : 1995/04/13/00:00:00
```

Axis	Coord	Type	Name	Proj	Shape	Tile	Coord value at pixel	Coord incr	Units	
0	0	Direction	Right Ascension	SIN	256	64	15:22:00.000	128.00	-1.500000e+01 arcsec	
1	0	Direction	Declination	SIN	256	64	+05.04.00.000	128.00	1.500000e+01 arcsec	
2	1	Stokes	Stokes			1	1	I		
3	2	Spectral	Frequency			46	8	1.41281e+09	0.00	2.441406e+04 Hz
			Velocity					1603.56	0.00	-5.152860e+00 km/s

If you choose mode='list', you get the summary in the logger and a listing of keywords and values to the terminal:

```
CASA <2>: imhead('ngc5921.usecase.clean.image',mode='list')
Available header items to modify:
```

```
General --
-- object N5921_2
-- telescope VLA
-- observer TEST
-- epoch "1995/04/13/00:00:00"
Retrieving restfreqency
-- restfrequency "1420405752.0Hz"
-- projection "SIN"
-- bunit Jy/beam
-- beam 51.5204238892arcsec, 45.598236084arcsec, 14.6546726227deg
-- min -0.0104833962396
-- max 0.0523551553488
axes --
-- ctype1 Right Ascension
-- ctype2 Declination
-- ctype3 Stokes
-- ctype4 Frequency
```

```

crpix --
-- crpix1 128.0
-- crpix2 128.0
-- crpix3 0.0
-- crpix4 0.0
crval --
-- crval1 4.02298392585 rad
-- crval2 0.0884300154344 rad
-- crval3 1.0
-- crval4 1412808153.26 Hz
cdelt --
-- cdelt1 -7.27220521664e-05 rad
-- cdelt2 7.27220521664e-05 rad
-- cdelt3 1.0
-- cdelt4 24414.0625 Hz
units --
-- cunit1 rad
-- cunit2 rad
-- cunit3
-- cunit4 Hz

```

The values for these keywords can be queried using `mode='get'`. This opens sub-parameters

```

mode          =      'get'   #  Options: get, put, summary, list, stats
hditem       =      ''     #  header item to get or put

```

Note that the `mode='get'` option returns a Python dictionary containing the current value of the `hditem`. This dictionary can be manipulated in Python in the usual manner. For example, continuing the above example:

```

CASA <3>: imagename = 'ngc5921.usecase.clean.image'
CASA <4>: mode = 'get'
CASA <5>: hditem = 'observer'
CASA <6>: hdvalue = imhead()
***  

observer :: TEST  

CASA <7>: print hdvalue
TEST

```

You can set the values for these keywords using `mode='put'`. This opens sub-parameters

```

mode          =      'put'   #  Options: get, put, summary, list, stats
hditem       =      ''     #  header item to get or put
hdvalue      =      ''     #  header value to set (for mode=put)

```

Continuing the example further:

```
CASA <8>: mode = 'put'
CASA <9>: hdvalue = 'CASA'
CASA <10>: imhead()

CASA <11>: mode = 'list'
CASA <12>: imhead()
Available header items to modify:
```

```
General --
    -- object
    -- telescope VLA
    -- observer CASA
...
...
```

6.3 Continuum Subtraction on an Image Cube (imcontsub)

One method to separate line and continuum emission in an image cube is to specify a number of line-free channels in that cube, make a linear fit to the visibilities in those channels, and subtract the fit from the whole cube. Note that the task `uvcontsub` serves a similar purpose; see § 4.7.4 for a synopsis of the pros and cons of either method.

The `imcontsub` task will subtract a polynomial baseline fit to the specified channels from an image cube.

The default inputs are:

```
# imcontsub :: Continuum subtraction on images
imagingname = ''      # Name of the input image
linefile = ''          # Output line image file name
contfile = ''          # Output continuum image file name
fitorder = 0           # Polynomial order for the continuum estimation
box = ''               # Select one or more box regions
chans = ''             # Select the channel(spectral) range
stokes = ''            # Stokes params to image (I,IV,IQU,IQUV)
async = False
```

Region selection using `box` is detailed in § 6.1.1.

Image cube plane selection using `chans` and `stokes` are described in § 6.1.2.

BETA ALERT: `imcontsub` has issues when the image does not contain a spectral or stokes axis. Errors are generated when run on an image missing one or both of these axes. You will need to use the Toolkit (e.g. the `ia.adddegaxes` method) to add degenerate missing axes to the image.

6.3.1 Examples for `imcontsub`)

For example, in a cube named `cube2403` with 97 spectral line channels it has been determined that channels 0 through 17 and channels 79 through 96 are line-free. Then:

```

default('imcontsub')

imagename = 'cube2403'
linefile  = 'line2403'
contfile  = 'cont2403'
fitorder  = 1
chan      = '0~17, 79~96'
stokes    = 'I'

imcontsub()

```

will fit a first order polynomial to the visibilities in channels 0 through 17 and 79 through 96, subtract that fit from the input cube `cube2403` and write the result to the cube `line2403`. The fitted continuum itself is written to the cube `cont2403` and, if so desired, can be averaged to create a single high signal-to-noise continuum image.

6.4 Image-plane Component Fitting (imfit)

The inputs are:

```

# imfit :: Fit 2-dimentional Gaussian(s) on image region(s)
imagename      = ''      # Name of the input image
box            = ''      # Specify one or more box regions for the fit.
region         = ''      # Image Region. Use viewer
mask           = ''      # Mask to be applied to the image
fixed          = ''      # Pparameters to hold fixed (not implemented).
usecleanbeam   = False   # Estimate the true source size.
estfile        = ''      # Initial estimate of parameters (Not yet implemented).
residfile     = ''      # Residual image removing fit. (Not yet implemented)
async          = False   # If true, run asynchronously

```

BETA ALERT: This task is new to Patch 2.0 and has not been as extensively tested as the other tasks. Currently, it can fit only a single Gaussian component. This restriction will be lifted in future patches.

6.5 Mathematical Operations on an Image (immath)

The inputs are:

```

# immath :: Perform math operations on images
outfile = ''      # File where the output is saved
mode   = 'evalexpr' # mode for math operation (evalexpr, spix, pola, poli)
exp    = ''      # Mathematical expression using images

mask   = ''      # Mask to be applied to the images

```

```

region =      ''    # File path which contains an Image Region
box   =      ''    # Select one or more box regions in the input images
chans =      ''    # Select the channel(spectral) range
stokes =      ''    # Stokes params to image (I,IV,IQU,IQUV)
async  =     False  # If true run asynchronously

```

In all cases, `outfile` must be supplied with the name of the new output file to create.

The `mode` parameter selects what `immath` is to do.

The default `mode='evalexpr'` lets the user specify a mathematical operation to carry out on one or more input images. The sub-parameter `expr` contains the Lattice Expression Language (LEL) string describing the image operations. See § 6.1.3 for more on LEL strings and the `expr` parameter.

Mask specification is done using the `mask` parameter. This can optionally contain an on-the-fly mask expression (in LEL) or point to an image with a pixel mask. See § 6.1.4 for more on the use of the `mask` parameter. See also § 6.1.3 for more on LEL strings.

Region selection is carried out through the `region` and `box` parameters. See § 6.1.1 for more on region selection.

Image plane selection is controlled by `chans` and `stokes`. See § 6.1.2 for details on plane selection.

BETA ALERT: As of Patch 2, LEL expressions (as in `expr`) use 0-based array indices.

6.5.1 Examples for `immath`

The following are examples using `immath`. Note that the image names in the `expr` are assumed to refer to existing image files in the current working directory.

6.5.1.1 Simple math

Double all values in an image:

```
immath( expr='myimage.im'*2 , outfile='double.im' )
```

Take the sine of an image and add it to another:

```
immath(expr='SIN("image2.im")+"image1.im" , outfile='newImage.im')
```

Note that the two input images used in `expr` need to be the same size.

Add only the plane associated with the 'V' Stokes value and the first channel together in two images:

```
immath(expr='image1+"image2" , chans='1' , stokes='V')
```

Select a single plane (the 5th channel) of the 3-D cube and subtract it from the original image:

```

default('immath')
outfile='ngc5921.chan5.image'
expr='ngc5921.clean.image'
chans='5'
go

default('immath')
outfile='ngc5921.clean.sub5.image'
expr='ngc5921.clean.image"-ngc5921.chan5.image",
go

```

Note that in this example the 2-D plane gets expanded out and the values are applied to each plane in the 3-D cube.

Select and save the inner 1/4 of an image for channels 40,42,44 as well as channels 10 and below:

```

default('immath')
expr='ngc5921.clean.image'
box='64,64,192,192'
chans='<10;40,42,44'
outfile='ngc5921.clean.inner'
go

```

BETA ALERT: Note that if chan selects more than one channel then the output image has a number of channels given by the span from the lowest and highest channel selected in chan. In the example above, it will have 45 channels. The ones not selected will be masked in the output cube. If we had set

```
chans = '40,42,44'
```

then there would be 5 output channels corresponding to channels 40,41,42,43,44 of the MS with 41,43 masked. Also, the chans='<10' selects channels 0–9.

Note that the chans syntax allows the operators '<', '<=', '>', '>'. For example,

```

chans = '<17,>79'
chans = '<=16,>=80'

```

do the same thing.

Divide an image by another, making sure we are not dividing by zero:

```

default('immath')
expr="orion.image"/iif("my.image"==0,1.0,"my.image")
outfile='my_orion.image'
go

```

Note that this will put 1.0 in the output image where the divisor image is zero. You can also just mask below a certain level in the divisor image, e.g.

```
default('immath')
expr='orion.image"/"my.image"["my.image">0.1]'
outfile='my_orion.image'
go
```

6.5.1.2 Polarization manipulation

Create a polarized intensity image from a IQUV image:

```
default( 'immath')
outfile='I.im'; expr='3C138_pcal"'; stokes='I'; go();
outfile='Q.im'; expr='3C138_pcal"'; stokes='Q'; go();
outfile='U.im'; expr='3C138_pcal"'; stokes='U'; go();
outfile='V.im'; expr='3C138_pcal"'; stokes='V'; go();
outfile='pol_intensity',
stokes='',
expr='sqrt("I.im""*I.im" + "Q.im""*Q.im" + "U.im""*U.im" + "V.im""*V.im" )',
go
```

6.5.1.3 Primary beam correction/uncorrection

In a script using `mode='evalexpr'`, you might want to assemble the string for `expr` using string variables that contain the names of files. Since you need to include quotes inside the `expr` string, use a different quote outside (or escape the string, e.g. `'`). For example, to do a primary beam correction on the NGC5921 cube,

```
imname = 'ngc5921.usecase.clean'
imagename = imname
...
clean()

default('immath')
clnimage = imname + '.image'
pbimage = imname + '.flux'
pbcorimage = imname + '.pbcor'

outfile = pbcorimage
expr=""'+clnimage+'/'+'pbimage+',['+'pbimage+','>0.1]"

immath()
```

Note that we did not use a `minpb` when we cleaned, so we use the trick above to effectively set a cutoff in the primary beam `.flux` image of 0.1.

For more on LEL strings, see AIPS++ Note 223

<http://aips2.nrao.edu/docs/notes/223/223.html>

or in § 6.1.3 above.

6.5.1.4 Spectral analysis

One can make an integrated 1-d spectrum over the whole image by rebinning (integrating) over the two coordinate axes in a specified region. For example, using the NGC5921 image cube (with 46 channels):

```
immath(outfile="ngc5921.demo.spectrum.all",mode="evalexpr",
      expr="rebin('ngc5921.demo.clean.image',[256,256,1,1])")
```

The resulting image has shape [1,1,1,46] as desired. You can view this with the `viewer` and will see a 1-D spectrum.

One can also do this with a box:

```
immath(outfile="ngc5921.demo.spectrum.box",mode="evalexpr",
      expr="rebin('ngc5921.demo.clean.image',[256,256,1,1])",box="118,118,141,141")
```

BETA ALERT: One cannot specify a region without it collapsing the channel axis (even when told to use all axes or channels).

BETA ALERT: The following uses the toolkit (§ 6.11). You can make an ascii file containing only the values (no other info though):

```
ia.open('ngc5921.demo.spectrum.all')
ia.toASCII('ngc5921.demo.spectrum.all.ascii')
```

You can also extract to a record inside Python:

```
myspec = ia.torecord()
```

which you can then manipulate in Python.

6.5.2 Using masks in `immath`

The `mask` parameter is used inside `immath` to apply a mask to all the images used in `expr` before calculations are done (if you are curious, it uses the `ia.subimage` tool method to make virtual images that are then input in the LEL to the `ia.imagecalc` method).

For example, lets assume that we have made a single channel image using `clean` for the NGC5921 data (see § 5.10.1).

```
default('clean')

vis = 'ngc5921.ms.contsub'
imagename = 'ngc5921.chan21.clean'
mode = 'channel'
nchan = 1
```

```

start = 21
step = 1

field = '0'
spw = ''
imsize = [256,256]
cell = [15.,15.]
alg = 'clark'
gain = 0.1
niter = 6000
threshold=8.0
weighting = 'briggs'
rmode = 'norm'
robust = 0.5

mask = ''
cleanbox = [108,108,148,148]

clean()

```

There is now a file 'ngc5921.chan21.clean.cleanbox.mask' that is an image with values 1.0 inside the `cleanbox` region and 0.0 outside.

We can use this to mask the clean image:

```

default('immath')
expr='ngc5921.chan21.clean.image',
mask='ngc5921.chan21.clean.cleanbox.mask">0.5'
outfile='ngc5921.chan21.clean.imasked'
go

```

Note that there are also *pixel masks* that can be contained in each image. These are Boolean masks, and are implicitly used in the calculation for each image in `expr`. If you want to use the mask in a different image not in `expr`, try it in `mask`:

```

# First make a pixel mask inside ngc5921.chan21.clean.cleanbox.mask
ia.open('ngc5921.chan21.clean.cleanbox.mask')
ia.calcmask('ngc5921.chan21.clean.cleanbox.mask">0.5')
ia.summary()
ia.close()
# There is now a 'mask0' mask in this image as reported by the summary

# Now apply this pixel mask in immath
default('immath')
expr='("ngc5921.chan21.clean.image"',
mask='mask(ngc5921.chan21.clean.cleanbox.mask)',
outfile='ngc5921.chan21.clean.imasked1'
go

```

Note that nominally the axes of the mask must be congruent to the axes of the images in `expr`. However, one exception is that the image in `mask` can have *fewer* axes (but not axes that exist but

are of the wrong lengths). In this case `immath` will extend the missing axes to cover the range in the images in `expr`. Thus, you can apply a mask made from a single channel to a whole cube.

```
# drop degenerate stokes and freq axes from
#    ngc5921.chan21.clean.cleanbox.mask
ia.open('ngc5921.chan21.clean.cleanbox.mask')
im2 = ia.subimage(outfile='ngc5921.chan21.mymask',dropdeg=True)
im2.summary()
im2.close()
ia.close()
# ngc5921.chan21.mymask has only RA and Dec axes

# Now apply this mask to the whole cube
default('immath')
expr='("ngc5921.clean.image"',
mask='"ngc5921.chan21.mymask">0.5',
outfile='ngc5921.cube.imasked'
go
```

For more on masks as used in LEL, see

<http://aips2.nrao.edu/docs/notes/223/223.html>

or in § 6.1.4 above.

6.6 Computing the Moments of an Image Cube (`immoments`)

For spectral line datasets, the output of the imaging process is an `image cube`, with a frequency or velocity channel axis in addition to the two sky coordinate axes. This can be most easily thought of as a series of `image planes` stacked along the spectral dimension.

A useful product to compute is to collapse the cube into a *moment* image by taking a linear combination of the individual planes:

$$M_m(x_i, y_i) = \sum_k^N w_m(x_i, y_i, v_k) I(x_i, y_i, v_k) \quad (6.1)$$

for pixel i and channel k in the cube I . There are a number of choices to form the m moment, usually approximating some polynomial expansion of the intensity distribution over velocity mean or sum, gradient, dispersion, skew, kurtosis, etc.). There are other possibilities (other than a weighted sum) for calculating the image, such as median filtering, finding minima or maxima along the spectral axis, or absolute mean deviations. And the axis along which to do these calculation need not be the spectral axis (ie. do moments along Dec for a RA-Velocity image). We will treat all of these as generalized instances of a “moment” map.

The `immoments` task will compute basic moment images from a cube. The default inputs are:

```
# immoments :: Compute moments of an image cube:

imagename      =      ''      # Input image name
moments        =      [0]      # List of moments to compute
axis           =      3      # Axis for moment calculation
planes          =      ''      # Set of planes/channels to use for moment(e.g,"3~20,21")
includepix     =      [-1]     # Range of pixel values to include
excludepix    =      [-1]     # Range of pixel values to exclude
outfile         =      ''      # Output image file name (or root for multiple moments)
async          =      False    # if True, run in the background, prompt is freed
```

This task will operate on the input file given by `imagename` and produce a new image or set of images based on the name given in `outfile`.

The `moments` parameter chooses which moments are calculated. The choices for the operation mode are:

```
moments=-1 - mean value of the spectrum
moments=0 - integrated value of the spectrum
moments=1 - intensity weighted coordinate; traditionally used to get
            'velocity fields'
moments=2 - intensity weighted dispersion of the coordinate; traditionally
            used to get 'velocity dispersion'
moments=3 - median of I
moments=4 - median coordinate
moments=5 - standard deviation about the mean of the spectrum
moments=6 - root mean square of the spectrum
moments=7 - absolute mean deviation of the spectrum
moments=8 - maximum value of the spectrum
moments=9 - coordinate of the maximum value of the spectrum
moments=10 - minimum value of the spectrum
moments=11 - coordinate of the minimum value of the spectrum
```

The meaning of these is described in the CASA Reference Manual:

<http://casa.nrao.edu/docs/casaref/image.moments.html>

If a single moment is chosen, the `outfile` specifies the exact name of the output image. If multiple `moments` are chosen, then `outfile` will be used as the root of the output filenames, which will get different suffixes for each moment. For example, if `moments=[0,1]` and `outfile='ngc5921.usecase.moments'` then the output image names will be '`ngc5921.usecase.moments.integrated`' and '`ngc5921.usecase.moments.wt`' respectively.

The `axis` parameter sets the axis along which the moment is “collapsed” or calculated. This is a 0-based index. Usually this is either the third (`axis=2`) or fourth (`axis=3`) axis of the image cube.

The `planes` parameter sets the range of image cube planes (along the specified `axis`) to include in the moment calculation. **BETA ALERT:** As of Patch 2, the `planes` parameter is now 0-based, as per other specifications.

The `includepix` and `excludepix` parameters are used to set ranges for the inclusion and exclusion of pixels based on values. For example, `includepix=[0.05,100.0]` will include pixels with values from 50 mJy to 1000 Jy, and `excludepix=[100.0,1000.0]` will exclude pixels with values from 100 to 1000 Jy.

6.6.1 Hints for using (`immoments`)

In order to make an unbiased moment-0 image, do not put in any thresholding using `includepix` or `excludepix`. This is so that the (presumably) zero-mean noise fluctuations in off-line parts of the image cube will cancel out. If your image has large biases, like a pronounced clean bowl due to missing large-scale flux, then your moment-0 image will be biased also. It will be difficult to alleviate this with a threshold, but you can try.

To make a usable moment-1 (or higher) image, on the other hand, it is critical to set a reasonable threshold to exclude noise from being added to the moment maps. Something like a few times the rms noise level in the usable planes seems to work (put into `includepix` or `excludepix` as needed). Also use `planes` to ignore channels with bad data.

6.6.2 Examples using (`immoments`)

For example, using the NGC5921 example (§ F.1):

```
default('immoments')

imagine = 'ngc5921.usecase.clean.image'

# Do first and second moments
moments = [0,1]

# Need to mask out noisy pixels, currently done
# using hard global limits
excludepix = [-100,0.009]

# Include all planes
planes = ''

# Output root name
outfile = 'ngc5921.usecase.moments'

immoments()

# It will have made the images:
# -----
# ngc5921.usecase.moments.integrated
# ngc5921.usecase.moments.weighted_coord
```

Other examples of NGC2403 (a moment zero image of a VLA line dataset) and NGC4826 (a moment one image of a BIMA CO line dataset) are shown in Figure 6.1.




Figure 6.1: NGC2403 VLA moment zero (left) and NGC4826 BIMA moment one (right) images as shown in the `viewer`.

BETA ALERT: We are working on improving the thresholding of planes beyond the global cutoffs in `includepix` and `excludepix`.

6.7 Computing image statistics (`imstat`)

The `imstat` task will calculate statistics on a region of an image, and return the results as a return value in a Python dictionary.

The inputs are:

```
# imstat :: Displays statistical information on an image or image region
imagingname = ''      # Name of the input image
box         = ''      # Select one or more box regions
chans       = ''      # Select the channel(spectral) range
stokes      = ''      # Stokes params to image (I,IV,IQU,IQUV)
async       = False
```

Region selection is carried out through the `box` parameter. See § 6.1.1 for more on region selection using this parameter.

Image plane selection is controlled by `chans` and `stokes`. See § 6.1.2 for details on plane selection.

BETA ALERT: As with `imcontsub`, if the image is missing one or more of the stokes and spectral axes, then `imstat` will fail. See the discussion of the workaround for this in § 6.3.

6.7.1 Using the task return value

The contents of the return value of `imstat` are in a Python dictionary of key-value sets. For example,

```
xstat = imstat()
```

will assign this to the Python variable `xstat`. **BETA ALERT:** The return of the statistics as a return value (and not a global variable) is new to Patch 2.0.

The keys for `xstat` are then:

KEYS	
<code>blc</code>	- absolute PIXEL coordinate of the bottom left corner of the bounding box surrounding the selected region
<code>blcf</code>	- Same as <code>blc</code> , but uses WORLD coordinates instead of pixels
<code>trc</code>	- the absolute PIXEL coordinate of the top right corner of the bounding box surrounding the selected region
<code>trcf</code>	- Same as <code>trc</code> , but uses WORLD coordinates instead of pixels
<code>flux</code>	- the integrated flux density if the beam is defined and the if brightness units are \$Jy/beam\$
<code>npts</code>	- the number of unmasked points used
<code>max</code>	- the maximum pixel value
<code>min</code>	- minimum pixel value
<code>maxpos</code>	- absolute PIXEL coordinate of maximum pixel value
<code>maxposf</code>	- Same as <code>maxpos</code> , but uses WORLD coordinates instead of pixels
<code>minpos</code>	- absolute pixel coordinate of minimum pixel value
<code>minposf</code>	- Same as <code>minpos</code> , but uses WORLD coordinates instead of pixels
<code>sum</code>	- the sum of the pixel values: \$\sum I_i\$
<code>sumsq</code>	- the sum of the squares of the pixel values: \$\sum I_i^2\$
<code>mean</code>	- the mean of pixel values: $ar\{I\} = \sum I_i / n$
<code>sigma</code>	- the standard deviation about the mean: $\sigma = (\sum I_i - ar\{I\})^2 / (n-1)$
<code>rms</code>	- the root mean square: $\sqrt{\sum I_i^2 / n}$
<code>median</code>	- the median pixel value (if robust=T)
<code>medabsdevmed</code>	- the median of the absolute deviations from the median (if robust=T)
<code>quartile</code>	- the inter-quartile range (if robust=T). Find the points which are 25% largest and 75% largest (the median is 50% largest), find their difference and divide that difference by 2.

For example, an `imstat` call might be

```
default('imstat')
imagename = 'ngc5921.usecase.clean.image' # The NGC5921 image cube
box       = '108,108,148,148'             # 20 pixels around the center
chans    = '21'                           # channel 21
```

```
xstat = imstat()
```

In the terminal window, `imstat` reports:

```
Statistics on  ngc5921.usecase.clean.image
```

Region ---

```
-- bottom-left corner (pixel) [blc]: [108, 108, 0, 21]
-- top-right corner (pixel) [trc]: [148, 148, 0, 21]
-- bottom-left corner (world) [blcf]: 15:22:20.076, +04.58.59.981, I, 1.41332e+09Hz
-- top-right corner( world) [trcf]: 15:21:39.919, +05.08.59.981, I, 1.41332e+09Hz
```

Values --

```
-- flux [flux]: 0.111799236126
-- number of points [npts]: 1681.0
-- maximum value [max]: 0.029451508075
-- minimum value [min]: -0.00612453464419
-- position of max value (pixel) [maxpos]: [124, 131, 0, 21]
-- position of min value (pixel) [minpos]: [142, 110, 0, 21]
-- position of max value (world) [maxposf]: 15:22:04.016, +05.04.44.999, I, 1.41332e+09Hz
-- position of min value (world) [minposf]: 15:21:45.947, +04.59.29.990, I, 1.41332e+09Hz
-- Sum of pixel values [sum]: 1.32267159822
-- Sum of squared pixel values [sumsq]: 0.0284534543692
```

Statistics ---

```
-- Mean of the pixel values [mean]: 0.000786836167885
-- Standard deviation of the Mean [sigma]: 0.00403944306904
-- Root mean square [rms]: 0.00411418313161
-- Median of the pixel values [median]: 0.000137259965413
-- Median of the deviations [medabsdevmed]: 0.00152346317191
-- Quartile [quartile]: 0.00305395200849
```

The return value in `xstat` is

```
CASA <152>: xstat
Out[152]:
{'blc': array([108, 108, 0, 21]),
 'blcf': '15:22:20.076, +04.58.59.981, I, 1.41332e+09Hz',
 'flux': array([ 0.11179924]),
 'max': array([ 0.02945151]),
 'maxpos': array([124, 131, 0, 21]),
 'maxposf': '15:22:04.016, +05.04.44.999, I, 1.41332e+09Hz',
 'mean': array([ 0.00078684]),
 'medabsdevmed': array([ 0.00152346]),
 'median': array([ 0.00013726]),
 'min': array([-0.00612453]),
 'minpos': array([142, 110, 0, 21]),
 'minposf': '15:21:45.947, +04.59.29.990, I, 1.41332e+09Hz',
```

```
'npts': array([ 1681.]),
'quartile': array([ 0.00305395]),
'rms': array([ 0.00411418]),
'sigma': array([ 0.00403944]),
'sum': array([ 1.3226716]),
'sumsq': array([ 0.02845345]),
'trc': array([148, 148, 0, 21]),
'trcf': '15:21:39.919, +05.08.59.981, I, 1.41332e+09Hz'}
```

BETA ALERT: The return dictionary currently includes NumPy `array` values, which have to be accessed by an array index to get the array value.

To access these dictionary elements, use the standard Python dictionary syntax, e.g.

```
xstat[<key string>][<array index>]
```

For example, to extract the standard deviation as a number

```
mystddev = xstat['sigma'][0]
```

6.7.2 Examples using imstat

We give a few examples of the use of `imstat`, in particular to extract the information from the return value.

Select a two box region:

```
# box 1, bottom-left coord is 2,3 and top-right coord is 14,15
# box 2, bottom-left coord is 30,31 and top-right coord is 42,43
xstat = imstat( 'myImage', box='2,3,14,15;30,31,42,43' )
```

Select the same two box regions but only channels 4 and 5:

```
xstat = imstat( 'myImage', box='2,3,14,15;30,31,42,43', chan='4~5' )
```

Select all channels greater than 20 as well as channel 0, and print the mean and standard deviation:

```
xstat = imstat( 'myImage', chans='>20;0' )
print "Mean is: ", xstat['mean'][0], " s.d. ", xstat['sigma'][0]
```

Find statistical information for the Q Stokes value only then the I Stokes values only, and print out the statistical values that we are interested in:

```
xstat = imstat( 'myimage', stokes='Q' )
s1=xstat
imstat( 'myimage', stokes='I' )
s2=xstat
print "      |   MIN   |   MAX   |   MEAN"
print "  Q    | ",s1['min'][0]," | ",s1['max'][0]," |   ,," |   ,s1['mean'][0]
print "  I    | ",s2['min'][0]," | ",s2['max'][0]," |   ,," |   ,s2['mean'][0]
```

6.8 Extracting data from an image (imval)

The `imval` task will extract the values of the data and mask from a specified region of an image and place in the task return value as a Python dictionary.

The inputs are:

```
# imval :: Get the data value(s) and/or mask value in an image.
imagename = ''      # Name of the input image
region     = ''      # Image Region. Use viewer
box        = ''      # Select one or more box regions
chans      = ''      # Select the channel(spectral) range
stokes     = ''      # Stokes params to image (I,IV,IQU,IQUV)
async      = False
```

Region selection is carried out through the `box` parameter. See § 6.1.1 for more on region selection using this parameter. By default, `box=''` will extract the image information at the reference pixel on the direction axes.

Image plane selection is controlled by `chans` and `stokes`. See § 6.1.2 for details on plane selection. By default, `chans=''` and `stokes=''` will extract the image information in all channels and Stokes planes.

For instance,

```
xval = imval('myimage', box='144,144', stokes='I' )
```

will extract the Stokes I value or spectrum at pixel 144,144, while

```
xval = imval('myimage', box='134,134.154,154', stokes='I' )
```

will extract a 21 by 21 pixel region.

Extractions are returned in NumPy arrays in the return value dictionay, plus some extra elements describing the axes and selection:

```
CASA <2>: xval = imval('ngc5921.demo.moments.integrated')
```

```
CASA <3>: xval
Out[3]:
{'axes': [[0, 'Right Ascension'],
           [1, 'Declination'],
           [3, 'Frequency'],
           [2, 'Stokes']],
 'blc': [128, 128, 0, 0],
 'data': array([ 0.89667124]),
 'mask': array([ True], dtype=bool),
 'trc': [128, 128, 0, 0],
 'unit': 'Jy/beam.km/s'}
```

extracts the reference pixel value in this 1-plane image. Note that the 'data' and 'mask' elements are NumPy arrays, not Python lists.

To extract a spectrum from a cube:

```
CASA <8>: xval = imval('ngc5921.demo.clean.image',box='125,125')
```

```
CASA <9>: xval
Out[9]:
{'axes': [[0, 'Right Ascension'],
           [1, 'Declination'],
           [3, 'Frequency'],
           [2, 'Stokes']],
 'blc': [125, 125, 0, 0],
 'data': array([ 8.45717848e-04,  1.93370355e-03,  1.53750915e-03,
                2.88399984e-03,  2.38683447e-03,  2.89159478e-04,
                3.16268904e-03,  9.93389636e-03,  1.88773088e-02,
                3.01138610e-02,  3.14478502e-02,  4.03211266e-02,
                3.82498614e-02,  3.06552909e-02,  2.80734301e-02,
                1.72479432e-02,  1.20884273e-02,  6.13593217e-03,
                9.04005766e-03,  1.71429547e-03,  5.22095338e-03,
                2.49114982e-03,  5.30831399e-04,  4.80734324e-03,
                1.19265869e-05,  1.29435991e-03,  3.75700940e-04,
                2.34788167e-03,  2.72604497e-03,  1.78467855e-03,
                9.74952069e-04,  2.24676146e-03,  1.82263291e-04,
                1.98463408e-06,  2.02975096e-03,  9.65532148e-04,
                1.68218743e-03,  2.92119570e-03,  1.29359076e-03,
                -5.11484570e-04,  1.54162932e-03,  4.68662125e-04,
                -8.50282842e-04, -7.91683051e-05,  2.95954203e-04,
                -1.30133145e-03]),
 'mask': array([ True,  True,  True,  True,  True,  True,  True,  True,
                True,  True,  True,  True,  True,  True,  True,  True,
                True,  True,  True,  True,  True,  True,  True,  True,
                True,  True,  True,  True,  True,  True,  True,  True,  True],
               dtype=bool),
 'trc': [125, 125, 0, 45],
 'unit': 'Jy/beam'}
```

To extract a region from the plane of a cube:

```
CASA <13>: xval = imval('ngc5921.demo.clean.image',box='126,128,130,129',chans='23')
```

```
CASA <14>: xval
Out[14]:
{'axes': [[0, 'Right Ascension'],
           [1, 'Declination'],
           [3, 'Frequency'],
           [2, 'Stokes']],
 'blc': [126, 128, 0, 23],
 'data': array([[ 0.00938627,  0.01487772],
                [ 0.00955847,  0.01688832],
```

```
[ 0.00696965,  0.01501907],
[ 0.00460964,  0.01220793],
[ 0.00358087,  0.00990202]]),
'mask': array([[ True,  True],
   [ True,  True],
   [ True,  True],
   [ True,  True],
   [ True,  True]], dtype=bool),
'trc': [130, 129, 0, 23],
'unit': 'Jy/beam'}
```

```
CASA <15>: print xval['data'][0][1]
0.0148777160794
```

In this example, a rectangular box was extracted, and you can see the order in the array and how to address specific elements.

6.9 Regridding an Image (imregrid)

It is occasionally necessary to regrid an image onto a new coordinate system. The `imregrid` task will regrid one image onto the coordinate system of another, creating an output image. In this task, the user need only specify the names of the input, template, and output images.

If the user needs to do more complex operations, such as regridding an image onto an arbitrary (but known) coordinate system, changing from Equatorial to Galactic coordinates, or precessing Equinoxes, the CASA toolkit can be used (see sidebar). Some of these facilities will eventually be provided in task form.

The default inputs are:

```
# imregrid :: regrid an image onto a template image
imagename      =      ''          # Name of input image
template       =      ''          # Name of reference image
output         =      ''          # Name of output regridded image
async          =     False        #
```

The `output` image will have the data in `imagename` regridded onto the coordinate system of `template` image.

Inside the Toolkit:

More complex coordinate system and image regridding operation can be carried out in the toolkit. The `coordsys` (`cs`) tool and the `ia.regrid` method are the relevant components.

6.10 Image Import/Export to FITS

These tasks will allow you to write your CASA image to a FITS file that other packages can read, and to import existing FITS files into CASA as an image.

6.10.1 FITS Image Export (exportfits)

To export your images to fits format use the `exportfits` task. The inputs are:

```
# exportfits :: Convert a CASA image to a FITS file

imagingname      =      ''      # Name of input CASA image
fitsimage        =      ''      # Name of output FITS image
velocity         =      False    # Prefer velocity for spectral axis
optical          =      True     # Prefer optical velocity definition
bitpix           =      -32     # Bits per pixel (-32 (floating point), 16 (integer))
minpix           =      0       # Minimum pixel value
maxpix           =      0       # Maximum pixel value
overwrite        =      False    # Overwrite pre-existing output file
dropdeg          =      False    # Drop degenerate axes
deglast          =      False    # Put degenerate axes last in header
async            =      True     # if True run in the background. Recommended
```

For example,

```
exportfits('ngc5921.usecase.clean.image','ngc5921.usecase.image.fits')
```

BETA ALERT: Setting `async=True` is recommended because there is a flaw in the Beta version of the FITS classes that will cause subsequent FITS import (`importfits` or `importuvfits`) after an export to fail. Using asynchronous export will circumvent this by forcing the creation and use of a new tool object rather than using default one.

6.10.2 FITS Image Import (importfits)

You can also use the `importfits` task to import a FITS image into CASA image table format. Note, the CASA `viewer` can read fits images so you don't need to do this if you just want to look at the image. The inputs for `importfits` are:

```
# importfits :: Convert an image FITS file into a CASA image:

fitsimage        =      ''      # Name of input image FITS file
imagingname      =      ''      # Name of output CASA image
whichrep         =      0       # Which coordinate representation (if multiple)
whichhdu         =      0       # Which image (if multiple)
zeroblanks       =      True    # If blanked fill with zeros (not NaNs)
overwrite        =      False   # Overwrite pre-existing imagingname
async            =      False   # if True run in the background, prompt is freed
```

For example, we can read the above image back in

```
importfits('ngc5921.usecase.image.fits','ngc5921.usecase.image.im')
```

6.11 Using the CASA Toolkit for Image Analysis

Although this cookbook is aimed at general users employing the tasks, we include here a more detailed description of doing image analysis in the CASA toolkit. This is because there are currently only a few tasks geared towards image analysis, as well as due to the breadth of possible manipulations that the toolkit allows that more sophisticated users will appreciate.

To see a list of the `ia` methods available, use the CASA `help` command:

```
CASA <1>: help ia
-----> help(ia)
Help on image object:

class image(__builtin__.object)
| image object
|
| Methods defined here:
|
| __init__(...)
|     x.__init__(...) initializes x; see x.__class__.__doc__ for signature
|
| __str__(...)
|     x.__str__() <==> str(x)
|
| adddegaxes(...)
|     Add degenerate axes of the specified type to the image' :
|         outfile
|             direction = false
|             spectral = false
|             stokes
|             linear    = false
|             tabular   = false
|             overwrite = false
| -----
|
| addnoise(...)

...
|
| unlock(...)
|     Release any lock on the image' :
| -----
|
| -----
| Data and other attributes defined here:
|
| __new__ = <built-in method __new__ of type object at 0x55d0f20>
|     T.__new__(S, ...) -> a new object with type S, a subtype of T
```

Inside the Toolkit:

The image analysis tool (`ia`) is the workhorse here. It appears in the User Reference Manual as the `image` tool. Other relevant tools for analysis and manipulation include `measures` (`me`), `quanta` (`qa`) and `coordsys` (`cs`).

or for a compact listing use <TAB> completion on `ia.`, e.g.

```
CASA <2>: ia.
Display all 101 possibilities? (y or n)
ia.__class__          ia.fitsky                  ia.newimagefromshape
ia.__delattr__        ia.fromarray               ia.open
ia.__doc__            ia.fromascii               ia.outputvariant
ia.__getattribute__   ia.fromfits                ia.pixelvalue
ia.__hash__           ia.fromforeign             ia.putchunk
ia.__init__           ia.fromimage               ia.putregion
ia.__new__            ia.fromshape               ia.rebin
ia.__reduce__         ia.getchunk               ia.regrid
ia.__reduce_ex__      ia.getregion              ia.remove
ia.__repr__           ia.getslice               ia.removefile
ia.__setattr__        ia.hanning                ia.rename
ia.__str__            ia.haslock                ia.replacemaskedpixels
ia.adddegaxes         ia.histograms             ia.restoringbeam
ia.addnoise           ia.history                ia.rotate
ia.boundingbox        ia.imagecalc              ia.sepconvolve
ia.brightnessunit     ia.imageconcat             ia.set
ia.calc               ia.insert                 ia.setboxregion
ia.calcmask          ia.isopen                 ia.setbrightnessunit
ia.close              ia.ispersistent           ia.setcoordsys
ia.continuumsub       ia.lock                  ia.sethistory
ia.convertflux        ia.makearray              ia.setmiscoinfo
ia.convolve           ia.makecomplex            ia.setrestoringbeam
ia.convolve2d         ia.maketestimage         ia.shape
ia.coordmeasures     ia.maskhandler            ia.statistics
ia.coordsys          ia.maxfit                ia.subimage
ia.decompose          ia.miscinfo              ia.summary
ia.deconvolvecomponentlist ia.modify               ia.toASCII
ia.done               ia.moments               ia.tofits
ia.echo               ia.name                  ia.topixel
ia.fft                ia.newimage              ia.toworld
ia.findsources        ia.newimagefromarray        ia.twopointcorrelation
ia.fitallprofiles    ia.newimagefromfile         ia.type
ia.fitpolynomial     ia.newimagefromfits        ia.unlock
ia.fitprofile         ia.newimagefromimage
```

A common use of the `ia` tool is to do region statistics on an image. The `imhead` task has `mode='stats'` to do this quickly over the entire image cube. The tool can do this on specific planes or sub-regions. For example, in the Jupiter 6cm example script (§ F.2), the `ia` tool is used to get on-source and off-source statistics for regression:

```
# The variable clnimage points to the clean image name

# Pull the max and rms from the clean image
ia.open(clnimage)
```

```

on_statistics=ia.statistics()
thistest_immax=on_statistics['max'][0]
oldtest_immax = 1.07732224464
print ' Clean image ON-SRC max should be ',oldtest_immax
print ' Found : Max in image = ',thistest_immax
diff_immax = abs((oldtest_immax-thistest_immax)/oldtest_immax)
print ' Difference (fractional) = ',diff_immax

print ''
# Now do stats in the lower right corner of the image
box = ia.setboxregion([0.75,0.00],[1.00,0.25],frac=true)
off_statistics=ia.statistics(region=box)
thistest_imrms=off_statistics['rms'][0]
oldtest_imrms = 0.0010449
print ' Clean image OFF-SRC rms should be ',oldtest_imrms
print ' Found : rms in image = ',thistest_imrms
diff_imrms = abs((oldtest_imrms-thistest_imrms)/oldtest_imrms)
print ' Difference (fractional) = ',diff_imrms

print ''
print ' Final Clean image Dynamic Range = ',thistest_immax/thistest_imrms
print ''
print ' ===== '
ia.close()

```

BETA ALERT: Bad things can happen if you open some tools, like `ia`, in the Python command line on files and forget to close them before running scripts that use the `os.system('rm -rf <filename>')` call to clean up. We are in the process of cleaning up cases like this where there can be stale handles on files that have been manually deleted, but for the meantime be warned that you might get exceptions (usually of the “`SimpleOrderedMap-remove`” flavor, or even Segmentation Faults and core-dumps!

6.12 Examples of CASA Image Analysis

Here are some examples of image analysis.

BETA ALERT: Note that the syntax has been changing recently and these may get out of date quickly!

6.12.1 Spectral Line Image Analysis with NGC5921

The following is an example use of the image analysis tasks on the NGC5921 VLA data that we calibrated and imaged in the previous chapters (§ 4.8.1,5.10.1). This assumes you have already run those and have all of the defined variables in your session, as well as the final split calibrated ms files and image cubes on disk.

The full NGC5921 example script can be found in Appendix F.1.

```
#####
#                                     #
# Image Analysis Script for NGC 5921      #
#                                     #
# Updated      STM 2008-03-25 (Beta Patch 1.0)  #
#                                     #
#                                     clean    --> <prefix>.clean.image +   #
#                                     |           <prefix>.clean.model +   #
#                                     |           <prefix>.clean.residual   #
#                                     v           #                                     #
#####

# Set up some useful variables
# The prefix to use for all output files
prefix='ngc5921.usecase'

# The split MS filename
msfile = prefix + '.split.ms'

#
# Clean will have made the images:
# -----
# ngc5921.usecase.clean.image
# ngc5921.usecase.clean.model
# ngc5921.usecase.clean.residual
# ngc5921.usecase.clean.boxclean.mask

clnimage = imname+'.image'

=====
#
# Print the image header
#
print '--Imhead--'
default('imhead')

imagename = clnimage

mode = 'summary'

imhead()

# A summary of the cube will be seen in the logger
=====

#
# Get the cube statistics
#
print '--Imstat (cube)--'
```

```
default('imstat')

imagename = clnimage

# Do whole image
box = ''
# or you could stick to the cleanbox
#box = '108,108,148,148'

cubestats = imstat()

# Statistics will printed to the terminal, and cubestats
# will contain a dictionary of the statistics

=====
#
# Get some image moments
#
print '--ImMoments--'
default('immoments')

imagename = clnimage

# Do first and second moments
moments = [0,1]

# Need to mask out noisy pixels, currently done
# using hard global limits
excludepix = [-100,0.009]

# Include all planes
planes = ''

# Output root name
momfile = prefix + '.moments'
outfile = momfile

immoments()

momzeroimage = momfile + '.integrated'
momoneimage = momfile + '.weighted_coord'

# It will have made the images:
# -----
# ngc5921.usecase.moments.integrated
# ngc5921.usecase.moments.weighted_coord

#
=====

#
# Get some statistics of the moment images
```

```
#  
print '--Imstat (moments)--'  
default('imstat')  
  
imagename = momzeroimage  
momzerostats = imstat()  
  
imagename = momoneimage  
momonestats = imstat()  
  
#=====  
#  
print ' NGC5921 results '  
print ' ===== '  
  
#  
# Now use the stats produced by imstat above  
#  
print ''  
# Pull the max from the cubestats dictionary  
# created above using imstat  
thistest_immax=cubestats['max'][0]  
print ' Clean image max = ',thistest_immax  
  
print ''  
# Pull the rms from the cubestats dictionary  
thistest_imrms=cubestats['rms'][0]  
print ' Clean image rms = ',thistest_imrms  
  
print ''  
# Pull the max from the momzerostats dictionary  
thistest_momzeromax=momzerostats['max'][0]  
print ' Moment 0 image max = ',thistest_momzeromax  
  
print ''  
# Pull the mean from the momonestats dictionary  
thistest_momoneavg=momonestats['mean'][0]  
print ' Moment 1 image mean = ',thistest_momoneavg  
  
print ''  
print '--- Done ---'  
  
#  
#=====
```

Chapter 7

Visualization With The CASA Viewer

This chapter describes how to display data with the `casaviewer` either as a stand-alone or through the `viewer` task. You can display both images and Measurement Sets.

7.1 Starting the viewer

Within the casapy environment, the `viewer` task can be used to display an image or MS. The inputs are:

```
# viewer :: View an image or visibility data set.

infile      =      ''    # (Optional) Name of file to visualize.
displaytype = 'raster' # (Optional) Type of visual rendering
                      # (raster, contour, vector or marker).
                      # lel if an lel expression is given
                      # for infile (advanced).
```

Examples of starting the `viewer`:

```
CASA <1>: viewer()

CASA <2>: viewer('ngc5921.usecase.ms')

CASA <3>: viewer('ngc5921.usecase.clean.image')

CASA <4>: viewer('ngc5921.usecase.clean.image.rstr')

CASA <5>: viewer('ngc5921.usecase.clean.image', 'contour')

CASA <6>: viewer('"ngc5921.usecase.clean.image"^2', 'lel')
```




Figure 7.1: The **Viewer Display Panel** (left) and **Data Display Options** (right) panels that appear when the `viewer` is called with the image cube from NGC5921 (`viewer('ngc5921.usecase.clean.image')`). The initial display is of the first channel of the cube.

The first of these creates an empty **Viewer Display Panel** (§ 7.2.1) and a **Load Data** window (§ 7.2.4). The second starts the `viewer` loaded with a Measurement Set. The third example starts the `viewer` with an image cube (see Figure 7.1).

Example four brings up a display panel as it was when its state was saved to the given 'restore' file (`ngc5921.usecase.clean.image.rstr`). This includes the data displayed as well as options and viewer settings. (See § 7.2.2, **Saving and Restoring Viewer State**).

Examples five and six are less common cases, which make use of the second parameter (`displaytype`). Example five displays the image in contour form. Example six uses 'Lattice (Image) Expression Language' to display the square of the image data.

NOTE: the `viewer` task now determines file types (images, MSs, restore files) automatically. It is no longer necessary to specify `filetype='ms'` explicitly.




Figure 7.2: The **Viewer Display Panel** (left) and **Data Display Options** (right) panels that appear when the viewer is called with the NGC5921 Measurement Set (`viewer('ngc5921.usecase.ms')`).

7.1.1 Running the CASA viewer outside casapy

`casaviewer` is the name of the stand-alone viewer application that is available with a CASA installation. From the operating system prompt, the following commands are equivalent to the `casapy` task commands given previously:

```
casaviewer &
casaviewer ms_filename &
casaviewer image_filename &
casaviewer restore_filename &
```

```
casaviewer image_filename contour &
casaviewer '"image_filename"^2' lel &
```

7.2 The viewer GUI

The CASA viewer application consists of a number of graphical user interface (GUI) windows that respond to mouse and keyboard input. Here we describe the **Viewer Display Panel** (§ 7.2.1) and the **Load Data** window (§ 7.2.4). They are used for both image and MS viewing. Several other windows are context-specific and are described in the sections on viewing images (§ 7.3) and Measurement Sets (§ 7.4).

7.2.1 The Viewer Display Panel

The Viewer Display Panel is the the window that actually displays the image or MS. This is shown in the left panels of Figures 7.1 and 7.2. Note that this panel is the same whether an image or MS is being displayed.

At the top of the Viewer Display Panel are the menus:

- **Data**
 - **Open** — choose a data file to load and display
 - **Register** — select/de-select the (previously-loaded) data file(s) which should display right now (menu expands to the right showing all loaded data)
 - **Close** — close (unload) selected data file (menu expands to the right)
 - **Adjust** — open the Data Display Options ('Adjust') panel
 - **Print** — print the displayed image
 - **Save Panel State** — to a 'restore' file (xml format)
 - **Restore Panel State** — from a restore file
 - **Close Panel** — close the Viewer Display Panel (will exit if this is the last display panel open)
 - **Quit Viewer** — close all display panels and exit
- **Display Panel**
 - **New Panel** — create another Viewer Display Panel (cleared)
 - **Panel Options** — open the Display Panel's options window
 - **Save Panel State**
 - **Restore Panel State**
 - **Print** — print displayed image

- **Close Panel** — close the Viewer Display Panel (will exit if this is the last display panel open)

- **Tools**

- **Annotations** — not yet available (greyed out)
- **Spectral Profile** — plot frequency/velocity profile of point or region of image
- **Region Manager** — save regions and control their extent

- **View**

- **Main Toolbar** — show/hide top row of icons
- **Mouse Toolbar** — show/hide second row of mouse-button action selection icons
- **Animator** — show/hide tapedeck control panel
- **Position Tracking** — show/hide bottom position tracking report box

Below this is the **Main Toolbar** (Figure 7.3), the top row of icons for fast access to some of these menu items:

- **folder** (`Data:Open` shortcut) — show the Load Data panel
- **wrench** (`Data:Adjust` shortcut) — show the Data Display Options ('Adjust') panel
- **panels** (`Data:Register` shortcut) — show the menu of loaded data
- **delete** (`Data:Close` shortcut) — closes/unloads selected data
- **new panel** (`Display Panel>New Panel`)
- **panel wrench** (`Display Panel>Panel Options`) — show the Display Panel's options window
- **save** — save panel state to a 'restore' file
- **restore** — restore panel state from a restore file
- **region save** (`Tools:Region Manager`) — save/control regions.
(Note: some of these newer buttons do not appear in older figures of this document).
- **print** (`Display Panel>Print`) — print data
- **magnifier box** — Zoom out all the way
- **magnifier plus** — Zoom in (by a factor of 2)
- **magnifier minus** — Zoom out (by a factor of 2)



Figure 7.3: The display panel's **Main Toolbar** appears directly below the menus and contains 'shortcut' buttons for most of the frequently-used menu items.



Figure 7.4: The '**Mouse Tool**' Bar allows you to assign separate mouse buttons to tools you control with the mouse within the image display area. Initially, zooming, color adjustment, and rectangular regions are assigned to the left, middle and right mouse buttons, respectively.

Below this are the eight **Mouse Tool** buttons (Figure 7.4). These allow assignment of *each* of the three mouse buttons to a different operation on the display area. Clicking a mouse tool icon will [re-]assign **the mouse button that was clicked** to that tool. The icons show which mouse button is currently assigned to which tool.

The 'escape' key can be used to cancel any mouse tool operation that was begun but not completed, and to erase any tool showing in the display area.

- **Zooming (magnifying glass icon):** To zoom into a selected area, press the Zoom tool's mouse button (the **left** button by default) on one corner of the desired rectangle and drag to the desired opposite corner. Once the button is released, the zoom rectangle can still be moved or resized by dragging. To complete the zoom, double-click inside the selected rectangle (double-clicking *outside* it will zoom *out* instead).
- **Panning (hand icon):** Press the tool's mouse button on a point you wish to move, drag it to the position where you want it moved, and release. *Note: The arrow keys, Page Up, Page Down, Home and End keys can also be used to scroll through your data any time you are zoomed in. (Click on the main display area first, to be sure the keyboard is 'focused' there).*
- **Stretch-shift colormap fiddling (crossed arrows):** This is usually the handiest color adjustment; it is assigned to the **middle** mouse button by default.
- **Brightness-contrast colormap fiddling (light/dark sun)**
- **Positioning (bombsight):** This tool can place a 'crosshair' marker on the display to select a position. It is used to flag Measurement Set data or to select an image position for spectral profiles. Click on the desired position with the tool's mouse button to place the crosshair; once placed you can drag it to other locations. Double-click is not needed for this tool. See § 7.2.3 for more detail.

- **Rectangle and Polygon region drawing:** The rectangle region tool is assigned to the **right** mouse button by default. As with the zoom tool, a rectangle region is generated by dragging with the assigned mouse button; the selection is confirmed by double-clicking within the rectangle. Polygon regions are created by clicking the assigned mouse button at the desired vertices, clicking the final location twice to finish. Once created, a polygon can be moved by dragging from inside, or reshaped by dragging the handles at the vertices. Double-click inside to confirm region selection. See § 7.2.3 for the uses of this tool.
- **Polyline drawing:** A polyline can be created by selecting this tool. It is manipulated similarly to the polygon region tool: create segments by clicking at the desired positions and then double-click to finish the line. [Uses for this tool are still to be implemented].

The main **Display Area** lies below the toolbars.

Underneath the display area is an **Animator** panel. The most prominent feature is the “tape deck” which provides movement between image planes along a selected third dimension of an image cube. This set of buttons is only enabled when a registered image reports that it has more than one plane along its ‘Z axis’. In the most common case, the animator selects the frequency channel. From left to right, the tape deck controls allow the user to:

- **rewind** to the start of the sequence (i.e., the first plane)
- **step backwards** by one plane
- **play backwards**, or repetitively step backwards
- **stop** any current play
- **play forward**, or repetitively step forward
- **step forward** by one plane
- **fast forward** to the end of the sequence

To the right of the tape deck is an editable text box indicating the current frame (channel) number and a label showing the total number of frames. Below that is a slider for controlling the (nominal) animation speed. To the right is a ‘Full/Compact’ toggle. In ‘Full’ mode (the default), a slider controlling frame number and a ‘Blink mode’ control are also available.

‘Blink’ mode is useful when more than one raster image is registered. In that mode, the tapedeck controls *which image* is displayed at the moment rather than the particular image plane (set that in ‘Normal’ mode first). The registered images must cover the same portion of the sky and use the same coordinate projection.

Note: *In ‘Normal’ mode, it is advisable to have only ONE raster image registered at a time, to avoid confusion. Unregister (or close) the others.*

At the bottom of the Display Panel is the **Position Tracking** panel. As the mouse moves over the main display, this panel shows information such as flux density, position (e.g. RA and Dec), Stokes,

and frequency (or velocity), for the point currently under the cursor. Each registered image/MS displays its own tracking information. Tracking can be 'frozen' (and unfrozen again) with the space bar. (Click on the main display area first, to be sure the keyboard is 'focused' there).

The Animator or Tracking panels can be hidden or detached (and later re-attached) by using the boxes at upper right of the panels; this is useful for increasing the size of the display area. (Use the 'View' menu to show a hidden panel again). The individual tracking areas (one for each registered image) can be hidden using the checkbox at upper left of each area.

7.2.2 Saving and Restoring Display Panel State

It is straightforward to save a display panel's current state (what data is on display along with data and panel settings). Select 'Save' (the unadorned floppy toolbutton) and confirm the filename. It is usually advisable (but not required) to retain the file's '.rstr' extension.

Press 'Restore' (the button to the right of Save) to choose a previously-created restore file. You can also select restore files from the Load Data window.

It is possible to restore MSs or images, multiple layers such as contour-over-raster, and LEL displays. You can also save the panel state with no data loaded, to restore preferred initial settings such as overall panel size. Animation and zoom state should likewise restore themselves.

Restore is fairly forgiving about data location, and will find files located:

- in the original location recorded in the restore file
- in the current working directory (where you started the viewer)
- in the restore file's directory
- in the original location relative to the restore file

This means that restore files will generally work if moved together with data files. The process is less forgiving if you save the display of an LEL (image) expression, however; the files must be in the locations specified in the original LEL expression. If a data file is not found, restore will attempt to proceed but results will vary.

Restore files are in ascii (xml) format, and some obvious manual edits are possible. However, these files are longer and more complex than you might imagine. Use caution, and back up restore files you want to preserve. If you make a mistake, the viewer may not recognize the file as a restore file; other unexpected results could also occur. It is usually easier and safer to make changes on the display panel and then save the restore file again.

7.2.3 Region Selection and Positioning

You can draw regions or select positions on the display with the mouse, once you have selected the appropriate tool(s) on the **Mouse Toolbar** (see above).

The **Rectangle Region** drawing tool currently works for the following:

- Region statistics reporting for images,
- Region spectral profiles for images, via the **Tools:Spectral Profile** menu,
- Flagging of Measurement Sets
- Creating and Saving an image region for various types of analysis (§ 7.3.5)
- Selecting Clean regions interactively (§ 5.3.5)

The **Polygon Region** drawing has the same uses, except that polygon region flagging of an MS is not supported.

The **Positioning** crosshair tool works for the last two of the above.

The **Spectral Profile** display (see § 7.3.4), when active, updates on *each change* of the rectangle, polygon, or crosshair. Flagging with the crosshair also responds to single click or drag.

Region statistics are printed in the terminal window (not the logger) by double-clicking the completed region. The **Rectangle Region** tool's mouse button must also be double-clicked to confirm an MS flagging edit.

Here is an example of region statistics from the viewer:

```
ngc5921.usecase.clean.image-contour      (Jy/beam)

n          Std Dev      RMS      Mean      Variance      Sum
52          0.01067    0.02412    0.02168    0.0001139    1.127

Flux        Med |Dev|  IntQtlRng  Median      Min       Max
0.09526    0.009185   0.01875    0.02076    0.003584    0.04181
```

7.2.4 The Load Data Panel

You can use the **Load Data - Viewer** GUI to interactively choose images or MS to load into the viewer. An example of this panel is shown in Figure 7.5. This panel is accessed through the **Data:Open** menu or Open icon of the **Viewer Display Panel**. It also appears if you open the **viewer** without any **infile** specified.

Selecting a file on disk in the **Load Data** panel will provide options for how to display the data. Images can be displayed as:

1. Raster Image,
2. Contour Map,
3. Vector map, or
4. Marker Map.




Figure 7.5: The **Load Data - Viewer** panel that appears if you open the `viewer` without any `infile` specified, or if you use the `Data:Open` menu or Open icon. You can see the images and MS available in your current directory, and the options for loading them.

You can also enter a 'Lattice (image) Expression' in the box provided (§ 6.1.3). For example, you might enter:

```
'my.clean.im' - 'my.dirty.im'
```

to display the difference between the two images. (The images should have the same coordinates and extents).

A MS can only be displayed as a raster.

7.2.4.1 Registered vs. Open Datasets

When you 'load' data as described above, it is first *opened*, and then *registered* on all existing **Display Panels**. The distinction is subtle. An 'open' dataset has been prepared in memory from disk; it may be registered (enabled for drawing) on one **Display Panel** and not on another. All open datasets will have a tab in the **Data Options** window, whether currently registered or not. On the other hand, only those datasets registered on a particular panel will show in its **Tracking** area.

At present, it is useful to have more than one image registered on a panel *only* if you are displaying a contour image over a raster image (§ 7.3.3) or 'blinking' between images (see **Animator** in § 7.2.1). (In future we also hope to provide transparent overlay of raster images).

It is the user's responsibility – and highly advisable – to unregister (or close) datasets that are no longer in use, using the **Register** or **Close** toolbutton or menu. In future the viewer will attempt to aid in unregistering datasets which are not 'compatible' with a newly-loaded one (different sky area, e.g., or MS vs. image).

If you close a dataset, you must reload it from disk as described above to see it again. That can take a little time for MSs, especially. If you unregister a dataset, it is set to draw immediately when you re-register it, with its options as you have previously set them. In general, close unneeded datasets but unregister those you'll be working with again.

7.3 Viewing Images

You have several options for viewing an image. These are seen at the right of the **Load Data - Viewer** panel described in § 7.2.4 and shown in Figure 7.6 when an image is selected. They are:

- **Raster Image** — a greyscale or color image,
- **Contour Map** — contours of intensity as a line plot,
- **Vector Map** — vectors (as in polarization) as a line plot,
- **Marker Map** — a line plot with symbols to mark positions.

The **Raster Image** is the default image display, and is what you get if you invoke the **viewer** from **casapy** with an image file name. In this case, you will need to use the **Open** menu to bring up the **Load Data** panel to choose a different display.

7.3.1 Viewing a raster map

A raster map of an image shows pixel intensities in a two-dimensional cross-section of gridded data with colors selected from a finite set of (normally) smooth and continuous colors, i.e., a colormap.




Figure 7.6: The **Load Data - Viewer** panel as it appears if you select an image. You can see all options are available to load the image as a **Raster Image**, **Contour Map**, **Vector Map**, or **Marker Map**. In this example, clicking on the **Raster Image** button would bring up the displays shown in Figure 7.1.

Starting the `casaviewer` with an image as a raster map will look something like the example in Figure 7.1.

You will see the GUI which consists of two main windows, entitled "Viewer Display Panel" and "Load Data". In the "Load Data" panel, you will see all of the viewable files in the current working directory along with their type (Image, Measurement Set, etc). After selecting a file, you are presented with the available display types (raster, contour, vector, marker) for these data. Clicking on the button **Raster Map** will create a display as above.

The data display can be adjusted by the user as needed. This is done through the **Data Display Options** panel. This window appears when you choose the `Data:Adjust` menu or use the wrench icon from the **Main Toolbar**. This also comes up by default along with the **Viewer Display Panel** when the data is loaded.

The **Data Display Options** window is shown in the right panel of Figure 7.1. It consists of a tab for each image or MS loaded, under which are a cascading series of expandable categories. For an

image, these are:

- **Display axes**
- **Hidden axes**
- **Basic Settings**
- **Position tracking**
- **Axis labels**
- **Axis label properties**
- **Beam Ellipse**
- **Color Wedge**

The **Basic Settings** category is expanded by default. To expand a category to show its options, click on it with the left mouse button.

7.3.1.1 Raster Image — Basic Settings

This roll-up is open by default. It has some commonly-used parameters that alter the way the image is displayed; three of these affect the colors used. An example of this part of the panel is shown in Figure 7.7.




Figure 7.7: The **Basic Settings** category of the **Data Display Options** panel as it appears if you load the image as a **Raster Image**. This is a zoom-in for the data displayed in Figure 7.1.

The options available are:

- **Basic Settings: Aspect ratio**

This option controls the horizontal-vertical size ratio of data pixels on screen. **Fixed world** (the default) means that the aspect ratio of the pixels is set according to the coordinate system of the image (i.e., true to the projected sky). **Fixed lattice** means that data pixels will always be square on the screen. Selecting **flexible** allows the map to stretch independently in each direction to fill as much of the display area as possible.

- **Basic Settings: Pixel treatment**

This option controls the precise alignment of the edge of the current 'zoom window' with the data lattice. **edge** (the default) means that whole data pixels are always drawn, even on the edges of the display. For most purposes, **edge** is recommended. **center** means that data pixels on the edge of the display are drawn only from their centers inwards. (Note that a data pixel's center is considered its 'definitive' position, and corresponds to a whole number in 'data pixel' or 'lattice' coordinates).

- **Basic Settings: Resampling mode**

This setting controls how the data are resampled to the resolution of the screen. **nearest** (the default) means that screen pixels are colored according to the intensity of the nearest data point, so that each data pixel is shown in a single color. **bilinear** applies a bilinear interpolation between data pixels to produce smoother looking images when data pixels are large on the screen. **bicubic** applies an even higher-order (and somewhat slower) interpolation.

- **Basic Settings: Data Range**

You can use the entry box provided to set the minimum and maximum data values mapped to the available range of colors as a list [**min**, **max**]. For very high dynamic range images, you will probably want to enter a **max** less than the data maximum in order to see detail in lower brightness-level pixels. The next setting also helps very much with high dynamic range data.

- **Basic settings: Scaling power cycles**

This option allows logarithmic scaling of data values to colormap cells.

The color for a data value is determined as follows: first, the value is clipped to lie within the data range specified above, then mapped to an index into the available colors, as described in the next paragraph. The color corresponding to this index is determined finally by the current colormap and its 'fiddling' (shift/slope) and brightness/contrast settings (see **Mouse Toolbar**, above). Adding a **Color Wedge** to your image can help clarify the effect of the various color controls.

The **Scaling power cycles** option controls the mapping of clipped data values to colormap indices. Set to zero (the default), a straight linear relation is used. For negative scaling values, a logarithmic mapping assigns a larger fraction of the available colors to lower data values (this is usually what you want). Setting **dataMin** to something around the noise level is often useful/appropriate in conjunction with a negative 'Power cycles' setting.

For positive values, a larger fraction of the colormap is used for the high data values.¹

¹The actual functions are computed as follows:

See Figure 7.8 for sample curves.




Figure 7.8: Example curves for scaling power cycles.

- **Basic settings: Colormap**

You can select from a variety of colormaps here. Hot Metal, Rainbow and Greyscale colormaps are the ones most commonly used.

7.3.1.2 Raster Image — Other Settings

Many of the other settings on the **Data Options** panel for raster images are self-explanatory, such as those which affect **Beam ellipse** drawing (only available if your image provides beam data), or the form of the **Axis labeling** and **Position tracking** information. You can also give your image a **Color wedge**, a key to the current mapping from data values to colors.

You can control which of your image's axes are on the vertical and horizontal display axes and which on the animation or 'movie' axis, within the **Display axes** drop-down. You must set the X, Y and Z (animation) axes so that each shows a *different* image axis, in order for your choice to take effect.

If your image has a fourth axis (typically Stokes), it can be controlled by a slider within the **Hidden axes** drop-down.

For negative scaling values (say $-p$), the data is scaled linearly from the range (`dataMin` – `dataMax`) to the range $(1 - 10^p)$. Then the program takes the log (base 10) of that value (arriving at a number from 0 to p) and scales that linearly to the number of available colors. Thus the data is treated as if it had p decades of range, with an equal number of colors assigned to each decade.

For positive scaling values, the inverse (exponential) functions are used. If p is the (positive) value chosen, The data value is scaled linearly to lie between 0 and p , and 10 is raised to this power, yielding a value in the range $(1 - 10^p)$. Finally, that value is scaled linearly to the number of available colors.

7.3.2 Viewing a contour map

Viewing a contour image is similar to the process above. A contour map shows lines of equal data value (e.g., flux density) for the selected plane of gridded data (Figure 7.9). Several **Basic Settings** options control the contour levels used. Contour maps are particularly useful for overlaying on raster images so that two different measurements of the same part of the sky can be shown simultaneously.




Figure 7.9: The **Viewer Display Panel** (left) and **Data Display Options** panel (right) after choosing **Contour Map** from the **Load Data** panel. The image shown is for channel 11 of the NGC5921 cube, selected using the **Animator** tape deck, and zoomed in using the tool bar icon. Note the different options in the open **Basic Settings** category of the **Data Display Options** panel.

7.3.3 Overlay contours on a raster map

Contours of either a second data set or the same data set can be used for comparison or to enhance visualization of the data. The Data Options Panel will have multiple tabs which allow adjusting each overlay individually (Note tabs along the top). **Beware:** it's easy to forget which tab is active!

Also note that **axis labeling** is controlled by the *first-registered* image overlay that has labeling turned on (whether raster or contour), so make label adjustments within that tab.

To add a Contour overlay, open the **Load Data** panel (Use the **Data** menu or click on the Folder icon), select the data set and select **Contour**. See Figure 7.10 for an example using NGC5921.




Figure 7.10: The **Viewer Display Panel** (left) and **Data Display Options** panel (right) after overlaying a **Contour Map** on a **Raster Image** from the same image cube. The image shown is for channel 11 of the NGC5921 cube, selected using the **Animator** tape deck, and zoomed in using the tool bar icon. The tab for the contour plot is open in the **Data Display Options** panel.

7.3.4 Spectral Profile Plotting

From the **Tools** menu, the **Spectral Profile** plotting tool can be selected. This will pop up a new **Image Profile** window containing an x-y plot of the intensity versus spectral axis (usually velocity). You can then select a region with the **Rectangle** or **Polygon Region** drawing tools, or pinpoint a position using the **Crosshair** tool. The profile for the region or position selected will then appear in the **Image Profile** window. This profile will update in real time to track changes

to the region or crosshair, which can be moved by click-dragging the mouse. See Figure 7.11.




Figure 7.11: The **Image Profile** panel that appears if you use the `Tools:Spectral Profile` menu, and then use the rectangle or polygon tool to select a region in the image. You can also use the crosshair to get the profile at a single position in the image. The profile will change to track movements of the region or crosshair if moved by dragging with the mouse.

7.3.5 Managing and Saving Regions

To save a region of an image you have on display, first open the Region Manager window (the `Tools:Region Manager` menu item, or the corresponding toolbutton). A window will appear as in Figure 7.12.

Under **Region Extent**, choose whether you want your region to be confined to the viewed plane only, or to extend over all channels or all image planes.

Then trace out your region on the display panel using the rectangle or polygon region mouse tools (§ 7.2.1, § 7.2.3), and confirm by double-clicking inside the region. Figure 7.13 shows an image




Figure 7.12: The **Region Manager** panel that appears if you select the Tools:Region Manager menu item.

region selected with the polygon tool.

Note: *The extent of the region is determined by the extent button in effect when the region is defined, not when it is saved. Therefore it is important to select the extent before double-clicking the region with the mouse.* If you neglected to do this, you can just double-click again within the region after you select the extent and before saving.

Make any desired adjustments to the offered pathname and press `Save Last region` to save the region to a file. The example Casa commands below illustrate usage of such files.

```
reg = rg.fromfiletorecord( "my.im.rgn" )
ia.open( "my.im" )
ia.statistics( region=reg )
```

BETA ALERT: Visual region management is incomplete. Very soon, the region will be placed inside the image file rather than stored separately. Compound regions with iterative additions/deletions and better visual feedback will also be provided.

Note that the current Region Extent choice also affects the image points used in computing statistics (§ 7.2.3).

7.3.6 Adjusting Canvas Parameters/Multi-panel displays

The display area can also be manipulated with the following controls in the **Panel Options** (or 'Viewer Canvas Manager') window. Use the wrench icon with a 'P' (or the 'Display Panel' menu) to show this window.




Figure 7.13: Selecting an image region with the polygon tool.

- Margins - specify the spacing for the left, right, top, and bottom margins
- Number of panels - specify the number of panels in x and y and the spacing between those

panels.

- Background Color - white or black (more choices to come)

7.3.6.1 Setting up multi-panel displays

Figure 7.14 illustrates a multi-panel display along with the Viewer Canvas Manager settings which created it.




Figure 7.14: A multi-panel display set up through the **Viewer Canvas Manager**.

7.3.6.2 Background Color

The **Background Color** selection can be used to change the background color from its default of **black**. Currently, the only other choice is **white**, which is more appropriate for printing or inclusion in documents.




Figure 7.15: The **Load Data - Viewer** panel as it appears if you select an MS. The only option available is to load this as a **Raster Image**. In this example, clicking on the **Raster Image** button would bring up the displays shown in Figure 7.2.

7.4 Viewing Measurement Sets

Visibility data can also be displayed and flagged directly from the viewer. For Measurement Set files the only option for display is 'Raster' (similar to AIPS task TVFLG). An example of MS display is shown in Figure 7.2; loading of an MS is shown in Figure 7.15.

Warning: *Only one MS should be registered at a time on a Display Panel.* Only one MS can be shown in any case. You do not have to close other images/MSs, but you should at least 'unregister' them from the Display Panel used for viewing the MS. If you wish to see other images or MSs at the same time, create multiple Display Panel windows.

7.4.1 Data Display Options Panel for Measurement Sets

The **Data Display Options** panel provides adjustments for MSs similar to those for images, and also includes flagging options. As with images, this window appears when you choose the

Data:Adjust menu or use the wrench icon from the **Main Toolbar**. It is also shown by default when an MS is loaded. The right panel of Figure 7.2 shows a **Data Options** window. It has a tab for each open MS, containing a set of categories. The options within each category can be either 'rolled up' or expanded by clicking the category label.

For a Measurement Set, the categories are:

- **Advanced**
- **MS and Visibility Selection**
- **Display Axes**
- **Flagging Options**
- **Basic Settings**
- **Axis Drawing and Labels**
- **Color Wedge**

7.4.1.1 MS Options — Basic Settings

The **Basic Settings** roll-up is expanded by default. It contains entries similar to those for a raster image (§ 7.3.1.1). Together with the brightness/contrast and colormap adjustment icons on the **Mouse Toolbar** of the Display Panel, they are especially important for adjusting the color display of your MS.

The available Basic options are:

- **Data minimum/maximum**

This has the same usage as for raster images. Lowering the data maximum will help brighten weaker data values.

- **Scaling power cycles**

This has exactly the same usage as for raster images (see § 7.3.1.1). Again, lowering this value often helps make weaker data visible. If you want to view several fields with very different amplitudes simultaneously, this is typically one of the best adjustments to make early, together with the **Colormap fiddling** mouse tool, which is on the middle mouse button by default.

- **Colormap**

Greyscale or **Hot Metal** colormaps are generally good choices for MS data.

7.4.1.2 MS Options— MS and Visibility Selections

- Visibility Type
- Visibility Component
- Moving Average Size

This roll-up provides choice boxes for Visibility Type (Observed, Corrected, Model, Residual) and Component (Amplitude, Phase, Real, or Imaginary).




Figure 7.16: The MS for NGC4826 BIMA observations has been loaded into the viewer. We see the first of the spw in the Display Panel, and have opened up **MS and Visibility Selections** in the **Data Display Options** panel. The display panel raster is not full of visibilties because spw 0 is continuum and was only observed for the first few scans. This is a case where the different spectral windows have different numbers of channels also.

Changes to Visibility Type or Component (changing from Phase to Amplitude, for example) require the data to be retrieved again from the disk into memory, which can be a lengthy process. When a large MS is first selected for viewing, the user must trigger this retrieval manually by pressing the **Apply** button (located below all the options), after selecting the data to be viewed (see **Field IDs** and **Spectral Windows**, below).

Tip: Changing visibility type between 'Observed' and 'Corrected' can also be used to assure that data and flags are reloaded from disk. You should do this if you're using another flagging tool

such as autoflag simultaneously, so that the viewer sees the other tool's new edits and doesn't overwrite them with obsolete flags. The **Apply** button alone won't reload unless something within the viewer itself requires it; in the future, a button will be provided to reload flags from the disk unconditionally.

You can also choose to view the difference from a running mean or the local RMS deviation of either Phase or Amplitude. There is a slider for choosing the nominal number of time slots in the 'local neighborhood' for these displays.

(Note: **Insufficient Data** is shown in the tracking area during these displays when there is no other unflagged data in the local neighborhood to compare to the point in question. The moving time windows will not extend across changes in either field ID or scan number boundaries, so you may see this message if your scan numbers change with every time stamp. An option will be added later to ignore scan boundaries).

- Field IDs
- Spectral Windows

You can retrieve and edit a selected portion of the MS data by entering the desired Spectral Window and Field ID numbers into these boxes. **Important:** Especially with large MSs, often the first thing you'll want to do is to select **spectral windows** which all have the **same number of channels** and the **same polarization setup**. It also makes sense to edit only a few fields at a time. Doing this will also greatly reduce data retrieval times and memory requirements.

You can separate the ID numbers with spaces or commas; you do not need to enter enclosing brackets. Changes to either entry box will cause the selected MS data to be reloaded from disk.

If you select, say, spectral windows 7, 8, 23, and 24, the animator, slice position sliders, and axis labeling will show these as 0, 1, 2, and 3 (the 'slice positions' or 'pixel coordinates' of the chosen spectral windows). Looking at the position tracking display is the best way to avoid confusion in such cases. It will show something like: Sp Win 23 (s 2) when you are viewing spectral window 23 (plane 2 of the selected spectral windows).

Changes to MS selections will not be allowed until you have saved (or discarded) any previous edits you have made (see **Flagging Options -- Save Edits**, below). A warning is printed on the console (not the logger).

Initially, all fields and spectral windows are selected. To revert to this 'unselected' state, choose 'Original' under the wrench icons next to the entry boxes.

See Figure 7.16 for an example showing the use of the **MS** and **Visibility Selections** controls when viewing an MS.

7.4.1.3 MS Options — Display Axes

This roll-up is very similar to that for images: it allows the user to choose which axes (from Time, Baseline, Polarization, Channel, and Spectral Window) are on the display and the animator.

There are also sliders here for choosing positions on the remaining axes. (It's useful to note that the data *is* actually stored internally in memory as an array with these five axes).




Figure 7.17: The MS for NGC4826 from Figure 7.16, now with the **Display Axes** open in the **Data Display Options** panel. By default, `channels` are on the **Animation Axis** and thus in the tape deck, while `spectral window` and `polarization` are on the **Display Axes** sliders.

For MSs, changing the choice of axis on one control will automatically swap axes, maintaining different axes on each control. Changing axes or slider/animator positions does not normally require pressing **Apply** — the new slice is shown immediately. However, the display may be partially or completely grey in areas if the required data is not currently in memory, either because no data has been loaded yet, or because not all the selected data will fit into the allowed memory. Press the **Apply** button in this case to load the data (see § 7.4.1.6 and `Max. Visibility Memory` at the end of § 7.4.1.5).

Within the **Display Axes** rollup you may also select whether to order the baseline axis by antenna1-antenna2 (the default) or by (unprojected) baseline length.

See Figures 7.17–7.18 showing the use of the **Display Axes** controls to change the axes on the animation and sliders.




Figure 7.18: The MS for NGC4826, continuing from Figure 7.17. We have now put `spectral window` on the **Animation Axis** and used the tapedeck to step to spw 2, where we see the data from the rest of the scans. Now `channels` is on a **Display Axes** slider, which has been dragged to show Channel 33.

7.4.1.4 MS Options — Flagging Options

These options allow you to edit (flag or unflag) MS data. The Crosshair and Rectangle Region **Mouse Tools** (§ 7.2.3) are used on the display to select the area to edit. When using the Rectangle Region tool, double-click inside the selected rectangle to confirm the edit.

The options below determine how edits will be applied.

- **Show Flagged Regions...**

You have the option to display flagged regions in the background color (as in TVFLG) or to highlight them with color. In the former case, flagged regions look just like regions of no data. With the (default) color option, flags are shown in shades of blue: darker blue for flags already saved to disk, lighter blue for new flags not yet saved; regions with no data will be shown in black.

- **Flag or Unflag**

This setting determines whether selected regions will be flagged or unflagged. This does *not*

affect previous edits; it only determines the effect which later edits will have. Both flagging and unflagging edits can be accumulated and then saved in one pass through the MS.

- **Flag/Unflag All...**

These flagging extent checkboxes allow you to extend your edit over any of the five data axes. For example, to flag *all* the data in a given time range, you would check all the axes *except* Time, and then select the desired time range with the **Rectangle Region** mouse tool. Such edits will extend along the corresponding axes over the entire selected MS (whether loaded into memory or not) and optionally over unselected portions of the MS as well (**Use Entire MS**, below). Use care in selecting edit extents to assure that you're editing all the data you wish to edit.

- **Flag/Unflag Entire Antenna?**

This control can be used to extend subsequent edits to all baselines which include the desired antenna[s]. For example, if you set this item to 'Yes' and then click the crosshair on a visibility point with baseline 3-19, the edit would extend over baselines 0-3, 1-3, 2-3, 3-3, 3-4, ... 3-**nAntennas-1**. Note that the second antenna of the selection (19) is irrelevant here – you can click anywhere within the 'Antenna 3 block', i.e., where the *first* antenna number is 3, to select all baselines which include antenna 3.

This item controls the edit extent only along the baseline axis. If you wish to flag *all* the data for a given antenna, you must still check the boxes to flag all Times, Channels, Polarizations and Spectral Windows. There would be no point, however, in activating *both* this item and the 'Flag All Baselines' checkbox. You can flag an antenna in a limited range of times, etc., by using the appropriate checkboxes and selecting a rectangular region of visibilities with the mouse.

Note: You do not need to include the entire 'antenna block' in your rectangle (and you may stray into the next antenna if you try). Anywhere within the block will work. To flag higher-numbered antennas, it often helps to zoom in.

- **Undo Last Edit**

- **Undo All Edits**

The 'Undo' buttons do the expected thing: completely undo the effect of the last edit (or all unsaved edits). Please note, however, that only unsaved edits can be undone here; there is no ability to revert to the flagging state at the start of the session once flags have been saved to disk (unless you have previously saved a 'flag version'. The flag version tool is not available through the viewer directly).

- **Use Entire MS When Saving Edits?**

"Yes" means that saving the edits will flag/unflag over the entire MS, *including* fields (and possibly spectral windows) which are not currently selected for viewing. Specifically, data within time range(s) you swept out with the mouse (even for unselected fields) will be edited.

In addition, if "Flag/Unflag All..." boxes were checked, such edits will extend throughout the MS. Note that only unselected *times* (fields) can be edited *without* checking extent boxes for

the edits as well. Unselected spectral windows, e.g., will *not* be edited unless the edit also has "Flag/Unflag All Spectral Windows" checked.

Warning: Beware of checking "All Spectral Windows" unless you have also checked "All Channels" or turned "Entire MS" off; channel edits appropriate to the selected spectral windows may not be appropriate to unselected ones. Set "Use Entire MS" to "No" if your edits need to apply only to the portion of the MS you have selected for viewing. *Edits can often be saved significantly faster this way as well.*

Also note that checkboxes apply to individual edits, and must be checked before making the edit with the mouse. "Use Entire MS", on the other hand, applies to all the edits saved at one time, and must be set as desired before pressing "Save Edits".

- **Save Edits**

MS editing works like a text editor in that you see all of your edits immediately, but nothing is committed to disk until you press 'Save Edits'. Feel free to experiment with all the other controls; nothing but 'Save Edits' will alter your MS on disk. As mentioned previously, however, there is no way to undo your edits once they are saved, except by manually entering the reverse edits (or restoring a previously-saved 'flag version').

Also, *you must save (or discard) your edits before changing the MS selections*. If edits are pending, the selection change will not be allowed, and a warning will appear on the console.

If you close the MS in the viewer, *unsaved edits are simply discarded*, without prior warning. It's important, therefore, to remember to save them yourself. You can distinguish unsaved flags (when using the 'Flags In Color' option), because they are in a lighter shade of blue.

The program must make a pass through the MS on disk to save the edits. This can take a little time; progress is shown in the console window.

7.4.1.5 MS Options— Advanced

These settings can help optimize your memory usage, especially for large MSs. A rule of thumb is that they can be increased until response becomes sluggish, when they should be backed down again.

You can run the unix 'top' program and hit 'M' in it (to sort by memory usage) in order to examine the effects of these settings. Look at the amount of RSS (main memory) and SWAP used by the X server and 'casaviewer' processes. If that sounds familiar and easy, then fiddling with these settings is for you. Otherwise, the default settings should provide reasonable performance in most cases.

- **Cache size**

The value of this option specifies the maximum number of different views of the data to save so that they can be redrawn quickly. If you run an animation or scroll around zoomed data, you will notice that the data displays noticeably faster the second time through because of this feature. Often, setting this value to the number of animation frames is ideal Note, however, that on multi-panel displays, each panel counts as one cached image.

Large images naturally take more room than small ones. The memory used for these images will show up in the X server process. If you need more Visibility Memory (below) for a really large ms, it is usually better to forgo caching a large number of views.

- **Max. Visibility Memory**

This option specifies how many megabytes of memory may be used to store visibility data from the measurement set internally. *Even if you do not adjust this entry, it is useful to look at it to see how many megabytes are required to store your entire (selected) MS in memory.* If the slider setting is above this, the whole selected MS will fit into the memory buffer. Otherwise, some data planes will be 'greyed out' (see **Apply Button**, § 7.4.1.6 below), and the selected data will have to be viewed one buffer at a time, which is somewhat less convenient. In most cases, this means you should **select fewer fields or spectral windows** – see § 7.4.1.2. The 'casaviewer' process contains this buffer memory (it contains the entire viewer, but the memory buffer can take most of the space).

7.4.1.6 MS Options — Apply Button

When viewing large MSs the display may be partially or completely grey in areas where the required data is not currently in memory, either because no data has been loaded yet, or because not all the selected data will fit into the allowed memory (see **Max. Visibility Memory** above). When the cursor is over such an area, the following message shows in the position tracking area:

```
press 'Apply' on Adjust panel to load data
```

Pressing the **Apply** button (which lies below all the options) will reload the memory buffer so that it includes the slice you are trying to view.

The message **No Data** has a different meaning; in that case, there simply *is* no data in the selected MS at the indicated position.

For large measurement sets, loading visibility data into memory is the most time-consuming step. Progress feedback is provided in the console window. Again, careful selection of the data to be viewed can greatly speed up retrieval.

7.5 Printing from the Viewer

You can use the **Data:Print** menu or the **Print** button to bring up the **Viewer Print Manager**. From this panel, you can print a hardcopy of what is in the Display Panel, or save it in a variety of formats.

Figure 7.19 shows an example of printing to a file. The key to making acceptable hardcopies (particularly for printing or inclusion in documents) is to set the background color and line widths to appropriate values so the plot and labels show up in the limited resolution of the hardcopy.




Figure 7.19: Setting up to print to a file. The background color has been set to `white`, the line width to 2, and the print resolution to 600 dpi (for an postscript plot). To make the plot, use the **Save** button on the **Viewer Print Manager** panel (positioned in the figure in the upper right) and select a format with the drop-down, or use the **Print** button to send directly to a printer.

Use the **Viewer Canvas Manager** (§ 7.3.6) to change the **Background Color** from its default of `black` to `white` if you are making plots for printing or inclusion in a document. You might also want to change the **colormap** accordingly.

Adjust the **Line Width** of the **Axis Label Properties** options in the **Data Display Options** panel so that the labels will be visible when printed. Increasing from the default of 1.4 to a value around 2 seems to work well.

You can choose an output file name in the panel. Be sure to make it a new name, otherwise it will not overwrite a previous file (and will not say anything about it).

If you will be printing to a postscript printer or to a PS or EPS file, dial up the **[PS] Resolution (dpi)** to its maximum of 600. This will increase the size of the PS file somewhat, but will make a much better plot. Use `gzip` to compress the PS file if necessary. Be sure to choose the desired

Output Media and Orientation for PS also.

BETA ALERT: The postscript printing capabilities of the `casaviewer` are currently limited due to some issues with the way we use Qt and do axis labels. Significant improvements have been made in Patch 3. This will be further upgraded in the future, but for now you will need to follow the suggestions above to get a useable plot. Note that `ghostview` may show a poorer version of the PS than you will get when you print.

Appendix A

Single Dish Data Processing

BETA ALERT: The single-dish analysis package within CASA is still experimental. It is included in the Beta release for the use of the ALMA computing and commissioning groups, and is not intended for general users. Therefore, this is included in this Cookbook as an appendix.

For single-dish spectral calibration and analysis, CASA uses the ATNF Spectral Analysis Package (ASAP). This is imported as the `sd` tool, and forms the basis for a series of tasks (the “SDtasks”) that encapsulate the functionality within the standard CASA task framework. ASAP was developed to support the Australian telescopes such as Mopra, Parkes, and Tidbinbilla, and we have adapted it for use within CASA for GBT and eventually ALMA data also [Note: some support for the ALMA Testing Facility (ATF) data are now available)]. For details on ASAP, see the ASAP home page at ATNF:

- <http://www.atnf.csiro.au/computing/software/asap/>

You can also download the ASAP User Guide and Reference Manual at this web site. There is also a brief tutorial. Note that within CASA, the ASAP tools are prefaced with `sd.`, e.g. where it says in the ASAP User Guide to use `scantable` you will use `sd.scantable` in CASA. See § A.3 for more information on the tools.

All of the ASAP functionality is available with a CASA installation. In the following, we outline how to access ASAP functionality within CASA with the tasks and tools, and the data flow for standard use cases.

If you run into trouble, be sure to check the list of known issues and features of ASAP and the SDtasks presented in § A.5 first.

A.1 Guidelines for Use of ASAP and SDtasks in CASA

A.1.1 Environment Variables

There are a number of environment variables that the ASAP tools (and thus the SDtasks) use to help control their operation. These are described in the ASAP User Guide as being in the `.asaprc`

file. Within CASA, these are contained in the Python dictionary `sd.rcParams` and are accessible through its keys and values. For SDtask users, the most important are the `verbose` parameter controlling the display of detailed messages from the tools. By default

```
sd.rcParams['verbose'] = True
```

and you get lots of messages. Also, the `scantable.storage` parameter controlling whether scantable operations are done in memory or on disk. The default

```
sd.rcParams['scantable.storage'] = 'memory'
```

does it in memory (best choice if you have enough), while to force the scantables to disk use

```
sd.rcParams['scantable.storage'] = 'disk'
```

which might be necessary to allow processing of large datasets. See § A.3.1 for more details on the ASAP environment variables.

A.1.2 Assignment

Some ASAP methods and function require you to assign that method to a variable which you can then manipulate. This includes `sd.scantable` and `sd.selector`, which make objects. For example,

```
s = sd.scantable('OrionS_rawACSmod', average=False)
```

A.1.3 Lists

For lists of scans or IFs, such as in `scanlist` and `iflist` in the SDtasks, the tasks and functions want a comma-separated Python list, e.g.

```
scanlist = [241, 242, 243, 244, 245, 246]
```

You can use the Python `range` function to generate a list of consecutive numbers, e.g.

```
scanlist = range(241,247)
```

giving the same list as above, e.g.

```
CASA <3>: scanlist=range(241,247)
CASA <4>: print scanlist
[241, 242, 243, 244, 245, 246]
```

You can also combine multiple ranges by summing lists

```
CASA <5>: scanlist=range(241,247) + range(251,255)
CASA <6>: print scanlist
[241, 242, 243, 244, 245, 246, 251, 252, 253, 254]
```

Note that in the future, the `sd` tools and SDtasks will use the same selection language as in the synthesis part of the package.

Spectral regions, such as those for setting masks, are pairs of min and max values for whatever spectral axis unit is currently chosen. These are fed into the tasks and tools as a list of lists, with each list element a list with the `[min,max]` for that sub-region, e.g.

```
masklist=[[1000,3000], [5000,7000]].
```

A.1.4 Dictionaries

Currently, the SDtasks return the Python dictionary for the results of line fitting (in `sdfit`) and region statistics (in `sdstat`). If you invoke these tasks by assigning variable for the return, you can then access the elements of these through the keywords, e.g.

```
CASA <10>: line_stat=sdstat()
Current fluxunit = K
No need to convert fluxunits
Using current frequency frame
Using current doppler convention

CASA <11>: line_stat
Out[11]:
{'eqw': 70.861755476162784,
 'max': 1.2750182151794434,
 'mean': 0.35996028780937195,
 'median': 0.23074722290039062,
 'min': -0.20840644836425781,
 'rms': 0.53090775012969971,
 'stddev': 0.39102539420127869,
 'sum': 90.350028991699219}
```

You can then use these values in scripts by accessing this dictionary, e.g.

```
CASA <12>: print "Line max = %5.3f K" % (line_stat['max'])
Line max = 1.275 K
```

for example.

A.1.5 Line Formatting

The SDtasks trap leading and trailing whitespace on string parameters (such as `infile` and `sdfile`), but ASAP does not, so be careful with setting string parameters. ASAP is also case-sensitive, with most parameters being upper-case, such as `ASAP` for the `sd.scantable.save` file format. The SDtasks are generally more forgiving.

Also, beware Python’s sensitivity to indenting.

A.2 Single Dish Analysis Tasks

A set of single dish tasks is available for simplifying basic reduction activities. Currently the list includes:

- **sdaverage** — select, calibrate, and average SD data
- **sdsMOOTH** — smooth SD spectra
- **sdbaseline** — fit/remove spectral baselines from SD data
- **sdcal** — combined the three tasks above to perform standard single dish processing all at once
- **sdcoadd** — merge/co-add multiple SD data
- **sdflag** — channel flagging of SD spectra
- **sdfit** — line fitting to SD spectra
- **sdlist** — print a summary of a SD dataset
- **sdplot** — plotting of SD spectra, including overlay of line catalog data
- **sdsave** — save SD data to different format
- **sdscale** — scale SD data
- **sdstat** — compute statistics of regions of SD spectra
- **sdtpimaging** — do a simple calibration and create an image from the total power raster scans

All of the SDtasks work from a file on disk rather than from a scanable in memory as the ASAP toolkit does (see § A.3. Inside the tasks we invoke a call to `sd.scantable` to read in the data. The scanable objects do not persist within CASA after completion of the tasks, and are destroyed to free up memory.

Three tasks `sdaverage`, `sdsMOOTH`, and `sdbaseline` are the workhorse for the calibration, selection, averaging, baseline fitting, and smoothing. The output datasets for each task are written to a file on disk. Alternatively, one can use the task `sdcal` to perform all the steps in the three tasks described above in a single task invocation. It is comparable to run `sdaverage`, `sdsMOOTH`, and `sdbaseline`, in that order, since `sdcal` internally calls these three tasks. Its operation is controlled by three main “mode” parameters: `calmode` (which selects the type of calibration, if any, to be applied), `kernel` (which selects the smoothing), and `blmode` (which selects baseline fitting). There are also parameters controlling the selection such as `scanlist`, `iflist`, `field`, `scanaverage`, `timeaverage`,

and `polaverage`. Note that `sdcal` can be run with `calmode='none'` to allow re-selection or writing out of data that is already calibrated.

There is a "wiring diagram" of the dataflow and control inputs for `sdcal` shown in Figure A.1. This might help you chart your course through the calibration.

The SDtasks support the import and export file formats supported by ASAP itself. For import, this includes: ASAP (scantables), MS (CASA measurement set), RPITS and SDFITS. For export, this includes: ASAP (scantables), MS (CASA measurement set), ASCII (text file), SDFITS (a flavor of SD FITS). The `sdsave` task is available exclusively for exporting with data selection options.

The `sdcoadd` task is available to merge data in separate data files into one.

You can get a brief summary of the data in a file using the `sdlist` task.

Plotting of spectra is handled in the `sdplot` task. It also offers some selection, averaging and smoothing options in case you are working from a dataset that has not been split or averaged. Note that there is some rudimentary plotting capability in many of SD tasks, controlled through the `plotlevel` parameter, to aid in the assessment of the performance of these tasks.

Scaling of the spectra and Tsys is available in the `sdscale`.

Basic statistics on spectral regions is available in the `sdstat` task. Results are passed in a Python dictionary return variable.

Basic Gaussian line-fitting is handled by the `sdfit` task. It can deal with the simpler cases, and offers some automation as well as interactive selection of fitting region, but more complicated fitting is best accomplished through the toolkit (`sd.fitter`).

Basic non-interactive channel flagging is available in the `sdflag` task. By default or by specifying `outfile` parameter, a new file is created containing dataset with the flag information. To update flags in the input data, `outfile='none'` must be set.

Limited total power data analysis functionality is available through a new task, `sdtpimaging`. This task directly access the Measurement Set without converting it to scantable format.




Figure A.1: Wiring diagram for the SDtask `sdcal`. The stages of processing within the task are shown, along with the parameters that control them.

A.2.1 SDtask Summaries

The following are the list of parameters and brief descriptions of each of the SDtasks. These descriptions are also contained in the information produced by `help <taskname>`, once `asap_init` has been invoked. Note that you can use `inp <taskname>` on these as for other tasks.

A.2.1.1 sdaverage

Keyword arguments:

```

sdfile -- name of input SD dataset
fluxunit -- units for line flux
    options: 'K', 'Jy', ''
    default: '' (keep current fluxunit)
    WARNING: For GBT data, see description below.
    >>> fluxunit expandable parameter
telescopeparm -- the telescope characteristics
    options: (str) name or (list) list of gain info
    default: '' (none set)
    example: if telescopeparm='', it tries to get the telescope
             name from the data.
             Full antenna parameters (diameter,ap.eff.) known
             to ASAP are
             'ATPKSMB', 'ATPKSHOH', 'ATMOPRA', 'DSS-43',
             'CEDUNA', 'HOBART'. For GBT, it fixes default fluxunit
             to 'K' first then convert to a new fluxunit.
             telescopeparm=[104.9,0.43] diameter(m), ap.eff.
             telescopeparm=[0.743] gain in Jy/K
             telescopeparm='FIX' to change default fluxunit
             see description below

specunit -- units for spectral axis
    options: (str) 'channel', 'km/s', 'GHz', 'MHz', 'kHz', 'Hz'
    default: '' (=current)
    example: this will be the units for masklist

frame -- frequency frame for spectral axis
    options: (str) 'LSRK', 'REST', 'TOPO', 'LSRD', 'BARY',
             'GEO', 'GALACTO', 'LGROUP', 'CMB'
    default: currently set frame in scantable
    WARNING: frame='REST' not yet implemented

doppler -- doppler mode
    options: (str) 'RADIO', 'OPTICAL', 'Z', 'BETA', 'GAMMA'
    default: currently set doppler in scantable

calmode -- calibration mode
    options: 'ps', 'nod', 'fs', 'fsotf', 'quotient', 'none'
```

```

default: 'none'
example: choose mode 'none' if you have
          already calibrated and want to
          try averaging
scanlist -- list of scan numbers to process
    default: [] (use all scans)
    example: [21,22,23,24]
          this selection is in addition to field,
          iflist, and pollist
field -- selection string for selecting scans by name
    default: '' (no name selection)
    example: 'FLS3a*'
          this selection is in addition to scanlist,
          iflist, and pollist
iflist -- list of IF id numbers to select
    default: [] (use all IFs)
    example: [15]
          this selection is in addition to scanlist,
          field, and pollist
pollist -- list of polarization id numbers to select
    default: [] (use all polarizations)
    example: [1]
          this selection is in addition to scanlist,
          field, and iflist
channelrange -- channel range selection
    default: [] (use all channel)
    example: [0,5000]
          Note that specified values are recognized as
          'channel' regardless of the value of specunit
scanaverage -- average integrations within scans
    options: (bool) True,False
    default: False
    example: if True, this happens in read-in
              For GBT, set False!
timeaverage -- average times for multiple scan cycles
    options: (bool) True,False
    default: False
    example: if True, this happens after calibration
>>>timeaverage expandable parameter
tweight -- weighting for time average
    options: 'none'
          'var'   (1/var(spec) weighted)
          'tsys'  (1/Tsys**2 weighted)
          'tint'  (integration time weighted)
          'tintsy' (Tint/Tsys**2)

```

```

        'median' ( median averaging)
        default: 'none'
averageall -- average multi-resolution spectra
            spectra are averaged by referring
            their frequency coverage
        default: False

polaverage -- average polarizations
    options: (bool) True,False
    default: False
    >>>polaverage expandable parameter
    pweight -- weighting for polarization average
        options: 'none'
            'var' (1/var(spec) weighted)
            'tsys' (1/Tsys**2 weighted)
        default: 'none'
tau -- atmospheric optical depth
    default: 0.0 (no correction)
outfile -- Name of output file
    default: '' (<sdfile>_cal)
outform -- format of output file
    options: 'ASCII','SDFITS','MS','ASAP'
    default: 'ASAP'
    example: the ASAP format is easiest for further sd
            processing; use MS for CASA imaging.
            If ASCII, then will append some stuff to
            the outfile name
overwrite -- overwrite the output file if already exists
    options: (bool) True,False
    default: False
    WARNING: if outform='ASCII', this parameter is ignored
plotlevel -- control for plotting of results
    options: (int) 0=none, 1=some, 2=more, <0=hardcopy
    default: 0 (no plotting)
    example: plotlevel<0 as abs(plotlevel), e.g.
            -1 => hardcopy of final plot (will be named
            <outfile>_calspec.eps)
    WARNING: be careful plotting in fsotf mode!

```

DESCRIPTION:

Task **sdaverage** performs data selection, calibration for single-dish spectra. By setting **calmode='none'** one can run **sdaverage** on already calibrated data, for further selection , averaging and atmospheric optical depth correction.

If you give multiple IFs in `iflist`, then your scutable will have multiple IFs. This can be handled, but there can be funny interactions later on. We recommend you split each IF out into separate files by re-running `sdaverage` with each IF in turn.

ASAP recognizes the data of the "AT" telescopes, but currently does not know about the GBT or any other telescope. This task does know about GBT. Telescope name is obtained from the data. If you wish to change the `fluxunit` (see below), by leaving the sub-parameter `telescopeparm` unset (`telescopeparm=''`), it will use internal telescope parameters for flux conversion for the data from AT telescopes and it will use an approximate aperture efficiency conversion for the GBT data. If you give `telescopeparm` a list, then if the list has a single float it is assumed to be the gain in Jy/K, if two or more elements they are assumed to be telescope diameter (m) and aperture efficiency respectively.

Note that `sdaverage` assumes that the `fluxunit` is set correctly in the data already. If not, then set `telescopeparm='FIX'` and it will set the default units to `fluxunit` without conversion. NOTE: If the data in `sdfile` is an ms from GBT and the default flux unit is missing, this task automatically fixes the default `fluxunit` to 'K' before the conversion.

Beta Patch 3 New Features: Two new parameters were added:

1. To save the output spectra in a certain range of channels, you set the range in `channelrange`.
2. Averaging of multi-resolution spectra can be achieved by setting the sub-parameter in `timeaverage`, `averageall` to True. It generally handles multi-IFs by selecting overlaps in IFs and assigning new IFs in the output spectra.

A.2.1.2 `sdsMOOTH`

Keyword arguments:

```

sdfile -- name of input SD dataset
scanaverage -- average integrations within scans
    options: (bool) True, False
    default: False
    example: if True, this happens in read-in
              For GBT, set False!
scanlist -- list of scan numbers to process
    default: [] (use all scans)
    example: [21,22,23,24]
              this selection is in addition to field,
              iflist, and pollist
field -- selection string for selecting scans by name
    default: '' (no name selection)
    example: 'FLS3a*'
              this selection is in addition to scanlist,
              iflist,pollist
iflist -- list of IF id numbers to select

```

```

default: [] (use all IFs)
example: [15]
        this selection is in addition to scanlist,
        field, and pollist
pollist -- list of polarization id numbers to select
default: [] (use all polarizations)
example: [1]
        this selection is in addition to scanlist,
        field, and iflist
kernel -- type of spectral smoothing
options: 'hanning','gaussian','boxcar'
default: 'hanning'
>>>kernel expandable parameter
kwidth -- width of spectral smoothing kernel
options: (int) in channels
default: 5
example: 5 or 10 seem to be popular for boxcar
         ignored for hanning (fixed at 5 chans)
         (0 will turn off gaussian or boxcar)
outfile -- Name of output ASAP format(scantable) file
default: '' (<sdfile>_sm)
outform -- format of output file
options: 'ASCII','SDFITS','MS','ASAP'
default: 'ASAP'
example: the ASAP format is easiest for further sd
         processing; use MS for CASA imaging.
         If ASCII, then will append some stuff to
         the outfile name
overwrite -- overwrite the output file if already exists
options: (bool) True,False
default: False
WARNING: if outform='ASCII', this parameter is ignored
plotlevel -- control for plotting of results
options: (int) 0=none, 1=some, 2=more, <0=hardcopy
default: 0 (no plotting)
example: plotlevel<0 as abs(plotlevel), e.g.
         -1 => hardcopy of final plot (will be named
         <outfile>_smspec.eps)

```

DESCRIPTION:

Task **sdsMOOTH** performs smoothing of the single-dish spectra. Set **plotlevel** ≤ 1 to plot spectrum before and after smoothing.

A.2.1.3 sdbaseline

Keyword arguments:

```
sdfiile -- name of input SD dataset
telescopeparm -- the telescope name or characteristics
    options: (str) name or (list) list of gain info
    default: '' (none set)
    example: telescopeparm='' if GBT or AT telescopes
              telescopeparm=[104.9,0.43] diameter(m), ap.eff.
              telescopeparm=[0.743] gain in Jy/K
              telescopeparm='FIX' to change default fluxunit
              see description below
fluxunit -- units for line flux
    options: 'K', 'Jy', ''
    default: '' (keep current fluxunit)
    WARNING: For GBT data, see description below.
specunit -- units for spectral axis
    options: (str) 'channel', 'km/s', 'GHz', 'MHz', 'kHz', 'Hz'
    default: '' (=current)
    example: this will be the units for masklist
frame -- frequency frame for spectral axis
    options: (str) 'LSRK', 'REST', 'TOPO', 'LSRD', 'BARY',
              'GEO', 'GALACTO', 'LGROUP', 'CMB'
    default: currently set frame in scantable
    WARNING: frame='REST' not yet implemented
doppler -- doppler mode
    options: (str) 'RADIO', 'OPTICAL', 'Z', 'BETA', 'GAMMA'
    default: currently set doppler in scantable
scanlist -- list of scan numbers to process
    default: [] (use all scans)
    example: [21,22,23,24]
              this selection is in addition to field,
              iflist, and pollist
field -- selection string for selecting scans by name
    default: '' (no name selection)
    example: 'FLS3a*'
              this selection is in addition to scanlist,
              iflist, and pollist
iflist -- list of IF id numbers to select
    default: [] (use all IFs)
    example: [15]
              this selection is in addition to scanlist,
              field, and pollist
pollist -- list of polarization id numbers to select
    default: [] (use all polarizations)
```

```

example: [1]
        this selection is in addition to scanlist,
        field, and iflist
tau -- atmospheric optical depth
    default: 0.0 (no correction)
blmode -- mode for baseline fitting
    options: (str) 'auto','list','interact'
    default: 'auto'
example: blmode='auto' uses expandable parameters
        in addition to blpoly to run linefinder
        to determine line-free regions
        USE WITH CARE! May need to tweak the parameters,
        thresh, avg_limit, and edge.
        blmode='interact' allows adding and deleting mask
        regions by drawing rectangles on the plot with mouse.
        Draw a rectangle with LEFT-mouse to ADD the region to
        the mask and with RIGHT-mouse to DELETE the region.

>>> blmode expandable parameters
thresh -- S/N threshold for linefinder
    default: 5
example: a single channel S/N ratio above which the channel is
        considered to be a detection
avg_limit -- channel averaging for broad lines
    default: 4
example: a number of consecutive channels not greater than
        this parameter can be averaged to search for broad lines
edge -- channels to drop at beginning and end of spectrum
    default: 0
example: [1000] drops 1000 channels at beginning AND end
        [1000,500] drops 1000 from beginning and 500 from end

Note: For bad baselines threshold should be increased,
and avg_limit decreased (or even switched off completely by
setting this parameter to 1) to avoid detecting baseline
undulations instead of real lines.

blpoly -- order of baseline polynomial
    options: (int) (<0 turns off baseline fitting)
    default: 5
example: typically in range 2-9 (higher values
        seem to be needed for GBT)
interactive -- interactive mode for baseline fitting
    options: (bool) True,False
    default: False

```

```

WARNING: Currently this just asks whether you accept
          the displayed fit and if not, continues
          without doing any baseline fit.

masklist -- list of mask regions to INCLUDE in BASELINE fit
    default: [] (entire spectrum)
    example: [[1000,3000],[5000,7000]]
              if blmode='auto' then this mask will be applied
              before fitting

outfile -- Name of output file
    default: '' (<sdfile>_bs)

outform -- format of output file
    options: 'ASCII','SDFITS','MS','ASAP'
    default: 'ASAP'
    example: the ASAP format is easiest for further sd
              processing; use MS for CASA imaging.
              If ASCII, then will append some stuff to
              the outfile name

overwrite -- overwrite the output file if already exists
    options: (bool) True,False
    default: False
    WARNING: if outform='ASCII', this parameter is ignored

plotlevel -- control for plotting of results
    options: (int) 0=none, 1=some, 2=more, <0=hardcopy
    default: 0 (no plotting)
    example: plotlevel<0 as abs(plotlevel), e.g.
              -1 => hardcopy of final plot (will be named
              <outfile>_bspec.eps)
    WARNING: be careful plotting in fsotf mode!

```

DESCRIPTION:

Task `sdbaseline` performs baseline fitting/removal for single-dish spectra. The fit parameters, terms and rms of base-line are saved to an ASCII file, `<outfile>.blparam.txt`.

Also, see the notes on `fluxunit` and `telescopeparm` in the section for `sdaverage`. See the `sdaverage` description for information on `fluxunit` conversion and the `telescopeparm` parameter.

Beta Patch 3 New Features: By setting `blmode='interact'`, you can set/unset mask regions interactively using mouse buttons. Current mask regions will be shown in yellow shade in the plot. Baseline fit parameters and rms of fitted spectra are automatically saved to an ASCII file, `<outfile>.blparam.txt`.

A.2.1.4 sdcal

Keyword arguments:

```

sdfilename -- name of input SD dataset
fluxunit -- units for line flux
    options: 'K', 'Jy', ''
    default: '' (keep current fluxunit)
WARNING: For GBT data, see description below.
>>> fluxunit expandable parameter
telescopeparam -- the telescope characteristics
    options: (str) name or (list) list of gain info
    default: '' (none set)
    example: if telescopeparam='', it tries to get the telescope
              name from the data.
              Full antenna parameters (diameter,ap.eff.) known
              to ASAP are
              'ATPKSMB', 'ATPKSHOH', 'ATMOPRA', 'DSS-43',
              'CEDUNA', 'HOBART'. For GBT, it fixes default fluxunit
              to 'K' first then convert to a new fluxunit.
              telescopeparam=[104.9,0.43] diameter(m), ap.eff.
              telescopeparam=[0.743] gain in Jy/K
              telescopeparam='FIX' to change default fluxunit
              see description below

specunit -- units for spectral axis
    options: (str) 'channel','km/s','GHz','MHz','kHz','Hz','',''
    default: '' (=current)
    example: this will be the units for masklist
frame -- frequency frame for spectral axis
    options: (str) 'LSRK','REST','TOPO','LSRD','BARY',
              'GEO','GALACTO','LGROUP','CMB'
    default: currently set frame in scantable
WARNING: frame='REST' not yet implemented
doppler -- doppler mode
    options: (str) 'RADIO','OPTICAL','Z','BETA','GAMMA'
    default: currently set doppler in scantable
calmode -- calibration mode
    options: 'ps','nod','fs','fsotf','quotient','none'
    default: 'none'
    example: choose mode 'none' if you have
              already calibrated and want to
              try baselines or averaging
scanlist -- list of scan numbers to process
    default: [] (use all scans)
    example: [21,22,23,24]
              this selection is in addition to field,
              iflist, and pollist
field -- selection string for selecting scans by name

```

```
default: '' (no name selection)
example: 'FLS3a*'
        this selection is in addition to scanlist,
        iflist, and pollist
iflist -- list of IF id numbers to select
    default: [] (use all IFs)
    example: [15]
        this selection is in addition to scanlist,
        field, and pollist
pollist -- list of polarization id numbers to select
    default: [] (use all polarizations)
    example: [1]
        this selection is in addition to scanlist,
        field, and iflist
channelrange -- channel range selection
    default: [] (use all channel)
    example: [0,5000]
        Note that specified values are recognized as
        'channel' regardless of the value of specunit
average -- averaging on spectral data
    options: (bool) True,False
    default: False
    >>>average expandable parameter
    scanaverage -- average integrations within scans
        options: (bool) True,False
        default: False
        example: if True, this happens in read-in
                  For GBT, set False!
    timeaverage -- average times for multiple scan cycles
        options: (bool) True,False
        default: False
        example: if True, this happens after calibration
tweight -- weighting for time average
    options: 'none'
            'var'   (1/var(spec) weighted)
            'tsys'  (1/Tsys**2 weighted)
            'tint'  (integration time weighted)
            'tintsys' (Tint/Tsys**2)
            'median' ( median averaging)
    default: 'none'
averageall -- average multi-resolution spectra
            spectra are averaged by referring
            their frequency coverage
    default: False
polaverage -- average polarizations
```

```

        options: (bool) True, False
        default: False
pweight -- weighting for polarization average
        options: 'none'
                'var' (1/var(spec) weighted)
                'tsys' (1/Tsys**2 weighted)

tau -- atmospheric optical depth
        default: 0.0 (no correction)

kernel -- type of spectral smoothing
        options: 'none', 'hanning', 'gaussian', 'boxcar'
        default: 'none'
>>> kernel expandable parameter
kwidth -- width of spectral smoothing kernel
        options: (int) in channels
        default: 5
        example: 5 or 10 seem to be popular for boxcar
                ignored for hanning (fixed at 5 chans)
                (0 will turn off gaussian or boxcar)

blmode -- mode for baseline fitting
        options: (str) 'none', 'auto', 'list'
        default: 'none'
        example: blmode='auto' uses expandable parameters
                in addition to blpoly to run linefinder
                to determine line-free regions
                USE WITH CARE! May need to tweak the parameters,
                thresh, avg_limit, and edge.

>>> blmode expandable parameters
thresh -- S/N threshold for linefinder
        default: 5
        example: a single channel S/N ratio above which the channel is
                considered to be a detection
avg_limit -- channel averaging for broad lines
        default: 4
        example: a number of consecutive channels not greater than
                this parameter can be averaged to search for broad lines
edge -- channels to drop at beginning and end of spectrum
        default: 0
        example: [1000] drops 1000 channels at beginning AND end
                [1000,500] drops 1000 from beginning and 500 from end

```

Note: For bad baselines threshold should be increased,
and avg_limit decreased (or even switched off completely by
setting this parameter to 1) to avoid detecting baseline
undulations instead of real lines.

```

blpoly -- order of baseline polynomial
    options: (int) (<0 turns off baseline fitting)
    default: 5
    example: typically in range 2-9 (higher values
              seem to be needed for GBT)
interactive -- interactive mode for baseline fitting
    options: (bool) True,False
    default: False
    WARNING: Currently this just asks whether you accept
              the displayed fit and if not, continues
              without doing any baseline fit.
masklist -- list of mask regions to INCLUDE in BASELINE fit
    default: [] (entire spectrum)
    example: [[1000,3000],[5000,7000]]
              if blmode='auto' then this mask will be applied
              before fitting
outfile -- Name of output file
    default: '' (<sdfilename>_cal)
outform -- format of output file
    options: 'ASCII','SDFITS','MS','ASAP'
    default: 'ASAP'
    example: the ASAP format is easiest for further sd
              processing; use MS for CASA imaging.
              If ASCII, then will append some stuff to
              the outfile name
overwrite -- overwrite the output file if already exists
    options: (bool) True,False
    default: False
    WARNING: if outform='ASCII', this parameter is ignored
plotlevel -- control for plotting of results
    options: (int) 0=none, 1=some, 2=more, <0=hardcopy
    default: 0 (no plotting)
    example: plotlevel<0 as abs(plotlevel), e.g.
              -1 => hardcopy of final plot (will be named
              <outfile>_calspec.eps)
    WARNING: be careful plotting in fsotf mode!

```

DESCRIPTION:

Task **sdcal** performs data selection, calibration, and/or spectral baseline fitting for single-dish spectra. This task internally calls the tasks, **sdaverage**, **sdssmooth**, and **sdbaseline** and it can be used to run all the three steps in one task execution. By setting **calmode='none'** one can run **sdcal** on already calibrated data, for further selection , averaging and atmospheric optical depth correction. See the **sdaverage** description for information on **fluxunit** conversion and the **telescopeparm** parameter.

Beta Patch 3 New Features: Two new parameters were added:

1. To save the output spectra in a certain range of channels, you set the range in `channelrange`.
2. Averaging of multi-resolution spectra can be achieved by setting the sub-parameter of `average`, `averageall` to True. It generally handles multi-IFs by selecting overlaps in IFs and assigning new IFs in the output spectra.

The interactive mask specification is not available in this task. Please use `sdbaseline` for such a case.

A.2.1.5 `sdcoadd`

Keyword arguments:

```

sdfilelist -- list of names of input SD dataset
telescopeparm -- the telescope characteristics

    options: (str) name or (list) list of gain info
    default: '' (none set)
    example: if telescopeparm='', it tries to get the telescope
             name from the data.
             Full antenna parameters (diameter,ap.eff.) known
             to ASAP are
             'ATPKSMB', 'ATPKSHOH', 'ATMOPRA', 'DSS-43',
             'CEDUNA', 'HOBART' and 'GBT'.
             telescopeparm=[104.9,0.43] diameter(m), ap.eff.
             telescopeparm=[0.743] gain in Jy/K
             telescopeparm='FIX' to change default fluxunit
             see description below

fluxunit -- units for line flux
    options: 'K', 'Jy', ''
    default: '' (keep current fluxunit of the first data in the sdfilelist)
specunit -- units for spectral axis
    options: (str) 'channel', 'km/s', 'GHz', 'MHz', 'kHz', 'Hz'
    default: '' (=current)
    example: this will be the units for masklist
frame -- frequency frame for spectral axis
    options: (str) 'LSRK', 'REST', 'TOPO', 'LSRD', 'BARY',
             'GEO', 'GALACTO', 'LGROUP', 'CMB'
    default: currently set frame in scantable
    WARNING: frame='REST' not yet implemented
doppler -- doppler mode
    options: (str) 'RADIO', 'OPTICAL', 'Z', 'BETA', 'GAMMA'
    default: currently set doppler in scantable

```

```

scanaverage -- average integrations within scans
    options: (bool) True,False
    default: False
    example: if True, this happens in read-in
              For GBT, set False!
timeaverage -- average times for multiple scan cycles
    options: (bool) True,False
    default: False
    example: if True, this happens after calibration
polaverage -- average polarizations
    options: (bool) True,False
    default: False
outfile -- Name of output file
    default: '' (scantable)
    example:
outform -- format of output file
    options: 'ASCII','SDFITS','MS','ASAP'
    default: 'ASAP'
    example: the ASAP format is easiest for further sd
              processing; use MS for CASA imaging.
              If ASCII, then will append some stuff to
              the outfile name
overwrite -- overwrite the output file if already exists
    options: (bool) True,False
    default: False
    WARNING: if outform='ASCII', this parameter is ignored

```

DESCRIPTION:

Task `sdcoadd` merges multiple single dish spectral data given by a list of spectral data file names in any of the following formats, ASAP, MS2, and SDFITS. The units of line flux, the units of spectral axis, frame, and doppler are assumed to be those of the first one in the `sdfielist` if not specified. The `timaverage` and `polaverage` are used to perform time and polarization averaging over scans on the merged scantable to obtain coadded spectra before saving to a file on disk.

A.2.1.6 `sdflag`

Keyword arguments:

```

sdfile -- name of input SD dataset
scanlist -- list of scan numbers to process
    default: [] (use all scans)
    example: [21,22,23,24]
              this selection is in addition to field
              and iflist
field -- selection string for selecting scans by name

```

```

default: '' (no name selection)
example: 'FLS3a*'
        this selection is in addition to scanlist
        and iflist
iflist -- list of IF id numbers to select
    default: [] (use all IFs)
    example: [15]
        this selection is in addition to scanlist
        and field
maskflag -- list of mask regions to apply flag/unflag
    default: [] (entire spectrum)
    example: [[1000,3000],[5000,7000]]
flagmode -- flag mode
    default: 'flag'
    options: 'flag','unflag','restore'
        in 'restore' mode, a history of flagging is
        displayed and current flag state is returned
outfile -- Name of output file
    default: '' (<sdfile>_f)
outform -- format of output file
    options: 'ASCII','SDFITS','MS','ASAP'
    default: 'ASAP'
    example: the ASAP format is easiest for further sd
            processing; use MS for CASA imaging.
overwrite -- overwrite the output file if already exists
    options: (bool) True,False
    default: False
    WARNING: if outform='ASCII', this parameter is ignored
plotlevel -- control for plotting of results
    options: (int) 0=none, 1=some, 2=more, <0=hardcopy
    default: 0 (no plotting)
    example: plotlevel<0 as abs(plotlevel), e.g.
            -1 => hardcopy of final plot (will be named
            <outfile>_flag.eps)
    WARNING: be careful plotting in fsotf mode!
-----
```

Returns: Current values of maskflag for each spectrum as a list,
 only if flagmode is set to 'restore'. Note that the
 'restore' mode refers scanlist, iflist, and pollist.

DESCRIPTION:

Task `sdflag` performs simple channel based flagging on spectra. The flag regions in channels can be specified in `maskflag`. This is not interactive flagging. If `plotlevel>=1`, the task asks you if

you really apply the flags before it is actually written to the data with a plot indicating flagged regions. The flags are not written to the current (input) datasets unless `outfile='none'`. Please note that this task is still experimental.

Beta Patch 3 New Features: Flagged regions (or values of flag masks already applied) of the input data can be listed by setting `flagmode='restore'`. It will print out a summary on the screen and returns maskflag values for each spectrum as a list.

A.2.1.7 sdfit

Keyword arguments:

```
sdfit -- name of input SD dataset
    default: none - must input file name
    example: 'mysd.asap'
        See sdcal for allowed formats.

fluxunit -- units for line flux
    options: (str) 'K','Jy',''
    default: '' (keep current fluxunit)
    WARNING: For GBT data, see description below.
    >>> fluxunit expandable parameter
    telescopeparm -- the telescope characteristics
        options: (str) name or (list) list of gain info
        default: '' (none set)
        example: if telescopeparm='', it tries to get the telescope
            name from the data.
        Full antenna parameters (diameter,ap.eff.) known
        to ASAP are
        'ATPKSMB', 'ATPKSHOH', 'ATMOPRA', 'DSS-43',
        'CEDUNA', 'HOBART'. For GBT, it fixes default
        fluxunit to 'K' first then convert to
        a new fluxunit.
        telescopeparm=[104.9,0.43] diameter(m), ap.eff.
        telescopeparm=[0.743] gain in Jy/K
        telescopeparm='FIX' to change default fluxunit
        see description below

specunit -- units for spectral axis
    options: (str) 'channel','km/s','GHz','MHz','kHz','Hz','',''
    default: '' (=current)

frame -- frequency frame for spectral axis
    options: (str) 'LSRK','REST','TOPO','LSRD','BARY',
             'GEO','GALACTO','LGROUP','CMB'
    default: currently set frame in scantable
    WARNING: frame='REST' not yet implemented

doppler -- doppler mode
```

```
options: (str) 'RADIO','OPTICAL','Z','BETA','GAMMA'
default: currently set doppler in scantable
scanlist -- list of scan numbers to process
    default: [] (use all scans)
    example: [21,22,23,24]
field -- selection string for selecting scans by name
    default: '' (no name selection)
    example: 'FLS3a*'
        this selection is in addition to scanlist
        and iflist
iflist -- list of IF id numbers to select
    default: [] (use all IFs)
    example: [15]
pollist -- list of polarization id numbers to select
    default: [] (use all polarizations)
    example: [1]
fitmode -- mode for fitting
    options: (str) 'list','auto'
    default: 'auto'
    example: 'list' will use maskline to define regions to
            fit for lines with nfit in each
            'auto' will use the linefinder to fit for lines
            using the following parameters
    >>> fitmode expandable parameters
thresh -- S/N threshold for linefinder
    default: 5
    example: a single channel S/N ratio above which
            the channel is considered to be a detection
min_nchan -- minimum number of consecutive channels for linefinder
    default: 3
    example: minimum number of consecutive channels required to
            pass threshold
avg_limit -- channel averaging for broad lines
    default: 4
    example: a number of consecutive channels not greater than
            this parameter can be averaged to search for
            broad lines
box_size -- running mean box size
    default: 0.2
    example: a running mean box size specified as a fraction
            of the total spectrum length
edge -- channels to drop at beginning and end of spectrum
    default: 0
    example: [1000] drops 1000 channels at beginning AND end
            [1000,500] drops 1000 from beginning and 500
```

```
from end
```

Note: For bad baselines threshold should be increased, and avg_limit decreased (or even switched off completely by setting this parameter to 1) to avoid detecting baseline undulations instead of real lines.

```
maskline -- list of mask regions to INCLUDE in LINE fitting
    default: all
    example: maskline=[[3900,4300]] for a single region, or
              maskline=[[3900,4300],[5000,5400]] for two, etc.
invertmask -- invert mask (EXCLUDE masklist instead)
    options: (bool) True, False
    default: False
    example: invertmask=True, then will make one region that is
              the exclusion of the maskline regions
nfit -- list of number of gaussian lines to fit in in maskline region
    default: 0 (no fitting)
    example: nfit=[1] for single line in single region,
              nfit=[2] for two lines in single region,
              nfit=[1,1] for single lines in each of two regions, etc.
fitfile -- name of output file for fit results
    default: no output fit file
    example: 'mysd.fit'
plotlevel -- control for plotting of results
    options: (int) 0=none, 1=some, 2=more
    default: 0 (no plotting)
    example: plotlevel=1 plots fit and residual
              no hardcopy available for fitter
WARNING: be careful plotting OTF data with lots of fields
```

Returns a Python dictionary of line statistics

```
keys:    'peak','cent','fwhm'
example: each value is a list of lists with one list of
          2 entries [fitvalue,error] per component.
          e.g. xstat['peak']=[[234.9, 4.8],[234.2, 5.3]]
          for 2 components.
```

DESCRIPTION:

Task **sdfit** is a basic line-fitter for single-dish spectra. It assumes that the spectra have been calibrated in **sdaverage** or **sdcal**.

Furthermore, it assumes that any selection of scans, IFs, polarizations, and time and channel averaging/smoothing has also already been done (in other sd tasks) as there are no controls for

these. Note that you can use `sdsave` to do selection, writing out a new scantable.

Note that multiple scans and IFs can in principle be handled, but we recommend that you use scanlist, field, and iflist to give a single selection for each fit.

For complicated spectra, `sdfit` does not do a good job of "auto-guessing" the starting model for the fit. We recommend you use `sd.fitter` in the toolkit which has more options, such as fixing components in the fit and supplying starting guesses by hand.

See the `sdaverage` description for information on `fluxunit` conversion and the `telescopeparm` parameter.

Beta Patch 3 New Features: Now fit all spectra specified in scanlist, iflist, and pollist.

A.2.1.8 `sdlist`

Keyword arguments:

```

sdfile -- name of input SD dataset
scanaverage -- average integrations within scans
    options: (bool) True, False
    default: False
    example: if True, this happens in read-in
              For GBT, set False!
listfile -- Name of output file for summary list
    default: '' (no output file)
    example: 'mysd_summary.txt'
overwrite -- overwrite the output file if already exists
    options: (bool) True, False
    default: False

```

DESCRIPTION:

Task `sdlist` lists the scan summary of the dataset after importing as a scantable into ASAP. It will optionally output this summary as file.

Note that if your `PAGER` environment variable is set to 'less' and you have set the '`verbose`' ASAP environment variable to True (the default), then the screen version of the summary will page. You can disable this for `sdlist` by setting `sd.rcParams['verbose']=False` before running `sdlist`. Set it back afterward if you want lots of information.

A.2.1.9 `sdplot`

Keyword arguments:

```

sdfile -- name of input SD dataset
fluxunit -- units for line flux
    options: 'K', 'Jy', ''

```

```

default: '' (keep current fluxunit)
WARNING: For GBT data, see description below.
>>> fluxunit expandable parameter
telescopeparm -- the telescope characteristics
    options: (str) name or (list) list of gain info
    default: '' (none set)
    example: if telescopeparm='', it tries to get the telescope
              name from the data.
    Full antenna parameters (diameter,ap.eff.) known
    to ASAP are
    'ATPKSMB', 'ATPKSHOH', 'ATMOPRA', 'DSS-43',
    'CEDUNA', 'HOBART'. For GBT, it fixes default fluxunit
    to 'K' first then convert to a new fluxunit.
    telescopeparm=[104.9,0.43] diameter(m), ap.eff.
    telescopeparm=[0.743] gain in Jy/K
    telescopeparm='FIX' to change default fluxunit
    see description below

specunit -- units for spectral axis
    options: (str) 'channel','km/s','GHz','MHz','kHz','Hz'
    default: '' (=current)
    example: this will be the units for masklist
frame -- frequency frame for spectral axis
    options: (str) 'LSRK','REST','TOPO','LSRD','BARY',
             'GEO','GALACTO','LGROUP','CMB'
    default: currently set frame in scantable
    WARNING: frame='REST' not yet implemented
doppler -- doppler mode
    options: (str) 'RADIO','OPTICAL','Z','BETA','GAMMA'
    default: currently set doppler in scantable
scanlist -- list of scan numbers to process
    default: [] (use all scans)
    example: [21,22,23,24]
        this selection is in addition to field
        iflist and pollist
field -- selection string for selecting scans by name
    default: '' (no name selection)
    example: 'FLS3a*'
        this selection is in addition to scanlist
        iflist and pollist
iflist -- list of IF id numbers to select
    default: [] (use all IFs)
    example: [15]
        this selection is in addition to scanlist
        field and pollist

```

```

pololist -- list of polarization id numbers to select
    default: [] (use all polarizations)
    example: [1]
        this selection is in addition to scanlist,
        field, and iflist
scanaverage -- average integs within scans
    options: (bool) True,False
    default: False
timeaverage -- average times for multiple scan cycles
    options: (bool) True,False
    default: False
    example: if True, this happens after calibration
    >>>timeaverage expandable parameter
    tweight -- weighting for time average
        options: 'none'
            'var'   (1/var(spec) weighted)
            'tsys'  (1/Tsys**2 weighted)
            'tint'  (integration time weighted)
            'tintsy' (Tint/Tsys**2)
            'median' ( median averaging)
        default: 'none'
polaverage -- average polarizations
    options: (bool) True,False
    default: False
    >>>polaverage expandable parameter
    pweight -- weighting for polarization average
        options: 'none'
            'var'   (1/var(spec) weighted)
            'tsys'  (1/Tsys**2 weighted)
kernel -- type of spectral smoothing
    options: 'hanning','gaussian','boxcar', 'none'
    default: 'none'
    >>>kernel expandable parameter
    kwidth -- width of spectral smoothing kernel
        options: (int) in channels
        default: 5
        example: 5 or 10 seem to be popular for boxcar
                ignored for hanning (fixed at 5 chans)
                (0 will turn off gaussian or boxcar)
plottype -- type of plot
    options: 'spectra','totalpower','pointing','azel'
    default: 'spectra'
stack -- code for stacking on single plot for spectral plotting
    options: 'p','b','i','t','s' or
            'pol', 'beam', 'if', 'time', 'scan'

```

```

default: 'p'
example: maximum of 25 stacked spectra
          stack by pol, beam, if, time, scan
panel -- code for splitting into multiple panels for spectral plotting
options: 'p','b','i','t','s' or
         'pol', 'beam', 'if', 'time', 'scan'
default: 'i'
example: maximum of 25 panels
          panel by pol, beam, if, time, scan
flrange -- range for flux axis of plot for spectral plotting
options: (list) [min,max]
default: [] (full range)
example: flrange=[-0.1,2.0] if 'K'
          assumes current fluxunit
sprange -- range for spectral axis of plot
options: (list) [min,max]
default: [] (full range)
example: sprange=[42.1,42.5] if 'GHz'
          assumes current specunit
linecat -- control for line catalog plotting for spectral plotting
options: (str) 'all','none' or by molecule
default: 'none' (no lines plotted)
example: linecat='SiO' for SiO lines
          linecat='*OH' for alcohols
          uses sprange to limit catalog
WARNING: specunit must be in frequency (*Hz)
          to plot from the line catalog!
          and must be 'GHz' or 'MHz' to use
          sprange to limit catalog
linedop -- doppler offset for line catalog plotting (spectral plotting)
options: (float) doppler velocity (km/s)
default: 0.0
example: linedop=-30.0
colormap -- the colours to be used for plot lines.
default: None
example: colormap="green red black cyan magenta" (html standard)
          colormap="g r k c m" (abbreviation)
          colormap="#008000 #00FFFF #FF0090" (RGB tuple)
          The plotter will cycle through these colours
          when lines are overlaid (stacking mode).
linestyles -- the linestyles to be used for plot lines.
default: None
example: linestyles="line dashed dotted dashdot dashdotdot dashdashdot".
          The plotter will cycle through these linestyles
          when lines are overlaid (stacking mode).

```

```

WARNING: Linestyles can be specified only one color has been set.
linewidth -- width of plotted lines.
    default: None
    example: linewidth=1 (integer)
              linewidth=0.75 (double)
histogram -- plot histogram
    options: (bool) True, False
    default: False
plotfile -- file name for hardcopy output
    options: (str) filename.eps,.ps,.png
    default: '' (no hardcopy)
    example: 'specplot.eps','specplot.png'
              Note this autodetects the format from
              the suffix (.eps,.ps,.png).
overwrite -- overwrite the output file if already exists
    options: (bool) True, False
    default: False

```

DESCRIPTION:

Task **sdplot** displays single-dish spectra. It assumes that the spectra have been calibrated in **sdcal**. It does allow selection of scans, IFs, polarizations, and some time and channel averaging/smoothing options also, but does not write out this data.

*** Only apply to 'spectra' **plottype** ***

Note that **colormap** and **linestyles** cannot be controlled at a time. The '**linestyles**' is ignored if both of them are specified. Some plot options, like annotation and changing titles, legends, fonts, and the like are not supported in this task. You should use **sd.plotter** from the ASAP toolkit directly for this.

This task uses the JPL line catalog as supplied by ASAP. If you wish to use a different catalog, or have it plot the line IDs from top or bottom (rather than alternating), then you will need to explore the **sd** toolkit also. See § A.3.9 for more information.

Note that multiple scans and IFs can in principle be handled through stacking and paneling, but this is fairly rudimentary at present and you have little control of what happens in individual panels. We recommend that you use **scanlist**, **field**, and **iflist** to give a single selection for each run.

After plotting, you can display a spectral value on a pop-up window along with mouse movement. Click the LEFT-mouse button over a spectrum to select it, and drag mouse in the panel to output its value at the x-position of mouse cursor. The selection is released when you release the mouse button.

*** other **plottype** options ***

plottype='totalpower' is used to plot the total power data. and only plot option is amplitude versus data row number. **plottype='azel'** plots azimuth and elevation tracks of the source.

`plottype='pointing'` plots antenna pointings. Currently most of the plotting parameters are ignored these modes.

See the `sdaverage` description for information on `fluxunit` conversion and the `telescopeparm` parameter.

WARNING: be careful plotting OTF (on-the-fly) mosaic data with lots of fields!

Beta Patch 3 New Features: For spectral plotting (`plottype='spectra'`), following new features are available:

- Now, some header information of the data are plotted at top
- Time averaging of integrations within each scan but not across scans can be done by setting `scanaverage=True` and `timeaverage=False`
- The control of plot line properties, `colormap`, `linestyles`, and `linewidth` are now available
- You can select a spectrum and display it's data value on a pop-up window interactively using mouse

A new `plottype` option, '`totalpower`' can be used to plot total power data. Currently it is limited to a plot in amplitude versus row number.

A.2.1.10 sdsave

Keyword arguments:

```

sdfile -- name of input SD dataset
scanlist -- list of to process
    default: [] (use all scans)
    example: [21,22,23,24]
        this selection is in addition to field,
        iflist, and pollist
field -- selection string for selecting scans by name
    default: '' (no name selection)
    example: 'FLS3a*'
        this selection is in addition to scanlist,
        iflist, and pollist
iflist -- list of IF id numbers to select
    default: [] (use all IFs)
    example: [15]
        this selection is in addition to scanlist,
        field, and pollist
pollist -- list of polarization id numbers to select
    default: [] (use all polarizations)
    example: [1]
        this selection is in addition to scanlist,
```

```

        field, and iflist
scanaverage -- average integrations within scans
    options: (bool) True,False
    default: False
    example: if True, average integrations before it is saved
timeaverage -- average times for multiple scan cycles
    options: (bool) True,False
    default: False
    >>>timeaverage expandable parameter
    tweight -- weighting for time average
        options: 'none'
            'var'   (1/var(spec) weighted)
            'tsys'  (1/Tsys**2 weighted)
            'tint'  (integration time weighted)
            'tintsys' (Tint/Tsys**2)
            'median' ( median averaging)
    default: 'none'

polaverage -- average polarizations
    options: (bool) True,False
    default: False
    >>>polaverage expandable parameter
    pweight -- weighting for polarization average
        options: 'none'
            'var'   (1/var(spec) weighted)
            'tsys'  (1/Tsys**2 weighted)

outfile -- name of output dataset
    default: ''
outform -- output data format
    default: 'ASAP'
    Options: 'ASAP', 'MS2', 'SDFITS', 'ASCII'
overwrite -- overwrite the output file if already exists
    options: (bool) True,False
    default: False
    WARNING: if outform='ASCII', this parameter is ignored

```

DESCRIPTION:

Task `sdsave` writes the single dish data to a disk file in specified format (ASAP, MS2, SDFITS, ASCII). It is possible to save the subset of the data by selecting scan numbers, IF ids and field names. The ASAP (scantable) format is recommended for further analysis using `sd` tool. For further imaging using `imager`, save the data to the Measurement Set (MS2).

A.2.1.11 sdscale

Keyword arguments:

```

sdfile -- name of input SD dataset
factor -- scaling factor
    default: 1 (no scaling)
scaletsys -- scaling of associated Tsys
    default: False
outfile -- output file name
    outfile=''' will write the data to a file named,
    <sdfile>_scaled<factor>
    default: ''
overwrite -- overwrite the output file if already exists
    options: (bool) True, False
    default: False

```

DESCRIPTION:

Task **sdscale** performs scaling of single-dish spectra. By setting **scaletsys** = **True**, associated Tsys is also scaled. Tsys informations are written into the file 'sdscale.log' as well as they are displayed in the terminal window. The **infile** can be any of ASAP, MS, SDFITS, or RPFITS format. If **outfile** name is given or **outfile=''**(default), the scaled data is written to a new file with the same format as the input data (Note: in case of the RPFITS format input data, it will be written to SDFITS format).

Beta Patch 3 New Features: Tsys values before and after scaling are display and stored in **sdscale.log**.

A.2.1.12 sdstat**Keyword arguments:**

```

sdfile -- name of input SD dataset
    default: none - must input file name
    example: 'mysd.asap'
        See sdcal for allowed formats.
fluxunit -- units for line flux
    options: (str) 'K', 'Jy', ''
    default: '' (keep current fluxunit)
    WARNING: For GBT data, see description below.
    >>> fluxunit expandable parameter
telescopeparm -- the telescope characteristics
    options: (str) name or (list) list of gain info
    default: '' (none set)
    example: if telescopeparm='', it tries to get the telescope
            name from the data.

```

```

Full antenna parameters (diameter,ap.eff.) known
to ASAP are
'ATPKSMB', 'ATPKSHOH', 'ATMOPRA', 'DSS-43',
'CEDUNA', 'HOBART'. For GBT, it fixes default fluxunit
to 'K' first then convert to a new fluxunit.
telescopeparm=[104.9,0.43] diameter(m), ap.eff.
telescopeparm=[0.743] gain in Jy/K
telescopeparm='FIX' to change default fluxunit
see description below

specunit -- units for spectral axis
    options: (str) 'channel', 'km/s', 'GHz', 'MHz', 'kHz', 'Hz', ''
    default: '' (=current)
frame -- frequency frame for spectral axis
    options: (str) 'LSRK', 'REST', 'TOPO', 'LSRD', 'BARY',
              'GEO', 'GALACTO', 'LGROUP', 'CMB'
    default: currently set frame in scantable
    WARNING: frame='REST' not yet implemented
doppler -- doppler mode
    options: (str) 'RADIO', 'OPTICAL', 'Z', 'BETA', 'GAMMA'
    default: currently set doppler in scantable
scanlist -- list of scan numbers to process
    default: [] (use all scans)
    example: [21,22,23,24]
field -- selection string for selecting scans by name
    default: '' (no name selection)
    example: 'FLS3a*'
            this selection is in addition to scanlist
            iflist, and pollist
iflist -- list of IF id numbers to select
    default: [] (use all IFs)
    example: [15]
            this selection is in addition to field, scanlist
            and pollist
pollist -- list of polarization id numbers to select
    default: [] (use all pols)
    example: [1]
            this selection is in addition to field, scanlist
            and iflist
masklist -- list of mask regions to INCLUDE in stats
    default: [] (whole spectrum)
    example: [4000,4500] for one region
              [[1000,3000],[5000,7000]]
              these must be pairs of [lo,hi] boundaries
invertmask -- invert mask (EXCLUDE masklist instead)

```

```

options: (bool) True, False
default: false
interactive -- determines interactive masking
options: (bool) True, False
default: False
example: interactive=True allows adding and deleting mask
regions by drawing rectangles on the plot with mouse.
Draw a rectangle with LEFT-mouse to ADD the region to
the mask and with RIGHT-mouse to DELETE the region.
statfile -- name of output file for line statistics
default: '' (no output statistics file)
example: 'stat.txt'

```

```

Returns: a Python dictionary of line statistics
keys: 'rms', 'stddev', 'max', 'min', 'sum', 'median', 'mean',
      'eqw'
example: xstat=sdstat(); print "rms = ",xstat['rms']
these can be used for testing in scripts or
for regression

'eqw' is equivalent width (sum/mag) where mag
is either max or min depending on which has
greater magnitude.

```

DESCRIPTION:

Task **sdstat** computes basic statistics (rms,mean,median,sum) for single-dish spectra. It assumes that the spectra have been calibrated. Furthermore, it assumes that any time and channel averaging/smoothing has also already been done as there are no controls for these. Note that you can run **sdcal** with **calmode='none'** and do selection, writing out a new scantable.

Note that multiple scans and IFs can in principle be handled, but we recommend that you use **scanlist**, **field**, **iflist**, and **pollist** to give a single selection for each run.

See the **sdcal** description for information on **fluxunit** conversion and the **telescopeparm** parameter.

WARNING: If you do have multiple scantable rows, then **xstat** values will be lists.

Beta Patch 3 New Features: The calculated statistics are written into a file specified by **statfile**. Interactive mask specification is possible with **interactive=True**. Integrated intensity will be shown on the screen and will be included in the saved statfile (but not yet available in the returned dictionary).

A.2.1.13 sdtpimaging

Keyword arguments:

```

sdfile -- name of input SD (MS) dataset
calmode -- calibration mode (currently only baseline subtraction)
    options: 'baseline', 'none'
    default: 'none'
    example: choose mode 'none' if you have
            already calibrated and want to do
            plotting nd/or imaging
>>> calmode='baseline' expandable parameters
masklist -- mask in numbers of rows from each edge of each scan to be
            included for baseline fitting
    default: none
    example: [30,30] or [30]
            used first 30 rows and last 30 rows of each scan for
            the baseline
blpoly -- polynomial order for the baseline fit
    default: 1
flaglist -- list of scan numbers to flag (ranges can be accepted)
    default: [] (use all scans)
    example: [[0,3],80]
            flag the scan range [0,3] = [0,1,2,3] and scan 80
antenna -- select data based on antenna name(s) or id(s) in string
    default: '' (use all antennas)
    example: '0,1', 'DV01'
    WARNING: currently baseline subtraction properly
            only one of the antennas.
createimage -- do imaging?
    default: False
>>> createimage=True expandable parameters
imagename -- output image name
    default: none
    example: 'mySDimage.im'
imsize -- x and y image size in pixels, symmetric for single value
    default: [256,256]
    example: imsize=200 (equivalent to [200,200])
cell -- x and y cell size. default unit arcmin
    default: '1.0arcmin'
    example: cell=['0.2arcmin, 0.2arcmin']
            cell='0.2arcmin' (equivalent to example above)
phasecenter -- image phase center: direction measure or fieldid
    default: 0
    example: 'J2000 13h44m00 -17d02m00', 'AZEL -123d48m29 15d41m41'
ephemsrccname -- ephemeris source name to proper shifting to center on

```

```

        the moving source for imaging
default: ''
        if the source name in the data matches one of the known
        solar objects by the system, this task automatically set
        the source name.
example: 'moon'
plotlevel -- control for plotting of results
options: (int) 0=none, 1=some, 2=more, &lt;0=hardcopy
default: 0 (no plotting)
example: plotlevel&lt;0 as abs(plotlevel), e.g.
        -1: hardcopy plot (will be named &lt;sdfile&gt;_scans.eps)
        1: plot raw data, calibrated data (for calmode='baseline')
            plot raw or if exist calibrated data (for calmode='none')
        2: plot raw data, progressively display baseline fitting
            for each scan, and final calibrated data
            (for calmode='baseline').

```

DESCRIPTION:

Task `sdtpimaging` performs data selection, calibration, and imaging for single-dish totalpower raster scan data. This is a still experimental task made to work for the data taken at the ALMA Testing Facility (ATF). Currently, this task directly accesses the Measurement Set data because of the data access efficiency. So it differs from other single-dish tasks that mostly operate on the ASAP scitable data format. By setting `calmode='none'`, one can run `sdtpimaging` to plot the data (raw or calibrated, if exists) and further imaging by setting `createimage=True`. The calibration available at this moment is just a simple baseline subtraction for each scan. The fitted regions set by `masklist` are the common for all the scans. Selection of the antennas can be made by setting antenna ID(s) or antenna name(s) in string (e.g. '0', '0,1', 'DV01',etc.). For baseline subtraction, it currently works properly for a single antenna selection. So a separate `sdtpimaging` task needs to be run for each antenna. It currently assumes that the data has a single `spw(=0)` and `fieldid(=0)`. By setting `flaglist`, one can set flag by scan numbers to be excluded from imaging. (Note: 'scan numbers' are determined from state id and related to `SUB_SCAN` column in STATE subtable and they are typically different from `SCAN_NUMBER` in MS.)

A.2.2 Single Dish Analysis Use Cases With SDTasks

A.2.2.1 GBT Position Switched Data Analysis

As an example, the following illustrates the use of the SDtasks for the Orion data set, which contains the HCCCN line in one of its IFs. This walk-through contains comments about setting parameter values and some options during processing.

```
#####
#####
```

```
#  
# ORION-S SDtasks Use Case  
# Position-Switched data  
# Version TT 2008-10-14 (updated)  
# Version STM 2007-03-04  
#  
# This is a detailed walk-through  
# for using the SDtasks on a  
# test dataset.  
#  
#####  
import time  
import os  
  
# NOTE: you should have already run  
# asap_init()  
# to import the ASAP tools as sd.<tool>  
# and the SDtasks  
  
#  
# This is the environment variable  
# pointing to the head of the CASA  
# tree that you are running  
casapath=os.environ['AIPSPATH']  
  
#  
# This bit removes old versions of the output files  
os.system('rm -rf sdusecase_orions* ')  
#  
# This is the path to the OrionS GBT ms in the data repository  
datapath=casapath+='/data/regression/ATST5/OrionS/OrionS_rawACSmod'  
#  
# The following will remove old versions of the data and  
# copy the data from the repository to your  
# current directory. Comment this out if you already have it  
# and don't want to recopy  
os.system('rm -rf OrionS_rawACSmod')  
copystring='cp -r '+datapath+' .'  
os.system(copystring)  
  
# Now is the time to set some of the more useful  
# ASAP environment parameters (the ones that the  
# ASAP User Manual claims are in the .asaprc file).  
# These are in the Python dictionary sd.rcParams  
# You can see whats in it by typing:
```

```
#sd.rcParams
# One of them is the 'verbose' parameter which tells
# ASAP whether to spew lots of verbiage during processing
# or to keep quiet. The default is
#sd.rcParams['verbose']=True
# You can make ASAP run quietly (with only task output) with
#sd.rcParams['verbose']=False

# Another key one is to tell ASAP to save memory by
# going off the disk instead. The default is
#sd.rcParams['scantable.storage']='memory'
# but if you are on a machine with small memory, do
#sd.rcParams['scantable.storage']='disk'

# You can reset back to defaults with
#sd.rcdefaults

#####
#
# ORION-S HC3N
# Position-Switched data
#
#####
startTime=time.time()
startProc=time.clock()

#####
# List data
#####
# List the contents of the dataset
# First reset parameter defaults (safe)
default('sdlist')

# You can see its inputs with
#inp('sdlist')
# or just
#inp
# now that the defaults('sdlist') set the
# taskname='sdlist'
#
# Set the name of the GBT ms file
sdfile = 'OrionS_rawACSmod'

# Set an output file in case we want to
# refer back to it
```

```

listfile = 'sdusecase_orions_summary.txt'
sdlist()

# You could also just type
#go

# You should see something like:
#
#-----
# Scan Table Summary
#-----
#Beams:          1
#IFs:           26
#Polarisations: 2   (linear)
#Channels:      8192
#
#Observer:      Joseph McMullin
#Obs Date:     2006/01/19/01:45:58
#Project:       AGBT06A_018_01
#Obs. Type:    OffOn:PSWITCHOFF:TPWCAL
#Antenna Name: GBT
#Flux Unit:    Jy
#Rest Freqs:   [4.5490258e+10] [Hz]
#Abcissa:      Channel
#Selection:    none
#
#Scan Source      Time      Integration
#      Beam    Position (J2000)
#        IF      Frame  RefVal      RefPix  Increment
#-----
# 20 OrionS_psr  01:45:58   4 x    30.0s
#      0 05:15:13.5 -05.24.08.2
#      0    LSRK  4.5489354e+10  4096    6104.233
#      1    LSRK  4.5300785e+10  4096    6104.233
#      2    LSRK  4.4074929e+10  4096    6104.233
#      3    LSRK  4.4166215e+10  4096    6104.233
# 21 OrionS_ps   01:48:38   4 x    30.0s
#      0 05:35:13.5 -05.24.08.2
#      0    LSRK  4.5489354e+10  4096    6104.233
#      1    LSRK  4.5300785e+10  4096    6104.233
#      2    LSRK  4.4074929e+10  4096    6104.233
#      3    LSRK  4.4166215e+10  4096    6104.233
# 22 OrionS_psr  01:51:21   4 x    30.0s
#      0 05:15:13.5 -05.24.08.2
#      0    LSRK  4.5489354e+10  4096    6104.233

```

```

#          1      LSRK  4.5300785e+10  4096   6104.233
#          2      LSRK  4.4074929e+10  4096   6104.233
#          3      LSRK  4.4166215e+10  4096   6104.233
# 23 OrionS_ps    01:54:01    4 x    30.0s
#          0 05:35:13.5 -05.24.08.2
#          0      LSRK  4.5489354e+10  4096   6104.233
#          1      LSRK  4.5300785e+10  4096   6104.233
#          2      LSRK  4.4074929e+10  4096   6104.233
#          3      LSRK  4.4166215e+10  4096   6104.233
# 24 OrionS_psr   02:01:47    4 x    30.0s
#          0 05:15:13.5 -05.24.08.2
#          12     LSRK  4.3962126e+10  4096   6104.2336
#          13     LSRK  4.264542e+10   4096   6104.2336
#          14     LSRK  4.159498e+10   4096   6104.2336
#          15     LSRK  4.3422823e+10  4096   6104.2336
# 25 OrionS_ps    02:04:27    4 x    30.0s
#          0 05:35:13.5 -05.24.08.2
#          12     LSRK  4.3962126e+10  4096   6104.2336
#          13     LSRK  4.264542e+10   4096   6104.2336
#          14     LSRK  4.159498e+10   4096   6104.2336
#          15     LSRK  4.3422823e+10  4096   6104.2336
# 26 OrionS_psr   02:07:10    4 x    30.0s
#          0 05:15:13.5 -05.24.08.2
#          12     LSRK  4.3962126e+10  4096   6104.2336
#          13     LSRK  4.264542e+10   4096   6104.2336
#          14     LSRK  4.159498e+10   4096   6104.2336
#          15     LSRK  4.3422823e+10  4096   6104.2336
# 27 OrionS_ps    02:09:51    4 x    30.0s
#          0 05:35:13.5 -05.24.08.2
#          12     LSRK  4.3962126e+10  4096   6104.2336
#          13     LSRK  4.264542e+10   4096   6104.2336
#          14     LSRK  4.159498e+10   4096   6104.2336
#          15     LSRK  4.3422823e+10  4096   6104.2336

# The HC3N and CH3OH lines are in IFs 0 and 2 respectively
# of scans 20,21,22,23. We will pull these out in our
# calibration.

#####
# Calibrate data
#####
# We will use the sdcal task to calibrate the data.
# Set the defaults
default('sdcal')

```

```
# You can see the inputs with
#inp

# Set our sdfile (which would have been set from our run of
# sdlist if we were not cautious and reset defaults).
sdfile = 'OrionS_rawACSmod'
fluxunit = 'K'

# Lets leave the spectral axis in channels for now
specunit = 'channel'

# This is position-switched data so we tell sdcal this
calmode = 'ps'

# For GBT data, it is safest to not have scitable pre-average
# integrations within scans.
average = True
scanaverage = False

# We do want sdcal to average up scans and polarization after
# calibration however. The averaging of scans are weighted by
# integration time and Tsys, and the averaging of polarization
# by Tsys.
timeaverage = True
tweight = 'tintsys'
polaverage = True
pweight = 'tsys'
# Do an atmospheric optical depth (attenuation) correction
# Input the zenith optical depth at 43 GHz
tau = 0.09

# Select our scans and IFs (for HC3N)
scanlist = [20,21,22,23]
iflist = [0]

# We do not require selection by field name (they are all
# the same except for on and off)
field = ''

# We will do some spectral smoothing
# For this demo we will use boxcar smoothing rather than
# the default
#kernel='hanning'
# We will set the width of the kernel to 5 channels
kernel = 'boxcar'
```

```
kwidth = 5

# We wish to fit out a baseline from the spectrum
# The GBT has particularly nasty baselines :(
# We will let ASAP use auto_poly_baseline mode
# but tell it to drop the 1000 edge channels from
# the beginning and end of the spectrum.
# A 2nd-order polynomial will suffice for this test.
# You might try higher orders for fun.
blmode = 'auto'
blpoly = 2
edge = [1000]

# We will not give it regions as an input mask
# though you could, with something like
#masklist=[[1000,3000],[5000,7000]]
masklist = []

# By default, we will not get plots in sdcal (but
# can make them using sdplot).
plotlevel = 0
# But if you wish to see a final spectrum, set
#plotlevel = 1
# or even
#plotlevel = 2
# to see intermediate plots and baselining output.

# Now we give the name for the output file
outfile = 'sdusecase_orions_hc3n.asap'

# We will write it out in ASAP scantable format
outform = 'asap'

# You can look at the inputs with
#inp

# Before running, lets save the inputs in case we want
# to come back and re-run the calibration.
saveinputs('sdcal','sdcal.orions.save')
# These can be recovered by
#execfile 'sdcal.orions.save'

# We are ready to calibrate
sdcal()
```

```
# Note that after the task ran, it produced a file
# sdcal.last which contains the inputs from the last
# run of the task (all tasks do this). You can recover
# this (anytime before sdcal is run again) with
#execfile 'sdcal.last'

#####
# List data
#####
# List the contents of the calibrated dataset
# Set the input to the just created file
sdfile = outfile
listfile = ''
sdlist()

# You should see:
#
#-----
# Scan Table Summary
#-----
#Beams:          1
#IFs:           26
#Polarisations: 1   (linear)
#Channels:      8192
#
#Observer:      Joseph McMullin
#Obs Date:     2006/01/19/01:45:58
#Project:       AGBT06A_018_01
#Obs. Type:    OffOn:PSWITCHOFF:TPWCAL
#Antenna Name: GBT
#Flux Unit:    K
#Rest Freqs:   [4.5490258e+10] [Hz]
#Abcissa:      Channel
#Selection:    none
#
#Scan Source      Time      Integration
#      Beam    Position (J2000)
#          IF      Frame   RefVal          RefPix   Increment
#-----
#  0 OrionS_ps    01:52:05    1 x    08:00.5
#      0    05:35:13.5 -05.24.08.2
#          0      LSRK  4.5489354e+10    4096    6104.233
#
# Note that our scans are now collapsed (timeaverage=True) but
# we still have our IF 0
```

```
#####
# Plot data
#####
default('sdplot')

# The file we produced after calibration
# (if we hadn't reset defaults it would have
# been set - note that sdplot,sdfit,sdstat use
# sdfile as the input file, which is the output
# file of sdcal).
sdfile = 'sdusecase_orions_hc3n.asap'

# Lets just go ahead and plot it up as-is
sdplot()

# Looks ok. Plot with x-axis in GHz
specunit='GHz'
sdplot()

# Note that the rest frequency in the scantable
# is set correctly to the HCCCN line at 45.490 GHz.
# So you can plot the spectrum in km/s
specunit='km/s'
sdplot()

# Zoom in
sprange=[-100,50]
sdplot()

# Lets plot up the lines to be sure
# We have to go back to GHz for this
# (known deficiency in ASAP)
specunit='GHz'
sprange=[45.48,45.51]
linecat='all'
sdplot()

# Too many lines! Focus on the HC3N ones
linecat='HCCCN'
sdplot()

# Finally, we can convert from K to Jy
# using the aperture efficiencies we have
# coded into the sdtasks
```

```
# For GBT data, do not set telescopeparm
fluxunit='Jy'
telescopeparm=''
sdplot()

# Lets save this plot
plotfile='sdusecase_orions_hc3n.eps'
sdplot()

#####
# Off-line Statistics
#####
# Now do some region statistics
# First the line-free region
# Set parameters
default('sdstat')
sdfile = 'sdusecase_orions_hc3n.asap'

# Keep the default spectrum and flux units
# K and channel
fluxunit = ''
specunit = ''

# Pick out a line-free region
# You can bring up a default sdplot again
# to check this
masklist = [[5000,7000]]

# This is a line-free region so we don't need
# to invert the mask
invertmask = False

# You can check with
#inp

# sdstat returns some results in
# the Python dictionary.  You can assign
# this to a variable
off_stat=sdstat()

# and look at it
off_stat
# which should give
# {'eqw': 38.563105620704945,
#  'max': 0.15543246269226074,
```

```
# 'mean': -0.0030361821409314871,
# 'median': -0.0032975673675537109,
# 'min': -0.15754437446594238,
# 'rms': 0.047580458223819733,
# 'stddev': 0.047495327889919281,
# 'sum': -6.0754003524780273}

#You see it has some keywords for the various
#stats. We want the standard deviation about
#the mean, or 'stddev'
print "The off-line std. deviation = ",off_stat['stddev']
# which should give
# The off-line std. deviation = 0.0474953278899

# or better formatted (using Python I/O formatting)
print "The off-line std. deviation = %5.3f K" \%(
    off_stat['stddev'])
# which should give
# The off-line std. deviation = 0.047 K

#####
# On-line Statistics
#####
# Now do the line region
# Continue setting or resetting parameters
masklist = [[3900,4200]]

line_stat = sdstat()

# look at these
line_stat
# which gives
# {'eqw': 73.335154614280981,
# 'max': 0.92909121513366699,
# 'mean': 0.22636228799819946,
# 'median': 0.10317134857177734,
# 'min': -0.13283586502075195,
# 'rms': 0.35585442185401917,
# 'stddev': 0.27503398060798645,
# 'sum': 68.135047912597656}

# of particular interest are the max value
print "The on-line maximum = %5.3f K" % (line_stat['max'])
# which gives
```

```
# The on-line maximum = 0.929 K

# and the estimated equivalent width (in channels)
# which is the sum/max
print "The estimated equivalent width = %5.1f channels" \%\\
      (line_stat['eqw'])
# which gives
# The estimated equivalent width = 73.3 channels

#####
# Line Fitting
#####
# Now we are ready to do some line fitting
# Default the parameters
default('sdfit')

# Set our input file
sdfile = 'sdusecase_orions_hc3n.asap'

# Stick to defaults
# fluxunit = 'K', specunit = 'channel'
fluxunit = ''
specunit = ''

# We will try auto-fitting first
fitmode = 'auto'
# A single Gaussian
nfit = [1]
# Leave the auto-parameters to their defaults for
# now, except ignore the edge channels
edge = [1000]

# Lets see a plot while doing this
plotlevel = 1

# Save the fit output in a file
fitfile = 'sdusecase_orions_hc3n.fit'

# Go ahead and do the fit
fit_stat=sdfit()

# If you had verbose mode on, you probably saw something
# like:
#
# 0: peak = 0.811 K , centre = 4091.041 channel, FWHM = 72.900 channel
```

```

#      area = 62.918 K channel
#
# The fit is output in the dictionary

fit_stat
#
# {'cent': [[4091.04052734375, 0.72398632764816284]],
#  'fwhm': [[72.899894714355469, 1.7048574686050415]],
#  'nfit': 1,
#  'peak': [[0.81080442667007446, 0.016420882195234299]]}
#
# So you can write them out or test them:
print "The line-fit parameters were:"
print "      maximum = %6.3f +/- %6.3f K" \
      (fit_stat['peak'][0][0],fit_stat['peak'][0][1])
print "      center = %6.1f +/- %6.1f channels" \
      (fit_stat['cent'][0][0],fit_stat['cent'][0][1])
print "      FWHM = %6.2f +/- %6.2f channels" \
      (fit_stat['fwhm'][0][0],fit_stat['fwhm'][0][1])
#
# Which gives:
# The line-fit parameters were:
#      maximum = 0.811 +/- 0.016 K
#      center = 4091.0 +/- 0.7 channels
#      FWHM = 72.90 +/- 1.70 channels

# We can do the fit in km/s also
specunit = 'km/s'
# For some reason we need to help it along with a mask
maskline = [-50,0]

fitfile = 'sdusecase_orions_hc3n_kms.fit'
fit_stat_kms = sdfit()
# Should give (if in verbose mode)
# 0: peak = 0.811 K , centre = -27.134 km/s, FWHM = 2.933 km/s
#      area = 2.531 K km/s
#
#
# with
fit_stat_kms
# giving
# {'cent': [[-27.133651733398438, 0.016480101272463799]],
#  'fwhm': [[2.93294358253479, 0.038807671517133713]],
```

```

# 'nfit': 1,
# 'peak': [[0.81080895662307739, 0.0092909494414925575]]}

print "The line-fit parameters were:"
print "    maximum = %6.3f +/- %6.3f K" \%(
    (fit_stat_kms['peak'][0][0],fit_stat_kms['peak'][0][1])
print "    center = %6.2f +/- %6.2f km/s" \%(
    (fit_stat_kms['cent'][0][0],fit_stat_kms['cent'][0][1])
print "    FWHM = %6.4f +/- %6.4f km/s" \%(
    (fit_stat_kms['fwhm'][0][0],fit_stat_kms['fwhm'][0][1])

# The line-fit parameters were:
#     maximum = 0.811 +/- 0.009 K
#     center = -27.13 +/- 0.02 km/s
#     FWHM = 2.9329 +/- 0.0388 km/s

#####
#
# End ORION-S Use Case
#
#####

```

A.2.2.2 Imaging of Total Power Raster Scans

This example illustrates the use of `sdtpimaging` for the total power raster scans of the Moon taken at ATF.

```

# load single dish module
# asap_init()

# The data used here (uid__X1e1_X3197_X1.ms) is the total power
# raster scans of the Moon taken at ATF (with both antennas).
# It is in MS format which was converted from the ASDM format.

# Do data plotting only
default(sdtpimaging)
inp()
plotlevel=2
# select antenna 1 (Vertex antenna)
antenna='1'
sdfile='uid__X1e1_X3197_X1.ms'
sdtpimaging()

```




Figure A.2: Total power data display using `sdtpimaging`, with `calmode='baseline'`. The top panel shows uncalibrated data versus row numbers. The middle panel shows baseline fitting of each scan (only shown here the last scan). The bottom panel shows the calibrated (baseline subtracted) data.

```
# Now, rerun sdtpimaging to do actual data reduction (applying
# baseline subtraction from each scan, and then do imaging).
#
# Do baseline subtraction
calmode='baseline'
masklist=[30] # use 30 data points from each end of scan for fitting
# Do imaging
createimage=True
imagename='moon.im'
imagesize=[200,200]
```

```

cell=[0.2] # in arcmin
phasename='AZEL 187d54m22s 41d03m0s'
ephemsrcname='moon' # specify ephemeris source name (can be omitted)
plotlevel=1
#plotlevel=2 to see progress of each fitting
sdtpimaging()

```

A.3 Using The ASAP Toolkit Within CASA

ASAP is included with the CASA installation/build. It is not loaded upon start-up, however, and must be imported as a standard Python package. A convenience function exists for importing ASAP along with a set of prototype tasks for single dish analysis:

```
CASA <1>: asap_init
```

Once this is done, all of the ASAP functionality is now under the Python 'sd' tool. **Note:** This means that if you are following the ASAP cookbook or documentation, all of the commands should be invoked with a 'sd.' before the native ASAP command.

The ASAP interface is essentially the same as that of the CASA toolkit, that is, there are groups of functionality (aka tools) which have the ability to operate on your data. Type:

```

CASA <4>: sd.<TAB>
sd.__class__           sd._validate_bool      sd.list_scans
sd.__date__            sd._validate_int       sd.mask_and
sd.__delattr__         sd.asapfitter          sd.mask_not
sd.__dict__             sd.asaplinefind      sd.mask_or
sd.__doc__              sd.asaplog            sd.merge
sd.__file__             sd.asaplotbase        sd.os
sd.__getattribute__    sd.asaplotgui         sd.plf
sd.__hash__             sd.asapmath           sd.plotter
sd.__init__             sd.asapplotter        sd.print_log
sd.__name__             sd.asapreader         sd.quotient
sd.__new__              sd.average_time      sd.rc
sd.__path__             sd.calfs              sd.rcParams
sd.__reduce__           sd.calnod             sd.rcParamsDefault
sd.__reduce_ex__        sd.calps              sd.rc_params
sd.__repr__             sd.commands           sd.rcdefaults
sd.__setattr__          sd.defaultParams      sd.reader
sd.__str__              sd.dosigref          sd.scantable
sd.__version__          sd.dototalpower      sd.selector
sd._asap                sd.fitter             sd.simple_math
sd._asap_fname          sd.is_ipython         sd.sys
sd._asaplog             sd.linecatalog        sd.unique
sd._is_sequence_or_number sd.linefinder        sd.version
sd._n_bools             sd.list_files        sd.welcome
sd._to_list             sd.list_rcparameters sd.xyplotter

```

...to see the list of tools.

In particular, the following are essential for most reduction sessions:

- `sd.scantable` - the data structure for ASAP and the core methods for manipulating the data; allows importing data, making data selections, basic operations (averaging, baselines, etc) and setting data characteristics (e.g., frequencies, etc).
- `sd.selector` - selects a subset of data for subsequent operations
- `sd.fitter` - fit data
- `sd.plotter` - plotting facilities (uses `matplotlib`)

The `scantable` functions are used most often and can be applied to both the initial scantable and to any spectrum from that scan table. Type

```
sd.scantable.<TAB>
```

(using TAB completion) to see the full list.

A.3.1 Environment Variables

The `asaprc` environment variables are stored in the Python dictionary `sd.rcParams` in CASA. This contains a number of parameters that control how ASAP runs, for both tools and tasks. You can see what these are set to by typing at the CASA prompt:

```
CASA <2>: sd.rcParams
Out[2]:
{'insitu': True,
 'plotter.colours': '',
 'plotter.decimate': False,
 'plotter.ganged': True,
 'plotter.gui': True,
 'plotter.histogram': False,
 'plotter.linestyles': '',
 'plotter.panelling': 's',
 'plotter.papertype': 'A4',
 'plotter.stacking': 'p',
 'scantable.autoaverage': True,
 'scantable.freqframe': 'LSRK',
 'scantable.save': 'ASAP',
 'scantable.storage': 'memory',
 'scantable.verbosesummary': False,
 'useplotter': True,
 'verbose': True}
```

The use of these parameters is described in detail in the ASAP Users Guide.

You can also change these parameters through the `sd.rc` function. The use of this is described in `help sd.rc`:

```
CASA <3>: help(sd.rc)
Help on function rc in module asap:

rc(group, **kwargs)
Set the current rc params. Group is the grouping for the rc, eg
for scantable.save the group is 'scantable', for plotter.stacking, the
group is 'plotter', and so on. kwargs is a list of attribute
name/value pairs, eg

    rc('scantable', save='SDFITS')

sets the current rc params and is equivalent to

    rcParams['scantable.save'] = 'SDFITS'

Use rcdefaults to restore the default rc params after changes.
```

A.3.2 Import

Data can be loaded into ASAP by using the `scantable` function which will read a variety of recognized formats (RPFITS, varieties of SDFITS, and the CASA Measurement Set). For example:

```
CASA <1>: scans = sd.scantable('OrionS_rawACSmod', average=False)
Importing OrionS_rawACSmod...
```

NOTE: It is important to use the `average=False` parameter setting as the calibration routines supporting GBT data require all of the individual times and phases.

NOTE: GBT data may need some pre-processing prior to using ASAP. In particular, the program which converts GBT raw data into CASA Measurement Sets tends to proliferate the number of spectral windows due to shifts in the tracking frequency; this is being worked on by GBT staff. In addition, GBT SDFITS is currently not readable by ASAP (in progress).

NOTE: The Measurement Set to scantable conversion is able to deduce the reference and source data and assigns an '`r`' to the reference data to comply with the ASAP conventions.

NOTE: GBT observing modes are identifiable in scantable in the name assignment: position switched ('`_ps`'), Nod ('`_nod`'), and frequency switched ('`_fs`'). These are combined with the reference data assignment. (For example, the reference data taken in position switched mode observation are assigned as '`_psr`').

New Feature: It is now possible to read the ATF interferometric data as a single dish data to further examine it using ASAP Toolkit and the SD tasks. The usage is the same as importing

single dish data (e.g. `s=sd.scantable(your_ATF_synthesis_ms, 'False')`). It is still experimental and limited to the data obtained with the two-element synthesis data.

Use the `summary` function to examine the data and get basic information:

```
CASA <8>: scans.summary()
```

Scan Table Summary

Beams:	1
IFs:	26
Polarisations:	2 (linear)
Channels:	8192
Observer:	Joseph McMullin
Obs Date:	2006/01/19/01:45:58
Project:	AGBT06A_018_01
Obs. Type:	OffOn:PSWITCHOFF:TPWCAL
Antenna Name:	GBT
Flux Unit:	Jy
Rest Freqs:	[4.5490258e+10] [Hz]
Abcissa:	Channel
Selection:	none

Scan	Source	Time	Integration		
	Beam	Position (J2000)			
	IF	Frame	RefVal	RefPix	Increment
20	OrionS_psr	01:45:58	4 x	30.0s	
0		05:15:13.5 -05.24.08.2			
0	LSRK	4.5489354e+10	4096	6104.233	
1	LSRK	4.5300785e+10	4096	6104.233	
2	LSRK	4.4074929e+10	4096	6104.233	
3	LSRK	4.4166215e+10	4096	6104.233	
21	OrionS_ps	01:48:38	4 x	30.0s	
0		05:35:13.5 -05.24.08.2			
0	LSRK	4.5489354e+10	4096	6104.233	
1	LSRK	4.5300785e+10	4096	6104.233	
2	LSRK	4.4074929e+10	4096	6104.233	
3	LSRK	4.4166215e+10	4096	6104.233	
22	OrionS_psr	01:51:21	4 x	30.0s	
0		05:15:13.5 -05.24.08.2			
0	LSRK	4.5489354e+10	4096	6104.233	
1	LSRK	4.5300785e+10	4096	6104.233	
2	LSRK	4.4074929e+10	4096	6104.233	
3	LSRK	4.4166215e+10	4096	6104.233	
23	OrionS_ps	01:54:01	4 x	30.0s	
0		05:35:13.5 -05.24.08.2			
0	LSRK	4.5489354e+10	4096	6104.233	
1	LSRK	4.5300785e+10	4096	6104.233	
2	LSRK	4.4074929e+10	4096	6104.233	

```

      3      LSRK  4.4166215e+10  4096   6104.233
24 OrionS_psr      02:01:47    4 x    30.0s
      0 05:15:13.5 -05.24.08.2
      12     LSRK  4.3962126e+10  4096   6104.2336
      13     LSRK  4.264542e+10  4096   6104.2336
      14     LSRK  4.159498e+10  4096   6104.2336
      15     LSRK  4.3422823e+10  4096   6104.2336
25 OrionS_ps      02:04:27    4 x    30.0s
      0 05:35:13.5 -05.24.08.2
      12     LSRK  4.3962126e+10  4096   6104.2336
      13     LSRK  4.264542e+10  4096   6104.2336
      14     LSRK  4.159498e+10  4096   6104.2336
      15     LSRK  4.3422823e+10  4096   6104.2336
26 OrionS_psr      02:07:10    4 x    30.0s
      0 05:15:13.5 -05.24.08.2
      12     LSRK  4.3962126e+10  4096   6104.2336
      13     LSRK  4.264542e+10  4096   6104.2336
      14     LSRK  4.159498e+10  4096   6104.2336
      15     LSRK  4.3422823e+10  4096   6104.2336
27 OrionS_ps      02:09:51    4 x    30.0s
      0 05:35:13.5 -05.24.08.2
      12     LSRK  4.3962126e+10  4096   6104.2336
      13     LSRK  4.264542e+10  4096   6104.2336
      14     LSRK  4.159498e+10  4096   6104.2336
      15     LSRK  4.3422823e+10  4096   6104.2336

```

A.3.3 Scantable Manipulation

Within ASAP, data is stored in a `scantable`, which holds all of the observational information and provides functionality to manipulate the data and information. The building block of a `scantable` is an integration which is a single row of a scantable. Each row contains just one spectrum for each beam, IF and polarization.

Once you have a `scantable` in ASAP, you can select a subset of the data based on scan numbers, sources, or types of scan; note that each of these selections returns a new 'scantable' with all of the underlying functionality:

```

CASA <5>: scan27=scans.get_scan(27)                      # Get the 27th scan
CASA <6>: scans20to24=scans.get_scan(range(20,25))       # Get scans 20 - 24
CASA <7>: scans_on=scans.get_scan('*_ps')                 # Get ps scans on source
CASA <8>: scansOrion=scans.get_scan('Ori*')              # Get all Orion scans

```

To copy a scantable, do:

```
CASA <15>: ss=scans.copy()
```

A.3.3.1 Data Selection

In addition to the basic data selection above, data can be selected based on IF, beam, polarization, scan number as well as values such as Tsys. To make a selection you create a `selector` object which you then define with various selection functions, e.g.,

```
sel = sd.selector()      # initialize a selector object
                          # sel.<TAB> will list all options
sel.set_ifs(0)           # select only the first IF of the data
scans.set_selection(sel) # apply the selection to the data
print scans              # shows just the first IF
```

A.3.3.2 State Information

Some properties of a scantable apply to all of the data, such as example, spectral units, frequency frame, or Doppler type. This information can be set using the `scantable.set_xxxx` methods. These are currently:

```
CASA <1>: sd.scantable.set_<TAB>
sd.scantable.set_dirframe    sd.scantable.set_fluxunit    sd.scantable.set_restfreqs
sd.scantable.set_doppler     sd.scantable.set_freqframe   sd.scantable.set_selection
sd.scantable.set_feedtype    sd.scantable.set_instrument  sd.scantable.set_unit
```

For example, `sd.scantable.set_fluxunit` sets the default units that describe the flux axis:

```
scans.set_fluxunit('K') # Set the flux unit for data to Kelvin
```

Choices are 'K' or 'Jy'. Note: the `scantable.set_fluxunit` function only changes the `name` of the current fluxunit. To change fluxunits, use `scantable.convert_flux` as described in § A.3.4.2 instead (currently you need to do some gymnastics for non-AT telescopes).

Use `sd.scantable.set_unit` to set the units to be used on the spectral axis:

```
scans.set_unit('GHz') # Use GHZ as the spectral axis for plots
```

The choices for the units are 'km/s', 'channel', or '*Hz' (e.g. 'GHz', 'MHz', 'kHz', 'Hz'). This does the proper conversion using the current frame and Doppler reference as can be seen when the spectrum is plotted.

You can use `sd.scantable.set_freqframe` to set the frame in which the frequency (spectral) axis is defined:

```
CASA <2>: help(sd.scantable.set_freqframe)
Help on method set_freqframe in module asap.scantable:

set_freqframe(self, frame=None) unbound asap.scantable.scantable method
Set the frame type of the Spectral Axis.
```

Parameters:

```
frame: an optional frame type, default 'LSRK'. Valid frames are:  
'REST', 'TOPO', 'LSRD', 'LSRK', 'BARY',  
'GEO', 'GALACTO', 'LGROUP', 'CMB'
```

Examples:

```
scan.set_freqframe('BARY')
```

The most useful choices here are `frame = 'LSRK'` (the default for the function) and `frame = 'TOPO'` (what the GBT actually observes in). Note that the '`REST`' option is not yet available. The Doppler frame is set with `sd.scantable.set_doppler`:

```
CASA <3>: help(sd.scantable.set_doppler)
```

```
Help on method set_doppler in module asap.scantable:
```

```
set_doppler(self, doppler='RADIO') unbound asap.scantable.scantable method  
Set the doppler for all following operations on this scantable.
```

Parameters:

```
doppler: One of 'RADIO', 'OPTICAL', 'Z', 'BETA', 'GAMMA'
```

Finally, there are a number of functions to query the state of the scantable. These can be found in the usual way:

```
CASA <4>: sd.scantable.get<TAB>  
sd.scantable.get_abcissa      sd.scantable.get_restfreqs    sd.scantable.getbeamnos  
sd.scantable.get_azimuth      sd.scantable.get_scan       sd.scantable.getcycle  
sd.scantable.get_column_names sd.scantable.get_selection  sd.scantable.getif  
sd.scantable.get_direction    sd.scantable.get_sourcename sd.scantable.getifnos  
sd.scantable.get_elevation    sd.scantable.get_time      sd.scantable.getpol  
sd.scantable.get_fit          sd.scantable.get_tsys      sd.scantable.getpolnos  
sd.scantable.get_fluxunit     sd.scantable.get_unit     sd.scantable.getscan  
sd.scantable.get_parangle     sd.scantable.getbeam      sd.scantable.getscannos
```

These include functions to get the current values of the states mentioned above, as well as methods to query the number of scans, IFs, and polarizations in the scantable, and their designations. See the inline help for the individual functions for more information.

A.3.3.3 Masks

Several functions (fitting, baseline subtraction, statistics, etc) may be run on a range of channels (or velocity/frequency ranges). You can create masks of this type using the `create_mask` function:

```
# spave = an averaged spectrum  
spave.set_unit('channel')  
rmsmask=spave.create_mask([5000,7000]) # create a region over channels 5000-7000  
rms=spave.stats(stat='rms',mask=rmsmask) # get rms of line free region  
  
rmsmask=spave.create_mask([3000,4000],invert=True) # choose the region  
# *excluding* the specified channels
```

The mask is stored in a simple Python variable (a list) and so may be manipulated using an Python facilities.

A.3.3.4 Scantable Management

`scantables` can be listed via:

```
CASA <33>: sd.list_scans()
The user created scantables are:
['scans20to24', 's', 'scan27']
```

As every `scantable` will consume memory, if you will not use it any longer, you can explicitly remove it via:

```
del <scantable name>
```

A.3.3.5 Scantable Mathematics

It is possible to do simple mathematics directly on `scantables` from the CASA command line using the `+, -, *, /` operators as well as their cousins `+=, -=, *=, /=`

```
CASA <10>: scan2=scan1+2.0 # add 2.0 to data
CASA <11>: scan *= 1.05    # scale spectrum by 1.05
```

NOTE: mathematics between two scantables is not currently available in ASAP.

A.3.3.6 Scantable Save and Export

ASAP can save scantables in a variety of formats, suitable for reading into other packages. The formats are:

- ASAP – This is the internal format used for ASAP. It is the only format that allows the user to restore the data, fits, etc, without loosing any information. As mentioned before, the ASAP scantable is a CASA Table (memory-based table). This function just converts it to a disk-based table. You can access this with the CASA `browsetable` task or any other CASA table tasks.
- SDFITS – The Single Dish FITS format. This format was designed for interchange between packages but few packages can actually read it.
- ASCII – A simple text based format suitable for the user to process using Python or other means.

- Measurement Set (V2: CASA format) – Saves the data in a Measurement Set. All CASA tasks which use an MS should work on this.

```
scans.save('output_filename','format'), e.g.,
CASA <19>: scans.save('FLS3a_calfs','MS2')
```

A.3.4 Calibration

For some observatories, the calibration happens transparently as the input data contains the Tsys measurements taken during the observations. The nominal 'Tsys' values may be in Kelvin or Jansky. The user may wish to apply a Tsys correction or apply gain-elevation and opacity corrections.

A.3.4.1 Tsys scaling

If the nominal Tsys measurement at the telescope is wrong due to incorrect calibration, the `scale` function allows it to be corrected.

```
scans.scale(1.05,tsys=True) # by default only the spectra are scaled
# (and not the corresponding Tsys) unless tsys=True
```

A.3.4.2 Flux and Temperature Unit Conversion

To convert measurements in Kelvin to Jansky (and vice versa), the `convert_flux` function may be used. This converts and scales the data to the selected units. The user may need to supply the aperture efficiency, telescope diameter or the Jy/K factor

```
scans.convert_flux(eta=0.48, d=35.) # Unknown telescope
scans.convert_flux(jypk=15) # Unknown telescope (alternative)
scans.convert_flux() # known telescope (mostly AT telescopes)
scans.convert_flux(eta=0.48) # if telescope diameter known
```

A.3.4.3 Gain-Elevation and Atmospheric Optical Depth Corrections

At higher frequencies, it is important to make corrections for atmospheric opacity and gain-elevation effects. **NOTE:** Currently, the MS to scantable conversion does not adequately populate the azimuth and elevation in the `scantable`. As a result, one must calculate these via:

```
scans.recalc_azel()
Computed azimuth/elevation using
Position: [882590, -4.92487e+06, 3.94373e+06]
Time: 01:48:38 Direction: 05:35:13.5 -05.24.08.2
=> azel: 154.696 43.1847 (deg)
Time: 01:48:38 Direction: 05:35:13.5 -05.24.08.2
```

```

=> azel: 154.696 43.1847 (deg)
Time: 01:48:38 Direction: 05:35:13.5 -05.24.08.2
=> azel: 154.696 43.1847 (deg)
Time: 01:48:38 Direction: 05:35:13.5 -05.24.08.2
=> azel: 154.696 43.1847 (deg)
Time: 01:48:38 Direction: 05:35:13.5 -05.24.08.2
=> azel: 154.696 43.1847 (deg)
...

```

Once you have the correct Az/El, you can correct for a *known* opacity by:

```

scans.opacity(tau=0.09) # Opacity from which the correction factor:
# exp(tau*zenith-distance)

```

A.3.4.4 Calibration of GBT data

Data from the GBT is uncalibrated and comes as sets of integrations representing the different phases within a calibration cycle (e.g., on source, calibration on, on source, calibration off, on reference, calibration on; on reference, calibration off). Currently, there are a number of routines emulating the standard GBT calibration (in GBTIDL):

- calps - calibrate position switched data
- calfs - calibrate frequency switched data
- calnod - calibration nod (beam switch) data

All these routines calibrate the spectral data to antenna temperature adopting the GBT calibration method as described in the GBTIDL calibration document available at:

- http://wwwlocal.gb.nrao.edu/GBT/DA/gbtidl/gbtidl_calibration.pdf

There are two basic steps:

First: determine system temperature using a noise tube calibrator (sd.dototalpower())

For each integration, the system temperature is calculated from CAL noise on/off data as:

$$T_{sys} = T_{cal} \times \frac{\langle ref_{caloff} \rangle}{\langle ref_{calon} - ref_{caloff} \rangle} + \frac{T_{cal}}{2}$$

`ref` refers to reference data and the spectral data are averaged across the bandpass. Note that the central 80% of the spectra are used for the calculation.

Second, determine antenna temperature (sd.dosigref())

The antenna temperature for each channel is calculated as:

$$T_a(\nu) = T_{sys} \times \frac{sig(\nu) - ref(\nu)}{ref(\nu)}$$

where $sig = \frac{1}{2}(sig_{calon} + sig_{caloff})$, $ref = \frac{1}{2}(sig_{calon} + sig_{caloff})$.

Each calibration routine may be used as:

```
scans=sd.scantable('inputdata',False)          # create a scantable called 'scans'
calibrated_scans = sd.calps(scans,[scanlist]) # calibrate scantable with position-switched
                                                # scheme
```

Note: For calps and calnod, the scanlist must be scan pairs in correct order as these routines only do minimal checking.

A.3.5 Averaging

One can average polarizations in a scantable using the `sd.scantable.average_pol` function:

```
averaged_scan = scans.average_pol(mask,weight)
```

where:

Parameters:

mask:	An optional mask defining the region, where the averaging will be applied. The output will have all specified points masked.
weight:	Weighting scheme. 'none' (default), 'var' (1/var(spec) weighted), or 'tsys' (1/Tsys**2 weighted)

Example:

```
spave = stave.average_pol(weight='tsys')
```

One can also average scans over time using `sd.average_time`:

```
sd.average_time(scantable,mask,scanav,weight,align)
```

where:

Parameters:

one scan or comma separated scans	
compel:	if True, enable averaging of multi-resolution spectra.
mask:	an optional mask (only used for 'var' and 'tsys' weighting)
scanav:	True averages each scan separately. False (default) averages all scans together,
weight:	Weighting scheme. 'none' (mean no weight) 'var' (1/var(spec) weighted) 'tsys' (1/Tsys**2 weighted) 'tint' (integration time weighted) 'tintsys' (Tint/Tsys**2) 'median' (median averaging)

```


```

Example:

```
stave = sd.average_time(scans,weight='tintsys')
```

Note that alignment of the velocity frame should be done before averaging if the time spanned by the scantable is long enough. This is done through the `align=True` option in `sd.averagetime`, or explicitly through the `sd.scantable.freq_align` function, e.g.

```
CASA <62>: sc = sd.scantable('orions_scan20to23_if0to3.asap',False)
CASA <63>: sc.freq_align()
Aligned at reference Epoch 2006/01/19/01:49:23 (UTC) in frame LSRK
CASA <64>: av = sd.averagetimes(sc)
```

The time averaging can also be applied to multiple scantables. This might have been taken on different days, for example. The `sd.averagetime` function takes multiple scantables as input. However, if taken at significantly different times (different days for example) then `sd.scantable.freq_align` must be used to align the velocity scales to the same time, e.g.

```
CASA <65>: sc1 = sd.scantable('orions_scan21_if0to3.asap',False)
CASA <66>: sc2 = sd.scantable('orions_scan23_if0to3.asap',False)
CASA <67>: sc1.freq_align()
Aligned at reference Epoch 2006/01/19/01:49:23 (UTC) in frame LSRK
CASA <68>: sc2.freq_align(reftime='2006/01/19/01:49:23')
Aligned at reference Epoch 2006/01/19/01:54:46 (UTC) in frame LSRK
CASA <69>: scav = sd.averagetimes(sc1,sc2)
```

A.3.6 Spectral Smoothing

Smoothing on data can be done as follows:

```
scantable.smooth(kernel,      # type of smoothing: 'hanning' (default), 'gaussian', 'boxcar'
                  width,        # width in pixels (ignored for hanning); FWHM for gaussian.
                  insitu)       # if False (default), do smoothing in-situ; otherwise,
                           # make new scantable
```

Example:

```
# spave is an averaged spectrum
spave.smooth('boxcar',5)    # do a 5 pixel boxcar smooth on the spectrum
sd.plotter.plot(spave)     # should see smoothed spectrum
```

A.3.7 Baseline Fitting

The function `sd.scantable.poly_baseline` carries out a baseline fit, given an mask of channels (if desired):

```
msk=scans.create_mask([100,400],[600,900])
scans.poly_baseline(msk,order=1)
```

This will fit a first order polynomial to the selected channels and subtract this polynomial from the full spectrum.

The `auto_poly_baseline` function can be used to automatically baseline your data without having to specify channel ranges for the line free data. It automatically figures out the line-free emission and fits a polynomial baseline to that data. The user can use masks to fix the range of channels or velocity range for the fit as well as mark the band edge as invalid:

```
scans.auto_poly_baseline(mask=edge,order,threshold,chan_avg_limit,plot,insitu):
```

Parameters:

<code>mask:</code>	an optional mask retrieved from <code>scantable</code>
<code>edge:</code>	an optional number of channel to drop at the edge of spectrum. If only one value is specified, the same number will be dropped from both sides of the spectrum. Default is to keep all channels. Nested tuples represent individual edge selection for different IFs (a number of spectral channels can be different)
<code>order:</code>	the order of the polynomial (default is 0)
<code>threshold:</code>	the threshold used by line finder. It is better to keep it large as only strong lines affect the baseline solution.
<code>chan_avg_limit:</code>	a maximum number of consecutive spectral channels to average during the search of weak and broad lines. The default is no averaging (and no search for weak lines). If such lines can affect the fitted baseline (e.g. a high order polynomial is fitted), increase this parameter (usually values up to 8 are reasonable). Most users of this method should find the default value sufficient.
<code>plot:</code>	plot the fit and the residual. In this each individual fit has to be approved, by typing 'y' or 'n'
<code>insitu:</code>	if <code>False</code> a new <code>scantable</code> is returned. Otherwise, the scaling is done in-situ The default is taken from <code>.asaprc</code> (<code>False</code>)

Example:

```
scans.auto_poly_baseline(order=2,threshold=5)
```

A.3.8 Line Fitting

Multi-component Gaussian fitting is available. This is done by creating a fitting object, specifying fit parameters and finally fitting the data. Fitting can be done on a `scantable` selection or an

entire `scantable` using the `auto_fit` function.

```
#spave is an averaged spectrum
f=sd.fitter()                      # create fitter object
msk=spave.create_mask([3928,4255])   # create mask region around line
f.set_function(gauss=1)               # set a single gaussian component
f.set_scan(scantable,msk)            # set the scantable and region
#
# Automatically guess start values
f.fit()                             # fit
f.plot(residual=True)                # plot residual
f.get_parameters()                  # retrieve fit parameters
# 0: peak = 0.786 K , centre = 4091.236 channel, FWHM = 70.586 channel
# area = 59.473 K channel
f.store_fit('orions_hc3n_fit.txt')   # store fit
#
# To specify initial guess:
# set a single gaussian component
# set initial guesses for Gaussian
# for first component (0)
# (peak,center,fwhm)
#
# For multiple components set
# initial guesses for each, e.g.
# set two gaussian components
# set initial guesses for Gaussian
# for first component (0)
# set initial guesses for Gaussian
# for second component (1)
```

A.3.9 Plotting

A.3.9.1 ASAP plotter

The ASAP plotter uses the same Python matplotlib library as in CASA (for x-y plots). It is accessed via the:

```
sd.plotter<TAB>      # see all functions (omitted here)
sd.plotter.plot(scans) # the workhorse function
sd.plotter.set<TAB>
sd.plotter.set_abscissa    sd.plotter.set_legend    sd.plotter.set_range
sd.plotter.set_colors       sd.plotter.set_linestyles  sd.plotter.set_selection
sd.plotter.set_colours     sd.plotter.set_mask      sd.plotter.set_stacking
sd.plotter.set_font        sd.plotter.set_mode      sd.plotter.set_title
sd.plotter.set_histogram   sd.plotter.set_ordinate
sd.plotter.set_layout      sd.plotter.set_panelling
```

Spectra can be plotted at any time, and it will attempt to do the correct layout depending on whether it is a set of scans or a single scan.

The details of the plotter display (matplotlib) are detailed in the earlier section.

A.3.9.2 Line Catalog

ASAP allows to load a custom line catalog in ASCII format. The ASCII text file must have at least 4 columns with Molecule name, frequency in MHz, frequency error and intensity (any units). If the molecule name contains any spaces, they must be wrapped in quotes "". A sample of the ASCII catalog is shown below.

```
H2D+    3955.2551 228.8818 -7.1941
H2D+    12104.7712 177.1558 -6.0769
H2D+    45809.2731 118.3223 -3.9494
CH      701.6811   .0441  -7.1641
CH      724.7709   .0456  -7.3912
CH      3263.7940  .1000  -6.3501
CH      3335.4810  .1000  -6.0304
```

You can load the ASCII line catalog, for example, if it is called `my_custom_linecat.txt`, by following command.

```
mycatlog = sd.linecatlog('my_custom_linecat.txt')
```

Use `sd.plotter.plot_line` to overlay the line catalog on the plot. (Currently overplotting line catalog works only spectra plotted in frequency.)

```
scans.set_unit('GHz')
sd.plotter.plot(scans)
sd.plotter.plot_line(mycatlog)
```

Following are some useful functions to control the line catalog access. See ASAP User Guide for more complete descriptions.

```
mycatlog.save('my_custom_linecat.tbl') # save to the internal table format
mycatlog.set_frequency_limits(100,115,'GHz') #set a frequency range for line selection
mycatlog.set_name('*OH') # select all alcohols
```

A.3.10 Setting/Getting Rest Frequencies

The rest frequencies used in the data can be retrieve by `sd.scantable.get_restfreqs()` and set to new values by `sd.scantable.set_restfreqs()`. The CASA version of ASAP now can store multiple rest frequencies for each IF.

```
scans.get_restfreqs()          #retrieve current rest frequencies
#[0: [45490258000.0]
```

All the rest frequencies currently set to the data are listed in python dictionary for each MOLECULE_ID.

To set multiple rest frequencies to spectra for a particular IF, for example,

```
#Select IFs, then set rest frequencies,
sel=sd.selector()
sel.setifs(0)
scans.set_selection(sel)
scans.set_restfreqs([45490258000.0,45590258000.0,45690258000.0])
```

NOTE: there is no functionality yet to select a specific rest frequency to apply to a specific line, etc. Currently, the first one in the list of the rest frequencies is used for such calculation.

A.3.11 Single Dish Spectral Analysis Use Case With ASAP Toolkit

Below is a script that illustrates how to reduce single dish data using ASAP within CASA. First a summary of the dataset is given and then the script.

```
#               MeasurementSet Name: /home/rohir3/jocular/SD/OrionS_rawACSmod      MS Version 2
#
# Project: AGBT06A_018_01
# Observation: GBT(1 antennas)
#
#Data records: 256      Total integration time = 1523.13 seconds
#   Observed from 01:45:58 to 02:11:21
#
#Fields: 4
# ID    Name        Right Ascension  Declination   Epoch
# 0    OrionS      05:15:13.45    -05.24.08.20  J2000
# 1    OrionS      05:35:13.45    -05.24.08.20  J2000
# 2    OrionS      05:15:13.45    -05.24.08.20  J2000
# 3    OrionS      05:35:13.45    -05.24.08.20  J2000
#
#Spectral Windows: (8 unique spectral windows and 1 unique polarization setups)
# SpwID  #Chans Frame Ch1(MHz)  Resoln(kHz) TotBW(kHz)  Ref(MHz)  Corrs
# 0       8192  LSRK  45464.3506  6.10423298  50005.8766  45489.3536  RR  LL  HC3N
# 1       8192  LSRK  45275.7825  6.10423298  50005.8766  45300.7854  RR  LL  HN15CO
# 2       8192  LSRK  44049.9264  6.10423298  50005.8766  44074.9293  RR  LL  CH3OH
# 3       8192  LSRK  44141.2121  6.10423298  50005.8766  44166.2151  RR  LL  HCCC15N
# 12      8192  LSRK  43937.1232  6.10423356  50005.8813  43962.1261  RR  LL  HNCO
# 13      8192  LSRK  42620.4173  6.10423356  50005.8813  42645.4203  RR  LL  H15NCO
# 14      8192  LSRK  41569.9768  6.10423356  50005.8813  41594.9797  RR  LL  HNC180
# 15      8192  LSRK  43397.8198  6.10423356  50005.8813  43422.8227  RR  LL  SiO
#
# Scans: 21-24  Setup 1 HC3N et al
# Scans: 25-28  Setup 2 SiO et al
```

```


casapath=os.environ['AIPSPATH']

#ASAP script                                # COMMENTS
#-----
import asap as sd                          #import ASAP package into CASA
os.environ['AIPSPATH']=casapath             #Orion-S (SiO line reduction only)
                                           #Notes:
                                           #scan numbers (zero-based) as compared to GBTIDL

                                           #changes made to get to OrionS_rawACSmod
                                           #modifications to label sig/ref positions
                                           #set this environment variable back - ASAP changes it

s=sd.scantable('OrionS_rawACSmod',False)#load the data without averaging

```



```

s.summary()                                     #summary info
s.set_fluxunit('K')                           # make 'K' default unit
scal=sd.calps(s,[20,21,22,23])               # Calibrate HC3N scans

scal.recalc_azel()                            # recalculate az/el to

```




Figure A.4: Two panel plot of the calibrated spectra. The GBT data has a separate scan for the SOURCE and REFERENCE positions so scans 20,21,22 and 23 result in these two spectra.

```

scal.opacity(0.09)                      # do opacity correction
sel=sd.selector()                        # Prepare a selection
sel.set_ifs(0)                            # select HC3N IF
scal.set_selection(sel)                  # get this IF
stave=sd.average_time(scal,weight='tintsys')    # average in time
spave=stave.average_pol(weight='tsys')      # average polarizations; Tsys-weighted (1/Tsys**2) average
sd.plotter.plot(spave)                   # plot

spave.smooth('boxcar',5)                 # boxcar 5
spave.auto_poly_baseline(order=2)        # baseline fit order=2
sd.plotter.plot(spave)                  # plot

spave.set_unit('GHz')
sd.plotter.plot(spave)
sd.plotter.set_histogram(hist=True)       # draw spectrum using histogram
sd.plotter.axhline(color='r', linewidth=2) # zline
sd.plotter.save('orions_hc3n_reduced.eps')# save postscript spectrum

spave.set_unit('channel')
rmsmask=spave.create_mask([5000,7000])   # get rms of line free regions
rms=spave.stats(stat='rms',mask=rmsmask)# rms
#-----
#Scan[0] (OrionS_ps) Time[2006/01/19/01:52:05]:
# IF[0] = 0.048

```




Figure A.5: Calibrated spectrum with a line at zero (using histograms).

```

#-----
# LINE

linemask=spave.create_mask([3900,4200])
max=spave.stats('max',linemask)          # IF[0] = 0.918
sum=spave.stats('sum',linemask)          # IF[0] = 64.994
median=spave.stats('median',linemask)    # IF[0] = 0.091
mean=spave.stats('mean',linemask)        # IF[0] = 0.210

# Fitting
spave.set_unit('channel')               # set units to channel
sd.plotter.plot(spave)                 # plot spectrum
f=sd.fitter()
msk=spave.create_mask([3928,4255])      # create region around line
f.set_function(gauss=1)                 # set a single gaussian component
f.set_scan(spave,msk)                  # set the data and region for the fitter
f.fit()                                # fit
f.plot(residual=True)                  # plot residual

f.get_parameters()                      # retrieve fit parameters
#   0: peak = 0.786 K , centre = 4091.236 channel, FWHM = 70.586 channel
#       area = 59.473 K channel
f.store_fit('orions_hc3n_fit.txt')     # store fit
# Save the spectrum

```

```
spave.save('orions_hc3n_reduced','ASCII',True) # save the spectrum
```

A.4 Single Dish Imaging

Single dish imaging is supported within CASA using standard tasks and tools. The data must be in the Measurement Set format. Once there, you can use the `im` (imager) tool to create images:

Tool example:

```
scans.save('outputms','MS2')                                     # Save your data from ASAP into an MS

im.open('outputms')                                              # open the data set
im.selectvis(nchan=901,start=30,step=1,                           # choose a subset of the data
             spwid=0,field=0)                                         # (just the key emission channels)
dir='J2000 17:18:29 +59.31.23'                                    # set map center
im.defineimage(nx=150,cellx='1.5arcmin',                           # define image parameters
              phasecenter=dir,mode='channel',start=30,                # (note it assumes symmetry if ny,celly
              nchan=901,step=1)                                         # aren't specified)

im.setoptions(ftmachine='sd',cache=1000000000)                      # choose SD gridding
im.setsoptions(convsupport=4)                                       # use this many pixels to support the
                                                               # gridding function used
                                                               # (default=prolate spheroidal wave function)
im.makeimage(type='singledish',                                     # make the image
             image='FLS3a_HI.image')
```

A.4.1 Single Dish Imaging Use Case With ASAP Toolkit

Again, the data summary and then the script is given below.

```
# Project: AGBT02A_007_01
# Observation: GBT(1 antennas)
#
#   Telescope   Observation Date      Observer      Project
#   GBT          [                  4.57539e+09, 4.5754e+09]Lockman    AGBT02A_007_01
#   GBT          [                  4.57574e+09, 4.57575e+09]Lockman    AGBT02A_007_02
#   GBT          [                  4.5831e+09, 4.58313e+09]Lockman    AGBT02A_031_12
#
# Thu Feb 1 23:15:15 2007      NORMAL ms::summary:
# Data records: 76860      Total integration time = 7.74277e+06 seconds
#     Observed from 22:05:41 to 12:51:56
#
# Thu Feb 1 23:15:15 2007      NORMAL ms::summary:
# Fields: 2
#   ID   Name           Right Ascension  Declination   Epoch
#   0    FLS3a          17:18:00.00    +59.30.00.00  J2000
#   1    FLS3b          17:18:00.00    +59.30.00.00  J2000
```

```

#
# Thu Feb 1 23:15:15 2007      NORMAL ms::summary:
# Spectral Windows: (2 unique spectral windows and 1 unique polarization setups)
#   SpwID #Chans Frame Ch1(MHz)  Resoln(kHz) TotBW(kHz) Ref(MHz) Corrs
#   0       1024  LSRK  1421.89269  2.44140625  2500        1420.64269  XX  YY
#   1       1024  LSRK  1419.39269  2.44140625  2500        1418.14269  XX  YY

# FLS3 data calibration
# this is calibration part of FLS3 data
#
casapath=os.environ['AIPSPATH']
import asap as sd
os.environ['AIPSPATH']=casapath

print '--Import--'

s=sd.scantable('FLS3_all_newcal_SP',false)           # read in MeasurementSet

print '--Split--'

# splitting the data for each field
s0=s.get_scan('FLS3a*')
s0.save('FLS3a_HI.asap')                            # split the data for the field of interest
del s0                                               # save this scantable to disk (asap format)
                                                       # free up memory from scantable

print '--Calibrate--'
s=sd.scantable('FLS3a_HI.asap')                     # read in scantable from disk (FLS3a)
s.set_fluxunit('K')                                 # set the brightness units to Kelvin
scanns = s.getscannos()                            # get a list of scan numbers
sn=list(scanns)                                    # convert it to a list
print "No. scans to be processed:", len(scanns)

res=sd.calfs(s,sn)                                # calibrate all scans listed using frequency
                                                       # switched calibration method

print '--Save calibrated data--'
res.save('FLS3a_calfs', 'MS2')                    # Save the dataset as a MeasurementSet

print '--Image data--'

im.open('FLS3a_calfs')                            # open the data set
im.selectvis(nchan=901,start=30,step=1,
spwid=0,field=0)                                # choose a subset of the data
dir='J2000 17:18:29 +59.31.23'                  # (just the key emission channels)
im.defineimage(nx=150,cellx='1.5arcmin',          # set map center
phasecenter=dir,mode='channel',start=30,          # define image parameters
nchan=901,step=1)                                # (note it assumes symmetry if ny,celly
                                                       # aren't specified)

im.setoptions(ftmachine='sd',cache=1000000000)     # choose SD gridding
im.setsdoptions(convsupport=4)                    # use this many pixels to support the

```

```
# gridding function used
# (default=prolate spheroidal wave function)
im.makeimage(type='singledish',image='FLS3a_HI.image') # make the image
```




Figure A.6: FLS3a HI emission. The display illustrates the visualization of the data cube (left) and the profile display of the cube at the cursor location (right); the Tools menu of the Viewer Display Panel has a Spectral Profile button which brings up this display. By default, it grabs the left-mouse button. Pressing down the button and moving in the display will show the profile variations.

A.5 Known Issues, Problems, Deficiencies and Features

The Single-Dish calibration and analysis package within CASA is still very much under development. Not surprisingly, there are a number of issues with ASAP and the SDtasks that are known and are under repair. Some of these are non-obvious "features" of the way ASAP or `sd` is implemented, or limitations of the current Python tasking environment. Some are functions that have yet to be implemented. These currently include:

1. `sd.plotter`

Currently you can get hardcopy only after making a viewed plot. Ideally, ASAP should allow you to choose the device for plotting when you set up the plotter.

Multi-panel plotting is poor. Currently you can only add things (like lines, text, etc.) to the first panel. Also, `sd.plotter.set_range()` sets the same range for multiple panels, while we would like it to be able to set the range for each independently, including the default ranges.

The appearance of the plots need to be made a lot better. In principle matplotlib can make "publication quality" figures, but in practice you have to do a lot of work to make it do that, and our plots are not good.

The `sd.plotter` object remembers things throughout the session and thus can easily get confused. For example you have to reset the range `sd.plotter.set_range()` if you have ever set it manually. This is not always the expected behavior but is a consequence of having `sd.plotter` be its own object that you feed data and commands to.

Eventually we would like the capability to interactively set things using the plots, like select frequency ranges, identify lines, start fitting.

2. `sd.selector`

The selector object only allows one selection of each type. It would be nice to be able to make a union of selections (without resorting to query) for the `set_name` - note that the others like scans and IFs work off lists which is fine. Should make `set_name` work off lists of names.

3. `sd.scantable`

There is no useful inline help on the scantable constructor when you do `help sd.scantable`, nor in help `sd`.

The inline help for `scantable.summary` claims that there is a verbose parameter, but there is not. The `scantable.verbosesummary` asaprc parameter (e.g. in `sd.rcParams`) does nothing.

GBT data has undefined fluxunit ('', should be 'K'), incorrect freqframe ('LSRK', is really 'TOPO') and reference frequency (set to that of the first IF only).

The `sd.scantable.freq_align` does not yet work correctly.

Need to add to `scantable.stats`: '`maxord`', '`minord`' - the ordinate (channel, vel, freq) of the max/min

4. `sd` general issues

There should be a `sdhelp` equivalent of `toolhelp` and `tasklist` for the `sd` tools and tasks.

The current output of ASAP is verbose, and is controlled by setting `sd.rcParams['verbose']=False` (or `True`). At the least we should make some of the output less cryptic.

Strip off leading and trailing whitespace on string parameters.

5. SDtasks general issues

The SDtasks work off of files saved onto disk in one of the scantable supported formats. It might be useful to be able to work off of scantables in memory (passing the objects) but this would require changes to the tasking system. Note that this behavior is consistent throughout the casapy tasks.

6. `sdaverage` (and `sdcal`)

`averageall=True` is still experimental since test was insufficient because of a lack of test data.

7. `sdcal`

Can crash if `timeaverage=True` and/or `polaverage=True` and you give a list of scans that contain a combination of IFs. We need to make the tools smarter about this, but in the meantime you should restrict your scanlist and iflist to scans with the same set of IFs.

8. `sdfit`

Only way to handle multi-IFs is to set `fitmode='auto'`. (`linefinder` is applied for each spectra and derives initial guesses) For `fitmode='list'`, there are no way to give initial guesses for each IFs by hand.

9. `sdplot`

Only handles included JPL line catalog.

Also, see `sd.plotter` issues above.

10. `sdstat`

Cannot return the location (channel, frequency, or velocity) of the maximum or minimum.

Appendix B

Simulation

BETA ALERT: The simulation capabilities are currently under development. What we do have is mostly at the Toolkit level. We have only a single task `almasimmos` at the present time. Stay tuned. For the Beta Release, we include this chapter in the Appendix for the use of telescope commissioners and software developers.

The capability for simulating observations and datasets from the EVLA and ALMA are an important use-case for CASA. This not only allows one to get an idea of the capabilities of these instruments for doing science, but also provides benchmarks for the performance and utility of the software for processing “realistic” datasets. To that end, we are developing the `simulator` (`sm`) tool, as well as a series of simulation tasks.

Inside the Toolkit:

The simulator methods are in the `sm` tool. Many of the other tools are also helpful when constructing and analyzing simulations.

B.1 Simulating ALMA with `almasimmos`

BETA ALERT: This is an experimental task that is under development. Its functionality and parameters will be changing, so check the on-line documentation for the latest updates.

The inputs are:

```
# almasimmos :: ALMA Mosaic simulation task

Please see the on-line documentation for this task.

project      =      'mysim'    #  name of simulated project
modelimage   =      ''        #  image name to derive simulate visibilities
complist     =      ''        #  componentlist table to derive simulated visibilities
antennalist  =      ''        #  antenna position ascii file
direction    =  'J2000 19h00m00 -40d00m00' #  mosaic center direction
nmosx       =      1        #  number of pointings along x
```

```

nmosy          =      1   #  number of pointings along y
pointingspacing = '5arcmin' #  spacing in between beams
refdate        = '2012/05/21/22:05:00' #  center time/date of simulated observation
totaltime      = '7200s'   #  total time of observation
integration    = '10s'     #  integration (sampling) time
mode           = 'channel' #  type of selection: channel, continuum
alg            = 'clark'   #  deconvolution algorithm: clark,hogbom,multiscale
niter          = 500      #  number iterations
nchan          = 1         #  number of channels to select
startfreq      = '89GHz'   #  frequency of first channel
chanwidth      = '10MHz'   #  channel width
imsize         = [250, 250] #  Image pixel size (x,y)
cell           = '10arcsec' #  Cell size e.g., 10arcsec
stokes          = 'I'       #  Stokes parameters to image
weighting       = 'natural' #  Weighting of visibilities
display         = True      #  Plot simulation result images,figures

```

This task takes an input model image or list of components, plus a list of antennas (locations and sizes), and simulates a particular observation (specifies by mosaic setup and observing cycles and times). This is currently very simplistic. For example, it does not include noise by default, or gain errors (but see the on-line wiki documentation for how to do these). The output is a MS suitable for further processing in CASA.

Its name implies that it is for ALMA, but it is mostly general as you can give it any antenna setup — it does have the ALMA observatory location hardwired in and sets the telescope name to ‘ALMA’ but that’s about it. The task could be easily modified for other instruments.

BETA ALERT: Because of the experimental nature of this task, we do not provide extensive documentation in this cookbook. For this purpose, there is an on-line “wiki” devoted to this task:

<https://wikio.nrao.edu/bin/view/ALMA/SimulatorCookbook>

Here you can find what documentation we do have, along with example files that are needed to specify antenna locations, and a FAQ.

Appendix C

Obtaining and Installing CASA

C.1 Installation Script

Currently you must be able to log into your system as the root user or an administrator user to install CASA.

The easiest way to install CASA on a RedHat Enterprise Linux (or compatible) system is to use our installation script, load-casapy. This script will ftp the CASA RPMs and install them. To use it, first use the link above to download it to your hard disk. Next, make sure execute permission is set for the file.

Install CASA into /usr by logging in as root and running:

```
load-casapy -root
```

This option will install CASA into /usr, but it can only be run by the root user.

Alternatively, you can visit our FTP server, download the rpms, and install them by hand. Note: you must be root/administrater to install CASA in this manner.

See the following for more details:

<https://wikio.nrao.edu/bin/view/Software/ObtainingCASA>

C.2 Startup

This section assumes that CASA has been installed on your LINUX or OSX system. *For NRAO-AOC testers, you should do the following on an AOC RHE4 machine:*

```
> . /home/casa/casainit.sh  
or  
> source /home/casa/casainit.csh
```

Appendix D

Python and CASA

CASA uses Python, IPython and matplotlib within the package. IPython is an enhanced, interactive shell to Python which provides many features for efficient command line interaction, while matplotlib is a Python 2-D plotting library for publication quality figures in different hardcopy formats.

From www.python.org: "Python is an interpreted, interactive, object-oriented programming language". Python is used as the underlying command line interface/scripting language to CASA. Thus, CASA inherits the features and the annoyances of Python. For example, since Python is inherently 0-based in its indexing of arrays, vectors, etc, CASA is also 0-based; any Index inputs (e.g., start (for start channel), fieldIndex, antennaID, etc) will start with 0. Another example is that indenting of lines means something to Python, of which users will have to be aware.

Some key links are:

- <http://python.org> – Main Python page
- <http://python.org/doc/2.4.2/ref/ref.html> – Python Reference
- <http://python.org/doc/2.4.2/tut/tut.html> – Python Tutorial
- <http://ipython.scipy.org> – IPython page
- <http://matplotlib.sourceforge.net> – matplotlib page

Each of the features of these components behave in the standard way within CASA . In the following sections, we outline the key elements for analysis interactions; see the Python references and the IPython page for the full suite of functionality.

D.1 Automatic parentheses

Automatic parenthesis is enabled for calling functions with argument lists; this feature is intended to allow less typing for common situations. IPython will display the interpretation of the line,

beneath the one typed, as indicated by the '----->'. Default behavior in CASA is to have automatic parenthesis enabled.

D.2 Indentation

Python pays attention to indentation of lines in scripts or when you enter them interactively. It uses indentation to determine the level of nesting in loops. Be careful when cutting and pasting, if you get the wrong indentation, then unpredictable things can happen (usually it just gives an error).

A blank line can be used to return the indentation to a previous level. For example, expanded parameters in tasks cause indentation in subsequent lines in the interface. For example, the following snippet of inputs from `clean` can be cut and pasted without error due to the blank line after the indented parameters:

```
mode          = 'channel'      # Type of selection
nchan        = -1             # Number of channels to select
start        = 0              # Start channel
step         = 1              # Increment between channels/velocity
width        = 1              # Channel width

alg          = 'clark'         # Algorithm to use
```

If the blank line were not there, an error would result if you pasted this at the `casapy` prompt.

D.3 Lists and Ranges

Sometimes, you need to give a task a list of indices. For example, some tasks and tools expect a comma-separated Python list, e.g.

```
scanlist = [241, 242, 243, 244, 245, 246]
```

You can use the Python `range` function to generate a list of consecutive numbers, e.g.

```
scanlist = range(241,247)
```

giving the same list as above, e.g.

```
CASA <1>: scanlist=range(241,247)
CASA <2>: print scanlist
[241, 242, 243, 244, 245, 246]
```

Note that `range` starts from the first limit and goes to one below the second limit (Python is 0-based, and `range` is designed to work in loop functions). If only a single limit is given, the first limit is treated as 0, and the one given is used as the second, e.g.

```
CASA <3>: iflist=range(4)
CASA <4>: print iflist
[0, 1, 2, 3]
```

You can also combine multiple ranges by summing lists

```
CASA <5>: scanlist=range(241,247) + range(251,255)
CASA <6>: print scanlist
[241, 242, 243, 244, 245, 246, 251, 252, 253, 254]
```

D.4 Dictionaries

Python dictionaries are data structures that contain **key:value** pairs, sort of like a hash array. These are useful to store mini-databases of things. In CASA, the parameter values are kept in a dictionary behind the scenes.

To initialize a dictionary, say we call it `mydict`, for use:

```
CASA <7>: mydict = {}
```

To add members:

```
CASA <8>: mydict['source'] = '0137+331'
CASA <9>: mydict['flux'] = 5.4
```

To see its contents:

```
CASA <10>: mydict
Out[10]: {'flux': 5.4, 'source': '0137+331'}
CASA <11>: print mydict
{'source': '0137+331', 'flux': 5.4}
```

To access a specific entry:

```
CASA <12>: print mydict['flux']
5.4
```

D.4.1 Saving and Reading Dictionaries

To save a simple dictionary to a file:

```
CASA <13>: dictfile = open('mydictfile.py','w')
CASA <14>: print >>dictfile,"mydict = ",mydict
CASA <15>: dictfile.close()
CASA <16>: !cat mydictfile.py
```

```
IPython system call: cat mydictfile.py
mydict = {'source': '0137+331', 'flux': 5.4000000000000004}

CASA <17>: mydict = {}
CASA <18>: run mydictfile.py
CASA <19>: mydict
Out[19]: {'flux': 5.400000000000004, 'source': '0137+331'}
```

More complex dictionaries, like those produced by `imstat` that contain NumPy arrays, require a different approach to save. The `pickle` module lets you save general data structures from Python. For example:

```
CASA <20>: import pickle
CASA <21>: xstat
Out[21]:
{'blc': array([0, 0, 0, 0]),
 'blcf': '15:24:08.404, +04.31.59.181, I, 1.41281e+09Hz',
 'flux': array([ 4.0795296]),
 'max': array([ 0.05235516]),
 'maxpos': array([134, 134, 0, 38]),
 'maxposf': '15:21:53.976, +05.05.29.998, I, 1.41374e+09Hz',
 'mean': array([ 1.60097857e-05]),
 'medabsdevmed': array([ 0.00127436]),
 'median': array([-1.17422514e-05]),
 'min': array([-0.0104834]),
 'minpos': array([160, 1, 0, 30]),
 'minposf': '15:21:27.899, +04.32.14.923, I, 1.41354e+09Hz',
 'npts': array([ 3014656.]),
 'quartile': array([ 0.00254881]),
 'rms': array([ 0.00202226]),
 'sigma': array([ 0.0020222]),
 'sum': array([ 48.26399646]),
 'sumsq': array([ 12.32857318]),
 'trc': array([255, 255, 0, 45]),
 'trcf': '15:19:52.390, +05.35.44.246, I, 1.41391e+09Hz'}
```

```
CASA <22>: mydict
Out[22]: {'flux': 5.400000000000004, 'source': '0137+331'}
```

```
CASA <23>: pickfile = 'myxstat.pickle'
CASA <24>: f = open(pickfile, 'w')
CASA <25>: p = pickle.Pickler(f)
CASA <26>: p.dump(xstat)
CASA <27>: p.dump(mydict)
CASA <28>: f.close()
```

The dictionaries are now saved in `pickle` file `myxstat.pickle` in the current directory.

To retrieve:

```
CASA <29>: xstat2 = {}
```

```
CASA <30>: mydict2 = {}
CASA <31>: f = open(pickfile)
CASA <32>: u = pickle.Unpickler(f)
CASA <33>: xstat2 = u.load()
CASA <34>: mydict2 = u.load()
CASA <35>: f.close()
CASA <36>: xstat2
Out[36]:
{'blc': array([0, 0, 0, 0]),
 'blcf': '15:24:08.404, +04.31.59.181, I, 1.41281e+09Hz',
 'flux': array([ 4.0795296]),
 'max': array([ 0.05235516]),
 'maxpos': array([134, 134, 0, 38]),
 'maxposf': '15:21:53.976, +05.05.29.998, I, 1.41374e+09Hz',
 'mean': array([ 1.60097857e-05]),
 'medabsdevmed': array([ 0.00127436]),
 'median': array([-1.17422514e-05]),
 'min': array([-0.0104834]),
 'minpos': array([160, 1, 0, 30]),
 'minposf': '15:21:27.899, +04.32.14.923, I, 1.41354e+09Hz',
 'npts': array([ 3014656.]),
 'quartile': array([ 0.00254881]),
 'rms': array([ 0.00202226]),
 'sigma': array([ 0.0020222]),
 'sum': array([ 48.26399646]),
 'sumsq': array([ 12.32857318]),
 'trc': array([255, 255, 0, 45]),
 'trcf': '15:19:52.390, +05.35.44.246, I, 1.41391e+09Hz'}
```

```
CASA <37>: mydict2
Out[37]: {'flux': 5.400000000000004, 'source': '0137+331'}
```

Thus, you can make scripts that save information and use it later, like for regressions.

Note that these examples use Python file-handling and IO, as well as importing modules such as `pickle`. See your friendly Python reference for more on this kind of stuff. Its fairly obvious how it works.

D.5 Control Flow: Conditionals, Loops, and Exceptions

There are a number of ways to control the flow of execution in Python, including conditionals (`if`), loops (`for` and `while`), and exceptions (`try`). We will discuss the first two below.

D.5.1 Conditionals

The standard `if` block handles conditional execution or branches in Python:

```

if <expression>:
    <statements>
elif <expression>:
    <statements>
elif <expression>:
    <statements>
...
else:
    <statements>

```

Insert a `pass` statement if you want no action to be taken for a particular clause. The `<expression>` should reduce down to `True` or `False`.

For example,

```

if ( importmode == 'vla' ):
    # Import the data from VLA Export to MS
    default('importvla')
    print "Use importvla to read VLA Export and make an MS"

    archivefiles = datafile
    vis = msfile
    bandname = exportband
    autocorr = False
    antnamescheme = 'new'
    project = exportproject

    importvla()

elif ( importmode == 'fits' ):
    # Import the data from VLA Export to MS
    default('importuvfits')
    print "Use importuvfits to read UVFITS and make an MS"

    fitsfile = datafile
    vis = msfile
    async = False

    importuvfits()

else:
    # Copy from msfile
    print "Copying "+datafile+" to "+msfile
    os.system('cp -r '+datafile+' '+msfile)
    vis = msfile

```

chooses branches based on the value of the `importmode` Python variable (set previously in script).

D.5.2 Loops

The `for` loop

```
for iter in seq:  
    <statements>
```

iterates over elements of a sequence `seq`, assigning each in turn to `iter`. The sequence is usually a list of values.

For example,

```
splitsms = 'polcal_20080224.cband.all.split.ms'  
srclist = ['0137+331','2136+006','2202+422','2253+161','0319+415','0359+509']  
spwlist = ['0','1']  
  
for src in srclist:  
  
    for spwid in spwlist:  
  
        imname = splitsms + '.' + src + '.' + spwid + '.clean'  
        clean(vis=splitsms,field=src,spw=spwid,imagermode='csclean',  
              stokes='IQUV',psfmode='hogbom',imsize=[288,288],cell=[0.4,0.4],niter=1000,  
              threshold=1.3,mask=[134,134,154,154])  
  
    # Done with spw  
  
# Done with sources
```

As usual, blocks are closed by blank lines of the previous indentation level.

You can use the `range` (§ D.3) Python function to generate a numerical loop:

```
vis = 'polcal_20080224.cband.all.ms'  
for i in range(0,6):  
    fld = str(i)  
    plotxy(vis,field=fld,xaxis='uvdist',yaxis='amp')  
  
# Done with fields [0, 1, 2, 3, 4, 5]
```

There is also a `while` loop construct

```
while <expression>:  
    <statements>
```

which executes the statement block while the `<expression>` is True. The `while` loop can also take an `else` block.

For example,

```

# Do an explicit set of clean iterations down to a limit
prevrms = 1.e10
while rms > 0.001 :
    clean(vis=splitms,field=src,spw=spwid,imagername=imname,
          stokes='IQUV',psfmode='hogbom',imagermode='csclean',
          imsize=[288,288],cell=[0.4,0.4],niter=200,
          threshold=1.3,mask=[134,134,154,154])

    offstat=imstat(imname+'.residual',box='224,224,284,284')
    rms=offstat['sigma'][0]
    if rms > prevrms:
        break                # the rms has increased, stop

    prevrms = rms

# Clean until the off-source rms residual, reaches 0.001 Jy

```

Note that you can exit a loop using the `break` statement, as we have here when the rms increases.

D.6 System shell access

For scripts, the `os.system` methods are the preferred way to access system shell commands (see § D.6.1).

In interactive mode, any input line beginning with a '!' character is passed verbatim (minus the '!') to the underlying operating system. Several common commands (`ls`, `pwd`, `less`) may be executed with or without the '!'. Note that the `cd` command must be executed without the '!', and the `cp` command must use '!' as there is a conflict with the `cp` tool in `casapy`.

For example:

```

CASA [1]: pwd
/export/home/corsair-vml/jmcnulli/data
CASA [2]: ls n*
ngc5921.ms ngc5921.py
CASA [3]: !cp -r ../test.py .

```

D.6.1 Using the `os.system` methods

To use this, you need the `os` package. This should be loaded by default by `casapy`, but if not you can use

```
import os
```

in your script.

For example, in our scripts we use this to clean up any existing output files

```
# The prefix to use for all output files
prefix='ngc5921.usecase'

# Clean up old files
os.system('rm -rf '+prefix+'*)
```

Note that the `os` package has many useful methods. You can see these by using tab-completion:

```
CASA <2>: os.<tab>
Display all 223 possibilities? (y or n)
os.EX_CANTCREATE          os.X_OK                  os.fdatasync           os.readlink
os.EX_CONFIG                os._Environ             os.fdopen               os.remove
os.EX_DATAERR               os.__all__              os.fork                 os.removedirs
os.EX_IOERR                  os.__class__            os.forkpty              os.rename
os.EX_NOHOST                 os.__delattr__         os.fpathconf            os.renames
os.EX_NOINPUT                 os.__dict__             os.fstat                os.rmdir
os.EX_NOPERM                  os.__doc__              os.fstatvfs             os.sep
os.EX_NOUSER                  os.__file__             os.fsync                os.setegid
os.EX_OK                     os.__getattribute__    os.ftruncate            os.seteuid
os.EX_OSERR                   os.__hash__             os.getcwd               os.setgid
os.EX_OSFILE                  os.__init__             os.getcwddu             os.setgroups
os.EX_PROTOCOL                 os.__name__             os.getegid              os.setpgid
os.EX_SOFTWARE                 os.__new__              os.getenv               os.setgrp
os.EX_TEMPFAIL                 os.__reduce__          os.geteuid              os.setregid
os.EX_UNAVAILABLE              os.__reduce_ex__       os.getgid               os.setreuid
os.EX_USAGE                    os.__repr__             os.getgroups             os.setsid
os.F_OK                      os.__setattr__          os.getloadavg            os.setuid
os.NGROUPS_MAX                 os.__str__              os.getlogin              os.spawnl
os.O_APPEND                   os._copy_reg            os.getpgid              os.spawnle
os.O_CREAT                     os._execvpe             os.getpgrp              os.spawnlp
os.O_DIRECT                    os._exists              os.getpid               os.spawnlpe
os.O_DIRECTORY                  os._exit                os.getppid              os.spawnnv
os.O_DSYNC                     os._get_exports_list   os.getsid               os.spawnve
os.O_EXCL                      os._make_stat_result  os.getuid               os.spawnvp
os.O_LARGEFILE                  os._make_statvfs_result  os.isatty              os.spawnvpe
os.O_NDELAY                     os._pickle_stat_result  os.kill                os.stat
os.O_NOCTTY                     os._pickle_statvfs_result  os.killpg              os.stat_float_times
os.O_NOFOLLOW                   os._spawnvef            os.lchown              os.stat_result
os.O_NONBLOCK                   os.abort                os.linesep              os.statvfs
os.O_RDONLY                     os.access               os.link                os.statvfs_result
os.O_RDWR                       os.altsep               os.listdir              os.strerror
os.O_RSYNC                      os.chdir                os.lseek               os.symlink
os.O_SYNC                        os.chmod                os.lstat                os.sys
os.O_TRUNC                      os.chown                os.major                os.sysconf
os.O_WRONLY                     os.chroot               os.makedev              os.sysconf_names
os.P_NOWAIT                     os.close                os.makedirs             os.system
os.P_NOWAITO                    os.confstr              os.minor                os.tcgetpgrp
os.P_WAIT                       os.confstr_names        os.mkdir                os.tcsetpgrp
os.R_OK                         os.ctermid              os.mkfifo               os.tempnam
os.SEEK_CUR                      os.curdir               os.mknod                os.times
os.SEEK_END                     os.defpath              os.name                os.tmpfile
```

os.SEEK_SET	os.devnull	os.nice	os.tmpnam
os.TMP_MAX	os.dup	os.open	os.ttyname
os.UserDict	os.dup2	os.openpty	os.umask
os.WCONTINUED	os.environ	os.pardir	os.uname
os.WCOREDUMP	os.error	os.path	os.unlink
os.WEXITSTATUS	os.execl	os.pathconf	os.unsetenv
os.WIFCONTINUED	os.execle	os.pathconf_names	os.urandom
os.WIFEXITED	os.execlp	os.pathsep	os.utime
os.WIFSIGNALED	os.execlpe	os.pipe	os.wait
os.WIFSTOPPED	os.execv	os.popen	os.wait3
os.WNOHANG	os.execve	os.popen2	os.wait4
os.WSTOPSIG	os.execvp	os.popen3	os.waitpid
os.WTERMSIG	os.execvpe	os.popen4	os.walk
os.WUNTRACED	os.extsep	os.putenv	os.write
os.W_OK	os.fchdir	os.read	

D.6.2 Directory Navigation

In addition, filesystem navigation is aided through the use of bookmarks to simplify access to frequently-used directories:

```
CASA [4]: cd /home/ballista/jmcmulli/other_data
CASA [4]: pwd
/home/ballista/jmcmulli/other_data
CASA [5]: bookmark other_data
CASA [6]: cd /export/home/corsair-vml/jmcmulli/data
CASA [7]: pwd
/export/home/corsair-vml/jmcmulli/data
CASA [8]: cd -b other_data
(bookmark:data) -> /home/ballista/jmcmulli/other_data
```

D.6.3 Shell Command and Capture

See also § D.8 for the use of the command history.

1. sx shell_command, !!shell_command - this captures the output to a list

```
CASA [1]: sx pwd # stores output of 'pwd' in a list
Out[1]: ['/home/basho3/jmcmulli/pretest']

CASA [2]: !!pwd # !! is a shortcut for 'sx'
Out[2]: ['/home/basho3/jmcmulli/pretest']

CASA [3]: sx ls v* # stores output of 'pwd' in a list
Out[3]:
['vla_calplot.jpg',
 'vla_calplot.png',
 'vla_msplot_cals.jpg',
```

```
'vla_msplot_cals.png',
'vla_plotcal_bpss.jpg',
'vla_plotcal_bpss.png',
'vla_plotcal_fcal.jpg',
'vla_plotcal_fcal.png',
'vla_plotvis.jpg',
'vla_plotvis.png']

CASA [4]: x=_ # remember '_' is a shortcut for the output from the last command

CASA [5]: x
Out[5]:
['vla_calplot.jpg',
'vla_calplot.png',
'vla_msplot_cals.jpg',
'vla_msplot_cals.png',
'vla_plotcal_bpss.jpg',
'vla_plotcal_bpss.png', 'vla_plotcal_fcal.jpg',
'vla_plotcal_fcal.png',
'vla_plotvis.jpg',
'vla_plotvis.png']

CASA [6]: y=Out[2] # or just refer to the enumerated output

CASA [7]: y
Out[7]: ['/home/basho3/jmcmulli/pretest']
```

2. sc - captures the output to a variable; options are '-l' and '-v'

```
CASA [1]: sc x=pwd # capture output from 'pwd' to the variable 'x'

CASA [2]: x
Out[2]: '/home/basho3/jmcmulli/pretest'

CASA [3]: sc -l x=pwd # capture the output from 'pwd' to the variable 'x' but
           # split newlines into a list (similar to sx command)

CASA [4]: x
Out[4]: ['/home/basho3/jmcmulli/pretest']

CASA [5]: sc -v x=pwd # capture output from 'pwd' to a variable 'x' and
           # show what you get (verbose mode)
x ==
'/home/basho3/jmcmulli/pretest'

CASA [6]: x
Out[6]: '/home/basho3/jmcmulli/pretest'
```

D.7 Logging

There are two components to logging within CASA. Logging of all command line inputs is done via IPython.

Upon startup, CASA will log all commands to a file called `ipython.log`. This file can be changed via the use of the `ipythonrc` file. This log file can be edited and re-executed as appropriate using the `execfile` feature (§ D.11).

The following line sets up the logging for CASA . There are four options following the specification of the logging file: 1) append, 2) rotate (each session of CASA will create a new log file with a counter incrementing `ipython.log.1`, `ipython.log.2` etc, 3) over (overwrite existing file), and 4) backup (renames existing log file to `log_name`).

```
logfile ./ipython.log append
```

The command `logstate` will provide details on the current logging setup:

```
CASA [12]: logstate
File:  ipython.log
Mode:  append
State: active
```

Logging can be turned on and off using the `logon`, `logoff` commands.

The second component is the output from applications which is directed to the file `./casapy.log`. See § 1.4.2 for more on the `casalogger`.

D.8 History and Searching

Numbered input/output history is provided natively within IPython. Command history is also maintained on-line.

```
CASA [11]: x=1
CASA [12]: y=3*x
CASA [13]: z=x**2+y**2
CASA [14]: x
Out[14]: 1
CASA [15]: y
Out[15]: 3
```

```
CASA [16]: z
Out[16]: 10

CASA [17]: Out[14] # Note: The 'Out' vector contains command output
Out[17]: 1

CASA [18]: _15      # Note: The return value can be accessed by _number
Out[18]: 3

CASA [19]: ___      # Note: The last three return values can be accessed as:
Out[19]: 10         #     -, --, ___
```

Command history can be accessed via the 'hist' command. The history is reset at the beginning of every CASA session, that is, typing 'hist' when you first start CASA will not provide any commands from the previous session. However, all of the commands are still available at the command line and can be accessed through the up or down arrow keys, and through searching.

```
CASA [22]: hist
1 : __IP.system("vi temp.py") # Note:shell commands are designated in this way
2 : ipmagic("run -i temp.py") # Note:magic commands are designated in this way
3 : ipmagic("hist ")
4 : more temp.py
5 : __IP.system("more temp.py")
6 : quickhelp()               # Note: autoparenthesis are added in the history
7 : im.open('ngc5921.ms')
8 : im.summary()
9 : ipmagic("pdoc im.setdata")
10: im.close()
11: quickhelp()
12: ipmagic("logstate ")
13: x=1
14: y=3*x
15: z=x**2+y**2
16: x
17: y
18: z
19: Out[16]
20: _17
21: ___
```

The history can be saved as a script or used as a macro for further use:

```
CASA [24]: save script.py 13:16
File 'script.py' exists. Overwrite (y/[N])? y
The following commands were written to file 'script.py':
x=1
y=3*x
z=x**2+y**2
```

```
CASA [25]: !more script.py
x=1
y=3*x
z=x**2+y**2
```

Note that the history commands will be saved up to, but not including the last value (i.e., history commands 13-16 saves commands 13, 14, and 15).

There are two mechanisms for searching command history:

1. Previous/Next: use **Ctrl-p** (previous,up) and **Ctrl-n** (next,down) to search through only the history items that match what you have typed so far (min-match completion). If you use **Ctrl-p** or **Ctrl-n** at a blank prompt, they behave just like the normal arrow keys.
2. Search: **Ctrl-r** opens a search prompt. Begin typing and the system searches your history for lines that contain what you've typed so far, completing what it can. For example:

```
CASA [37]: <Ctrl-r>
(reverse-i-search) '':
```

Typing anything after the colon will provide you with the last command matching the characters, for example, typing 'op' finds:

```
(reverse-i-search) 'op': im.open('ngc5921.ms')
```

Subsequent hitting of **Ctrl-r** will search for the next command matching the characters.

D.9 Macros

Macros can be made for easy re-execution of previous commands. For example to store the commands 13-15 to the macro 'example':

```
CASA [31]: macro example 13:16
Macro 'example' created. To execute, type its name (without quotes).
Macro contents:
x=1
y=3*x
z=x**2+y**2

CASA [32]: z
Out[32]: 6

CASA [33]: z=10

CASA [34]: example
Out[34]: Executing Macro...
```

```
CASA [35]: z
Out[35]: 6
```

```
CASA [36]:
```

D.10 On-line editing

You can edit files on-line in two ways:

1. Using the shell access via '!vi'
2. Using the ed function; this will edit the file but upon closing, it will try to execute the file; using the 'script.py' example above:

```
CASA [13]: ed script.py # this will bring up the file in your chosen editor
           # when you are finished editing the file,
           # it will automatically
           # execute it (as though you had done a
           # execfile 'script.py'
Editing... done. Executing edited code...
```

```
CASA [14]: x
Out[14]: 1
```

```
CASA [15]: y
Out[15]: 3
```

```
CASA [16]: z
Out[16]: 6
```

D.11 Executing Python scripts

Python scripts are simple text files containing lists of commands as if typed at the keyboard. Note: the auto-parentheses feature of IPython can not be used in scripts, that is, you should make sure all function calls have any opening and closing parentheses.

```
# file is script.py
# My script to plot the observed visibilities
plotxy('ngc5921.ms','uvdist') #yaxis defaults to amplitude
```

This can be done by using the execfile command to execute this script. execfile will execute the script as though you had typed the lines at the CASA prompt.

```
CASA [5]: execfile 'script.py'
-----> execfile('script.py')
```

D.12 How do I exit from CASA?

You can exit CASA by using the `quit` command. This will bring up the query

```
Do you really want to exit ([y]/n)?
```

to give you a chance in case you did not mean to exit. You can also quit using `%exit` or `CTRL-D`.

If you don't want to see the question "Do you really want to exit [y]/n?", then just type `Exit` or `exit` followed by return, and CASA will stop right then and there.

Appendix E

The Measurement Equation and Calibration

The visibilities measured by an interferometer must be calibrated before formation of an image. This is because the wavefronts received and processed by the observational hardware have been corrupted by a variety of effects. These include (but are not exclusive to): the effects of transmission through the atmosphere, the imperfect details amplified electronic (digital) signal and transmission through the signal processing system, and the effects of formation of the cross-power spectra by a correlator. Calibration is the process of reversing these effects to arrive at corrected visibilities which resemble as closely as possible the visibilities that would have been measured in vacuum by a perfect system. The subject of this chapter is the determination of these effects by using the visibility data itself.

E.1 The HBS Measurement Equation

The relationship between the observed and ideal (desired) visibilities on the baseline between antennas i and j may be expressed by the Hamaker-Bregman-Sault *Measurement Equation*¹:

$$\vec{V}_{ij} = J_{ij} \vec{V}_{ij}^{\text{IDEAL}}$$

where \vec{V}_{ij} represents the observed visibility, $\vec{V}_{ij}^{\text{IDEAL}}$ represents the corresponding ideal visibilities, and J_{ij} represents the accumulation of all corruptions affecting baseline ij . The visibilities are indicated as vectors spanning the four correlation combinations which can be formed from dual-polarization signals. These four correlations are related directly to the Stokes parameters which fully describe the radiation. The J_{ij} term is therefore a 4×4 matrix.

Most of the effects contained in J_{ij} (indeed, the most important of them) are antenna-based, i.e., they arise from measurable physical properties of (or above) individual antenna elements in a synthesis array. Thus, adequate calibration of an array of N_{ant} antennas forming $N_{\text{ant}}(N_{\text{ant}} - 1)/2$ baseline visibilities is usually achieved through the determination of only N_{ant} factors, such that

¹Hamaker, J.P., Bregman, J.D. & Sault, R.J. (1996), *Astronomy and Astrophysics Supplement*, v.117, p.137-147

$J_{ij} = J_i \otimes J_j^*$. For the rest of this chapter, we will usually assume that J_{ij} is factorable in this way, unless otherwise noted.

As implied above, J_{ij} may also be factored into the sequence of specific corrupting effects, each having their own particular (relative) importance and physical origin, which determines their unique algebra. Including the most commonly considered effects, the Measurement Equation can be written:

$$\vec{V}_{ij} = M_{ij} B_{ij} G_{ij} D_{ij} E_{ij} P_{ij} T_{ij} \vec{V}_{ij}^{\text{IDEAL}}$$

where:

- T_{ij} = Polarization-independent multiplicative effects introduced by the troposphere, such as opacity and path-length variation.
- P_{ij} = Parallactic angle, which describes the orientation of the polarization coordinates on the plane of the sky. This term varies according to the type of the antenna mount.
- E_{ij} = Effects introduced by properties of the optical components of the telescopes, such as the collecting area's dependence on elevation.
- D_{ij} = Instrumental polarization response. "D-terms" describe the polarization leakage between feeds (e.g. how much the R-polarized feed picked up L-polarized emission, and vice versa).
- G_{ij} = Electronic gain response due to components in the signal path between the feed and the correlator. This complex gain term G_{ij} includes the scale factor for absolute flux density calibration, and may include phase and amplitude corrections due to changes in the atmosphere (in lieu of T_{ij}). These gains are polarization-dependent.
- B_{ij} = Bandpass (frequency-dependent) response, such as that introduced by spectral filters in the electronic transmission system
- M_{ij} = Baseline-based correlator (non-closing) errors. By definition, these are not factorable into antenna-based parts.

Note that the terms are listed in the order in which they affect the incoming wavefront (G and B represent an arbitrary sequence of such terms depending upon the details of the particular electronic system). Note that M differs from all of the rest in that it is not antenna-based, and thus not factorable into terms for each antenna.

As written above, the measurement equation is very general; not all observations will require treatment of all effects, depending upon the desired dynamic range. E.g., bandpass need only be considered for continuum observations if observed in a channelized mode and very high dynamic range is desired. Similarly, instrumental polarization calibration can usually be omitted when observing (only) total intensity using circular feeds. Ultimately, however, each of these effects occurs at some level, and a complete treatment will yield the most accurate calibration. Modern high-sensitivity instruments such as ALMA and EVLA will likely require a more general calibration

treatment for similar observations with older arrays in order to reach the advertised dynamic ranges on strong sources.

In practice, it is usually far too difficult to adequately measure most calibration effects absolutely (as if in the laboratory) for use in calibration. The effects are usually far too changeable. Instead, the calibration is achieved by making observations of calibrator sources on the appropriate timescales for the relevant effects, and solving the measurement equation for them using the fact that we have $N_{\text{ant}}(N_{\text{ant}} - 1)/2$ measurements and only N_{ant} factors to determine (except for M which is only sparingly used). (*Note: By partitioning the calibration factors into a series of consecutive effects, it might appear that the number of free parameters is some multiple of N_{ant} , but the relative algebra and timescales of the different effects, as well as the multiplicity of observed polarizations and channels compensate, and it can be shown that the problem remains well-determined until, perhaps, the effects are direction-dependent within the field of view. Limited solvers for such effects are under study; the `calibrator` tool currently only handles effects which may be assumed constant within the field of view. Corrections for the primary beam are handled in the `imager` tool.*) Once determined, these terms are used to correct the visibilities measured for the scientific target. This procedure is known as cross-calibration (when only phase is considered, it is called phase-referencing).

The best calibrators are point sources at the phase center (constant visibility amplitude, zero phase), with sufficient flux density to determine the calibration factors with adequate SNR on the relevant timescale. The primary gain calibrator must be sufficiently close to the target on the sky so that its observations sample the same atmospheric effects. A bandpass calibrator usually must be sufficiently strong (or observed with sufficient duration) to provide adequate per-channel sensitivity for a useful calibration. In practice, several calibrators are usually observed, each with properties suitable for one or more of the required calibrations.

Synthesis calibration is inherently a bootstrapping process. First, the dominant calibration term is determined, and then, using this result, more subtle effects are solved for, until the full set of required calibration terms is available for application to the target field. The solutions for each successive term are relative to the previous terms. Occasionally, when the several calibration terms are not sufficiently orthogonal, it is useful to re-solve for earlier types using the results for later types, in effect, reducing the effect of the later terms on the solution for earlier ones, and thus better isolating them. This idea is a generalization of the traditional concept of self-calibration, where initial imaging of the target source supplies the visibility model for a re-solve of the gain calibration (G or T). Iteration tends toward convergence to a statistically optimal image. In general, the quality of each calibration and of the source model are mutually dependent. In principle, as long as the solution for any calibration component (or the source model itself) is likely to improve substantially through the use of new information (provided by other improved solutions), it is worthwhile to continue this process.

In practice, these concepts motivate certain patterns of calibration for different types of observation, and the `calibrator` tool in CASA is designed to accommodate these patterns in a general and flexible manner. For a spectral line total intensity observation, the pattern is usually:

1. Solve for G on the bandpass calibrator
2. Solve for B on the bandpass calibrator, using G

3. Solve for G on the primary gain (near-target) and flux density calibrators, using B solutions just obtained
4. Scale G solutions for the primary gain calibrator according to the flux density calibrator solutions
5. Apply G and B solutions to the target data
6. Image the calibrated target data

If opacity and gain curve information are relevant and available, these types are incorporated in each of the steps (in future, an actual solve for opacity from appropriate data may be folded into this process):

1. Solve for G on the bandpass calibrator, using T (opacity) and E (gain curve) solutions already derived.
2. Solve for B on the bandpass calibrator, using G , T (opacity), and E (gain curve) solutions.
3. Solve for G on primary gain (near-target) and flux density calibrators, using B , T (opacity), and E (gain curve) solutions.
4. Scale G solutions for the primary gain calibrator according to the flux density calibrator solutions
5. Apply T (opacity), E (gain curve), G , and B solutions to the target data
6. Image the calibrated target data

For continuum polarimetry, the typical pattern is:

1. Solve for G on the polarization calibrator, using (analytical) P solutions.
2. Solve for D on the polarization calibrator, using P and G solutions.
3. Solve for G on primary gain and flux density calibrators, using P and D solutions.
4. Scale G solutions for the primary gain calibrator according to the flux density calibrator solutions.
5. Apply P , D , and G solutions to target data.
6. Image the calibrated target data.

For a spectro-polarimetry observation, these two examples would be folded together.

In all cases the calibrator model must be adequate at each solve step. At high dynamic range and/or high resolution, many calibrators which are nominally assumed to be point sources become slightly resolved. If this has biased the calibration solutions, the offending calibrator may be imaged at any point in the process and the resulting model used to improve the calibration. Finally, if sufficiently strong, the target may be self-calibrated as well.

E.2 General Calibrator Mechanics

The calibrator tasks/tool are designed to solve and apply solutions for all of the solution types listed above (and more are in the works). This leads to a single basic sequence of execution for all solves, regardless of type:

1. Set the calibrator model visibilities
2. Select the visibility data which will be used to solve for a calibration type
3. Arrange to apply any already-known calibration types (the first time through, none may yet be available)
4. Arrange to solve for a specific calibration type, including specification of the solution timescale and other specifics
5. Execute the solve process
6. Repeat 1-4 for all required types, using each result, as it becomes available, in step 2, and perhaps repeating for some types to improve the solutions

By itself, this sequence doesn't guarantee success; the data provided for the solve must have sufficient SNR on the appropriate timescale, and must provide sufficient leverage for the solution (e.g., D solutions require data taken over a sufficient range of parallactic angle in order to separate the source polarization contribution from the instrumental polarization).

Appendix F

Annotated Example Scripts

Note: These data sets are available with the full CASA rpm distribution. Other data sets can be made available upon request. The scripts are intended to illustrate the types of commands needed for different types of reduction/astrophysical observations.

BETA ALERT: During the Beta Release period, we will be occasionally updating the syntax of the tasks, which may break older versions of the scripts. You can find the latest versions of these (and other) scripts at:

<http://casa.nrao.edu/Doc/Scripts/>

F.1 NGC 5921 — VLA red-shifted HI emission

Note: This script does not include any self-calibration steps.

The latest version of this script can be found at:

http://casa.nrao.edu/Doc/Scripts/ngc5921_usecase.py

```
#####
# Use Case Script for NGC 5921
#
# Converted by STM 2007-05-26
# Updated      STM 2007-06-15 (Alpha Patch 1)
# Updated      STM 2007-09-05 (Alpha Patch 2+)
# Updated      STM 2007-09-18 (Alpha Patch 2+)
# Updated      STM 2007-09-18 (Pre-Beta) add immoments
# Updated      STM 2007-10-04 (Beta) update
# Updated      STM 2007-10-10 (Beta) add export
# Updated      STM 2007-11-08 (Beta Patch 0.5) add RRusk stuff
# Updated      STM 2008-03-25 (Beta Patch 1.0)
```

```

# Updated      STM 2008-05-23 (Beta Patch 2.0) new tasking/clean/cal      #
# Updated      STM 2008-06-11 (Beta Patch 2.0)      #
#
# Features Tested:      #
#   The script illustrates end-to-end processing with CASA      #
#   as depicted in the following flow-chart.      #
#
#   Filenames will have the <prefix> = 'ngc5921.usecase'      #
#
#   Input Data          Process          Output Data      #
#
# NGC5921.fits --> importuvfits --> <prefix>.ms +      #
# (1.4GHz,           |           <prefix>.ms.flagversions      #
# 63 sp chan,       v           #      #
# D-array)         listobs     --> casapy.log      #
#                   |           #      #
#                   v           #      #
#                   flagautocorr      #
#                   |           #      #
#                   v           #      #
#                   setjy      #
#                   |           #      #
#                   v           #      #
#                   bandpass    --> <prefix>.bcal      #
#                   |           #      #
#                   v           #      #
#                   gaincal    --> <prefix>.gcal      #
#                   |           #      #
#                   v           #      #
#                   fluxscale   --> <prefix>.fluxscale      #
#                   |           #      #
#                   v           #      #
#                   applycal   --> <prefix>.ms      #
#                   |           #      #
#                   v           #      #
#                   split      --> <prefix>.cal.split.ms      #
#                   |           #      #
#                   v           #      #
#                   split      --> <prefix>.src.split.ms      #
#                   |           #      #
#                   v           #      #
#                   exportuvfits --> <prefix>.split.uvfits      #
#                   |           #      #
#                   v           #      #
#                   uvcontsub   --> <prefix>.ms.cont +      #
#                   |           <prefix>.ms.contsub      #
#                   v           #      #
#                   clean      --> <prefix>.clean.image +      #
#                   |           <prefix>.clean.model +      #
#                   |           <prefix>.clean.residual      #
#                   v           #      #

```

```

#           exportfits    --> <prefix>.clean.fits      #
#           |          #
#           v          #
#           imhead     --> casapy.log      #
#           |          #
#           v          #
#           imstat     --> xstat (parameter)      #
#           |          #
#           v          #
#           immoments   --> <prefix>.moments.integrated +  #
#           |           <prefix>.moments.weighted_coord  #
#           v          #
#####
import time
import os

#
# Set up some useful variables
#
# Get to path to the CASA home and strip off the name
pathname=os.environ.get('AIPSPATH').split()[0]

# This is where the NGC5921 UVFITS data will be
fitsdata=pathname+'/data/demo/NGC5921.fits'
#
# Or use data in current directory
#fitsdata='NGC5921.fits'

# The prefix to use for all output files
prefix='ngc5921.usecase'

# Clean up old files
os.system('rm -rf '+prefix+'*')

#
#=====
#
# Import the data from FITS to MS
#
print '--Import--'

# Safest to start from task defaults
default('importuvfits')

# Set up the MS filename and save as new global variable
msfile = prefix + '.ms'

# Use task importuvfits
fitsfile = fitsdata
vis = msfile

```

```

saveinputs('importuvfits',prefix+'.importuvfits.saved')

importuvfits()

#
# Note that there will be a ngc5921.usecase.ms.flagversions
# there containing the initial flags as backup for the main ms
# flags.
#
#=====
#
# List a summary of the MS
#
print '--Listobs--'

# Don't default this one and make use of the previous setting of
# vis. Remember, the variables are GLOBAL!

# You may wish to see more detailed information, like the scans.
# In this case use the verbose = True option
verbose = True

listobs()

# You should get in your logger window and in the casapy.log file
# something like:
#
# MeasurementSet Name: /home/sandrock2/smyers/Testing2/Sep07/ngc5921.usecase.ms
# MS Version 2
#
# Observer: TEST      Project:
# Observation: VLA
#
# Data records: 22653      Total integration time = 5280 seconds
# Observed from 09:19:00 to 10:47:00
#
#     ObservationID = 0          ArrayID = 0
#     Date           Timerange            Scan  FldId FieldName      SpwIds
#     13-Apr-1995/09:19:00.0 - 09:24:30.0    1      0 1331+30500002_0 [0]
#                               09:27:30.0 - 09:29:30.0    2      1 1445+09900002_0 [0]
#                               09:33:00.0 - 09:48:00.0    3      2 N5921_2        [0]
#                               09:50:30.0 - 09:51:00.0    4      1 1445+09900002_0 [0]
#                               10:22:00.0 - 10:23:00.0   5      1 1445+09900002_0 [0]
#                               10:26:00.0 - 10:43:00.0   6      2 N5921_2        [0]
#                               10:45:30.0 - 10:47:00.0   7      1 1445+09900002_0 [0]
#
# Fields: 3
#     ID  Code Name          Right Ascension  Declination  Epoch
#     0    C   1331+30500002_013:31:08.29    +30.30.32.96 J2000
#     1    A   1445+09900002_014:45:16.47    +09.58.36.07 J2000

```

```

# 2           N5921_2        15:22:00.00      +05.04.00.00 J2000
#
# Spectral Windows: (1 unique spectral windows and 1 unique polarization setups)
#   SpwID #Chans Frame Ch1(MHz)  Resoln(kHz) TotBW(kHz) Ref(MHz) Corrs
#   0       63    LSRK  1412.68608  24.4140625  1550.19688  1413.44902 RR LL
#
# Feeds: 28: printing first row only
#   Antenna  Spectral Window  # Receptors  Polarizations
#   1          -1              2            [          R, L]
#
# Antennas: 27:
#   ID  Name  Station  Diam.  Long.  Lat.
#   0   1    VLA:N7  25.0 m  -107.37.07.2  +33.54.12.9
#   1   2    VLA:W1  25.0 m  -107.37.05.9  +33.54.00.5
#   2   3    VLA:W2  25.0 m  -107.37.07.4  +33.54.00.9
#   3   4    VLA:E1  25.0 m  -107.37.05.7  +33.53.59.2
#   4   5    VLA:E3  25.0 m  -107.37.02.8  +33.54.00.5
#   5   6    VLA:E9  25.0 m  -107.36.45.1  +33.53.53.6
#   6   7    VLA:E6  25.0 m  -107.36.55.6  +33.53.57.7
#   7   8    VLA:W8  25.0 m  -107.37.21.6  +33.53.53.0
#   8   9    VLA:N5  25.0 m  -107.37.06.7  +33.54.08.0
#   9   10   VLA:W3  25.0 m  -107.37.08.9  +33.54.00.1
#  10  11   VLA:N4  25.0 m  -107.37.06.5  +33.54.06.1
#  11  12   VLA:W5  25.0 m  -107.37.13.0  +33.53.57.8
#  12  13   VLA:N3  25.0 m  -107.37.06.3  +33.54.04.8
#  13  14   VLA:N1  25.0 m  -107.37.06.0  +33.54.01.8
#  14  15   VLA:N2  25.0 m  -107.37.06.2  +33.54.03.5
#  15  16   VLA:E7  25.0 m  -107.36.52.4  +33.53.56.5
#  16  17   VLA:E8  25.0 m  -107.36.48.9  +33.53.55.1
#  17  18   VLA:W4  25.0 m  -107.37.10.8  +33.53.59.1
#  18  19   VLA:E5  25.0 m  -107.36.58.4  +33.53.58.8
#  19  20   VLA:W9  25.0 m  -107.37.25.1  +33.53.51.0
#  20  21   VLA:W6  25.0 m  -107.37.15.6  +33.53.56.4
#  21  22   VLA:E4  25.0 m  -107.37.00.8  +33.53.59.7
#  23  24   VLA:E2  25.0 m  -107.37.04.4  +33.54.01.1
#  24  25   VLA:N6  25.0 m  -107.37.06.9  +33.54.10.3
#  25  26   VLA:N9  25.0 m  -107.37.07.8  +33.54.19.0
#  26  27   VLA:N8  25.0 m  -107.37.07.5  +33.54.15.8
#  27  28   VLA:W7  25.0 m  -107.37.18.4  +33.53.54.8
#
# Tables:
#   MAIN                  22653 rows
#   ANTENNA                28 rows
#   DATA_DESCRIPTION         1 row
#   DOPPLER                <absent>
#   FEED                   28 rows
#   FIELD                   3 rows
#   FLAG_CMD                <empty>
#   FREQ_OFFSET              <absent>
#   HISTORY                  273 rows
#   OBSERVATION                1 row

```

```

#      POINTING          168 rows
#      POLARIZATION       1 row
#      PROCESSOR          <empty>
#      SOURCE              3 rows
#      SPECTRAL_WINDOW     1 row
#      STATE               <empty>
#      SYSCAL              <absent>
#      WEATHER              <absent>
#
#
#=====
#
# Get rid of the autocorrelations from the MS
#
print '--Flagautocorr--'

# Don't default this one either, there is only one parameter (vis)

flagautocorr()

#
#=====
#
# Set the fluxes of the primary calibrator(s)
#
print '--Setjy--'
default('setjy')

vis = msfile

#
# 1331+305 = 3C286 is our primary calibrator
# Use the wildcard on the end of the source name
# since the field names in the MS have inherited the
# AIPS qualifiers
field = '1331+305*'

# This is 1.4GHz D-config and 1331+305 is sufficiently unresolved
# that we dont need a model image. For higher frequencies
# (particularly in A and B config) you would want to use one.
modimage = ''

# Setjy knows about this source so we dont need anything more

saveinputs('setjy',prefix+'.setjy.saved')

setjy()

#
# You should see something like this in the logger and casapy.log file:
#

```

```

# 1331+30500002_0 spwid= 0 [I=14.76, Q=0, U=0, V=0] Jy, (Perley-Taylor 99)
#
# So its using 14.76Jy as the flux of 1331+305 in the single Spectral Window
# in this MS.
#
#=====
#
# Bandpass calibration
#
print '--Bandpass--'
default('bandpass')

# We can first do the bandpass on the single 5min scan on 1331+305
# At 1.4GHz phase stability should be sufficient to do this without
# a first (rough) gain calibration. This will give us the relative
# antenna gain as a function of frequency.

vis = msfile

# set the name for the output bandpass caltable
btable = prefix + '.bcal'
caltable = btable

# No gain tables yet
gaintable = ''
gainfield = ''
interp = ''

# Use flux calibrator 1331+305 = 3C286 (FIELD_ID 0) as bandpass calibrator
field = '0'
# all channels
spw = ''
# No other selection
selectdata = False

# In this band we do not need a-priori corrections for
# antenna gain-elevation curve or atmospheric opacity
# (at 8GHz and above you would want these)
gaincurve = False
opacity = 0.0

# Choose bandpass solution type
# Pick standard time-binned B (rather than BPOLY)
bandtype = 'B'

# set solution interval arbitrarily long (get single bpss)
solint = 86400.0

# reference antenna Name 15 (15=VLA:N2) (Id 14)
refant = '15'

```

```
saveinputs('bandpass',prefix+'.bandpass.saved')

bandpass()

#
#=====
#
# Use plotcal to examine the bandpass solutions
#
print '--Plotcal (bandpass)--'
default('plotcal')

caltable = btable
field = '0'

# No GUI for this script
showgui = False
# If you want to do this interactively and iterate over antenna, set
#iteration = 'antenna'
#showgui = True

# Set up 2x1 panels - upper panel amp vs. channel
subplot = 211
yaxis = 'amp'
# No output file yet (wait to plot next panel)

saveinputs('plotcal',prefix+'.plotcal.b.amp.saved')

plotcal()
#
# Set up 2x1 panels - lower panel phase vs. channel
subplot = 212
yaxis = 'phase'
# Now send final plot to file in PNG format (via .png suffix)
figfile = caltable + '.plotcal.png'

saveinputs('plotcal',prefix+'.plotcal.b.phase.saved')

plotcal()
#
# Note the rolloff in the start and end channels. Looks like
# channels 6-56 (out of 0-62) are the best
#
#=====

#
# Gain calibration
#
print '--Gaincal--'
default('gaincal')

# Armed with the bandpass, we now solve for the
```

```
# time-dependent antenna gains

vis = msfile

# set the name for the output gain caltable
gtable = prefix + '.gcal'
caltable = gtable

# Use our previously determined bandpass
# Note this will automatically be applied to all sources
# not just the one used to determine the bandpass
gaintable = btable
gainfield = ''

# Use nearest (there is only one bandpass entry)
interp = 'nearest'

# Gain calibrators are 1331+305 and 1445+099 (FIELD_ID 0 and 1)
field = '0,1'

# We have only a single spectral window (SPW 0)
# Choose 51 channels 6-56 out of the 63
# to avoid end effects.
# Channel selection is done inside spw
spw = '0:6~56'

# No other selection
selectdata = False

# In this band we do not need a-priori corrections for
# antenna gain-elevation curve or atmospheric opacity
# (at 8GHz and above you would want these)
gaincurve = False
opacity = 0.0

# scan-based G solutions for both amplitude and phase
gaintype = 'G'
solint = 'inf'
combine = ''
calmode = 'ap'

# minimum SNR allowed
minsnr = 1.0

# reference antenna 15 (15=VLA:N2)
refant = '15'

saveinputs('gaincal',prefix+'.gaincal.saved')

gaincal()
```

```

#
#=====
#
# Bootstrap flux scale
#
print '--Fluxscale--'
default('fluxscale')

vis = msfile

# set the name for the output rescaled caltable
ftable = prefix + '.fluxscale'
fluxtable = ftable

# point to our first gain cal table
caltable = gtable

# we will be using 1331+305 (the source we did setjy on) as
# our flux standard reference - note its extended name as in
# the FIELD table summary above (it has a VLA seq number appended)
reference = '1331*'

# we want to transfer the flux to our other gain cal source 1445+099
transfer = '1445*'

saveinputs('fluxscale',prefix+'.fluxscale.saved')

fluxscale()

# In the logger you should see something like:
# Flux density for 1445+09900002_0 in SpW=0 is:
#     2.48576 +/- 0.00123122 (SNR = 2018.94, nAnt= 27)

# If you run plotcal() on the tablein = 'ngc5921.usecase.fluxscale'
# you will see now it has brought the amplitudes in line between
# the first scan on 1331+305 and the others on 1445+099

#
#=====
#
# Now use plotcal to examine the gain solutions
#
print '--Plotcal (fluxscaled gains)--'
default('plotcal')

caltable = ftable
field = '0,1'

# No GUI for this script
showgui = False
# If you want to do this interactively and iterate over antenna, set

```

```
#iteration = 'antenna'
#showgui = True

# Set up 2x1 panels - upper panel amp vs. time
subplot = 211
yaxis = 'amp'
# No output file yet (wait to plot next panel)

saveinputs('plotcal',prefix+'.plotcal.gscaled.amp.saved')

plotcal()
#
# Set up 2x1 panels - lower panel phase vs. time
subplot = 212
yaxis = 'phase'
# Now send final plot to file in PNG format (via .png suffix)
figfile = caltable + '.plotcal.png'

saveinputs('plotcal',prefix+'.plotcal.gscaled.phase.saved')

plotcal()
#
# The amp and phase coherence looks good

=====
#
# Apply our calibration solutions to the data
# (This will put calibrated data into the CORRECTED_DATA column)
#
print '--ApplyCal--'
default('applycal')

vis = msfile

# We want to correct the calibrators using themselves
# and transfer from 1445+099 to itself and the target N5921

# Start with the fluxscale/gain and bandpass tables
gaintable = [ftable,btable]

# pick the 1445+099 out of the gain table for transfer
# use all of the bandpass table
gainfield = ['1','*']

# interpolation using linear for gain, nearest for bandpass
interp = ['linear','nearest']

# only one spw, do not need mapping
spwmap = []

# all channels
```

```
spw = ''
selectdata = False

# as before
gaincurve = False
opacity = 0.0

# select the fields for 1445+099 and N5921
field = '1,2'

applycal()

# Now for completeness apply 1331+305 to itself

field = '0'
gainfield = ['0','*']

# The CORRECTED_DATA column now contains the calibrated visibilities

saveinputs('applycal',prefix+'.applycal.saved')

applycal()

#
#=====
#
# Now use plotxy to plot the calibrated target data (before contsub)
#
print '--Plotxy (NGC5921)--'
default('plotxy')

vis = msfile

field = '2'
# Edge channels are bad
spw = '0:4~59'

# Time average across scans
timebin = '86000.'
crossscans = True

# No GUI for this script
interactive = False

# Set up 2x1 panels - upper panel amp vs. channel
subplot = 211
xaxis = 'channel'
yaxis = 'amp'
datacolumn = 'corrected'
# No output file yet (wait to plot next panel)
```

```
saveinputs('plotxy',prefix+'.plotxy.final.amp.saved')

plotxy()
#
# Set up 2x1 panels - lower panel phase vs. time
subplot = 212
yaxis = 'phase'
datacolumn = 'corrected'
# Now send final plot to file in PNG format (via .png suffix)
figfile = vis + '.plotxy.png'

saveinputs('plotxy',prefix+'.plotxy.final.phase.saved')

plotxy()

=====
#
# Split the gain calibrator data, then the target
#
print '--Split 1445+099 Data--'
default('split')

vis = msfile

# We first want to write out the corrected data for the calibrator

# Make an output vis file
calsplitms = prefix + '.cal.split.ms'
outputvis = calsplitms

# Select the 1445+099 field, all chans
field = '1445*'
spw = ''

# pick off the CORRECTED_DATA column
datacolumn = 'corrected'

saveinputs('split',prefix+'.split.1445.saved')

split()

#
# Now split NGC5921 data (before continuum subtraction)
#
print '--Split NGC5921 Data--'

splitms = prefix + '.src.split.ms'
outputvis = splitms

# Pick off N5921
field = 'N5921*'
```

```
saveinputs('split',prefix+'.split.n5921.saved')

split()

=====
#
# Export the NGC5921 data as UVFITS
# Start with the split file.
#
print '--Export UVFITS--'
default('exportuvfits')

srcuvfits = prefix + '.split.uvfits'

vis = splitms
fitsfile = srcuvfits

# Since this is a split dataset, the calibrated data is
# in the DATA column already.
datacolumn = 'data'

# Write as a multisource UVFITS (with SU table)
# even though it will have only one field in it
multisource = True

# Run asynchronously so as not to interfere with other tasks
# (BETA: also avoids crash on next importuvfits)
async = True

saveinputs('exportuvfits',prefix+'.exportuvfits.saved')

myhandle = exportuvfits()

print "The return value for this exportuvfits async task for tm is "+str(myhandle)

=====
#
# UV-plane continuum subtraction on the target
# (this will update the CORRECTED_DATA column)
#
print '--UV Continuum Subtract--'
default('uvcontsub')

vis = msfile

# Pick off N5921
field = 'N5921*'

# Use channels 4-6 and 50-59 for continuum
fitspw='0:4~6;50~59'
```

```
# Output all of spw 0
spw = '0'

# Averaging time (none)
solint = 0.0

# Fit only a mean level
fitorder = 0

# Do the uv-plane subtraction
fitmode = 'subtract'

# Let it split out the data automatically for us
splitdata = True

saveinputs('uvcontsub',prefix+'.uvcontsub.saved')

uvcontsub()

# You will see it made two new MS:
# ngc5921.usecase.ms.cont
# ngc5921.usecase.ms.contsub

srcsplitsms = msfile + '.contsub'

# Note that ngc5921.usecase.ms.contsub contains the uv-subtracted
# visibilities (in its DATA column), and ngc5921.usecase.ms.cont
# the pseudo-continuum visibilities (as fit).

# The original ngc5921.usecase.ms now contains the uv-continuum
# subtracted vis in its CORRECTED_DATA column and the continuum
# in its MODEL_DATA column as per the fitmode='subtract'

# Done with calibration
=====
#
# Now make a dirty image cube
#
print '--Clean (invert)--'
default('clean')

# Pick up our split source continuum-subtracted data
vis = srcsplitsms

# Make an image root file name
imname = prefix + '.dirty'
imagename = imname

# Set up the output image cube
mode = 'channel'
```

```
nchan = 46
start = 5
width = 1

# This is a single-source MS with one spw
field = '0'
spw = ''

# Set the output image size and cell size (arcsec)
imsize = [256,256]

# Pixel size 15 arcsec for this data (1/3 of 45" beam)
# VLA D-config L-band
cell = [15.,15.]

# Fix maximum number of iterations
niter = 0

# Set up the weighting
# Use Briggs weighting (a moderate value, on the uniform side)
weighting = 'briggs'
robust = 0.5

saveinputs('clean',prefix+'.invert.saved')

clean()

# Should find stuff in the logger like:
#
# Fitted beam used in restoration: 51.5204 by 45.5982 (arcsec)
#     at pa 14.6547 (deg)
#
# It will have made the images:
# -----
# ngc5921.usecase.clean.image
# ngc5921.usecase.clean.model
# ngc5921.usecase.clean.residual
# ngc5921.usecase.clean.boxclean.mask

dirtyimage = imname+'.image'

=====
#
# Get the dirty image cube statistics
#
print '--Imstat (dirty cube)--'
default('imstat')

imagename = dirtyimage

# Do whole image
```

```
box = ''  
  
dirtystats = imstat()  
  
# Statistics will printed to the terminal, and the output  
# parameter will contain a dictionary of the statistics  
  
#=====  
#  
# Now clean an image cube of N5921  
#  
print '--Clean (clean)--'  
default('clean')  
  
# Pick up our split source continuum-subtracted data  
vis = srcsplitsms  
  
# Make an image root file name  
imname = prefix + '.clean'  
imagename = imname  
  
# Set up the output image cube  
mode = 'channel'  
nchan = 46  
start = 5  
width = 1  
  
# This is a single-source MS with one spw  
field = '0'  
spw = ''  
  
# Standard gain factor 0.1  
gain = 0.1  
  
# Set the output image size and cell size (arcsec)  
imsizes = [256,256]  
  
# Do a simple Clark clean  
psfmode = 'clark'  
# No Cotton-Schwab iterations  
csclclean = False  
  
# If desired, you can do a Cotton-Schwab clean  
# but will have only marginal improvement for this data  
#csclclean = True  
# Twice as big for Cotton-Schwab (cleans inner quarter)  
#imsizes = [512,512]  
  
# Pixel size 15 arcsec for this data (1/3 of 45" beam)  
# VLA D-config L-band  
cell = [15.,15.]
```

```
# Fix maximum number of iterations
niter = 6000

# Also set flux residual threshold (in mJy)
threshold=8.0

# Set up the weighting
# Use Briggs weighting (a moderate value, on the uniform side)
weighting = 'briggs'
robust = 0.5

# Set a cleanbox +/-20 pixels around the center 128,128
mask = [108,108,148,148]

# But if you had a cleanbox saved in a file, e.g. "regionfile.txt"
# you could use it:
#mask='regionfile.txt'
#
# If you don't want any clean boxes or masks, then
#mask = ''

# If you want interactive clean set to True
#interactive=True
interactive=False

saveinputs('clean',prefix+'clean.saved')

clean()

# Should find stuff in the logger like:
#
# Fitted beam used in restoration: 51.5643 by 45.6021 (arcsec)
#      at pa 14.5411 (deg)
#
# It will have made the images:
# -----
# ngc5921.usecase.clean.image
# ngc5921.usecase.clean.model
# ngc5921.usecase.clean.residual
# ngc5921.usecase.clean.boxclean.mask

clnimage = imname+'.image'

=====
#
# Done with imaging
# Now view the image cube of N5921
#
#print '--View image--'
#viewer(clnimage,'image')
```

```
#=====
#  
# Export the Final CLEAN Image as FITS  
#  
print '--Final Export CLEAN FITS--'  
default('exportfits')  
  
clnfits = prefix + '.clean.fits'  
  
imagename = clnimage  
fitsimage = clnfits  
  
# Run asynchronously so as not to interfere with other tasks  
# (BETA: also avoids crash on next importfits)  
async = True  
  
saveinputs('exportfits',prefix+'.exportfits.saved')  
  
myhandle2 = exportfits()  
  
print "The return value for this exportfits async task for tm is "+str(myhandle2)  
  
#=====  
#  
# Print the image header  
#  
print '--Imhead--'  
default('imhead')  
  
imagename = clnimage  
  
mode = 'summary'  
  
imhead()  
  
# A summary of the cube will be seen in the logger  
  
#=====  
#  
# Get the cube statistics  
#  
print '--Imstat (cube)--'  
default('imstat')  
  
imagename = clnimage  
  
# Do whole image  
box = ''  
# or you could stick to the cleanbox  
#box = '108,108,148,148'
```

```
cubestats = imstat()

# Statistics will printed to the terminal, and the output
# parameter will contain a dictionary of the statistics

#=====
#
# Get some image moments
#
print '--ImMoments--'
default('immoments')

imagename = clnimage

# Do first and second moments
moments = [0,1]

# Need to mask out noisy pixels, currently done
# using hard global limits
excludepix = [-100,0.009]

# Include all planes
planes = ''

# Output root name
momfile = prefix + '.moments'
outfile = momfile

saveinputs('immoments',prefix+'.immoments.saved')

immoments()

momzeroimage = momfile + '.integrated'
momoneimage = momfile + '.weighted_coord'

# It will have made the images:
# -----
# ngc5921.usecase.moments.integrated
# ngc5921.usecase.moments.weighted_coord

#
#=====
#
# Get some statistics of the moment images
#
print '--Imstat (moments)--'
default('imstat')

imagename = momzeroimage
momzerostats = imstat()
```

```
imagename = momoneimage
momonestats = imstat()

=====
#
# Set up an output logfile
import datetime
datestring=datetime.datetime.isoformat(datetime.datetime.today())

outfile = 'out.'+prefix+'.'+datestring+'.log'
logfile=open(outfile,'w')
print >>logfile,'Results for '+prefix+' :'
print >>logfile,""

=====
#
# Can do some image statistics if you wish
# Treat this like a regression script
# WARNING: currently requires toolkit
#
print ' NGC5921 results '
print ' ======'

print >>logfile,' NGC5921 results '
print >>logfile,' ======'

#
# Use the ms tool to get max of the MSs
# Eventually should be available from a task
#
# Pull the max cal amp value out of the MS
ms.open(calsplitms)
thistest_cal = max(ms.range(["amplitude"]).get('amplitude'))
ms.close()
oldtest_cal = 34.0338668823
diff_cal = abs((oldtest_cal-thistest_cal)/oldtest_cal)

print ' Calibrator data ampl max = ',thistest_cal
print ' Previous: cal data max = ',oldtest_cal
print ' Difference (fractional) = ',diff_cal
print ''

print >>logfile,' Calibrator data ampl max = ',thistest_cal
print >>logfile,' Previous: cal data max = ',oldtest_cal
print >>logfile,' Difference (fractional) = ',diff_cal
print >>logfile,'

# Pull the max src amp value out of the MS
ms.open(srccsplitms)
thistest_src = max(ms.range(["amplitude"]).get('amplitude'))
```

```
ms.close()
oldtest_src = 46.2060050964 # now in all chans
diff_src = abs((oldtest_src-thistest_src)/oldtest_src)

print ' Target Src data ampl max = ',thistest_src
print ' Previous: src data max = ',oldtest_src
print ' Difference (fractional) = ',diff_src
print ''

print >>logfile,' Target Src data ampl max = ',thistest_src
print >>logfile,' Previous: src data max = ',oldtest_src
print >>logfile,' Difference (fractional) = ',diff_src
print >>logfile,'

#
# Now use the stats produced by imstat above
#
# First the dirty image
#
# Pull the max from the cubestats dictionary
# created above using imstat
thistest_dirtymax=dirtystats['max'][0]
oldtest_dirtymax = 0.0515365377069
diff_dirtymax = abs((oldtest_dirtymax-thistest_dirtymax)/oldtest_dirtymax)

print ' Dirty Image max = ',thistest_dirtymax
print ' Previous: max = ',oldtest_dirtymax
print ' Difference (fractional) = ',diff_dirtymax
print ''

print >>logfile,' Dirty Image max = ',thistest_dirtymax
print >>logfile,' Previous: max = ',oldtest_dirtymax
print >>logfile,' Difference (fractional) = ',diff_dirtymax
print >>logfile,'

# Pull the rms from the cubestats dictionary
thistest_dirtyrms=dirtystats['rms'][0]
oldtest_dirtyrms = 0.00243866862729
diff_dirtyrms = abs((oldtest_dirtyrms-thistest_dirtyrms)/oldtest_dirtyrms)

print ' Dirty Image rms = ',thistest_dirtyrms
print ' Previous: rms = ',oldtest_dirtyrms
print ' Difference (fractional) = ',diff_dirtyrms
print ''

print >>logfile,' Dirty Image rms = ',thistest_dirtyrms
print >>logfile,' Previous: rms = ',oldtest_dirtyrms
print >>logfile,' Difference (fractional) = ',diff_dirtyrms
print >>logfile,'

# Now the clean image
```

```

#
# Pull the max from the cubestats dictionary
# created above using imstat
thistest_immax=cubestats['max'][0]
oldtest_immax = 0.052414759993553162
diff_immax = abs((oldtest_immax-thistest_immax)/oldtest_immax)

print ' Clean Image max = ',thistest_immax
print ' Previous: max = ',oldtest_immax
print ' Difference (fractional) = ',diff_immax
print ''

print >>logfile,' Clean Image max = ',thistest_immax
print >>logfile,' Previous: max = ',oldtest_immax
print >>logfile,' Difference (fractional) = ',diff_immax
print >>logfile,'

# Pull the rms from the cubestats dictionary
thistest_imrms=cubestats['rms'][0]
oldtest_imrms = 0.0020218724384903908
diff_imrms = abs((oldtest_imrms-thistest_imrms)/oldtest_imrms)

print ' Clean image rms = ',thistest_imrms
print ' Previous: rms = ',oldtest_imrms
print ' Difference (fractional) = ',diff_imrms
print ''

print >>logfile,' Clean image rms = ',thistest_imrms
print >>logfile,' Previous: rms = ',oldtest_imrms
print >>logfile,' Difference (fractional) = ',diff_imrms
print >>logfile,'

# Now the moment images
#
# Pull the max from the momzerostats dictionary
thistest_momzeromax=momzerostats['max'][0]
oldtest_momzeromax = 1.40223777294
diff_momzeromax = abs((oldtest_momzeromax-thistest_momzeromax)/oldtest_momzeromax)

print ' Moment 0 image max = ',thistest_momzeromax
print ' Previous: m0 max = ',oldtest_momzeromax
print ' Difference (fractional) = ',diff_momzeromax
print ''

print >>logfile,' Moment 0 image max = ',thistest_momzeromax
print >>logfile,' Previous: m0 max = ',oldtest_momzeromax
print >>logfile,' Difference (fractional) = ',diff_momzeromax
print >>logfile,'

# Pull the mean from the momonestats dictionary
thistest_momoneavg=momonestats['mean'][0]

```

```

oldtest_momoneavg = 1479.77119646
diff_momoneavg = abs((oldtest_momoneavg-thistest_momoneavg)/oldtest_momoneavg)

print ' Moment 1 image mean = ',thistest_momoneavg
print ' Previous: m1 mean = ',oldtest_momoneavg
print ' Difference (fractional) = ',diff_momoneavg
print ''
print '--- Done ---'

print >>logfile,' Moment 1 image mean = ',thistest_momoneavg
print >>logfile,' Previous: m1 mean = ',oldtest_momoneavg
print >>logfile,' Difference (fractional) = ',diff_momoneavg
print >>logfile,''
print >>logfile,'--- Done ---'

# Should see output like:
#
# Clean image max should be  0.0524147599936
# Found : Image Max =  0.0523551553488
# Difference (fractional) =  0.00113717290288
#
# Clean image rms should be  0.00202187243849
# Found : Image rms =  0.00202226242982
# Difference (fractional) =  0.00019288621809
#
# Moment 0 image max should be  1.40223777294
# Found : Moment 0 Max =  1.40230333805
# Difference (fractional) =  4.67574844349e-05
#
# Moment 1 image mean should be  1479.77119646
# Found : Moment 1 Mean =  1479.66974528
# Difference (fractional) =  6.85586935973e-05
#
#=====
# Done
#
logfile.close()
print "Results are in "+outfile

```

F.1.1 NGC 5921 data summary

Summary created with `listobs('ngc5921.usecase.ms', verbose=True)`: This is written to the logger and the `casapy.log` file.

```

Observer: TEST      Project:
Observation: VLA

Data records: 22653      Total integration time = 5280 seconds
               Observed from 09:19:00 to 10:47:00

```

```

ObservationID = 0          ArrayID = 0
Date      Timerange           Scan  FldId FieldName      SpwIds
13-Apr-1995/09:19:00.0 - 09:24:30.0    1     0 1331+30500002_0 [0]
                           09:27:30.0 - 09:29:30.0    2     1 1445+09900002_0 [0]
                           09:33:00.0 - 09:48:00.0    3     2 N5921_2       [0]
                           09:50:30.0 - 09:51:00.0    4     1 1445+09900002_0 [0]
                           10:22:00.0 - 10:23:00.0    5     1 1445+09900002_0 [0]
                           10:26:00.0 - 10:43:00.0    6     2 N5921_2       [0]
                           10:45:30.0 - 10:47:00.0    7     1 1445+09900002_0 [0]

```

Fields: 3

ID	Name	Right Ascension	Declination	Epoch
0	1331+30500002_013:31:08.29	+30.30.32.96	J2000	
1	1445+09900002_014:45:16.47	+09.58.36.07	J2000	
2	N5921_2	15:22:00.00	+05.04.00.00	J2000

Spectral Windows: (1 unique spectral windows and 1 unique polarization setups)

SpwID	#Chans	Frame	Ch1(MHz)	Resoln(kHz)	TotBW(kHz)	Ref(MHz)	Corrs
0	63	LSRK	1412.68608	24.4140625	1550.19688	1413.44902	RR LL

Feeds: 28: printing first row only

Antenna	Spectral Window	# Receptors	Polarizations
1	-1	2	[R, L]

Antennas: 27:

ID	Name	Station	Diam.	Long.	Lat.
0	1	VLA:N7	25.0 m	-107.37.07.2	+33.54.12.9
1	2	VLA:W1	25.0 m	-107.37.05.9	+33.54.00.5
2	3	VLA:W2	25.0 m	-107.37.07.4	+33.54.00.9
3	4	VLA:E1	25.0 m	-107.37.05.7	+33.53.59.2
4	5	VLA:E3	25.0 m	-107.37.02.8	+33.54.00.5
5	6	VLA:E9	25.0 m	-107.36.45.1	+33.53.53.6
6	7	VLA:E6	25.0 m	-107.36.55.6	+33.53.57.7
7	8	VLA:W8	25.0 m	-107.37.21.6	+33.53.53.0
8	9	VLA:N5	25.0 m	-107.37.06.7	+33.54.08.0
9	10	VLA:W3	25.0 m	-107.37.08.9	+33.54.00.1
10	11	VLA:N4	25.0 m	-107.37.06.5	+33.54.06.1
11	12	VLA:W5	25.0 m	-107.37.13.0	+33.53.57.8
12	13	VLA:N3	25.0 m	-107.37.06.3	+33.54.04.8
13	14	VLA:N1	25.0 m	-107.37.06.0	+33.54.01.8
14	15	VLA:N2	25.0 m	-107.37.06.2	+33.54.03.5
15	16	VLA:E7	25.0 m	-107.36.52.4	+33.53.56.5
16	17	VLA:E8	25.0 m	-107.36.48.9	+33.53.55.1
17	18	VLA:W4	25.0 m	-107.37.10.8	+33.53.59.1
18	19	VLA:E5	25.0 m	-107.36.58.4	+33.53.58.8
19	20	VLA:W9	25.0 m	-107.37.25.1	+33.53.51.0
20	21	VLA:W6	25.0 m	-107.37.15.6	+33.53.56.4
21	22	VLA:E4	25.0 m	-107.37.00.8	+33.53.59.7
23	24	VLA:E2	25.0 m	-107.37.04.4	+33.54.01.1
24	25	VLA:N6	25.0 m	-107.37.06.9	+33.54.10.3

```

25 26     VLA:N9    25.0 m   -107.37.07.8 +33.54.19.0
26 27     VLA:N8    25.0 m   -107.37.07.5 +33.54.15.8
27 28     VLA:W7    25.0 m   -107.37.18.4 +33.53.54.8

```

Tables:

MAIN	22653 rows
ANTENNA	28 rows
DATA_DESCRIPTION	1 row
DOPPLER	<absent>
FEED	28 rows
FIELD	3 rows
FLAG_CMD	<empty>
FREQ_OFFSET	<absent>
HISTORY	353 rows
OBSERVATION	1 row
POINTING	168 rows
POLARIZATION	1 row
PROCESSOR	<empty>
SOURCE	3 rows
SPECTRAL_WINDOW	1 row
STATE	<empty>
SYSCAL	<absent>
WEATHER	<absent>

F.2 Jupiter — VLA continuum polarization

Note: This script includes interactive flagging and cleaning and self-calibration loops. Polarization calibration and imaging is still missing.

The latest version of this script can be found at:

http://casa.nrao.edu/Doc/Scripts/jupiter6cm_usecase.py

```
#####
#
# Use Case Script for Jupiter 6cm VLA
# Trimmed down from Use Case jupiter6cm_usecase.py
#
# Updated STM 2008-05-15 (Beta Patch 2.0)
# Updated STM 2008-06-11 (Beta Patch 2.0)
#
# This is a VLA 6cm dataset that was observed in 1999 to set the
# flux scale for calibration of the VLA. Included in the program
# were observations of the planets, including Jupiter.
#
# This is D-configuration data, with resolution of around 14"
#
```

```
# Includes polarization imaging and analysis          #
##
#####
import time
import os

#
#=====
#
# This script has some interactive commands: scriptmode = True
# if you are running it and want it to stop during interactive parts.

scriptmode = True

#=====
#
# Set up some useful variables - these will be set during the script
# also, but if you want to restart the script in the middle here
# they are in one place:

# This will prefix all output file names
prefix='jupiter6cm.usecase'

# This is the output MS file name
msfile = prefix + '.ms'

#
#=====
#
# Calibration variables
#
# Use same prefix as rest of script
calprefix = prefix

# spectral windows to process
usespw = ''
usespwlist = ['0','1']

# prior calibration to apply
usegaincurve = True
gainopacity = 0.0

# reference antenna 11 (11=VLA:N1)
calrefant = '11'

gtable = calprefix + '.gcal'
ftable = calprefix + '.fluxscale'
atable = calprefix + '.accum'

#
#=====
```

```

# Polarization calibration setup
#
dopolcal = True

ptable = calprefix + '.pcal'
xtable = calprefix + '.polx'

# Pol leakage calibrator
poldfield = '0137+331'

# Pol angle calibrator
polxfield = '1331+305'
# At Cband the fractional polarization of this source is 0.112 and
# the R-L PhaseDiff = 66deg (EVPA = 33deg)
polxfpol = 0.112
polxrlpd_deg = 66.0
# Dictionary of IPOL in the spw
polxipol = {'0' : 7.462,
             '1' : 7.510}

# Make Stokes lists for setjy
polxiquv = {}
for spw in ['0','1']:
    ipol = polxipol[spw]
    fpol = polxfpol
    ppol = ipol*fpol
    rlpd = polxrlpd_deg*pi/180.0
    qpol = ppol*cos(rlpd)
    upol = ppol*sin(rlpd)
    polxiquv[spw] = [ipol,qpol,upol,0.0]

#
# Split output setup
#
srcname = 'JUPITER'
srcsplitsms = calprefix + '.' + srcname + '.split.ms'
calname = '0137+331'
calsplitsms = calprefix + '.' + calname + '.split.ms'

#
#=====
#
# Intensity imaging parameters
#
# Same prefix for this imaging demo output
#
imprefix = prefix

# This is D-config VLA 6cm (4.85GHz) obs
# Check the observational status summary
# Primary beam FWHM = 45'/f_GHz = 557"

```

```

# Synthesized beam FWHM = 14"
# RMS in 10min (600s) = 0.06 mJy (thats now, but close enough)

# Set the output image size and cell size (arcsec)
# 4" will give 3.5x oversampling
clncell = [4.,4.]

# 280 pix will cover to 2xPrimaryBeam
# clean will say to use 288 (a composite integer) for efficiency
clnalg = 'clark'
clnmode = ''
# For Cotton-Schwab use
clnmode = 'csclean'
clnimsize = [288,288]

# iterations
clniter = 10000

# Also set flux residual threshold (0.04 mJy)
# From our listobs:
# Total integration time = 85133.2 seconds
# With rms of 0.06 mJy in 600s ==> rms = 0.005 mJy
# Set to 10x thermal rms
clnthreshold=0.05

#
# Filenames
#
imname1 = imprefix + '.clean1'
clnimage1 = imname1+'.image'
clnmodel1 = imname1+'.model'
clnresid1 = imname1+'.residual'
clnmask1 = imname1+'.clean_interactive.mask'

imname2 = imprefix + '.clean2'
clnimage2 = imname2+'.image'
clnmodel2 = imname2+'.model'
clnresid2 = imname2+'.residual'
clnmask2 = imname2+'.clean_interactive.mask'

imname3 = imprefix + '.clean3'
clnimage3 = imname3+'.image'
clnmodel3 = imname3+'.model'
clnresid3 = imname3+'.residual'
clnmask3 = imname3+'.clean_interactive.mask'

#
# Selfcal parameters
#
# reference antenna 11 (11=VLA:N1)
calrefant = '11'

```

```

#
# Filenames
#
selfcaltab1 = imprefix + '.selfcal1.gtable'
selfcaltab2 = imprefix + '.selfcal2.gtable'
smoothcaltab2 = imprefix + '.smoothcal2.gtable'

#
#=====
#
# Polarization imaging parameters
#
# New prefix for polarization imaging output
#
polprefix = prefix + '.polimg'

# Set up clean slightly differently
polclnalg = 'hogbom'
polclnmode = 'csclean'

polimname = polprefix + '.clean'
polimage = polimname+'.image'
polmodel = polimname+'.model'
polresid = polimname+'.residual'
polmask = polimname+'.clean_interactive.mask'

#
# Other files
#
ipolimage = polimage+'.I'
qpolimage = polimage+'.Q'
upolimage = polimage+'.U'

poliimage = polimage+'.poli'
polaimage = polimage+'.pola'

#
#=====
#
# Start processing
#=====
#
# Get to path to the CASA home and strip off the name
pathname=os.environ.get('AIPSPATH').split()[0]

# This is where the UVFITS data should be
#fitsdata=pathname+'/data/demo/jupiter6cm.fits'
# Or
#fitsdata=pathname+'/data/nrao/VLA/planets_6cm.fits'
fitsdata='/home/ballista/casa-devel/data/nrao/VLA/planets_6cm.fits'

```

```
#  
# Can also be found online at  
#http://casa.nrao.edu/Data/VLA/Planets6cm/planets_6cm.fits  
#fitsdata='planets_6cm.fits'  
  
# Clean up old files  
os.system('rm -rf '+prefix+'*')  
  
#  
#=====  
# Data Import and List  
#=====  
#  
# Import the data from FITS to MS  
#  
print '--Import--'  
  
# Safest to start from task defaults  
default('importuvfits')  
  
print "Use importuvfits to read UVFITS and make an MS"  
  
# Set up the MS filename and save as new global variable  
msfile = prefix + '.ms'  
  
print "MS will be called "+msfile  
  
# Use task importuvfits  
fitsfile = fitsdata  
vis = msfile  
importuvfits()  
  
#=====  
#  
# List a summary of the MS  
#  
print '--Listobs--'  
  
# Don't default this one and make use of the previous setting of  
# vis. Remember, the variables are GLOBAL!  
  
print "Use listobs to print verbose summary to logger"  
  
# You may wish to see more detailed information, in this case  
# use the verbose = True option  
verbose = True  
  
listobs()  
  
# You should get in your logger window and in the casapy.log file  
# something like:
```

```

#
#      Observer: FLUX99      Project:
# Observation: VLA
#
# Data records: 2021424      Total integration time = 85133.2 seconds
#   Observed from 23:15:27 to 22:54:20
#
#   ObservationID = 0      ArrayID = 0
#   Date          Timerange           Scan  FldId FieldName    SpwIds
#   15-Apr-1999/23:15:26.7 - 23:16:10.0    1     0 0137+331    [0, 1]
#                                23:38:40.0 - 23:48:00.0    2     1 0813+482    [0, 1]
#                                23:53:40.0 - 23:55:20.0    3     2 0542+498    [0, 1]
#   16-Apr-1999/00:22:10.1 - 00:23:49.9    4     3 0437+296    [0, 1]
#                                00:28:23.3 - 00:30:00.1    5     4 VENUS       [0, 1]
#                                00:48:40.0 - 00:50:20.0    6     1 0813+482    [0, 1]
#                                00:56:13.4 - 00:57:49.9    7     2 0542+498    [0, 1]
#                                01:10:20.1 - 01:11:59.9    8     5 0521+166    [0, 1]
#                                01:23:29.9 - 01:25:00.1    9     3 0437+296    [0, 1]
#                                01:29:33.3 - 01:31:10.0   10    4 VENUS       [0, 1]
#                                01:49:50.0 - 01:51:30.0   11    6 1411+522    [0, 1]
#                                02:03:00.0 - 02:04:30.0   12    7 1331+305    [0, 1]
#                                02:17:30.0 - 02:19:10.0   13    1 0813+482    [0, 1]
#                                02:24:20.0 - 02:26:00.0   14    2 0542+498    [0, 1]
#                                02:37:49.9 - 02:39:30.0   15    5 0521+166    [0, 1]
#                                02:50:50.1 - 02:52:20.1   16    3 0437+296    [0, 1]
#                                02:59:20.0 - 03:01:00.0   17    6 1411+522    [0, 1]
#                                03:12:30.0 - 03:14:10.0   18    7 1331+305    [0, 1]
#                                03:27:53.3 - 03:29:39.9   19    1 0813+482    [0, 1]
#                                03:35:00.0 - 03:36:40.0   20    2 0542+498    [0, 1]
#                                03:49:50.0 - 03:51:30.1   21    6 1411+522    [0, 1]
#                                04:03:10.0 - 04:04:50.0   22    7 1331+305    [0, 1]
#                                04:18:49.9 - 04:20:40.0   23    1 0813+482    [0, 1]
#                                04:25:56.6 - 04:27:39.9   24    2 0542+498    [0, 1]
#                                04:42:49.9 - 04:44:40.0   25    8 MARS        [0, 1]
#                                04:56:50.0 - 04:58:30.1   26    6 1411+522    [0, 1]
#                                05:24:03.3 - 05:33:39.9   27    7 1331+305    [0, 1]
#                                05:48:00.0 - 05:49:49.9   28    1 0813+482    [0, 1]
#                                05:58:36.6 - 06:00:30.0   29    8 MARS        [0, 1]
#                                06:13:20.1 - 06:14:59.9   30    6 1411+522    [0, 1]
#                                06:27:40.0 - 06:29:20.0   31    7 1331+305    [0, 1]
#                                06:44:13.4 - 06:46:00.0   32    1 0813+482    [0, 1]
#                                06:55:06.6 - 06:57:00.0   33    8 MARS        [0, 1]
#                                07:10:40.0 - 07:12:20.0   34    6 1411+522    [0, 1]
#                                07:28:20.0 - 07:30:10.1   35    7 1331+305    [0, 1]
#                                07:42:49.9 - 07:44:30.0   36    8 MARS        [0, 1]
#                                07:58:43.3 - 08:00:39.9   37    6 1411+522    [0, 1]
#                                08:13:30.0 - 08:15:19.9   38    7 1331+305    [0, 1]
#                                08:27:53.4 - 08:29:30.0   39    8 MARS        [0, 1]
#                                08:42:59.9 - 08:44:50.0   40    6 1411+522    [0, 1]
#                                08:57:09.9 - 08:58:50.0   41    7 1331+305    [0, 1]
#                                09:13:03.3 - 09:14:50.1   42    9 NGC7027    [0, 1]

```

```

#      09:26:59.9 - 09:28:40.0    43      6 1411+522      [0, 1]
#      09:40:33.4 - 09:42:09.9    44      7 1331+305      [0, 1]
#      09:56:19.9 - 09:58:10.0    45      9 NGC7027       [0, 1]
#      10:12:59.9 - 10:14:50.0    46      8 MARS          [0, 1]
#      10:27:09.9 - 10:28:50.0    47      6 1411+522      [0, 1]
#      10:40:30.0 - 10:42:00.0    48      7 1331+305      [0, 1]
#      10:56:10.0 - 10:57:50.0    49      9 NGC7027       [0, 1]
#      11:28:30.0 - 11:35:30.0    50      10 NEPTUNE      [0, 1]
#      11:48:20.0 - 11:50:10.0    51      6 1411+522      [0, 1]
#      12:01:36.7 - 12:03:10.0    52      7 1331+305      [0, 1]
#      12:35:33.3 - 12:37:40.0    53      11 URANUS      [0, 1]
#      12:46:30.0 - 12:48:10.0    54      10 NEPTUNE      [0, 1]
#      13:00:29.9 - 13:02:10.0    55      6 1411+522      [0, 1]
#      13:15:23.3 - 13:17:10.1    56      9 NGC7027       [0, 1]
#      13:33:43.3 - 13:35:40.0    57      11 URANUS      [0, 1]
#      13:44:30.0 - 13:46:10.0    58      10 NEPTUNE      [0, 1]
#      14:00:46.7 - 14:01:39.9    59      0 0137+331      [0, 1]
#      14:10:40.0 - 14:12:09.9    60      12 JUPITER      [0, 1]
#      14:24:06.6 - 14:25:40.1    61      11 URANUS      [0, 1]
#      14:34:30.0 - 14:36:10.1    62      10 NEPTUNE      [0, 1]
#      14:59:13.4 - 15:00:00.0    63      0 0137+331      [0, 1]
#      15:09:03.3 - 15:10:40.1    64      12 JUPITER      [0, 1]
#      15:24:30.0 - 15:26:20.1    65      9 NGC7027       [0, 1]
#      15:40:10.0 - 15:45:00.0    66      11 URANUS      [0, 1]
#      15:53:50.0 - 15:55:20.0    67      10 NEPTUNE      [0, 1]
#      16:18:53.4 - 16:19:49.9    68      0 0137+331      [0, 1]
#      16:29:10.1 - 16:30:49.9    69      12 JUPITER      [0, 1]
#      16:42:53.4 - 16:44:30.0    70      11 URANUS      [0, 1]
#      16:54:53.4 - 16:56:40.0    71      9 NGC7027       [0, 1]
#      17:23:06.6 - 17:30:40.0    72      2 0542+498      [0, 1]
#      17:41:50.0 - 17:43:20.0    73      3 0437+296      [0, 1]
#      17:55:36.7 - 17:57:39.9    74      4 VENUS        [0, 1]
#      18:19:23.3 - 18:20:09.9    75      0 0137+331      [0, 1]
#      18:30:23.3 - 18:32:00.0    76      12 JUPITER      [0, 1]
#      18:44:49.9 - 18:46:30.0    77      9 NGC7027       [0, 1]
#      18:59:13.3 - 19:00:59.9    78      2 0542+498      [0, 1]
#      19:19:10.0 - 19:21:20.1    79      5 0521+166      [0, 1]
#      19:32:50.1 - 19:34:29.9    80      3 0437+296      [0, 1]
#      19:39:03.3 - 19:40:40.1    81      4 VENUS        [0, 1]
#      20:08:06.7 - 20:08:59.9    82      0 0137+331      [0, 1]
#      20:18:10.0 - 20:19:50.0    83      12 JUPITER      [0, 1]
#      20:33:53.3 - 20:35:40.1    84      1 0813+482      [0, 1]
#      20:40:59.9 - 20:42:40.0    85      2 0542+498      [0, 1]
#      21:00:16.6 - 21:02:20.1    86      5 0521+166      [0, 1]
#      21:13:53.4 - 21:15:29.9    87      3 0437+296      [0, 1]
#      21:20:43.4 - 21:22:30.0    88      4 VENUS        [0, 1]
#      21:47:26.7 - 21:48:20.1    89      0 0137+331      [0, 1]
#      21:57:30.0 - 21:59:10.0    90      12 JUPITER      [0, 1]
#      22:12:13.3 - 22:14:00.1    91      2 0542+498      [0, 1]
#      22:28:33.3 - 22:30:19.9    92      4 VENUS        [0, 1]
#      22:53:33.3 - 22:54:19.9    93      0 0137+331      [0, 1]

```

```

#
# Fields: 13
#   ID  Name      Right Ascension  Declination  Epoch
#   0   0137+331  01:37:41.30    +33.09.35.13 J2000
#   1   0813+482  08:13:36.05    +48.13.02.26 J2000
#   2   0542+498  05:42:36.14    +49.51.07.23 J2000
#   3   0437+296  04:37:04.17    +29.40.15.14 J2000
#   4   VENUS     04:06:54.11    +22.30.35.91 J2000
#   5   0521+166  05:21:09.89    +16.38.22.05 J2000
#   6   1411+522  14:11:20.65    +52.12.09.14 J2000
#   7   1331+305  13:31:08.29    +30.30.32.96 J2000
#   8   MARS      14:21:41.37    -12.21.49.45 J2000
#   9   NGC7027   21:07:01.59    +42.14.10.19 J2000
#  10   NEPTUNE   20:26:01.14    -18.54.54.21 J2000
#  11   URANUS   21:15:42.83    -16.35.05.59 J2000
#  12   JUPITER   00:55:34.04    +04.45.44.71 J2000
#
# Spectral Windows: (2 unique spectral windows and 1 unique polarization setups)
#   SpwID  #Chans Frame Ch1(MHz)  Resoln(kHz)  TotBW(kHz)  Ref(MHz)  Corrs
#   0       1   TOPO  4885.1      50000       50000       4885.1    RR RL LR LL
#   1       1   TOPO  4835.1      50000       50000       4835.1    RR RL LR LL
#
# Feeds: 28: printing first row only
#   Antenna  Spectral Window  # Receptors  Polarizations
#   1        -1                  2           [          R, L]
#
# Antennas: 27:
#   ID  Name  Station  Diam.  Long.  Lat.
#   0   1    VLA:W9  25.0 m  -107.37.25.1 +33.53.51.0
#   1   2    VLA:N9  25.0 m  -107.37.07.8 +33.54.19.0
#   2   3    VLA:N3  25.0 m  -107.37.06.3 +33.54.04.8
#   3   4    VLA:N5  25.0 m  -107.37.06.7 +33.54.08.0
#   4   5    VLA:N2  25.0 m  -107.37.06.2 +33.54.03.5
#   5   6    VLA:E1  25.0 m  -107.37.05.7 +33.53.59.2
#   6   7    VLA:E2  25.0 m  -107.37.04.4 +33.54.01.1
#   7   8    VLA:N8  25.0 m  -107.37.07.5 +33.54.15.8
#   8   9    VLA:E8  25.0 m  -107.36.48.9 +33.53.55.1
#   9   10   VLA:W3  25.0 m  -107.37.08.9 +33.54.00.1
#  10  11   VLA:N1  25.0 m  -107.37.06.0 +33.54.01.8
#  11  12   VLA:E6  25.0 m  -107.36.55.6 +33.53.57.7
#  12  13   VLA:W7  25.0 m  -107.37.18.4 +33.53.54.8
#  13  14   VLA:E4  25.0 m  -107.37.00.8 +33.53.59.7
#  14  15   VLA:N7  25.0 m  -107.37.07.2 +33.54.12.9
#  15  16   VLA:W4  25.0 m  -107.37.10.8 +33.53.59.1
#  16  17   VLA:W5  25.0 m  -107.37.13.0 +33.53.57.8
#  17  18   VLA:N6  25.0 m  -107.37.06.9 +33.54.10.3
#  18  19   VLA:E7  25.0 m  -107.36.52.4 +33.53.56.5
#  19  20   VLA:E9  25.0 m  -107.36.45.1 +33.53.53.6
#  21  22   VLA:W8  25.0 m  -107.37.21.6 +33.53.53.0
#  22  23   VLA:W6  25.0 m  -107.37.15.6 +33.53.56.4
#  23  24   VLA:W1  25.0 m  -107.37.05.9 +33.54.00.5

```

```

# 24 25 VLA:W2 25.0 m -107.37.07.4 +33.54.00.9
# 25 26 VLA:E5 25.0 m -107.36.58.4 +33.53.58.8
# 26 27 VLA:N4 25.0 m -107.37.06.5 +33.54.06.1
# 27 28 VLA:E3 25.0 m -107.37.02.8 +33.54.00.5
#
# Tables:
# MAIN 2021424 rows
# ANTENNA 28 rows
# DATA_DESCRIPTION 2 rows
# DOPPLER <absent>
# FEED 28 rows
# FIELD 13 rows
# FLAG_CMD <empty>
# FREQ_OFFSET <absent>
# HISTORY 7058 rows
# OBSERVATION 1 row
# POINTING 2604 rows
# POLARIZATION 1 row
# PROCESSOR <empty>
# SOURCE <empty> (see FIELD)
# SPECTRAL_WINDOW 2 rows
# STATE <empty>
# SYSCAL <absent>
# WEATHER <absent>

#
#=====
# Data Examination and Flagging
#=====
#
# Use Plotxy to interactively flag the data
#
print '--Plotxy--'
default('plotxy')

print "Now we use plotxy to examine and interactively flag data"

vis = msfile

# The fields we are interested in: 1331+305,JUPITER,0137+331
selectdata = True

# First we do the primary calibrator
field = '1331+305'

# Plot only the RR and LL for now
correlation = 'RR LL'

# Plot amplitude vs. uvdist
xaxis = 'uvdist'
yaxis = 'amp'

```

```
multicolor = 'both'

# Use the field name as the title
selectplot = True
title = field+"  "

iteration = ''

plotxy()

print ""
print "-----"
print "Plotxy"
print "Showing 1331+305 RR LL for all antennas"
print "Use MarkRegion then draw boxes around points to flag"
print "You can use ESC to drop last drawn box"
print "When happy with boxes, hit Flag to flag"
print "You can repeat as necessary"

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

# You can also use flagdata to do this non-interactively
# (see below)

# Now look at the cross-polar products
correlation = 'RL LR'

plotxy()

print ""
print "-----"
print "Looking at RL LR"
print "Now flag the bad data here"

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

#-----
# Now do calibrator 0137+331
field = '0137+331'
correlation = 'RR LL'
xaxis = 'uvdist'
spw = ''
iteration = ''
antenna = ''

title = field+"  "
```

```

plotxy()

# You'll see a bunch of bad data along the bottom near zero amp
# Draw a box around some of it and use Locate
# Looks like much of it is Antenna 9 (ID=8) in spw=1

print ""
print "-----"
print "Plotting 0137+331 RR LL all antennas"
print "You see bad data along bottom"
print "Mark a box around a bit of it and hit Locate"
print "Look in logger to see what it is"
print "You see much is Antenna 9 (ID=8) in spw 1"

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

xaxis = 'time'
spw = '1'
correlation = ''

# Note that the strings like antenna='9' first try to match the
# NAME which we see in listobs was the number '9' for ID=8.
# So be careful here (why naming antennas as numbers is bad).
antenna = '9'

plotxy()

# YES! the last 4 scans are bad. Box 'em and flag.

print ""
print "-----"
print "Plotting vs. time antenna='9' and spw='1' "
print "Box up last 4 scans which are bad and Flag"

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

# Go back and clean up
xaxis = 'uvdist'
spw = ''
antenna = ''
correlation = 'RR LL'

plotxy()

# Box up the bad low points (basically a clip below 0.52) and flag

# Note that RL,LR are too weak to clip on.

```

```
print ""
print "-----"
print "Back to all data"
print "Clean up remaining bad points"

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

#-----
# Finally, do JUPITER
field = 'JUPITER'
correlation = 'RR LL'
iteration = ''
xaxis = 'uvdist'

title = field+"  "

plotxy()

# Here you will see that the final scan at 22:00:00 UT is bad
# Draw a box around it and flag it!

print ""
print "-----"
print "Now plot JUPITER versus uvdist"
print "Lots of bad stuff near bottom"
print "Lets go and find it - try Locate"
print "Looks like lots of different antennas but at same time"

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

correlation = ''
xaxis = 'time'

plotxy()

# Here you will see that the final scan at 22:00:00 UT is bad
# Draw a box around it and flag it!

print ""
print "-----"
print "Now plotting vs. time"
print "See bad scan at end - flag it!"

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')
```

```
# Now look at whats left
correlation = 'RR LL'
xaxis = 'uvdist'
spw = '1'
antenna = ''
iteration = 'antenna'

plotxy()

# As you step through, you will see that Antenna 9 (ID=8) is often
# bad in this spw. If you box and do Locate (or remember from
# 0137+331) its probably a bad time.

print ""
print "-----"
print "Looking now at SPW 1"
print "Now we set iteration to Antenna"
print "Step through antennas with Next"
print "See bad Antenna 9 (ID 8) as in 0137+331"

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

# The easiest way to kill it:

antenna = '9'
iteration = ''
xaxis = 'time'
correlation = ''

plotxy()

# Draw a box around all points in the last bad scans and flag 'em!

print ""
print "-----"
print "Now plotting vs. time antenna 9 spw 1"
print "Box up the bad scans and Flag"

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

# Now clean up the rest
xaxis = 'uvdist'
correlation = 'RR LL'
antenna = ''
spw = ''
```

```
# You will be drawing many tiny boxes, so remember you can
# use the ESC key to get rid of the most recent box if you
# make a mistake.

plotxy()

# Note that the end result is we've flagged lots of points
# in RR and LL. We will rely upon imager to ignore the
# RL LR for points with RR LL flagged!

print ""
print "-----"
print "Final cleanup of JUPITER data"
print "Back to uvdist plot, see remaining bad data"
print "You can draw little boxes around the outliers and Flag"
print "Depends how patient you are in drawing boxes!"
print "Could also use Locate to find where they come from"

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

print "Done with plotxy!"

#
#=====
#
# Use Flagmanager to save a copy of the flags so far
#
print '--Flagmanager--'
default('flagmanager')

print "Now will use flagmanager to save a copy of the flags we just made"
print "These are named xyflags"

vis = msfile
mode = 'save'
versionname = 'xyflags'
comment = 'Plotxy flags'
merge = 'replace'

flagmanager()

#
#=====
#
# Use Flagmanager to list all saved versions
#
print '--Flagmanager--'
default('flagmanager')

print "Now will use flagmanager to list all the versions we saved"
```

```
vis = msfile
mode = 'list'

flagmanager()

#
# Done Flagging
print '--Done with flagging--'

#
#=====
# Calibration
#=====
#
# Set the fluxes of the primary calibrator(s)
#
print '--Setjy--'
default('setjy')

print "Use setjy to set flux of 1331+305 (3C286)"

vis = msfile

#
# 1331+305 = 3C286 is our primary calibrator
field = '1331+305'

# Setjy knows about this source so we dont need anything more

setjy()

#
# You should see something like this in the logger and casapy.log file:
#
# 1331+305  spwid=  0  [I=7.462, Q=0, U=0, V=0] Jy, (Perley-Taylor 99)
# 1331+305  spwid=  1  [I=7.51, Q=0, U=0, V=0] Jy, (Perley-Taylor 99)
#

print "Look in logger for the fluxes (should be 7.462 and 7.510 Jy)"

#
#=====
#
# Initial gain calibration
#
print '--Gaincal--'
default('gaincal')

print "Solve for antenna gains on 1331+305 and 0137+331"
print "We have 2 single-channel continuum spw"
```

```
print "Do not want bandpass calibration"

vis = msfile

# set the name for the output gain caltable
caltable = gtable

print "Output gain cal table will be "+gtable

# Gain calibrators are 1331+305 and 0137+331 (FIELD_ID 7 and 0)
# We have 2 IFs (SPW 0,1) with one channel each

# selection is via the field and spw strings
field = '1331+305,0137+331'
spw = ''

# a-priori calibration application
gaincurve = usegaincurve
opacity = gainopacity

# scan-based G solutions for both amplitude and phase
gaintype = 'G'
calmode = 'ap'

# one solution per scan
solint = 'inf'
combine = ''

# do not apply parallactic angle correction (yet)
parang = False

# reference antenna
refant = calrefant

# minimum SNR 3
minsnr = 3

gaincal()

#
#=====
#
# Bootstrap flux scale
#
print '--Fluxscale--'
default('fluxscale')

print "Use fluxscale to rescale gain table to make new one"

vis = msfile
```

```
# set the name for the output rescaled caltable
fluxtable = ftable

print "Output scaled gain cal table is "+ftable

# point to our first gain cal table
caltable = gtable

# we will be using 1331+305 (the source we did setjy on) as
# our flux standard reference
reference = '1331+305'

# we want to transfer the flux to our other gain cal source 0137+331
# to bring its gain amplitudes in line with the absolute scale
transfer = '0137+331'

fluxscale()

# You should see in the logger something like:
#Flux density for 0137+331 in SpW=0 is:
#  5.42575 +/- 0.00285011 (SNR = 1903.7, nAnt= 27)
#Flux density for 0137+331 in SpW=1 is:
#  5.46569 +/- 0.00301326 (SNR = 1813.88, nAnt= 27)

#
#-----
# Plot calibration
#
print '--PlotCal--'
default('plotcal')

showgui = True

caltable = ftable
multiplot = True
yaxis = 'amp'

showgui = True

plotcal()

print ""
print "-----"
print "Plotcal"
print "Looking at amplitude in cal-table "+caltable

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

#
```

```
# Now go back and plot to file
#
showgui = False

yaxis = 'amp'

figfile = caltable + '.plotcal.amp.png'
print "Plotting calibration to file "+figfile
#saveinputs('plotcal',caltable.plotcal.amp.saved')
plotcal()

yaxis = 'phase'

figfile = caltable + '.plotcal.phase.png'
print "Plotting calibration to file "+figfile
#saveinputs('plotcal',caltable.plotcal.phase.saved')
plotcal()

#
#=====
# Polarization Calibration
#=====
#
if (dopolcal):
    print '--Polcal (D)--'
    default('polcal')

    print "Solve for polarization leakage on 0137+331"
    print "Pretend it has unknown polarization"

    vis = msfile

    # Start with the un-fluxscaled gain table
    gaintable = gtable

    # use settings from gaincal
    gaincurve = usegaincurve
    opacity = gainopacity

    # Output table
    caltable = ptable

    # Use a 3C48 tracked through a range of PA
    field = '0137+331'
    spw = ''

    # No need for further selection
    selectdata=False

    # Polcal mode (D+QU = unknown pol for D)
    poltype = 'D+QU'
```

```
# One solution for entire dataset
solint = 'inf'
combine = 'scan'

# reference antenna
refant = calrefant

# minimum SNR 3
minsnr = 3

#saveinputs('polcal',calprefix+'.polcal.saved')
polcal()

=====
#
# List polcal solutions
#
print '--Listcal (PolD)--'

listfile = caltable + '.list'

print "Listing calibration to file "+listfile

listcal()

=====
#
# Plot polcal solutions
#
print '--Plotcal (PolD)--'

iteration = ''
showgui = False

xaxis = 'real'
yaxis = 'imag'
figfile = caltable + '.plotcal.reim.png'
print "Plotting calibration to file "+figfile
#saveinputs('plotcal',caltable+'.plotcal.reim.saved')
plotcal()

xaxis = 'antenna'
yaxis = 'amp'
figfile = caltable + '.plotcal.antamp.png'
print "Plotting calibration to file "+figfile
#saveinputs('plotcal',caltable+'.plotcal.antamp.saved')
plotcal()

xaxis = 'antenna'
yaxis = 'phase'
```

```
figfile = caltable + '.plotcal.antphase.png'
print "Plotting calibration to file "+figfile
#saveinputs('plotcal',caltable+'.plotcal.antphase.saved')
plotcal()

xaxis = 'antenna'
yaxis = 'snr'
figfile = caltable + '.plotcal.antsnr.png'
print "Plotting calibration to file "+figfile
#saveinputs('plotcal',caltable+'.plotcal.antsnr.saved')
plotcal()

=====
# Do Chi (X) pol angle calibration
=====
# First set the model
print '--Setjy--'
default('setjy')

vis = msfile

print "Use setjy to set IQU fluxes of "+polxfield
field = polxfield

for spw in usespwlist:
    fluxdensity = polxiquiv[spw]

    #saveinputs('setjy',calprefix+'.setjy.polspw.'+spw+'.saved')
    setjy()

    #
    # Polarization (X-term) calibration
    #
    print '--PolCal (X)--'
    default('polcal')

    print "Polarization R-L Phase Calibration (linear approx)"

    vis = msfile

    # Start with the G and D tables
    gaintable = [gtable,ptable]

    # use settings from gaincal
    gaincurve = usegaincurve
    opacity = gainopacity

    # Output table
    caltable = xtable

    # previously set with setjy
```

```
field = polxfield
spw = ''

selectdata=False

# Solve for Chi
poltype = 'X'
solint = 'inf'
combine = 'scan'

# reference antenna
refant = calrefant

# minimum SNR 3
minsnr = 3

#saveinputs('polcal',calprefix+'.polcal.X.saved')
polcal()

=====
# Apply the Calibration
=====
#
# Interpolate the gains onto Jupiter (and others)
#
# print '--Accum--'
# default('accum')
#
# print "This will interpolate the gains onto Jupiter"
#
# vis = msfile
#
# tablein = ''
# incrtable = ftable
# calfield = '1331+305, 0137+331'
#
# # set the name for the output interpolated caltable
# caltable = atable
#
# print "Output cumulative gain table will be "+atable
#
# # linear interpolation
# interp = 'linear'
#
# # make 10s entries
# accumtime = 10.0
#
# accum()
#
# NOTE: bypassing this during testing
atable = ftable
```

```
# =====#
# Correct the data
# (This will put calibrated data into the CORRECTED_DATA column)
#
print '--ApplyCal--'
default('applycal')

print "This will apply the calibration to the DATA"
print "Fills CORRECTED_DATA"

vis = msfile

# Start with the interpolated fluxscale/gain table
gaintable = [atable,ptable,xtable]

# use settings from gaincal
gaincurve = usegaincurve
opacity = gainopacity

# select the fields
field = '1331+305,0137+331,JUPITER'
spw = ''
selectdata = False

# IMPORTANT set parang=True for polarization
parang = True

# do not need to select subset since we did accum
# (note that correct only does 'nearest' interp)
gainfield = ''

applycal()

#
# =====#
# Now split the Jupiter target data
#
print '--Split Jupiter--'
default('split')

vis = msfile

# Now we write out the corrected data to a new MS

# Select the Jupiter field
field = srcname
spw = ''
```

```
# pick off the CORRECTED_DATA column
datacolumn = 'corrected'

# Make an output vis file
outputvis = srcsplitms

print "Split "+field+" data into new ms "+srcsplitms

split()

# Also split out 0137+331 as a check
field = calname

outputvis = calsplitms

print "Split "+field+" data into new ms "+calsplitms

split()

=====
# Force scratch column creation so plotxy will work
#
vis = srcsplitms
clearcal()

vis = calsplitms
clearcal()

=====
# Use Plotxy to look at the split calibrated data
#
print '--Plotxy--'
default('plotxy')

vis = srcsplitms
selectdata = True

# Plot only the RR and LL for now
correlation = 'RR LL'

# Plot amplitude vs. uvdist
xaxis = 'uvdist'
datacolumn = 'data'
multicolor = 'both'

iteration = ''
selectplot = True
interactive = True

field = 'JUPITER'
yaxis = 'amp'
```

```
# Use the field name as the title
title = field+"

plotxy()

print ""
print "-----"
print "Plotting JUPITER corrected visibilities"
print "Look for outliers"

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

# Now go back and plot to files
interactive = False

#
# First the target
#
vis = srcsplitsms
field = srcname
yaxis = 'amp'
# Use the field name as the title
title = field+"
figfile = vis + '.plotxy.amp.png'
print "Plotting to file "+figfile
#saveinputs('plotxy',vis+'.plotxy.amp.saved')

plotxy()

yaxis = 'phase'
# Use the field name as the title
figfile = vis + '.plotxy.phase.png'
print "Plotting to file "+figfile
#saveinputs('plotxy',vis+'.plotxy.phase.saved')

plotxy()

#
# Now the calibrator
#
vis = calsplitsms
field = calname
yaxis = 'amp'
# Use the field name as the title
title = field+"
figfile = vis + '.plotxy.amp.png'
print "Plotting to file "+figfile
#saveinputs('plotxy',vis+'.plotxy.amp.saved')
```

```
plotxy()

yaxis = 'phase'
# Use the field name as the title
figfile = vis + '.plotxy.phase.png'
print "Plotting to file "+figfile
#saveinputs('plotxy',vis+'.plotxy.phase.saved')

plotxy()

print 'Calibration completed'
#
#=====
#
# Intensity Imaging/Selfcal
#
#=====
#
# Make the scratch columns in the split ms
#
print '--Clearcal--'
default('clearcal')

vis = srcsplitms

clearcal()

print "Created scratch columns for MS "+vis
print ""
#
#=====
#
# FIRST CLEAN / SELFCAL CYCLE
#=====
#
# Now clean an image of Jupiter
# NOTE: this uses the new combined invert/clean/mosaic task Patch 2
#
print '--Clean 1--'
default('clean')

# Pick up our split source data
vis = srcsplitms

# Make an image root file name
imname1 = imname1

print "Output images will be prefixed with "+imname1

# Set up the output continuum image (single plane mfs)
mode = 'mfs'
stokes = 'I'
```

```
print "Will be a single MFS continuum image"

# NOTE: current version field=' doesnt work
field = '*'

# Combine all spw
spw = ''

# Imaging mode params
psfmode = clnalg
imagermode = clnmode

# Imsize and cell
imsize = clnimsize
cell = clncell

# NOTE: will eventually have an imadvise task to give you this
# information

# Standard gain factor 0.1
gain = 0.1

# Fix maximum number of iterations and threshold
niter = clniter
threshold = clnthreshold

# Note - we can change niter and threshold interactively
# during clean

# Set up the weighting
# Use Briggs weighting (a moderate value, on the uniform side)
weighting = 'briggs'
robust = 0.5

# No clean mask or box
mask = ''

# Use interactive clean mode
interactive = True

# Moderate number of iter per interactive cycle
npercycle = 100

saveinputs('clean', imagename+'.clean.saved')
clean()

# When the interactive clean window comes up, use the right-mouse
# to draw rectangles around obvious emission double-right-clicking
# inside them to add to the flag region. You can also assign the
# right-mouse to polygon region drawing by right-clicking on the
```

```

# polygon drawing icon in the toolbar. When you are happy with
# the region, click 'Done Flagging' and it will go and clean another
# 100 iterations. When done, click 'Stop'.

print ""
print "-----"
print "Clean"
print "Final clean model is "+clnmodel1
print "Final restored clean image is "+clnimage1
print "The clean residual image is "+clnresid1
print "Your final clean mask is "+clnmask1

print ""
print "This is the final restored clean image in the viewer"
print "Zoom in and set levels to see faint emission"
print "Use rectangle drawing tool to box off source"
print "Double-click inside to print statistics"
print "Move box on-source and get the max"
print "Calcualte DynRange = MAXon/RMSoff"
print "I got 1.060/0.004 = 270"
print "Still not as good as it can be - lets selfcal"
print "Close viewer panel when done"

#
#-----
#
# If you did not do interactive clean, bring up viewer manually
viewer(clnimage1,'image')

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

# You can use the right-mouse to draw a box in the lower right
# corner of the image away from emission, the double-click inside
# to bring up statistics. Use the right-mouse to grab this box
# and move it up over Jupiter and double-click again. You should
# see stuff like this in the terminal:
#
# jupiter6cm.usecase.clean1.image      (Jy/beam)
#
# n          Std Dev      RMS       Mean      Variance     Sum
# 4712        0.003914   0.003927  0.0003205  1.532e-05  1.510
#
# Flux        Med |Dev|  IntQtlRng  Median      Min       Max
# 0.09417     0.002646   0.005294  0.0001885  -0.01125   0.01503
#
#
# On Jupiter:
#
# n          Std Dev      RMS       Mean      Variance     Sum

```

```

# 3640      0.1007      0.1027      0.02023      0.01015      73.63
#
# Flux      Med |Dev|   IntQtlRng   Median      Min       Max
# 4.592     0.003239    0.007120    0.0001329   -0.01396    1.060
#
# Estimated dynamic range = 1.060 / 0.003927 = 270 (poor)
#
# Note that the exact numbers you get will depend on how deep you
# take the interactive clean and how you draw the box for the stats.

=====
#
# Do some non-interactive image statistics
print '--Imstat--'
default('imstat')

imagename = clnimage1
on_statistics1 = imstat()

# Now do stats in the lower right corner of the image
# remember clnimsize = [288,288]
box = '216,1,287,72'
off_statistics1 = imstat()

# Pull the max and rms from the clean image
thistest_immax=on_statistics1['max'][0]
print ' Found : Max in image = ',thistest_immax
thistest_imrms=off_statistics1['rms'][0]
print ' Found : rms in image = ',thistest_imrms
print ' Clean image Dynamic Range = ',thistest_immax/thistest_imrms
print ''
#
#-----
#
# Self-cal using clean model
#
# Note: clean will have left FT of model in the MODEL_DATA column
# If you've done something in between, can use the ft task to
# do this manually.
#
print '--SelfCal 1--'
default('gaincal')

vis = srcsplitsms

print "Will self-cal using MODEL_DATA left in MS by clean"

# New gain table
caltable = selfcaltab1

print "Will write gain table "+selfcaltab1

```

```
# Don't need a-priori cals
selectdata = False
gaincurve = False
opacity = 0.0

# This choice seemed to work
refant = calrefant

# Do amp and phase
gaintype = 'G'
calmode = 'ap'

# Do 30s solutions with SNR>1
solint = 30.0
minsnr = 1.0
print "Calibrating amplitudes and phases on 30s timescale"

# Do not need to normalize (let gains float)
solnorm = False

gaincal()

#
#-----
# It is useful to put this up in plotcal
#
#
print '--PlotCal--'
default('plotcal')

caltable = selfcaltab1
multiplot = True
yaxis = 'amp'

plotcal()

print ""
print "-----"
print "Plotcal"
print "Looking at amplitude in self-cal table "+caltable

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

yaxis = 'phase'

plotcal()

print ""
```

```
print "-----"
print "Plotcal"
print "Looking at phases in self-cal table "+caltab

#
# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

#
#-----
#
# Correct the data (no need for interpolation this stage)
#
print '--ApplyCal--'
default('applycal')

vis = srcsplitms

print "Will apply self-cal table to over-write CORRECTED_DATA in MS"

gaintable = selfcaltab1

gaincurve = False
opacity = 0.0
field = ''
spw = ''
selectdata = False

calwt = True

applycal()

# Self-cal is now in CORRECTED_DATA column of split ms
#=====
# Use Plotxy to look at the self-calibrated data
#
print '--Plotxy--'
default('plotxy')

vis = srcsplitms
selectdata = True
field = 'JUPITER'

correlation = 'RR LL'
xaxis = 'uvdist'
yaxis = 'amp'
datacolumn = 'corrected'
multicolor = 'both'

# Use the field name as the title
```

```
selectplot = True
title = field+"  "

iteration = ''

plotxy()

print ""
print "-----"
print "Plotting JUPITER self-corrected visibilities"
print "Look for outliers, and you can flag them"

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

#
#=====
# SECOND CLEAN / SELFCAL CYCLE
#=====
#
print '--Clean 2--'
default('clean')

print "Now clean on self-calibrated data"

vis = srcsplitms

imagename = imname2

field = '*'
spw = ''
mode = 'mfs'
gain = 0.1

# Imaging mode params
psfmode = clnalg
imagermode = clnmode
imsize = clnimsize
cell = clncell
niter = clniter
threshold = clnthreshold

weighting = 'briggs'
robust = 0.5

mask = ''
interactive = True
npercycle = 100

saveinputs('clean',imagename+'.clean.saved')
```

```

clean()

print ""
print "-----"
print "Clean"
print "Final clean model is "+clnmodel2
print "Final restored clean image is "+clnimage2
print "The clean residual image is "+clnresid2
print "Your final clean mask is "+clnmask2

print ""
print "This is the final restored clean image in the viewer"
print "Zoom in and set levels to see faint emission"
print "Use rectangle drawing tool to box off source"
print "Double-click inside to print statistics"
print "Move box on-source and get the max"
print "Calcualte DynRange = MAXon/RMSoff"
print "This time I got 1.076 / 0.001389 = 775 (better)"
print "Still not as good as it can be - lets selfcal again"
print "Close viewer panel when done"

#
#-----
#
# If you did not do interactive clean, bring up viewer manually
viewer(clnimage2,'image')

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

# jupiter6cm.usecase.clean2.image      (Jy/beam)
#
# n          Std Dev     RMS        Mean       Variance     Sum
# 5236      0.001389   0.001390   3.244e-05  1.930e-06  0.1699
#
# Flux      Med |Dev| IntQtlRng Median      Min        Max
# 0.01060   0.0009064  0.001823   -1.884e-05 -0.004015  0.004892
#
#
# On Jupiter:
#
# n          Std Dev     RMS        Mean       Variance     Sum
# 5304      0.08512    0.08629    0.01418    0.007245   75.21
#
# Flux      Med |Dev| IntQtlRng Median      Min        Max
# 4.695     0.0008142   0.001657   0.0001557  -0.004526  1.076
#
# Estimated dynamic range = 1.076 / 0.001389 = 775 (better)
#
# Note that the exact numbers you get will depend on how deep you

```

```

# take the interactive clean and how you draw the box for the stats.
#
print ""
print "-----"
print "After this script is done you can continue on with"
print "more self-cal, or try different cleaning options"

#
#=====
# Image Analysis
#=====
#
# Can do some image statistics if you wish
print '--Imstat (Cycle 2)--'
default('imstat')

imagename = clnimage2
on_statistics2 = imstat()

# Now do stats in the lower right corner of the image
# remember clnimsize = [288,288]
box = '216,1,287,72'
off_statistics2 = imstat()

# Pull the max and rms from the clean image
thistest_immax=on_statistics2['max'][0]
print ' Found : Max in image = ',thistest_immax
thistest_imrms=off_statistics2['rms'][0]
print ' Found : rms in image = ',thistest_imrms
print ' Clean image Dynamic Range = ',thistest_immax/thistest_imrms
print ''

#=====
#
# Print results and regression versus previous runs
#
print ""
print ' Final Jupiter results '
print ' ===== '
print ''
# Pull the max and rms from the clean image
thistest_immax=on_statistics2['max'][0]
oldtest_immax = 1.07732224464
print ' Clean image ON-SRC max = ',thistest_immax
print ' Previously found to be = ',oldtest_immax
diff_immax = abs((oldtest_immax-thistest_immax)/oldtest_immax)
print ' Difference (fractional) = ',diff_immax

print ''
thistest_imrms=off_statistics2['rms'][0]
oldtest_imrms = 0.0010449

```

```
print ' Clean image OFF-SRC rms = ',thistest_imrms
print ' Previously found to be = ',oldtest_imrms
diff_imrms = abs((oldtest_imrms-thistest_imrms)/oldtest_imrms)
print ' Difference (fractional) = ',diff_imrms

print ''
print ' Final Clean image Dynamic Range = ',thistest_immax/thistest_imrms
print ''
print '--- Done with I Imaging and Selfcal---'

#
#=====
# Polarization Imaging
#=====
#
print '--Clean (Polarization)--'
default('clean')

print "Now clean polarized data"

vis = srcsplitsms

imagename = polimname

field = '*'
spw = ''
mode = 'mfs'
gain = 0.1

# Polarization
stokes = 'IQUV'

psfmode = polclnalg
imagermode = polclnmode

niter = clniter
threshold = clnthreshold

imsize = clnimsize
cell = clncell

weighting = 'briggs'
robust = 0.5

interactive = True
npercycle = 100

saveinputs('clean',imagename+'.clean.saved')
clean()

print ""
```

```
print "-----"
print "Clean"
print "Final restored clean image is "+polimage
print "Final clean model is "+polmodel
print "The clean residual image is "+polresid
print "Your final clean mask is "+polmask

#
#=====
# Image Analysis
#=====
#
# Polarization statistics
print '--Final Pol Imstat--'
default('imstat')

imagename = polimage

on_statistics = []
off_statistics = []

# lower right corner of the image (clnimsize = [288,288])
onbox = ''
# lower right corner of the image (clnimsize = [288,288])
offbox = '216,1,287,72'

for stokes in ['I','Q','U','V']:
    box = onbox
    on_statistics[stokes] = imstat()
    box = offbox
    off_statistics[stokes] = imstat()

#
# Peel off some Q and U planes
#
print '--Immath--'
default('immath')

mode = 'evalexpr'

stokes = 'I'
outfile = ipolimage
expr = '\"'+polimage+'\"'

immath()
print "Created I image "+outfile

stokes = 'Q'
outfile = qpolimage
expr = '\"'+polimage+'\"'
```

```
immath()
print "Created Q image "+outfile

stokes = 'U'
outfile = upolimage
expr = '\\"'+polimage+'\\"'

immath()
print "Created U image "+outfile

#
#-----
# Now make POLI and POLA images
#
stokes = ''
outfile = poliimage
mode = 'poli'
imagename = [qpolimage,upolimage]
# Use our rms above for debiasing
mysigma = 0.5*( off_statistics['Q']['rms'][0] + off_statistics['U']['rms'][0] )
#sigma = str(mysigma) +'Jy/beam'
# This does not work well yet
sigma = '0.0Jy/beam'

immath()
print "Created POLI image "+outfile

outfile = polaimage
mode = 'pola'

immath()
print "Created POLA image "+outfile

#
#-----
# Save statistics of these images
default('imstat')

imagename = poliimage
stokes = ''
box = onbox
on_statistics['POLI'] = imstat()
box = offbox
off_statistics['POLI'] = imstat()

#
#
#-----
# Display clean I image in viewer but with polarization vectors
#
# If you did not do interactive clean, bring up viewer manually
```

```
viewer(poliimage,'image')

print "Displaying pol I now. You should overlay pola vectors"
print "Bring up the Load Data panel:"
print ""
print "Use LEL for POLA VECTOR with cut above 6*mysigma in POLI = "+str(6*mysigma)
print "For example:"
print "'"+poliimage+"['"+poliimage+"']>0.0048]"
print ""
print "In the Data Display Options for the vector plot:"
print " Set the x,y increments to 2 (default is 3)"
print " Use an extra rotation this 90deg to get B field"
print "Note the lengths are all equal. You can fiddle these."
print ""
print "You can also load the poli image as contours"

# Pause script if you are running in scriptmode
if scriptmode:
    user_check=raw_input('Return to continue script\n')

# NOTE: the LEL will be something like
# 'jupiter6cm.usecase.polimg.clean.image.pola'['jupiter6cm.usecase.polimg.clean.image.poli']>0.005

#
# NOTE: The viewer can take complex images to make Vector plots, although
# the image analysis tasks (and ia tool) cannot yet handle these. But we
# can use the imagepol tool (which is not imported by default) to make
# a complex image of the linear polarized intensity for display.
# See CASA User Reference Manual:
# http://casa.nrao.edu/docs/casaref/imagepol-Tool.html
#
# Make an imagepol tool and open the clean image
potool = casac.homefinder.find_home_by_name('imagepolHome')
po = potool.create()
po.open(poliimage)
# Use complexlinpol to make a Q+iu image
complexlinpolimage = polimname + '.cmplxlinpol'
po.complexlinpol(complexlinpolimage)
po.close()

# You can now display this in the viewer, in particular overlay this
# over the intensity raster with the poli contours. The vector lengths
# will be proportional to the polarized intensity. You can play with
# the Data Display Options panel for vector spacing and length.
# You will want to have this masked, like the pola image above, on
# the polarized intensity. When you load the image, use the LEL:
# 'jupiter6cm.usecase.polimg.clean.cmplxlinpol'['jupiter6cm.usecase.polimg.clean.image.poli']>0.005

=====
#
# Print results
```

```

#
print ""
print ' Jupiter polarization results '
print ' ===== '
print ''
for stokes in ['I','Q','U','V','POLI']:
    print ''
    print ' ===== '
    print ''
    print ' Polarization (Stokes '+stokes+'):'
    mymax = on_statistics[stokes]['max'][0]
    mymin = on_statistics[stokes]['min'][0]
    myrms = off_statistics[stokes]['rms'][0]
    absmax = max(mymax,mymin)
    mydra = absmax/myrms
    print ' Clean image ON-SRC max = ',mymax
    print ' Clean image ON-SRC min = ',mymin
    print ' Clean image OFF-SRC rms = ',myrms
    print ' Clean image dynamic rng = ',mydra

print '--- Done ---'

#
#=====

```

F.3 VLA Polarization Calibration

This script analyzes a standard VLA Project POLCA run. This is a polarization calibration and monitoring program run by VLA staff.

The latest version of this script can be found at:

http://casa.nrao.edu/Doc/Scripts/run_polcal_20080224_cband_usecase.py

```

#####
#
# Use Case Script for POLCAL 6cm Data
# Using POLCA data 20080224 BnC-config C-band
#
# Last Updated STM 2008-05-23 (Beta Patch 2)
# Updated      STM 2008-06-11 (Beta Patch 2.0)
#     Uses new clean task
#
#####

import time
import os
```

```
import pickle

#
#=====
#
# This script may have some interactive commands: scriptmode = True
# if you are running it and want it to stop during interactive parts.

scriptmode = True

#=====
# SET UP THE SCRIPT CONTROL PARAMETERS HERE
#=====

#
# Set up some useful variables to control subsequent actions:

pathname=os.environ.get('AIPSPATH').split()[0]

# This name will prefix all output files
prefix = 'polcal_20080224.cband.all'

# Clean up old files
os.system('rm -rf '+prefix+'*')

#=====

# Import data from export or use already existing MS? Or UVFITS?
importmode = 'vla'          # 'vla','fits','ms'
# This is the name of the datafile used in import
# or the name of a previously made ms that will be copied
# NOTE: if an ms name must be different than prefix + '.ms'
#datafile = 'polcal_20080224.cband.edited.ms'
#datafile = '20080224C.UVF'
#
# NOTE: This file may be obtained from the CASA repository:
# http://casa.nrao.edu/Data/VLA/Polcal/POLCA_20080224_1
datafile = ['POLCA_20080224_1']
#
# If from export set these:
exportproject = 'POLCA'
exportband = 'C'
#
# Spectral windows to use in ms (usually 0,1)
usespw = ''
usespwlist = ['0','1']

# The ms will have this name
msfile = prefix + '.ms'

# These are names of calibration tables
gtable = prefix + '.gcal'
```

```

ftable = prefix + '.fluxscale'
ptable = prefix + '.pcal'
xtable = prefix + '.polx'

# Flagging:
myquackinterval = 14.0          # if >0 then quack scan beginnings
# Flagging these antennas (if blank then no flagging)
# NOTE: This script uses NEW names, so VLA ants are VAxx
flagants = ''
#flagants = 'EA*'                  # keep only VLA antennas
#flagants = 'VA*'                  # keep only EVLA antennas

#
# List of sources in ms
#
#   0     A    1924-292      19:24:51.06      -29.14.30.12  J2000
#   1     A    1743-038      17:43:58.86      -03.50.04.62  J2000
#   2     A    2202+422      22:02:43.29      +42.16.39.98  J2000
#   3     A    2253+161      22:53:57.75      +16.08.53.56  J2000
#   4     B    2136+006      21:36:38.59      +00.41.54.21  J2000
#   5     B    0137+331      01:37:41.30      +33.09.35.13  J2000
#   6     A    2355+498      23:55:09.46      +49.50.08.34  J2000
#   7     B    0319+415      03:19:48.16      +41.30.42.10  J2000
#   8     B    0359+509      03:59:29.75      +50.57.50.16  J2000
#
# These sources are the gain calibrators
gaincalfield = ['0137+331','2202+422','1743-038','1924-292','2136+006',
                 '2253+161','2355+498','0319+415','0359+509']
#
# These sources will have calibration transferred from srclist
targets = []

# Assemble field strings from lists
fieldgain = ''
if ( len(gaincalfield) > 0 ):
    for fn in range(len(gaincalfield)):
        if ( fn > 0 ):
            fieldgain += ','
        fieldgain += gaincalfield[fn]

fieldtargets = ''
if ( len(targets) > 0 ):
    for fn in range(len(targets)):
        if ( fn > 0 ):
            fieldtargets += ','
        fieldtargets += targets[fn]

#
# This list is used for final clean and stats
srclist = gaincalfield + targets

```

```

# Location of Cal Models
# e.g. for MacOSX
#fluxcaldir = '/opt/casa/data/nrao/VLA/CalModels/'
# or standard distro
fluxcaldir = pathname + '/data/nrao/VLA/CalModels/'
# or in place
#fluxcaldir = './'

# Calibration parameters:
fluxcalfield = '0137+331'          # primary calibrator for setjy
fluxcalmodel = '3C48_C.im'          # if non-blank use this model image
gaincalfield = ''                  # names of gain calibrators (''=all fields)
usegaincurve = False               # use a-priori antenna gain-elevation curve?
gainopacity = 0.0                 # a-priori atmospheric optical depth (Tau)
calrefant = 'VA15'                # reference antenna name for calibration (VA15,EA19)
gainsolint = 20.0                 # 20s for gaincal solutions
polcalfield = '2202+422'          # polarization (D-term) calibrator
polcalmode = 'D+QU'                # polarization (D-term) calibration mode
polduvrange = ''                  # uvrage for polcal D
setpolmodel = True                # if true then use setjy to set pol model
polxfield = '0137+331'            # polarization angle (X) calibrator
polxuvrange = ''                  # uvrage for polcal X
#
setjymode = 'set'                 # mode for fluxcal setjy: 'set', 'flux', 'ft'

# This is the name of the split file for corrected data
srcsplitsms = prefix + '.split.ms'

#
# Set up general clean parameters

# This is BnC-config VLA 6cm (4.85GHz) obs
# Check the observational status summary
# Primary beam FWHM = 45'/f_GHz = 557"
# Synthesized beam for VLA/EVLA at C-Band:
#      A-config FWHM = 0.4"
#      B-config FWHM = 1.2"
#      C-config FWHM = 3.9"
#      D-config FWHM = 14.0"
# RMS in 10min (600s) = 0.06 mJy (thats now, but close enough)
#
# Set the output image size and cell size (arcsec)
# 0.4" will give 3x oversampling at least
# clean will say to use a composite integer (e.g.288) for efficiency
#clnalg = 'clark'
clnalg = 'hogbom'
useccsclean = False
clnimsize = 288
clncell = 0.4
# Fix maximum number of iterations
clniter = 200

```

```

# Also set flux residual threshold (0.04 mJy)
# Our scans are around 120s
# With rms of 0.06 mJy in 600s ==> rms = 0.13 mJy
# Set to 10x thermal rms
clthreshold = 1.3

# Set up a clean box in the center (1/8 of image)
clncenter = clnimsize/2
clnblc = clncenter - clnimsize/8
clntrc = clncenter + clnimsize/8
# For poor uv coverage, use tigher box (6 x SynthBeam = 18xcell)
clnblc = clncenter - 10
clntrc = clncenter + 10
centerbox = [clnblc,clnblc,clntrc,clntrc]

myclnbox = centerbox
# Can also force interactive cleaning
#myclnbox = 'interactive'

aipsmodel = {}
#
#=====
#
# Polarization of X angle calibrator 0137+331
# If setpolmodel = True
#
# Set up fluxcalmodel
#
fcalmode = {}
#
# The flux model for 0137+331 (C-band)
fcalfiel = {}
#
# NOTE: you must have entries for all spw in usespwlist
# I,Q,U,V
fcalfiel['0'] = [5.405,0,0,0]
fcalfiel['1'] = [5.458,0,0,0]
fcalmode['0137+331'] = fcalfiel
# Put in 2202+422
# These values from AIPS (http://www.vla.nrao.edu/astro/calib/polar/2004/)
fcalfiel = {}
fcalfiel['0'] = [2.465,0,0,0]
fcalfiel['1'] = [2.461,0,0,0]
fcalmode['2202+422'] = fcalfiel
#
# Set up pcalmode
#
pcalmode = {}
#
# The polarization model for 0137+331
pcalfiel = {}
#
# NOTE: you must have entries for all spw in usespwlist

```

```

# From calibrator manual: C-band RLPD=-148deg P/I=0.041
# IPOL,FPOL,RLOPHASE
pcalfield['0'] = [5.405,0.041,-148.0]
pcalfield['1'] = [5.458,0.041,-148.0]
pcalmodel['0137+331'] = pcalfield
# Put in 2202+422 (with effective flux of 1.0 before fluxscale)
# These values from AIPS (http://www.vla.nrao.edu/astro/calib/polar/2004/)
pcalfield = {}
pcalfield['0'] = [1.0,0.072,-55.00]
pcalfield['1'] = [1.0,0.072,-55.00]
pcalmodel['2202+422'] = pcalfield
#
# Set the polmodel from pcalmodel
#
print '--Setting up Polarization models--'

polmodel = {}
for field in pcalmodel.keys() :
    spwmodel = {}
    # the RLPD is atan2(U,Q) so Q=I*P/I*cos(RLPD) U=I*P/I*sin(RLPD)
    for spw in usespwlist:
        ipol = pcalmodel[field][spw][0]
        fpol = pcalmodel[field][spw][1]
        rlpd_deg = pcalmodel[field][spw][2]
        rlpd = rlpd_deg*pi/180.0
        ppol = ipol*fpol
        qpol = ppol*cos(rlpd)
        upol = ppol*sin(rlpd)
        fluxdensity=[ipol,qpol,upol,0.0]

        pmodel = {}
        pmodel['rlpd_deg'] = rlpd_deg
        pmodel['rlpd'] = rlpd
        pmodel['fpol'] = fpol

        fmodel = {}
        fmodel['flux'] = fluxdensity
        fmodel['poln'] = pmodel
        spwmodel[spw] = fmodel

    polmodel[field] = spwmodel

print "Created polmodel dictionary"
print polmodel
#
=====
# Data Import and List
=====
#
if ( importmode == 'vla' ):
    #

```

```

# Import the data from VLA Export to MS
#
print '--ImportVLA--'
default('importvla')

print "Use importvla to read VLA Export and make an MS"

archivefiles = datafile
vis = msfile
bandname = exportband
autocorr = False
antnamescheme = 'new'
project = exportproject

saveinputs('importvla',prefix+'.importvla.saved')
importvla()

elif ( importmode == 'fits' ):
#
# Import the data from VLA Export to MS
#
print '--ImportUVFITS--'
default('importuvfits')

print "Use importuvfits to read UVFITS and make an MS"

fitsfile = datafile
vis = msfile
async = False

saveinputs('importuvfits',prefix+'.importuvfits.saved')
importuvfits()

else:
#
# Copy from msfile
#
print '--MS Copy--'
print "Copying "+datafile+" to "+msfile

os.system('cp -r '+datafile+' '+msfile)
vis = msfile

#
#=====
#
print '--Listobs--'

print "List summary of MS"

listobs()

#####

```

```

### Begin Task: listobs ####
#
# MeasurementSet Name:
#      /home/sandrock/smyers/Testing/2008-03/polcal_20080224/polcal_20080224.cband.raw.ms
# MS Version 2
#
#   Observer: unavailable      Project: POLCA
# Observation: VLA
# Data records: 318708      Total integration time = 9836.67 seconds
# Observed from 17:10:52 to 19:54:48
#
#   ObservationID = 0          ArrayID = 0
# Date           Timerange             Scan  FldId FieldName      SpwIds
# 24-Feb-2008/17:10:51.7 - 17:12:08.3    1     0 1924-292 [0, 1]
#                   17:21:01.7 - 17:22:18.3    2     1 1743-038 [0, 1]
#                   17:34:31.7 - 17:35:48.3    3     2 2202+422 [0, 1]
#                   17:45:01.7 - 17:46:18.3    4     3 2253+161 [0, 1]
#                   17:55:11.7 - 17:56:28.3    5     4 2136+006 [0, 1]
#                   18:08:01.7 - 18:09:18.3    6     5 0137+331 [0, 1]
#                   18:22:11.7 - 18:23:58.3    7     6 2355+498 [0, 1]
#                   18:32:51.7 - 19:07:58.3    8     2 2202+422 [0, 1]
#                   19:20:51.7 - 19:22:18.3    9     5 0137+331 [0, 1]
#                   19:32:11.7 - 19:33:48.3   10    7 0319+415 [0, 1]
#                   19:42:01.7 - 19:43:18.3   11    8 0359+509 [0, 1]
#                   19:53:31.7 - 19:54:48.3   12    2 2202+422 [0, 1]
#
# Fields: 9
# ID  Code Name          Right Ascension  Declination  Epoch
# 0   A   1924-292        19:24:51.06  -29.14.30.12 J2000
# 1   A   1743-038        17:43:58.86  -03.50.04.62 J2000
# 2   A   2202+422        22:02:43.29  +42.16.39.98 J2000
# 3   A   2253+161        22:53:57.75  +16.08.53.56 J2000
# 4   B   2136+006        21:36:38.59  +00.41.54.21 J2000
# 5   B   0137+331        01:37:41.30  +33.09.35.13 J2000
# 6   A   2355+498        23:55:09.46  +49.50.08.34 J2000
# 7   B   0319+415        03:19:48.16  +41.30.42.10 J2000
# 8   B   0359+509        03:59:29.75  +50.57.50.16 J2000
#
# Spectral Windows: (2 unique spectral windows and 1 unique polarization setups)
# SpwID #Chans Frame Ch1(MHz) ChanWid(kHz)TotBW(kHz) Ref(MHz) Corrs
# 0   1 TOPO  4885.1      50000       50000      4885.1      RR RL LR LL
# 1   1 TOPO  4835.1      50000       50000      4835.1      RR RL LR LL
#
# Feeds: 27: printing first row only
# Antenna Spectral Window # Receptors Polarizations
# 1      -1                2                  [      R, L]
#
# Antennas: 27:
# ID  Name Station Diam. Long. Lat.
# 0   EA24 VLA:W12  25.0 m -107.37.37.4 +33.53.44.2
# 1   EA16 VLA:W6   25.0 m -107.37.15.6 +33.53.56.4
# 2   EA01 VLA:W10  25.0 m -107.37.28.9 +33.53.48.9
# 3   EA19 VLA:W4   25.0 m -107.37.10.8 +33.53.59.1
# 4   VA08 VLA:W16  25.0 m -107.37.57.4 +33.53.33.0
# 5   EA17 VLA:W14  25.0 m -107.37.46.9 +33.53.38.9

```

```

#   6   VA06   VLA:W8    25.0 m   -107.37.21.6  +33.53.53.0
#   7   VA22   VLA:W2    25.0 m   -107.37.07.4  +33.54.00.9
#   8   EA04   UNKNOWN   25.0 m   -107.37.41.3  +33.53.42.0
#   9   VA20   VLA:E12   25.0 m   -107.36.31.7  +33.53.48.5
#  10   VA15   VLA:E4    25.0 m   -107.37.00.8  +33.53.59.7
#  11   VA28   VLA:E6    25.0 m   -107.36.55.6  +33.53.57.7
#  12   VA10   VLA:E8    25.0 m   -107.36.48.9  +33.53.55.1
#  13   EA14   VLA:E16   25.0 m   -107.36.09.8  +33.53.40.0
#  14   EA11   VLA:E10   25.0 m   -107.36.40.9  +33.53.52.0
#  15   VA03   VLA:E14   25.0 m   -107.36.21.3  +33.53.44.5
#  16   EA23   VLA:E18   25.0 m   -107.35.57.2  +33.53.35.1
#  17   EA21   VLA:E2    25.0 m   -107.37.04.4  +33.54.01.1
#  18   VA12   VLA:N4    25.0 m   -107.37.06.5  +33.54.06.1
#  19   VA02   VLA:N20   25.0 m   -107.37.13.2  +33.55.09.5
#  20   EA13   VLA:N16   25.0 m   -107.37.10.9  +33.54.48.0
#  21   EA26   VLA:N32   25.0 m   -107.37.22.0  +33.56.33.6
#  22   EA25   VLA:N24   25.0 m   -107.37.16.1  +33.55.37.7
#  23   VA09   VLA:N8    25.0 m   -107.37.07.5  +33.54.15.8
#  24   EA18   VLA:N12   25.0 m   -107.37.09.0  +33.54.30.0
#  25   VA07   VLA:N36   25.0 m   -107.37.25.6  +33.57.07.6
#  26   VA27   VLA:N28   25.0 m   -107.37.18.7  +33.56.02.5
#
#
# Tables:
#   MAIN           318708 rows
#   ANTENNA        27 rows
#   DATA_DESCRIPTION 2 rows
#   DOPPLER        2 rows
#   FEED           27 rows
#   FIELD          9 rows
#   FLAG_CMD       <empty>
#   FREQ_OFFSET    <absent>
#   HISTORY         6 rows
#   OBSERVATION    1 row
#   POINTING       <empty>
#   POLARIZATION    1 row
#   PROCESSOR      <empty>
#   SOURCE          9 rows
#   SPECTRAL_WINDOW 2 rows
#   STATE           <empty>
#   SYSCAL          <absent>
#   WEATHER         <absent>
#
### End Task: listobs ####
#####
#
# Note that the antennas are out of order as loaded by importvla
#
#=====
#
# Data Flagging if needed

```

```
#=====
#
if ( myquackinterval > 0.0 ):
    #
    # First quack the data
    #
    print '--Flagdata--'
    default('flagdata')

    print "Quacking scan beginnings using interval "+str(myquackinterval)

    vis = msfile
    correlation = ''
    field = ''
    antenna = ''
    spw = usespw
    mode = 'quack'
    quackinterval = myquackinterval

    saveinputs('flagdata',prefix+'.flagdata.quack.saved')
    flagdata()

    #
    # Use Flagmanager to save a copy of the flags so far
    #
    default('flagmanager')

    print "Now will use flagmanager to save the flags"

    vis = msfile
    mode = 'save'
    versionname = 'quack'
    comment = 'Quack '+str(myquackinterval)
    merge = 'replace'

    saveinputs('flagmanager',prefix+'.flagmanager.quack.saved')
    flagmanager()

    #
    if (flagants != '' and not flagants.isspace() ):
        print '--Flagdata--'
        default('flagdata')

        print "Flag all data to AN "+flagants

        vis = msfile
        correlation = ''
        field = ''
        spw = usespw
        mode = 'manualflag'
```

```

antenna = flagants

saveinputs('flagdata',prefix+'.flagdata.ants.saved')
flagdata()

#
# Use Flagmanager to save a copy of the flags so far
#
default('flagmanager')

print "Now will use flagmanager to save the flags"

vis = msfile
mode = 'save'
versionname = 'antflags'
comment = 'flag AN '+flagants
merge = 'replace'

saveinputs('flagmanager',prefix+'.flagmanager.ants.saved')
flagmanager()

#=====
# Calibration
#=====

#
# Set the fluxes of the primary calibrator(s)
#
if ( setjymode == 'flux' ):
    print '--Setjy--'
    default('setjy')

vis = msfile

print "Use setjy to set flux of "+fluxcalfield+" to point model"
field = fluxcalfield
spw = usespw

# If we need a model for flux calibrator then put this here
modimage = fluxcaldir + fluxcalmodel

# Loop over spw
for spw in usespwlist:
    fluxdensity = fcalmodel[fluxcalfield][spw]
    print "Setting SPW "+spw+" to "+str(fluxdensity)
    saveinputs('setjy',prefix+'.setjy.'+spw+'.saved')
    setjy()

elif ( setjymode == 'ft' ):
    print '--FT--'

```

```

default('ft')
vis = msfile
field = fluxcalfield

for spw in usespwlist:
    model = fluxcaldir + fluxcalmodel+'_'+spw+'_IQUV.model'
    print "Use FT to set model"+model
    saveinputs('ft',prefix+'.ft.0.saved')
    ft()

else:
    print '--Setjy--'
    default('setjy')

vis = msfile

print "Use setjy to set flux of "+fluxcalfield
field = fluxcalfield
spw = usespw

# If we need a model or fluxdensities then put those here
modimage = fluxcaldir + fluxcalmodel

saveinputs('setjy',prefix+'.setjy.saved')
setjy()
#
# You should see something like this in the logger and casapy.log file:
#
# 0137+331  spwid=  0  [I=5.405, Q=0, U=0, V=0] Jy, (Perley-Taylor 99)
# 0137+331  spwid=  1  [I=5.458, Q=0, U=0, V=0] Jy, (Perley-Taylor 99)

# cf. AIPS
# SETJY      '0137+331      ' IF =  1 FLUX = 5.4054 (Jy calcd)
# SETJY      '0137+331      ' IF =  2 FLUX = 5.4585 (Jy calcd)

print "Look in logger for the fluxes (should be 5.405 and 5.458 Jy)"

=====
#
# Initial gain calibration
#
print '--Gaincal--'
default('gaincal')

print "Solve for antenna gains on sources "+gaincalfield
print "We have 2 single-channel continuum spw"

vis = msfile

# set the name for the output gain caltable

```

```
print "Output gain table name is "+gtable
caltable = gtable

# All fields are calibrators
# We have 2 IFs (SPW 0,1) with one channel each

# Assemble field string from gaincalfield list
field = fieldgain
print "Calibrating using fields "+field

# Calibrate these spw
spw = usespw

# a-priori calibration application
gaincurve = usegaincurve
opacity = gainopacity

# do not apply parallactic angle correction
parang = False

# G solutions for both amplitude and phase using gainsolint
gaitype = 'G'
solint = gainsolint
calmode = 'ap'

# reference antenna
refant = calrefant

# minimum SNR 3
minsnr = 3

saveinputs('gaincal',prefix+'.gaincal.saved')
gaincal()

# use plotcal to view or listcal to list

=====
#
# List gain calibration
#
print '--Listcal--'

listfile = caltable + '.list'

print "Listing calibration to file "+listfile

listcal()

#
=====
```

```

# Bootstrap flux scale
#
print '--Fluxscale--'
default('fluxscale')

print "Use fluxscale to rescale gain table to make new one"

vis = msfile

# set the name for the output rescaled caltable
ftable = prefix + '.fluxscale'
fluxtable = ftable

print "Output scaled gain cal table is "+ftable

# point to our first gain cal table
caltable = gtable

# use the source we did setjy on as our flux standard reference
reference = fluxcalfield

# transfer the flux to all our other sources
# to bring amplitudes in line with the absolute scale
transfer = fieldgain

saveinputs('fluxscale',prefix+'.fluxscale.saved')
fluxscale()

# You should see in the logger something like:
# Found reference field(s): 0137+331
# Found transfer field(s): 1924-292 1743-038 2202+422 2253+161 2136+006 2355+498 0319+415 0359+509
# Flux density for 1924-292 in SpW=0 is: 8.25145 +/- 0.00988121 (SNR = 835.065, nAnt= 13)
# Flux density for 1924-292 in SpW=1 is: 8.22457 +/- 0.0140951 (SNR = 583.505, nAnt= 13)
# Flux density for 1743-038 in SpW=0 is: 5.31336 +/- 0.00603626 (SNR = 880.239, nAnt= 13)
# Flux density for 1743-038 in SpW=1 is: 5.3184 +/- 0.00480634 (SNR = 1106.54, nAnt= 13)
# Flux density for 2202+422 in SpW=0 is: 2.46545 +/- 0.00335055 (SNR = 735.833, nAnt= 13)
# Flux density for 2202+422 in SpW=1 is: 2.46072 +/- 0.00353799 (SNR = 695.512, nAnt= 13)
# Flux density for 2253+161 in SpW=0 is: 8.74607 +/- 0.0142334 (SNR = 614.474, nAnt= 13)
# Flux density for 2253+161 in SpW=1 is: 8.77219 +/- 0.0102289 (SNR = 857.587, nAnt= 13)
# Flux density for 2136+006 in SpW=0 is: 9.97863 +/- 0.013815 (SNR = 722.303, nAnt= 13)
# Flux density for 2136+006 in SpW=1 is: 9.99001 +/- 0.0170089 (SNR = 587.339, nAnt= 13)
# Flux density for 2355+498 in SpW=0 is: 1.29395 +/- 0.00181169 (SNR = 714.221, nAnt= 13)
# Flux density for 2355+498 in SpW=1 is: 1.29893 +/- 0.00217214 (SNR = 597.995, nAnt= 13)
# Flux density for 0319+415 in SpW=0 is: 13.5742 +/- 0.0221722 (SNR = 612.218, nAnt= 13)
# Flux density for 0319+415 in SpW=1 is: 13.5481 +/- 0.0230828 (SNR = 586.932, nAnt= 13)
# Flux density for 0359+509 in SpW=0 is: 5.13982 +/- 0.00906505 (SNR = 566.993, nAnt= 13)
# Flux density for 0359+509 in SpW=1 is: 5.10322 +/- 0.00990264 (SNR = 515.339, nAnt= 13)
# Storing result in polcal_20080224.cband.vla_3c84.fluxscale
# Writing solutions to table: polcal_20080224.cband.vla_3c84.fluxscale

=====

```

```
#  
# List fluxscale table  
#  
print '--Listcal--'  
  
caltable = ftable  
listfile = caltable + '.list'  
  
print "Listing calibration to file "+listfile  
  
listcal()  
  
#=====  
#  
# Plot final gain calibration  
#  
print '--Plotcal--'  
  
iteration = ''  
showgui = False  
  
xaxis = 'time'  
yaxis = 'amp'  
figfile = caltable + '.plot.amp.png'  
print "Plotting calibration to file "+figfile  
saveinputs('plotcal',prefix+'.plotcal.fluxscale.amp.saved')  
plotcal()  
  
xaxis = 'time'  
yaxis = 'phase'  
figfile = caltable + '.plot.phase.png'  
print "Plotting calibration to file "+figfile  
saveinputs('plotcal',prefix+'.plotcal.fluxscale.phase.saved')  
plotcal()  
  
xaxis = 'antenna'  
yaxis = 'amp'  
figfile = caltable + '.plot.antamp.png'  
print "Plotting calibration to file "+figfile  
saveinputs('plotcal',prefix+'.plotcal.fluxscale.antamp.saved')  
plotcal()  
  
if ( setpolmodel and polcalmode.count('X') > 0 ):  
    #  
    # ======  
    #  
    # Now run setjy to (re)set model for polxfield  
    #  
    print '--Setjy--'  
    default('setjy')
```

```
vis = msfile

print "Use setjy to set IQU fluxes of "+polxfield
field = polxfield

for spw in usespwlist:
    fluxdensity = polmodel[field][spw]['flux']

    saveinputs('setjy',prefix+'.setjy.polspw.'+spw+'.saved')
    setjy()

#=====
#
# Polarization (D-term) calibration
#
print '--PolCal--'
default('polcal')

print "Polarization D-term Calibration (linear approx) on "+polcalfiel

vis = msfile

# Start with the un-fluxscaled gain table
gaintable = gtable

# use settings from gaincal
gaincurve = usegaincurve
opacity = gainopacity

# Output table
ptable = prefix + '.pcal'
caltable = ptable

# Use an unpolarized source or a source tracked through a range of PA
field = polcalfiel
spw = usespw

selectdata=True
uvrange = polduvrange

# Polcal mode
poltype = polcalmode

# Currently 1-day timescale is hardwired
solint = 86400.

# reference antenna
refant = calrefant

# minimum SNR 3
```

```
minsnr = 3

saveinputs('polcal',prefix+'.polcal.saved')
polcal()

# You should see something like:
# Fractional polarization solution for 2202+422 (spw = 0):
# : Q = 0.00356182, U = 0.0717148 (P = 0.0718032, X = 43.5783 deg)
# Fractional polarization solution for 2202+422 (spw = 1):
# : Q = -0.00561314, U = -0.0720833 (P = 0.0723015, X = -47.2263 deg)

#=====
#
# List polcal solutions
#
print '--Listcal--'

listfile = caltable + '.list'

print "Listing calibration to file "+listfile

listcal()

#=====
#
# Plot polcal solutions
#
print '--Plotcal--'

iteration = ''
showgui = False

xaxis = 'real'
yaxis = 'imag'
figfile = caltable + '.plot.reim.png'
print "Plotting calibration to file "+figfile
saveinputs('plotcal',prefix+'.plotcal.polcal.d.reim.saved')
plotcal()

xaxis = 'antenna'
yaxis = 'amp'
figfile = caltable + '.plot.antamp.png'
print "Plotting calibration to file "+figfile
saveinputs('plotcal',prefix+'.plotcal.polcal.d.antamp.saved')
plotcal()

xaxis = 'antenna'
yaxis = 'phase'
figfile = caltable + '.plot.antphase.png'
print "Plotting calibration to file "+figfile
saveinputs('plotcal',prefix+'.plotcal.polcal.d.antphase.saved')
```

```

plotcal()

xaxis = 'antenna'
yaxis = 'snr'
figfile = caltable + '.plot.antsnr.png'
print "Plotting calibration to file "+figfile
saveinputs('plotcal',prefix+'.plotcal.polcal.d.antsnr.saved')
plotcal()

#=====
# Do Chi (X) pol angle calibration if possible
#=====

#
dopolx = False
if ( pcamodel.has_key(polxfield) ):
    dopolx = True

if ( setpolmodel and not polcalmode.count('X') > 0 ):
    #
    # =====
    #
    # Now run setjy if we havent already
    #

    print '--Setjy--'
    default('setjy')

    vis = msfile

    print "Use setjy to set IQU fluxes of "+polxfield
    field = polxfield

    for spw in usespwlist:
        fluxdensity = polmodel[field][spw]['flux']

        saveinputs('setjy',prefix+'.setjy.polspw.'+spw+'.saved')
        setjy()

    #
    # =====
    #
    # Polarization (X-term) calibration
    #
    print '--PolCal--'
    default('polcal')

    print "Polarization R-L Phase Calibration (linear approx)"

    vis = msfile

```

```
# Start with the G and D tables
gaintable = [gtable,ptable]

# use settings from gaincal
gaincurve = usegaincurve
opacity = gainopacity

# Output table
xtable = prefix + '.polx'
caltable = xtable

# previously set with setjy
field = polxfield
spw = usespw

selectdata=True
uvrange = polxuvrange

# Solve for Chi
poltype = 'X'
solint = 86400.

# reference antenna
refant = calrefant

# minimum SNR 3
minsnr = 3

saveinputs('polcal',prefix+'.polcal.X.saved')
polcal()

# You should get something like:
# Position angle offset solution for 0137+331 (spw = 0) = 72.437 deg.
# Position angle offset solution for 0137+331 (spw = 1) = -21.0703 deg.

#
# =====
#
# List polcal solutions
#
#print '--Listcal--'

listfile = caltable + '.list'

#print "Listing calibration to file "+listfile

#listcal()

#
# =====
#
```

```

# Plot polcal solutions
#
print '--Plotcal--'

xaxis = 'antenna'
yaxis = 'phase'
iteration = ''

showgui = False
figfile = caltable + '.plot.png'

print "Plotting calibration to file "+figfile
saveinputs('plotcal',prefix+'.plotcal.polcal.x.antphase.saved')
plotcal()

else:
    if (polxfield != '' and not polxfield.isspace() ):
        print "DO NOT HAVE PCALMODEL FOR "+polxfield
        print "PCALMODEL = ",pcalmodel

#=====
#
# Correct the data
# (This will put calibrated data into the CORRECTED_DATA column)
#
# First using gaincalfield
#
print '--ApplyCal--'
default('applycal')

print "This will apply the calibration to the DATA"
print "Fills CORRECTED_DATA"

vis = msfile

# Start with the fluxscaled G table, the D table, and the X table
if (dopolx):
    gaintable = [ftable,phtable,xtable]
else:
    gaintable = [ftable,phtable]

# use settings from gaincal
gaincurve = usegaincurve
opacity = gainopacity

# select all the data
spw = usespw
selectdata = False

# IMPORTANT set parang=True for polarization

```

```
parang = True

# use the list of gain calibrators, apply to themselves
field = fieldgain
gainselect = field
print "Applying calibration to gain calibrators "+field

saveinputs('applycal',prefix+'.applycal.saved')
applycal()

if ( len(targets) > 0 ):
    #
    # Now with targets if any (transfer from gaincalfield)
    #
    # Assemble field string from target list
    field = fieldtargets
    print "Applying calibration to targets "+field

    saveinputs('applycal',prefix+'.applycal.targets.saved')
    applycal()

#
#=====
#
# Now write out the corrected data
#
print '--Split--'
default('split')

vis = msfile

# Now we write out the corrected data to a new MS

# Make an output vis file
srcsplitsms = prefix + '.split.ms'
outputvis = srcsplitsms

# Select all data
field = ''

# Have to split all spw to preserve numbering
spw = ''

# pick off the CORRECTED_DATA column
datacolumn = 'corrected'

print "Split CORRECTED_DATA into DATA in new ms "+srcsplitsms

saveinputs('split',prefix+'.split.saved')
split()
```

```

#
#=====
#
# Plot up the visibilities for the main calibrators
#
print '--Plotxy--'
default('plotxy')

vis = srcsplitms

field = fluxcalfield
spw = ''

selectdata=True

xaxis = 'uvdist'

interactive=False

correlation='RR LL'
yaxis = 'amp'
figfile = prefix+'.split.'+field+'.uvplot.amp.png'
saveinputs('plotxy',prefix+'.plotxy.'+field+'.amp.saved')
plotxy()

correlation='RL LR'
yaxis = 'phase'
figfile = prefix+'.split.'+field+'.uvplot.rlphase.png'
saveinputs('plotxy',prefix+'.plotxy.'+field+'.rlphase.saved')
plotxy()

if ( polcalfield != fluxcalfield ):
    # Now the poln calibrator
    field = polcalfield

    correlation='RR LL'
    yaxis = 'amp'
    figfile = prefix+'.split.'+field+'.uvplot.amp.png'
    saveinputs('plotxy',prefix+'.plotxy.'+field+'.amp.saved')
    plotxy()

    correlation='RL LR'
    yaxis = 'phase'
    figfile = prefix+'.split.'+field+'.uvplot.rlphase.png'
    saveinputs('plotxy',prefix+'.plotxy.'+field+'.rlphase.saved')
    plotxy()

#
#=====
#
# CLEAN the sources
#=====

```

```
clnmodel = {}

#
#=====
# Loop over sources and spw
# Set up for new clean in patch 2
#
for src in srclist:

    srcmodel = {}

    for spwid in usespwlist:

        print '-- Clean '+src+' spw '+spwid+' --'
        default('clean')

        field = src
        spw = spwid

        # Pick up our split source data
        vis = srcsplitms

        # Make an image root file name
        imname1 = prefix + '.' + src + '.' + spwid + '.clean'
        imagename = imname1

        print " Output images will be prefixed with "+imname1

        # Set up the output continuum image (single plane mfs)
        mode = 'mfs'

        # All polarizations
        stokes = 'IQUV'

        # Use chose clean style
        psfmode = clnalg
        csclen = usecsclen

        imsize = [clnimsize,clnimsize]
        cell = [clncell,clncell]

        # Standard gain factor 0.1
        gain = 0.1

        niter = clniter

        threshold = clthreshold

        # Set up the weighting
        # Use Briggs weighting (a moderate value, on the uniform side)
        weighting = 'briggs'
```

```

robust = 0.5
# Use natural weighting
weighting = 'natural'

# Use the cleanbox
mask = myclnbox

saveinputs('clean',prefix+'.clean.'+src+'.'+spwid+'.saved')
clean()

# Set up variables
clnimage1 = imname1+'.image'
clnmodel1 = imname1+'.model'
clnresid1 = imname1+'.residual'
clnmask1 = imname1+'.mask'
clnpsf1 = imname1+'.psf'
clnflux1 = imname1+'.flux'

#
# =====
#
# Get some statistics of the clean image
#
default('imstat')

field = src
spw = spwid

# Use the clean box
mybox = str(clnblc)+','+str(clnblc)+','+str(clntrc)+','+str(clntrc)

spwmodel = {}

spwstats = {}
spwfluxes = {}
spwsum = {}
spwmod = {}

for stokes in ['I','Q','U','V']:

    # Use the clean image
    imagename = clnimage1
    box = mybox

    saveinputs('imstat',prefix+'.imstat.'+src+'.'+spwid+'.'+stokes+'.saved')
    xstat = imstat()

    spwstats[stokes] = xstat

    # Peak (max or min) in box
    xmax = xstat['max'][0]

```

```

xmin = xstat['min'][0]
if( abs(xmin) > abs(xmax) ):
    xpol = xmin
else:
    xpol = xmax

spwfluxes[stokes]= xpol

# Integrated flux in box
xsum = xstat['flux'][0]
spwsum[stokes]= xsum

# Use the clean model and no box
imagename = clnmodel1
box = ''

saveinputs('imstat',prefix+'.imstat.'+src+'.'+spwid+'.'+stokes+'.model.saved')
xstat = imstat()
# Integrated flux in image
xmod = xstat['sum'][0]
spwmod[stokes]= xmod

# Done with stokes

spwmodel['stat'] = spwstats
spwmodel['flux'] = spwfluxes
spwmodel['integ'] = spwsum
spwmodel['model'] = spwmod

# Use ia tool for pixel values in the restored image
imagename = clnimage1
# Get image values at the reference pixel
spwref = {}
ia.open(imagename)
#
# Stokes I
ipix = ia.pixelvalue()
# Get reference pixel
xref = ipix['pixel'][0]
yref = ipix['pixel'][1]
iflx = ipix['value']['value']
spwref['I'] = iflx
#
# Stokes Q
qpix = ia.pixelvalue([xref,yref,1,0])
qflx = qpix['value']['value']
spwref['Q'] = qflx
#
# Stokes U
upix = ia.pixelvalue([xref,yref,2,0])
uflx = upix['value']['value']

```

```

spwref['U'] = uflux
#
# Stokes V
vpix = ia.pixelvalue([xref,yref,3,0])
vflux = vpix['value']['value']
spwref['V'] = vflux
#
# Polarization quantities
pflux = sqrt( qflux**2 + uflux**2 )
fflux = pflux/iflux
xflux = atan2(uflux,qflux)*180.0/pi
spwref['P'] = pflux
spwref['F'] = fflux
spwref['X'] = xflux
spwref['xref'] = xref
spwref['yref'] = yref
#
# Now the values at the maximum of I
spwmax = {}
#
# Pull the maxpos of I
xref = spwstats['I']['maxpos'][0]
yref = spwstats['I']['maxpos'][1]
#
# Stokes I
iflux = spwstats['I']['max'][0]
spwmax['I'] = iflux
#
# Stokes Q
qpix = ia.pixelvalue([xref,yref,1,0])
qflux = qpix['value']['value']
spwmax['Q'] = qflux
#
# Stokes U
upix = ia.pixelvalue([xref,yref,2,0])
uflux = upix['value']['value']
spwmax['U'] = uflux
#
# Stokes V
vpix = ia.pixelvalue([xref,yref,3,0])
vflux = vpix['value']['value']
spwmax['V'] = vflux

spwmax['xref'] = xref
spwmax['yref'] = yref
# Done with ia tool
ia.close()

spwmodel['refval'] = spwref
spwmodel['maxval'] = spwmax

```

```

srcmodel[spwid] = spwmodel

# Done with spw

clnmodel[src] = srcmodel

# Done with srcs
#
#=====
# Report Final Stats
#=====
#
print 'Results for '+prefix+ ':'
print ""

import datetime
datestring=datetime.datetime.isoformat(datetime.datetime.today())

outfile = 'out.'+prefix+'.'+datestring+'.log'
logfile=open(outfile,'w')
print >>logfile,'Results for '+prefix+ ':'
print >>logfile,""

if ( polmodel.has_key(polxfield) ):
    # Check RL phase offset on X calibrator
    print "R-L phase residual from image of "+polxfield
    print ""
    print >>logfile,"R-L phase residual from image of "+polxfield+":"
    print >>logfile,""

src = polxfield
rlcor = {}

for spwid in usespwlist:
    ipol = clnmodel[src][spwid]['flux']['I']
    qpol = clnmodel[src][spwid]['flux']['Q']
    upol = clnmodel[src][spwid]['flux']['U']
    vpol = clnmodel[src][spwid]['flux']['V']
    rlpd = atan2(upol,qpol)
    rlpdcal = polmodel[src][spwid]['poln']['rlpd']
    rlpcor = rlpdcal - rlpd
    scor = sin(rlpcor); ccor = cos(rlpcor); rlpcor = atan2(scor,ccor)
    rlcor[spwid] = rlpcor
    rlpcor_deg = rlpcor*180.0/pl.pi

    print "R-L Phase Correction SPW "+spwid+" = %7.2f deg" % rlpcor_deg
    print >>logfile,"R-L Phase Correction SPW "+spwid+" = %7.2f deg" % rlpcor_deg

#

```

```

=====
#
# Loop over sources and spw
#
print ""
print "Final Stats:"
print ""

print >>logfile,""
print >>logfile,"Final Stats:"
print >>logfile,""

for src in srclist:

    print "Source "+src+" :"
    print >>logfile,"Source "+src+" :"

    for spwid in usespwlist:

        field = src
        spw = spwid

        # Get fluxes from images

        ipol = clnmodel[src][spwid]['flux']['I']
        qpol = clnmodel[src][spwid]['flux']['Q']
        upol = clnmodel[src][spwid]['flux']['U']
        vpol = clnmodel[src][spwid]['flux']['V']

        # Now get polarization results

        ppol = sqrt(qpol**2 + upol**2)
        fpol = ppol/ipol
        rlpd = atan2(upol,qpol)
        rlpd_deg = rlpd*180.0/pl.pi

        #print ' spw %s CASA I = %.3f Q = %.3f U = %.3f V = %.3f , \%'
        #(spwid,ipol,qpol,upol,vpol)
        print ' spw %s CASA I = %.3f P = %.3f F = %.4f X = %.2f deg' \%'
        #(spwid,ipol,ppol,fpol,rlpd_deg)
        print >>logfile,' spw %s CASA I = %.3f P = %.3f F = %.4f X = %.2f deg' \%'
        #(spwid,ipol,ppol,fpol,rlpd_deg)

        if (aipsmodel.has_key(src)):
            iflx = aipsmodel[src][spwid][0]/1000.0
            fflx = aipsmodel[src][spwid][1]
            rlaips_deg = aipsmodel[src][spwid][2]
            rlaips = rlaips_deg*pi/180.0

            pflx = iflx*fflx
            qflx = pflx*cos(rlaips)

```

```

uflx = pflx*sin(rlaips)
vflx = 0.0

print ' spw %s AIPS I = %7.3f P = %7.3f F = %7.4f X = %7.2f deg' \% 
      (spwid,iflx,pflx,fflx,rlaips_deg)
print >>logfile,' spw %s AIPS I = %7.3f P = %7.3f F = %7.4f X = %7.2f deg' \% 
      (spwid,iflx,pflx,fflx,rlaips_deg)

# Done with spw
print ""
print >>logfile,""

# Should see something like:
#
# R-L phase residual from image of 0137+331 :
#
# R-L Phase Correction SPW 0 =    0.50 deg
# R-L Phase Correction SPW 1 =    0.17 deg
#
# Final Stats:
#
# Source 0137+331 :
#   spw 0 CASA I =  5.320 P =  0.229 F =  0.0430 X = -148.50 deg
#   spw 1 CASA I =  5.362 P =  0.236 F =  0.0439 X = -148.17 deg
#
# Source 2202+422 :
#   spw 0 CASA I =  2.570 P =  0.185 F =  0.0719 X = -57.71 deg
#   spw 1 CASA I =  2.571 P =  0.188 F =  0.0733 X = -53.43 deg
#
# Source 1743-038 :
#   spw 0 CASA I =  5.545 P =  0.073 F =  0.0131 X = -1.69 deg
#   spw 1 CASA I =  5.543 P =  0.078 F =  0.0141 X =  4.38 deg
#
# Source 1924-292 :
#   spw 0 CASA I =  8.243 P =  0.058 F =  0.0070 X = 12.19 deg
#   spw 1 CASA I =  8.184 P =  0.073 F =  0.0089 X =  7.27 deg
#
# Source 2136+006 :
#   spw 0 CASA I = 10.491 P =  0.153 F =  0.0146 X = -171.61 deg
#   spw 1 CASA I = 10.521 P =  0.145 F =  0.0138 X = -160.12 deg
#
# Source 2253+161 :
#   spw 0 CASA I =  9.113 P =  0.527 F =  0.0578 X =  4.42 deg
#   spw 1 CASA I =  9.096 P =  0.524 F =  0.0576 X =  4.72 deg
#
# Source 2355+498 :
#   spw 0 CASA I =  1.340 P =  0.003 F =  0.0022 X = -162.58 deg
#   spw 1 CASA I =  1.355 P =  0.003 F =  0.0023 X =  151.08 deg
#
# Source 0319+415 :

```

```
# spw 0 CASA I = 14.147 P = 0.041 F = 0.0029 X = -79.67 deg
# spw 1 CASA I = 14.229 P = 0.043 F = 0.0030 X = -130.02 deg
#
# Source 0359+509 :
# spw 0 CASA I = 5.351 P = 0.090 F = 0.0168 X = -124.92 deg
# spw 1 CASA I = 5.333 P = 0.094 F = 0.0177 X = -128.78 deg
#
#=====
#
# Done
#
logfile.close()
print "Results are in "+outfile

#
#=====
#
# Now save stat dictionaries using Pickle
pickfile = prefix + '.pickle'
f = open(pickfile,'w')
p = pickle.Pickler(f)
p.dump(clnmodel)
p.dump(polmodel)
f.close()

print ""
print "Dictionaries clenmodel,polmodel saved in "+pickfile
print "Use Pickle to retrieve"
print ""

# e.g.
# f = open(pickfile)
# u = Unpickler(f)
# clenmodel = u.load()
# polmodel = u.load()
# f.close()

print ""
print "Completed Processing"
```

Appendix G

CASA Dictionaries

BETA ALERT: These tend to become out of date as we add new tasks or change names.

G.1 AIPS – CASA dictionary

Please see:

- <https://wikio.nrao.edu/bin/view/Software/CASA-AIPSDictionary>

BETA ALERT: This link is out-of-date and refers mostly to the Toolkit. We will update this with a task dictionary.

G.2 MIRIAD – CASA dictionary

Table G.1 provides a list of common Miriad tasks, and their equivalent CASA tool or tool function names. The two packages differ in both their architecture and calibration and imaging models, and there is often not a direct correspondence. However, this index does provide a scientific user of CASA who is familiar with MIRIAD, with a simple translation table to map their existing data reduction knowledge to the new package.

G.3 CLIC – CASA dictionary

Table G.2 provides a list of common CLIC tasks, and their equivalent CASA tool or tool function names. The two packages are very similar since the CASA software to reduce IRAM data is based on the CLIC reduction procedures.

Table G.1: MIRIAD – CASA dictionary

MIRIAD Task	Description	CASA task/tool
atlod	load ATCA data	atcafiller tool
blflag	Interactive baseline based editor/flagger	mp raster displays
cgcurs	Interactive image analysis	viewer
cgdisp	Image display, overlays	viewer
clean	Clean an image	clean
fits	FITS image filler	importfits
gpboot	Set flux density scale	fluxscale
gpcal	Polarization leakage and gain calibration	cb with 'G' and 'D'
gpcopy	copy calibration tables	<i>not needed</i>
gpplt	Plot calibration solutions	plotcal
imcomb	Image combination	im tool
imfit	Image-plane component fitter	ia.imagefitter
impol	Create polarization images	ia.imagepol
imstat	Image statistics	ia.statistics
imsub	Extract sub-image	ia.subimage
invert	Synthesis imaging	invert, im tool
linmos	linear mosaic combination of images	mosaic
maths	Calculations involving images	ia.imagecalc, ia.calc
mfcal	Bandpass and gain calibration	bandpass
prthd	Print header of image or uvdata	imhead, listobs
restor	Restore a clean component model	im tool
selfcal	selfcalibration of visibility data	clean, gaincal, etc.
tvclip	automated flagging based on clip levels	flagdata
tvdisp	Load image to TV display	viewer
tvflag	Interactive TB data editing	viewer
uvaver	Average/select data, apply calibration	applycal, split
uvfit	uv-plane component fitter	uvmodelfit
uvflag	Command-based flagging	flagdata
uvgen	Simulator	sm tool
uvlist	List uv-data	listvis (TBD)
uvmodel	Source model computation	ft
uvplt	uv-data plotting	plotxy
uvsplit	split uv file in sources and spectral windows	split

Table G.2: CLIC–CASA dictionary

CLIC Function	Description	CASA task/tool
load	Load data	almatifiller tool
print	Print text summary of data	listobs
flag	Flag data	plotxy, flagdata, viewer
phcor	Atmospheric phase correction	almatifiller
rf	Radio frequency bandpass	bandpass
phase	Phase calibration	gaincal
flux	Absolute flux calibration	setjy, fluxscale
ampl	Amplitude calibration	gaincal
table	Split out calibrated data (uv table)	split

Appendix H

Writing Tasks

BETA ALERT: This prescription for writing and incorporating tasks in CASA is for the power-user. This procedure is also likely to change in future releases.

It is possible to write your own task and have it appear in casapy. You must create two files, yourtask.xml and a task_yourtask.py. The xml file is used to describe the interface to the task and the task_yourtask.py does the actual work. The argument names must be the same in both the yourtask.xml and task_yourtask.py file. The yourtask.xml file is used to generate all the interface files so yourtask will appear in the casapy system.

Synopsis

- buildmytasks yourtask
- execfile 'PATH_TO_YOURTASK/yourtask.py' (from inside casapy)'

H.1 The XML file

The key to getting your task into casapy is constructing a task interface description XML file.

Some XML basics, an xml element begins with <element> and ends with </element>. If an XML element contains no other XML element you may specify it via <element/>. An XML element may have zero or more attributes which are specified by attribute="attribute value". You must put the attribute value in quotes, i.e. <element myattribute="attribute value">.

All task xml files must start with this header information.

```
<?xml version="1.0" encoding="UTF-8"?>
<?xml-stylesheet type="text/xsl" ?>
<casaxml xmlns="http://casa.nrao.edu/schema/psetTypes.html"
  xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
  xsi:schemaLocation="http://casa.nrao.edu/schema/casa.xsd"
```

```
file:///opt/casa/code/xmlcasa/xml/casa.xsd">
```

and the file must have the end tag

```
</casaxml>
```

Inside a `<task>` tags you will need to specify the following elements.

```
<task>
```

Attributes

type required, allowed value is "function"
name required

Subelements

shortdescription required
description required
input optional
output optional
returns optional
constraints optional

`<shortdescription>` - required by `<task>`; A short one-line description describing your task

Attributes

None

Subelements

None

`<description>` - required] by `<task>`, Also used by `<param>a`; A longer description describing your task with multiple lines

Attributes

None

Subelements

None

`<input>` - optional element used by `<task>`; An input block specifies which parameters are used for input

Attributes

None

Subelements

<param> , optional

<output> - optional An output element that contains a list of parameters that are "returned" by the task.

Attributes

None

Subelements

<param> , optional

<returns> - optional Value returned by the task

Attributes

type optional; as specified in <param>

Subelements

<description> , optional

<constraints> - optional A constraints element that lets you constrain params based on the values of other params.

Attributes

None

Subelements

<when> , required.

<param> - optional The input and output elements consist of param elements.

Attributes

type , required; allowed values are record, variant, string int, double, bool, intArray, doubleArray, boolArray, stringArray

name , required;

subparam , optional; allowed values True, False, Yes or No.

kind , optional;

mustexist , optional; allowed values True, False, Yes or No.

All param elements require name and type attributes.

Subelements

<description> , required;

<value> , optional;

<allowed> , optional;

<value> - optional Value returned by the task

Attributes

type , required; as specified in <param> attributes.

Subelements

<value> , optional

<allowed> - optional; Block of allowed values

Attributes

enum , required; maybe enum or range. If specified as enum only specific values are allowed. If specified as range then the value tags may have min and max attributes.

Subelements

<value> , optional

<when> - optional When blocks allow value specific handling for parameters

Attributes

param , required; Specifies special handling for a <param>

Subelements

<equals> , optional

<notequals> , optional

<equals> - optional Reset parameters if equal to the specified value

Attributes

value , required; the value of the parameter

Subelements

<default> , required

<notequals> - optional Reset specified parameters if not equal to the specified value

Attributes

value , required; The value of the parameter

Subelements

<default> , optional

<default> - optional Resets default values for specified parameters

Attributes

param , required; Name of the <param> to be reset.

Subelements

<value> , required, the revised value of the <param>.

<example> - optional An example block, typically in python

Attributes

lang optional; specifies the language of the example, defaults to python.

Subelements

None

H.2 The task_yourtask.py file

You must write the python code that does the actual work. The task_*.py file function call sequence must be the same as specified in the XML file. We may relax the requirement that the function call sequence exactly match the sequence in the XML file in a future release.

H.3 Example: The clean task

H.3.1 File clean.xml

Clean.xml gives a fairly comprehensive example of how to construct the XML file.

```
<?xml version="1.0" encoding="UTF-8"?>
<?xml-stylesheet type="text/xsl" ?>
<casaxml xmlns="http://casa.nrao.edu/schema/psetTypes.html"
  xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
  xsi:schemaLocation="http://casa.nrao.edu/schema/casa.xsd
  file:///opt/casa/code/xmlcasa/xml/casa.xsd">

<!-- This is the param set for clean -->
<!-- This does the equivalent of -->
<!-- imgr:=imager('anyfile.ms'); -->
<!-- imgr.setdata(mode='channel',nchan=100,start=1,step=1,fieldid=1) -->
<!-- imgr.setimage(nx=512,ny=,cellx='1arcsec',celly='1arcsec',stokes='I',-->
<!--           mode='channel',start=35,step=1,nchan=40, -->
<!--           fieldid=[1]) -->
<!-- imgr.weight('natural'); -->
<!-- imgr.clean(algorithm='csclen',niter=500,model='field1') -->

<task type="function" name="clean">

  <shortdescription>Deconvolve an image with selected algorithm</shortdescription>

  <description>
    Form images from visibilities. Handles continuum and spectral line cubes.
  </description>

  <input>

    <param type="string" name="vis" kind="ms" mustexist="true">
      <description>name of input visibility file</description>
```

```
<value></value>
</param>

<param type="string" name="imagename">
<description>Pre-name of output images</description>
<value></value>
</param>

<param type="string" name="field">
    <description>Field Name</description>
    <value></value>
</param>

<param type="any" name="spw">
<description>Spectral windows: channels: '\'\' is all </description>
<any type="variant"/>
<value type="string"></value>
</param>
<param type="bool" name="selectdata">
<description>Other data selection parameters</description>
<value>False</value>
</param>

<param type="string" name="timerange" subparam="true">
<description>Range of time to select from data</description>
<value></value>
</param>
<param type="string" name="uvrange" subparam="true">
<description>Select data within uvrange </description>
<value></value>
</param>
<param type="string" name="antenna" subparam="true">
<description>Select data based on antenna/baseline</description>
<value></value>
</param>
<param type="string" name="scan" subparam="true">
<description>scan number range</description>
<value></value>
</param>

<param type="string" name="mode">
<description>
    Type of selection (mfs, channel, velocity, frequency)
</description>
```

```
<value>mfs</value>
<allowed kind="enum">
<value>mfs</value>
<value>channel</value>
<value>velocity</value>
<value>frequency</value>
</allowed>
</param>

<param type="int" name="niter">
<description>Maximum number of iterations</description>
<value>500</value>
</param>

<param type="double" name="gain">
<description>Loop gain for cleaning</description>
<value>0.1</value>
</param>

<param type="double" name="threshold" units="mJy">
<description>Flux level to stop cleaning. Must include units</description>
<value>0.0</value>
</param>

<!-- Getting rid of this
<param type="bool" name="csclean">
<description>Use Cotton-Schwab style reconciliation with UV-data</description>
<value>False</value>

</param>
-->

<param type="string" name="psfmode">
<description>method of PSF calculation to use during minor cycles</description>
<value>clark</value>
<allowed kind="enum">
<value>clark</value>
<value>hogbom</value>
</allowed>
</param>

<param type="string" name="imageremode">
<description> Use csclean or mosaic. If '\'', use psfmode</description>
```

```
<value></value>
<allowed kind="enum">
<value></value>
<value>csclean</value>
<value>mosaic</value>
</allowed>

</param>
<param type="string" name="ftmachine" subparam="true">
<description>Gridding method for the image</description>
<value>mosaic</value>
<allowed kind="enum">
<value>mosaic</value>
<value>ft</value>
<value>sd</value>
<value>both</value>
</allowed>

</param>
<param type="bool" name="mosweight" subparam="true">
<description>Individually weight the fields of the mosaic</description>
<value>False</value>
</param>
<param type="string" name="scaletype" subparam="true">
<description>Controls scaling of pixels in the image plane.
    default=\`SAULT\`;
    example: scaletype=\`PBCOR\` Options: \`PBCOR\`,\`SAULT\`</description>
<value>SAULT</value>
<allowed kind="enum">
<value>SAULT</value>
<value>PBCOR</value>
</allowed>
</param>

<param type="intArray" name="multiscale">
<description>set deconvolution scales (pixels),
    default: multiscale=[] (standard CLEAN)</description>
<value type="vector">
<value></value>
</value>

</param>
<param type="int" name="negcomponent" subparam="true">
```

```
<description>
    Stop cleaning if the largest scale finds this number of neg components
</description>
<value>0</value>
</param>

<param type="bool" name="interactive">
<description>use interactive clean (with GUI viewer)</description>
<value>False</value>
</param>

<param type="any" name="mask">
<description>cleanbox(es), mask image(s), and/or region(s) used in cleaning
    </description>
<any type="variant"/>
<value type="stringArray"></value>
</param>

<param type="int" name="nchan" subparam="true">
<description>Number of channels (planes) in output image</description>
<value>1</value>
</param>

<param type="any" name="start" subparam="true">
<description>First channel in input to use</description>
<any type="variant"/>
<value type="int">0</value>
</param>

<param type="any" name="width" subparam="true">
<description>Number of input channels to average</description>
<any type="variant"/>
<value type="int">1</value>
</param>

<param type="intArray" name="imsize">
<description>x and y image size in pixels, symmetric for single value
    </description>
<value type="vector">
<value>256</value><value>256</value>
</value>
</param>
```

```
<param type="doubleArray" name="cell" units="arcsec">
<description>x and y cell size. default unit arcsec</description>
<value type="vector"><value>1.0</value><value>1.0</value></value>
</param>

<param type="any" name="phasecenter">
<description>Image phase center: position or field index</description>
<any type="variant"/>
<value type="string"></value>
</param>

<param type="string" name="restfreq">
<description>rest frequency to assign to image (see help)</description>
<value></value>
</param>

<param type="string" name="stokes">
<description>Stokes params to image (eg I,IV, QU,IQUV)</description>
<value>I</value>
<allowed kind="enum">
<value>I</value>
<value>IV</value>
<value>QU</value>
<value>IQUV</value>
<value>RR</value>
<value>LL</value>
<value>RRLL</value>
<value>XX</value>
<value>YY</value>
<value>XXYY</value>
</allowed>
</param>

<param type="string" name="weighting">
<description>Weighting to apply to visibilities</description>
<value>natural</value>
<allowed kind="enum">
<value>natural</value>
<value>uniform</value>
<value>briggs</value>
```

```
<value>briggsabs</value>
<value>radial</value>
<value>superuniform</value>
</allowed>
</param>

<param type="double" name="robust" subparam='true'>
<description>Briggs robustness parameter</description>
<value>0.0</value>
<allowed kind="range">
<value range="min">-2.0</value>
<value range="max">2.0</value>
</allowed>
</param>

<param type="bool" name="uvtaper">
<description>Apply additional uv tapering of  visibilities.</description>
<value>False</value>
</param>

<param type="stringArray" name="outertaper" subparam="true">
<description>uv-taper on outer baselines in uv-plane</description>
<value type="vector">
  <value></value>
</value>
</param>

<param type="stringArray" name="innertaper" subparam="true">
<description>uv-taper in center of uv-plane</description>
<value>1.0</value>
</param>

<param type="string" name="modelimage">
<description>Name of model image(s) to initialize cleaning</description>
<value></value>
</param>
<param type="stringArray" name="restoringbeam">
  <description>Output Gaussian restoring beam for CLEAN image</description>
  <value></value>
</param>
<param type="bool" name="pbcor">
<description>Output primary beam-corrected image</description>
<value>False</value>
</param>
```

```
<param type="double" name="minpb">
<description>Minimum PB level to use</description>
<value>0.1</value>
</param>

<param type="any" name="noise" subparam='true'>
<description>noise parameter for briggs abs mode weighting</description>
<any type="variant"/>
<value type="string">1.0Jy</value>
</param>

<param type="int" name="npixels" subparam='true'>
<description>number of pixels for superuniform or briggs weighting
</description>
<value>0</value>
</param>

<param type="int" name="npercycle" subparam='true'>
<description>Number of iterations before interactive prompt</description>
<value>100</value>
</param>
<param type="double" name="cyclefactor" subparam='true'>
<description>change depth in between of csclean cycle</description>
<value>1.5</value>
</param>
<param type="int" name="cyclespeedup" subparam='true'>
<description>Cycle threshold doubles in this number of iteration</description>
<value>-1</value>
</param>

<constraints>
    <when param="selectdata">
<equals type="bool" value="False"/>
<equals type="bool" value="True">
    <default param="timerange"><value type="string"></value>
    </default>
    <default param="uvrange"><value type="string"></value>
    </default>
```

```
<default param="antenna"><value type="string"></value>
</default>
<default param="scan"><value type="string"></value>
</default>
</equals>
</when>
<when param="multiscale">
<notequals type="vector" value="[] " >
<default param="negcomponent"><value>-1</value>
</default>
</notequals>
</when>
<when param="mode">
<equals value="mfs"/>
<equals value="channel">
<default param="nchan"><value>1</value></default>
<default param="start"><value>0</value>
<description>first input channel to use</description>
</default>
<default param="width"><value>1</value></default>
</equals>
<equals value="velocity">
<default param="nchan"><value>1</value></default>
<default param="start"><value type="string">0.0km/s</value>
<description>Velocity of first image channel: e.g. \\'0.0km/s\\'
</description>
</default>
<default param="width"><value type="string">1km/s</value>
<description>image channel width in velocity units:
e.g \\'-1.0km/s\\'</description>
</default>
</equals>
<equals value="frequency">
<default param="nchan"><value>1</value></default>
<default param="start"><value type="string">1.4GHz</value>
<description>Frequency of first image channel: e.q. \\'1.4GHz\\'
</description>
</default>
<default param="width"><value type="string">10kHz</value>
<description>Image channel width in frequency units:
e.g \\'1.0kHz\\'</description>
</default>
</equals>
</when>
```

```

<when param="weighting">
<equals value="natural"/>
    <equals value="uniform"/>
    <equals value="briggs">
<default param="robust"><value>0.0</value></default>
<default param="npixels"><value>0</value>
    <description>number of pixels to determine uv-cell size
                0=&gt; field of view</description>
</default>
    </equals>
<equals value="briggsabs">
<default param="robust"><value>0.0</value></default>
<default param="noise"><value type="string">1.0Jy</value></default>
<default param="npixels"><value>0</value>
    <description>number of pixels to determine uv-cell size
                0=&gt; field of view</description>
</default>
    </equals>
    <equals value="superuniform">
<default param="npixels"><value>0</value>
    <description>number of pixels to determine uv-cell size
                0=&gt; +/-3pixels</description>
</default>
    </equals>
    </when>
<when param="uvtaper">
<equals type="bool" value="False"/>
<equals type="bool" value="True">
<default param="outertaper"><value type="vector"></value></default>
<default param="innertaper"><value type="vector"></value></default>
    </equals>
    </when>
<when param="interactive">
<equals type="bool" value="False"/>
<equals type="bool" value="True">
    <default param="npercycle"><value>100</value></default>
    </equals>
    </when>
<when param="imageremode">
<equals value="/">
<equals value="csclean">
<default param="cyclefactor"><value>1.5</value></default>
<default param="cyclespeedup"><value>-1</value></default>
    </equals>
        <equals value="mosaic">

```

```

<default param="mosweight"><value>False</value></default>
<default param="ftmachine"><value type="string">mosaic</value>
    </default>
<default param="scaletype"><value type="string">SAULT</value>
    </default>
<default param="cyclefactor"><value>1.5</value></default>
<default param="cyclespeedup"><value>-1</value></default>
    </equals>
    </when>
<!--Get rid of that soon
    <when param="mosaicmode">
<equals type="bool" value="False"/>
<equals type="bool" value="True">
<default param="mosweight"><value>False</value></default>
<default param="ftmachine"><value type="string">mosaic</value></default>
<default param="scaletype"><value type="string">SAULT</value></default>
    </equals>
    </when>
-->
</constraints>

</input>

<returns type="void"/>

<example>
```

The main clean deconvolution task. It contains many functions

- 1) Make 'dirty' image and 'dirty' beam (psf)
- 2) Multi-frequency-continuum images or spectral channel imaging
- 3) Full Stokes imaging
- 4) Mosaicking of several pointings
- 5) Multi-scale cleaning
- 6) Interactive clean boxing
- 7) Initial starting model

```

vis -- Name of input visibility file
    default: none; example: vis='ngc5921.ms'
imagename -- Pre-name of output images:
    default: none; example: imagename='m2'
    output images are:
        m2.image; cleaned and restored image
        With or without primary beam correction
```

```

m2.psf; point-spread function (dirty beam)
m2.flux; relative sky sensitivity over field
m2.model; image of clean components
m2.residual; image of residuals
m2.interactive.mask; image containing clean regions
field -- Select fields in mosaic. Use field id(s) or field name(s).
      ['go listobs' to obtain the list id's or names]
      default: ''=all fields
      If field string is a non-negative integer, it is assumed to
      be a field index otherwise, it is assumed to be a
field name
      field='0~2'; field ids 0,1,2
      field='0,4,5~7'; field ids 0,4,5,6,7
      field='3C286,3C295'; field named 3C286 and 3C295
      field = '3,4C*'; field id 3, all names starting with 4C
spw -- Select spectral window/channels
      NOTE: This selects the data passed as the INPUT to mode
      default: ''=all spectral windows and channels
      spw='0~2,4'; spectral windows 0,1,2,4 (all channels)
      spw='0:5~61'; spw 0, channels 5 to 61
      spw='<2';   spectral windows less than 2 (i.e. 0,1)
      spw='0,10,3:3~45'; spw 0,10 all channels, spw 3,
channels 3 to 45.
      spw='0~2:2~6'; spw 0,1,2 with channels 2 through 6 in each.
      spw='0:0~10;15~60'; spectral window 0 with channels
0-10,15-60
      spw='0:0~10,1:20~30,2:1;2;3'; spw 0, channels 0-10,
      spw 1, channels 20-30, and spw 2, channels, 1,2 and 3
selectdata -- Other data selection parameters
      default: True
&ampgt&ampgt&ampgt selectdata=True expandable parameters
      See help par.selectdata for more on these
      timerange -- Select data based on time range:
      default = '' (all); examples,
      timerange = 'YYYY/MM/DD/hh:mm:ss~YYYY/MM/DD/hh:mm:ss'
      Note: if YYYY/MM/DD is missing date defaults to first
day in data set
      timerange='09:14:0~09:54:0' picks 40 min on first day
      timerange= '25:00:00~27:30:00' picks 1 hr to 3 hr
      30min on NEXT day
      timerange='09:44:00' pick data within one integration
      of time
      timerange='>10:24:00' data after this time
      uvrage -- Select data within uvrage (default units meters)
      default: '' (all); example:

```

```

        uvrage='0~1000klambda'; uvrage from 0-1000 kilo-lambda
        uvrage='>4klambda';uvranges greater than 4 kilo lambda
antenna -- Select data based on antenna/baseline
    default: '' (all)
    If antenna string is a non-negative integer, it is
assumed to be an antenna index, otherwise, it is
considered an antenna name.
    antenna='5&6'; baseline between antenna index 5 and
index 6.
    antenna='VA05&VA06'; baseline between VLA antenna 5
and 6.
    antenna='5&6;7&8'; baselines 5-6 and 7-8
    antenna='5'; all baselines with antenna index 5
    antenna='05'; all baselines with antenna number 05
(VLA old name)
    antenna='5,6,9'; all baselines with antennas 5,6,9
index numbers
    scan -- Scan number range.
    default: '' (all)
    example: scan='1~5'
    Check 'go listobs' to insure the scan numbers are in
order.
mode -- Frequency Specification:
    NOTE: See examples below:
    default: 'mfs'
    mode = 'mfs' means produce one image from all
specified data.
    mode = 'channel'; Use with nchan, start, width to specify
            output image cube. See examples below
    mode = 'velocity', means channels are specified in
velocity.
    mode = 'frequency', means channels are specified in
frequency.
&gt;&gt;&gt; mode expandable parameters (for modes other than 'mfs')
    Start, width are given in units of channels, frequency
or velocity as indicated by mode, but only channel
is complete.
    nchan -- Number of channels (planes) in output image
    default: 1; example: nchan=3
    start -- Start input channel (relative-0)
    default=0; example: start=5
    width -- Output channel width in units of the input
channel width (&gt;1 indicates channel averaging)
    default=1; example: width=4
examples:

```

```

spw = '0,1'; mode = 'mfs'
    will produce one image made from all channels in spw
0 and 1
    spw='0:5~28^2'; mode = 'mfs'
        will produce one image made with channels
(5,7,9,...,25,27)
    spw = '0'; mode = 'channel': nchan=3; start=5; width=4
        will produce an image with 3 output planes
        plane 1 contains data from channels (5+6+7+8)
        plane 2 contains data from channels (9+10+11+12)
        plane 3 contains data from channels (13+14+15+16)
    spw = '0:0~63^3'; mode='channel'; nchan=21; start = 0;
width = 1
        will produce an image with 20 output planes
        Plane 1 contains data from channel 0
        Plane 2 contains date from channel 2
        Plane 21 contains data from channel 61
    spw = '0:0~40^2'; mode = 'channel'; nchan = 3; start =
5; width = 4
        will produce an image with three output planes
        plane 1 contains channels (5,7)
        plane 2 contains channels (13,15)
        plane 3 contains channels (21,23)

psfmode -- method of PSF calculation to use during minor cycles:
    default: 'clark': Options: 'clark','hogbom'
    'clark' use smaller beam (faster, usually good enough)
    'hogbom' full-width of image (slower, better for poor
uv-coverage)

Note: psfmode will be used to clean if imagermode = ''
imagermode -- Advanced imaging e.g mosaic or Cotton-Schwab clean
    default: imagermode='': Options: '', 'csclean', 'mosaic'
    default '' => psfmode cleaning algorithm used
&gt;&gt;&gt; imagermode='mosaic' expandable parameter(s):
    Image as a mosaic of the different pointings (uses csclean
style too)
    mosweight -- Individually weight the fields of the mosaic
        default: False; example: mosweight=True
        This can be useful if some of your fields are more
        sensitive than others (i.e. due to time spent
on-source); this parameter will give more weight to
higher sensitivity fields in the overlap regions.

ftmachine -- Gridding method for the image;
    Options: ft (standard interferometric gridding), sd
    (standard single dish) both (ft and sd as appropriate),
    mosaic (gridding use PB as convolution function)

```

```

        default: 'mosaic'; example: ftmachine='ft'
scaletype -- Controls scaling of pixels in the image plane.
          (Not fully implemented...for now only controls
what is seen if interactive=True...but in the future will
control the image on which clean components are searched)
          default='SAULT'; example: scaletype='PBCOR'
          Options: 'PBCOR', 'SAULT'
          'SAULT' when interactive=True shows the residual
with constant noise across the mosaic. If
pbcor=False, the final output image is NOT
corrected for the PB pattern, and therefore is
not "flux correct". Division of SAULT
<imagename> .image by the <imagename> .flux image
will produce a "flux correct image", can also
be achieved by setting pbcor=True.
          'PBCOR' uses the SAULT scaling scheme for
deconvolution, but if interactive=True shows the
primary beam corrected image; the final PBCOR
image is "flux correct" if pbcor=True.

&ampgt&ampgt&ampgt imagermode='csclen' expandable parameter(s): Image using the
          Cotton-Schwab algorithm in between major cycles
cyclefactor -- Change the threshold at which
the deconvolution cycle will stop, degrid
and subtract from the visibilities. For
poor PSFs, reconcile often (cyclefactor=4 or
5); For good PSFs, use cyclefactor 1.5 to
2.0. Note: threshold = cyclefactor * max
sidelobe * max residual.
default: 1.5; example: cyclefactor=4
cyclespeedup -- Cycle threshold doubles in this
number of iterations default: -1;
example: cyclespeedup=3
          try cyclespeedup = 50 to speed up cleaning
multiscale -- set of scales to use in deconvolution. If set,
cleans with several resolutions using hogom clean. The
scale sizes are in units of cellsize. So if
cell='2arcsec', a multiscale scale=10 = 20arcsec. First
scale should always be 0 (point), we suggest second on
the order of synthesized beam, third 3-5 times
synthesized beam, etc. For example if synthesized beam
is 10" and cell=2", try multiscale = [0,5,15]. Note,
multiscale is currently a bit slow.
default: multiscale=[] (standard CLEAN using psfmode algorithm,
no multi-scale). Example: multiscale = [0,5,15]

&ampgt&ampgt&ampgt multiscale expandable parameter(s): negcomponent -- Stop

```

component search when the largest scale has found this number of negative components; -1 means continue component search even if the largest component is negative. default: -1; example: negcomponent=50

imsize -- Image pixel size (x,y)
 default = [256,256]; example: imsize=[350,350]
 imsize = 500 is equivalent to [500,500]

cell -- Cell size (x,y)
 default= '1.0arcsec';
 example: cell=['0.5arcsec','0.5arcsec'] or
 cell=['1arcmin', '1arcmin']
 cell = '1arcsec' is equivalent to ['1arcsec','1arcsec']
 NOTE:cell = 2.0 => ['2arcsec', '2arcsec']

phasecenter -- direction measure or fieldid for the mosaic center
 default: '' => first field selected ; example: phasecenter=6
 or phasecenter='J2000 19h30m00 -40d00m00'

restfreq -- Specify rest frequency to use for output image
 default=' Occationally it is necessary to set this (for example some VLA spectral line data). For example for NH_3 (1,1) put restfreq='23.694496GHz'

stokes -- Stokes parameters to image
 default='I'; example: stokes='IQUV';
 Options: 'I','IV','QU','IQUV','RR','LL','XX','YY','RRLL','XXYY'

niter -- Maximum number iterations,
 if niter=0, then no CLEANing is done ("invert" only)
 default: 500; example: niter=5000

gain -- Loop gain for CLEANing
 default: 0.1; example: gain=0.5

threshold -- Flux level at which to stop CLEANing
 default: '0.0mJy';
 example: threshold='2.3mJy' (always include units)
 threshold = '0.0023Jy'
 threshold = '0.0023Jy/beam' (okay also)

interactive -- use interactive clean (with GUI viewer)
 default: interactive=False
 example: interactive=True
 interactive clean allows the user to build the cleaning mask interactively using the viewer. The viewer will appear every npercycle iteration, but modify as needed. The final interactive mask is saved in the file imagename_interactive.mask. The initial masks use the union of mask and cleanbox (see below)

>>> interactive=True expandable parameter npercycle -- this is the number of iterations between each clean to update mask interactively. Set to about niter/5, but can also be

changed interactively.

mask -- Specification of cleanbox(es), mask image(s), and/or region(s) to be used for CLEANing. As long as the image has the same shape (size), mask images from a previous interactive session can be used for a new execution. NOTE: the initial clean mask actually used is the union of what is specified in mask and <imagename>.mask default: [] (no masking); Possible pecification types: (a) Explicit cleanbox pixel ranges example: mask=[110,110,150,145] clean region with blc=110,100; trc=150,145 (pixel values) (b) Filename with cleanbox pixel values with ascii format: example: mask='mycleanbox.txt' <fieldid blc-x blc-y trc-x trc-y> on each line

```
1 45 66 123 124
2 23 100 300 340
```

(c) Filename for image mask example: mask='myimage.mask'

(d) Filename for region specification (e.g. from viewer) example: mask='myregion.rgn'

(e) Combinations of any of the above example: mask=[[110,110,150,145], 'mycleanbox.txt', 'myimage.mask', 'myregion.rgn']

uv taper -- Apply additional uv tapering of the visibilities. default: uvtaper=False; example: uvtaper=True

&gt&gt&gt uvtaper=True expandable parameters

outertaper -- uv-taper on outer baselines in uv-plane [bmaj, bmin, bpa] taper Gaussian scale in uv or angular units. NOTE: uv taper in (klambda) is roughly on-sky FWHM(arcsec/200)

default: outertaper=[]; no outer taper applied

example: outertaper=['5klambda'] circular taper

FWHM=5 kilo-lambda

outertaper=['5klambda', '3klambda', '45.0deg']

outertaper=['10arcsec'] on-sky FWHM 10"

outertaper=['300.0'] default units are meters

in aperture plane

innertaper -- uv-taper in center of uv-plane [bmaj,bmin,bpa] Gaussian scale at which taper falls to zero at uv=0

default: innertaper=[]; no inner taper applied

NOT YET IMPLEMENTED

modelimage -- Name of model image(s) to initialize cleaning. If multiple images, then these will be added together to form initial staring model NOTE: these are in addition to any initial model in the <imagename>.model image file

default: '' (none); example: modelimage='orion.model'

modelimage=['orion.model','sdorion.image'] Note: if the

```

units in the image are Jy/beam as in a single-dish
image, then it will be converted to Jy/pixel as in a
model image, using the restoring beam in the image
header
weighting -- Weighting to apply to visibilities:
    default='natural'; example: weighting='uniform';
    Options: 'natural','uniform','briggs',
    'superuniform','briggsabs','radial'
&gt;&gt;&gt; Weighting expandable parameters
    For weighting='briggs' and 'briggsabs'
        robust -- Brigg's robustness parameter
        default=0.0; example: robust=0.5;
        Options: -2.0 to 2.0; -2 (uniform)/+2 (natural)
    For weighting='briggsabs'
        noise -- noise parameter to use for Briggs "abs"
weighting
    example noise='1.0mJy'
For superuniform/briggs/briggsabs weighting
    npixels -- number of pixels to determine uv-cell size
        for weight calculation
        example npixels=7
restoringbeam -- Output Gaussian restoring beam for CLEAN image
    [bmaj, bmin, bpa] elliptical Gaussian restoring beam
    default units are in arc-seconds for bmaj,bmin, degrees
    for bpa default: restoringbeam=[]; Use PSF calculated
    from dirty beam.
example: restoringbeam=['10arcsec'] circular Gaussian
    FWHM 10" example:
    restoringbeam=['10.0','5.0','45.0deg'] 10"x5"
        at 45 degrees
pbcor -- Output primary beam-corrected image
    default: pbcor=False; output un-corrected image
example: pbcor=True; output pb-corrected image (masked outside
    minpb) Note: if you set pbcor=False, you can later
    recover the pbcor image by dividing by the .flux image
    (e.g. using immath)
minpb -- Minimum PB level to use default=0.1; example:
    minpb=0.01 Note: this minpb is always in effect
    (regardless of pbcor=True/False)
async -- Run asynchronously
default = False; do not run asynchronously

```

</example>

```
</task>
```

```
</casaxml>
```

H.3.2 File task_clean.py

Task clean implementation file.

```
import os
from taskinit import *
from cleanhelper import *

def clean(vis, imagename, field, spw, selectdata, timerange, uvrangle, antenna,
          scan, mode, niter, gain, threshold, psfmode, imagermode, ftmachine,
          mosweight, scaletype, multiscale, negcomponent, interactive, mask,
          nchan, start, width, imsizE, cell, phasecenter, restfreq, stokes,
          weighting, robust, uvtaper, outertaper, innertaper, modelimage,
          restoringbeam, pbcor, minpb, noise, npixels, npercyclE, cyclEfactor,
          cyclespeedup):

#Python script

    casalog.origin('clean')

    maskimage=''
    if((mask==[]) or (mask=='')):
        mask=['']
    if (interactive):
        if( (mask=='') or (mask==['']) or (mask==[])):
            maskimage=imagename+'.mask'

    #try:
    if(1):
        imCln=imtool.create()
        imset=cleanhelper(imCln, vis)

        if((len(imagename)==0) or (imagename.isspace())):
            raise Exception, 'Cannot proceed with blank imagename'
        casalog.origin('clean')

            imset.defineimages(imsizE=imsizE, cell=cell, stokes=stokes,
```

```

mode=mode, spw=spw, nchan=nchan,
start=start, width=width,
restfreq=restfreq, field=field,
phasecenter=phasecenter)

imset.datselweightfilter(field=field, spw=spw,
timerange=timerange, uvrage=uvrange,
antenna=antenna, scan=scan,
wgtype=weighting, robust=robust,
noise=noise, npixels=npixels,
mosweight=mosweight,
innertaper=innertaper,
outertaper=outertaper)
if(maskimage=='' ):
maskimage=imagename+'.mask'
imset.makemaskimage(outputmask=maskimage, imagename=imagename,
maskobject=mask)

####define clean alg
alg=psfmode
if(multiscale==[0]):
multiscale=[]
if((type(multiscale)==list) and (len(multiscale)>0)):
alg='multiscale'
imCln.setscales(scalemode='uservector',
uservector=multiscale)
if(imagermode=='csclean'):
alg='mf'+alg
if(imagermode=='mosaic'):
if(alg.count('mf') <1):
alg='mf'+alg
imCln.setoptions(ftmachine=ftmachine, padding=1.0)
imCln.setvp(dovp=True)
####PBCOR or not
sclt='SAULT'
if((scaletype=='PBCOR') or (scaletype=='pbcor')):
sclt='NONE'
imCln.setvp(dovp=True)
else:
if(imagermode != 'mosaic'):
##make a pb for flux scale
imCln.setvp(dovp=True)
imCln.makeimage(type='pb', image=imagename+'.flux')

```

```

imCln.setvp(dovp=False)
##restoring
imset.setrestoringbeam(restoringbeam)
###model image
imset.convertmodelimage(modelimages=modelimage,
outputmodel=imagename+'.model')

#####after all the mask shenanigans...make sure to use the
#####last mask
maskimage=imset.outputmask
if(imagermode=='mosaic'):
    imCln.setmfcontrol(stoplargenegatives=negcomponent,scaletype=sclt,
                        minpb=minpb,cyclefactor=cyclefactor,
                        cyclespeedup=cyclespeedup,
                        fluxscale=[imagename+'.flux'])
else:
    imCln.setmfcontrol(stoplargenegatives=negcomponent,
                        cyclefactor=cyclefactor, cyclespeedup=cyclespeedup)

imCln.clean(algorithm=alg,niter=niter,gain=gain,
            threshold=qa.quantity(threshold,'mJy'),
            model=[imagename+'.model'],
            residual=[imagename+'.residual'],
            image=[imagename+'.image'],
            psfimage=[imagename+'.psf'],
            mask=maskimage, interactive=interactive,
            npercycle=npercycle)

imCln.close()
presdir=os.path.realpath('..')
newimage=imagename
if(imagename.count('/') > 0):
    newimage=os.path.basename(imagename)
    os.chdir(os.path.dirname(imagename))
result      = '\'' + newimage + '.image' + '\'';
fluxscale_image = '\'' + newimage + '.flux' + '\'';
if (pbcor):
    if(sclt != 'NONE'):
        ##otherwise its already divided
        ia.open(newimage+'.image')

pixmask = fluxscale_image+>+str(minpb);
ia.calcmask(pixmask,asdefault=True);

pixels='iif('+ fluxscale_image+>+str(minpb)+',
           + result+'/' +fluxscale_image+', 0)',
```

```
ia.calc(pixels=pixels)
ia.close()
else:
## people has imaged the fluxed corrected image
## but want the
## final image to be non-fluxed corrected
if(sclt=='NONE'):
ia.open(newimage+'.image')
result=newimage+'.image'
fluxscale_image=newimage+'.flux'
pixels=result+'*'+fluxscale_image
ia.calc(pixels=pixels)
ia.close()
os.chdir(presdir)

del imCln

# except Exception, instance:
# print '*** Error *** ',instance
# raise Exception, instance
```