10.1.4 HMAC_DRBG (...)

10.1.4.1 Discussion

HMAC_DRBG (...) uses several occurrences of an Approved keyed hash function and an Approved hash function. The same Approved hash function shall be used throughout. The hash function used shall meet or exceed the security requirements of the consuming application. Table 1 in Section 10.1.1 specifies the entropy and seed length requirements that shall be used for each hash function in order to meet a specified security level.

HMAC_DRBG (...) is specified using an internal functions: **Update** (...). This function is called during the instantiation, pseudorandom bit generation and reseeding processes to adjust the state when new entropy or additional input is provided.

10.1.4.2 Interaction with HMAC_DRBG (...)

10.1.4.2.1 Instantiating HMAC_DRBG (...)

Prior to the first request for pseudorandom bits, the HMAC_DRBG (...) shall be instantiated using the following call:

(status, usage_class) = Instantiate_Hash_DRBG (requested_strength, prediction_resistance_flag, personalization_string, mode),

as described in Sections 9.6.1 and 10.1.4.3.3.

10.1.4.2.2 Reseeding a HMAC_DRBG (...) Instantiation

When a **HMAC_DRBG** (...) instantiation requires reseeding, the DRBG **shall** be reseeded using the following call:

status = Reseed_HMAC_DRBG_Instantiation (usage_class, mode)
as described in Sections 9.7.2 and 10.1.4.3.4.

10.1.4.2.3 Generating Pseudorandom Bits Using HMAC_DRBG (...)

An application may request the generation of pseudorandom bits by HMAC_DRBG (...) using the following call:

(status, pseudorandom_bits) = HMAC_DRBG (usage_class, requested_no_of_bits, requested_strength, additional_input, prediction_resistance_requested, mode) as discussed in Sections 9.8.2 and 10.1.4.3.5.

10.1.4.2.4 Removing an HMAC_DRBG (...) Instantiation

An application may request the removal of an HMAC_DRBG (...) instantiation using the following call:

status = Uninstantiate_HMAC_DRBG (usage_class)

as described in Sections 9.X.X and 10.1.4.3.6.

10.1.4.2.5 Self Testing of the HMAC_DRBG (...) Process

An **HMAC_DRBG** (...) implementation is tested at power-up and on demand using the following call:

$$status = Self_Test_HMAC_DRBG()$$

as described in Sections 9.9 and 10.1.4.3.7.

10.1.4.3 Specifications

10.1.4.3.1 General

The instantiation and reseeding of **HMAC_DRBG** (...) consists of obtaining a *seed* with the appropriate amount of entropy. The entropy input is used to derive a *seed*, which is then used to derive elements of the initial *state* of the DRBG. The *state* consists of:

- 1. The value *V*, which is updated each time another *outlen* bits of output are produced (where *outlen* is the number of output bits in the underlying hash function).
- 2. The value *K*, which are updated at least once each time the DRBG generates pseudorandom bits.
- 3. The security strength of the DRBG instantiation.
- 4. A counter (ctr) that indicates the number of updates of V since new entropy_input was obtained whose entropy meets or exceeds the entropy requirement for the security strength.
- 5. A *prediction_resistance_flag* that indicates whether or not a prediction resistance capability is required for the DRBG.
- 6. (Optional) A transformation of the entropy input using a one-way function for later comparison with new entropy input when the DRBG is reseeded; this value **shall** be present if the DRBG will potentially be reseeded; it **may** be omitted if the DRBG will not be reseeded.

The variables used in the description of HMAC_DRBG (...) are:

additional	input	Optional additional input
ananiona	mpm	Optional additional input

ctr A counter that records the number of times that the

state has been updated since the DRBG instantiation was seeded, reseeded or prediction resistance was

obtained.

entropy input The bits containing entropy that are used to determine

the seed material.

Find_state_space (mode) A function that returns a usage_class indicating an

available state space. The *mode* indicates whether the request is made during normal operation or during

testing.

Get_entropy (min_entropy, outlen, 2³², mode)

A function that acquires a string of bits from an entropy input source. *min_entropy* indicates the minimum amount of entropy to be provided in the returned bits; *outlen* indicates the minimum number of bits to return; 2^{32} indicates the maximum number of bits that may be returned; *mode* is used to indicate whether the bits are to be obtained during normal operation or during testing. See Section 9.6.2.

K

A value in the state that is updated when the DRBG generates pseudorandom bits.

max_no_of_states

The maximum number of states and instantiations that an implementation can handle.

max updates

The maximum number of *state* updates allowed for the DRBG instantiation from one seeding, reseeding or prediction resistance operation.

min entropy

The minimum amount of entropy to be provided in the *entropy input*.

mode

An indication of whether a process is to be conducted for normal operations or for testing. $mode = 1 = Normal_operation$ indicates that normal operation is required; $mode = 2 = Fixed_1$ indicates that a predetermined value is to be used during instantiation, $mode = 3 = Fixed_2$ indicates that a predetermined value is to be used during reseeding, mode = 4 = Failure indicates that a failure indication is to be returned.

N

The number of bytes in the hash function output block.

old transformed entropy input

The *transformed_entropy_input* from the previous acquisition of *entropy_input* (e.g., used during reseeding).

outlen

The number of bits in the hash function output block.

personalization_string

A string that may be used to personalize a DRBG instantiation.

prediction_resistance_flag

Indicates whether or not prediction resistance is to be provided upon request during an instantiation. 1 = Allow_prediction_resistance: requests for prediction resistance will be handled; 0 =

No_prediction_resistance: requests for prediction resistance will return an error indication.

prediction resistance requested

Indicates whether or not prediction resistance is required during the actual generation of pseudorandom bits. 1 =

Provide prediction_resistance: prediction resistance required; 0 = No_prediction_resistance: prediction resistance not required.

The string of *pseudorandom_bits* that are generated during a single "call" to the **KHF_DRBG** (...) process.

The number of pseudorandom bits to be generated.

The security strength to be provided for the pseudorandom bits to be obtained from the DRBG.

The data used as the seed.

An array of *states* for different DRBG instantiations. A *state* is carried between calls to the DRBG. In the following specifications, the state for a $usage_class$ is defined as $state(usage_class) = \{V, K_0, K_1, strength, ctr, prediction_resistance_flag, transformed_entropy_input\}$. A particular element of the state is specified as $state(usage_class).element$; e.g., $state(usage_class).V$.

The status returned from a function call, where *status* = "Success" or an indication of failure. Failure messages are:

- 1. Invalid requested strength.
- 2. Cannot support prediction resistance.
- 3. No available state space.
- 4. Failure indication returned by the *entropy_input* source.
- 5. State not available for the indicated usage_class.
- 6. Entropy_input source failure.
- KHF_DRBG can no longer be used. Please reinstantiate or reseed.
- 8. Too many bits requested.
- 9. Prediction resistance capability not instantiated.

The security strength provided by the DRBG instantiation.

A temporary value.

A one-way transformation of the *entropy_input* for the DRBG.

The usage class of a DRBG instantiation. Used as a pointer to an instantiation's *state* values.

pseudorandom_bits

requested_no_of_bits requested strength

seed_material
state(usage class)

status

strength

temp

transformed_entropy_input

usage_class

10.1.4.3.2 Internal Function : The Update Function

The **Update** (...) function updates the internal state of the HMAC_DRBG (...) using seed material.

Update (...):

Input: string (seed material, K, V).

Output: string (K, V).

Process:

- 1. $K = \mathbf{HMAC}(K, V \parallel 0x00 \parallel seed material)$.
- 2. $V = \mathbf{HMAC}(K, V)$.
- 3. $K = \mathbf{HMAC}(K, V \parallel 0 \times 01 \parallel seed material)$.
- 4. $V = \mathbf{HMAC}(K, V)$.
- 5. ctr = ctr + 2.
- 6. Return (K, V).

10.1.4.3.3 Instantiation of HMAC_DRBG(...)

The following process or its equivalent **shall** be used to initially instantiate the **HMAC_DRBG** (...) process. Let **HMAC** (...) be the Approved keyed hash function that is based on an Approved hash function, and let **Hash** (...) be that hash function. Let *outlen* be the output length of the hash function in bits, and let N be the output length of the hash function in bytes.

Instantiate_HMAC_DRBG (...):

Input: integer (requested_strength, prediction_resistance_flag, personalization_string, mode).

Output: string status, integer usage class.

Process:

- If (requested_strength > the maximum security strength that can be provided by the hash function (see Table 1)), then Return ("Invalid requested_strength", 0).
- 2. If (prediction_resistance_flag = Allow_prediction_resistance) and prediction resistance cannot be supported, then **Return** ("Cannot support prediction resistance", 0).

Comment: Find state space.

- 3. (status, usage_class) = Find_state_space (mode).
- 4. If (status = "Failure"), then **Return** ("No available state space", 0).

Comment: Set the strength to one of

the five security strengths.

5. If $(requested_strength \le 80)$, then strength = 80

Else if $(requested_strength \le 112)$, then strength = 112

Else (requested strength \leq 128), then strength = 128

Else (requested strength \leq 192), then strength = 192

Else strength = 256.

Comment: Get the entropy input.

- 6. $min\ entropy = max\ (128, strength)$.
- 7. $(status, entropy_input) = Get_entropy (min_entropy, outlen, 2^{32}, mode).$
- 8. If (*status* = "Failure"), then **Return** ("Failure indication returned by the entropy source", 0).

Comment: Perform a one-way function on the *entropy_input* for later comparison during reseeding.

- 9. transformed_entropy_input = Hash (entropy_input).
- 10. seed_material = entropy_input || personalization_string.
- 11. $K = 0 \times 00 \ 00 \dots 00$.

Comment: N bytes of zeros.

12. $V = 0x01 \ 01...01$.

Comment: N bytes of ones.

- 13. ctr = 0.
- 14. (K, V) = Update (seed material, K, V).
- 15. state(usage_class) = {V, K, strength, ctr, prediction_resistance_flag, transformed_entropy_input}.
- 16. Return ("Success", usage_class).

If an implementation does not handle all five security strengths, then step 5 must be modified accordingly.

If no personalization_string will ever be provided, then the personalization_string parameter in the input may be omitted, and step 10 becomes seed_material = entropy input.

If an implementation will never be reseeded using the process specified in Section 10.1.4.3.3, then step 9 may be omitted, as well as the *transformed_entropy_input* in the *state* (see step 18).

If an implementation does not need the *prediction_resistance_flag* as a calling parameter (i.e., the **HMAC_DRBG** (....) routine in Section 10.1.2.3.4 either always or never acquires new entropy in step 7), then the *prediction_resistance_flag* in the calling parameters and in the *state* (see step 18) may be omitted, as well as omitting step 2.

10.1.4.3.4 Reseeding a HMAC_DRBG(...) Instantiation

The following or an equivalent process shall be used to explicitly reseed the **HMAC_DRBG** (...) process. Let **HMAC** (...) be the Approved keyed hash function that is based on an Approved hash function, and let **Hash** (...) be that hash function. Let *outlen* be the output length of the hash function in bits, and let N be the output length of the hash function in bytes.

Reseed_HMAC_DRBG_Instantiation (...):

Input: integer (usage class, mode).

Output: string status.

Process:

1. If ((usage_class > max_no_of_states) or (state (usage_class)) = {Null, Null, 0, 0, 0, Null}), then **Return** ("State not available for the indicated usage class").

Comment: Get the appropriate *state* values for the indicated *usage class*.

2. V = state(usage_class).V, K = state(usage_class).K, strength = state(usage_class).strength, prediction_resistance_flag = state(usage_class).prediction_resistance_flag, old_transformed_entropy_input = state(usage_class).transformed_entropy_input.

Comment: Get the new *entropy_input*.

- 3. $min_entropy = max (128, strength)$.
- 4. (status, entropy input) = $Get_{entropy}$ (min_entropy, outlen, 2^{32} , mode).
- 5. If (*status* = "Failure"), then **Return** ("Failure indication returned by the *entropy_input* source").

Comment: Compare the old entropy_input with the new entropy_input.

- 6. transformed entropy input = **Hash** (entropy input).
- 7. If (transformed_entropy_input = old_transformed_entropy_input), then Return ("Entropy_input source failure").
- 8. ctr = 0.
- 9. $(K, V) = Update (seed_material, K, V)$.
- 10. state(usage_class) = {V, K₀, K₁, strength, ctr, prediction_resistance_flag, transformed_entropy_input}.
- 11. Return ("Success").

10.1.4.3.5 Generating Pseudorandom Bits Using HMAC_DRBG(...)

The following process or an equivalent **shall** be used to generate pseudorandom bits. Let *outlen* be the output length of the hash function in bits, and let *N* be the output length of the hash function in bytes.

HMAC_DRBG(...):

Input: integer (usage_class, requested_no_of_bits, requested_strength, additional input, prediction resistance requested, mode).

Output: string (status, pseudorandom bits).

Process:

If ((usage_class > max_no_of_states) or (state (usage_class)) = {Null, Null, 0, 0, 0, Null}), then Return ("State not available for the indicated usage_class", Null).

Comment: Get the appropriate state values for the indicated usage class.

2. V = state(usage_class).V, K = state(usage_class).K, strength = state(usage_class).strength, ctr = state(usage_class).ctr, prediction_resistance_flag = state(usage_class).prediction_resistance_flag, old_transformed_entropy_bits = state(usage_class).transformed_entropy_bits.

Comment: If $ctr \ge max_updates$, then reseeding could not be done in step 14 (below) during the previous call because of no available entropy source.

- 3. If (ctr ≥ max_updates), then **Return** ("HMAC_DRBG can no longer be used. Please re-instantiate or reseed.", Null).
- 4. If (requested_strength > strength), then **Return** ("Invalid requested strength", Null).
- If (requested_no_of_bits > 2³⁵), then Return ("Too many bits requested", Null).
- 6. If ((prediction_resistance_requested = Provide_prediction_resistance) and (prediction_resistance_flag = No_prediction_resistance)), then **Return** ("Prediction resistance capability not instantiated", Null).
- 7. If (prediction resistance requested = Provide prediction resistance), then
 - 7.1 $min\ entropy = max\ (128, strength)$.
 - 7.2 (status, entropy_bits) = $Get_entropy$ (min_entropy, outlen, 2^{32} , mode).
 - 7.3 If (*status* = "Failure"), then **Return** ("Failure indication returned by the *entropy_input* source", Null).
 - 7.4 transformed entropy input = **Hash** (entropy input).

```
7.5 If (transformed_entropy_input = old_transformed_entropy_input), then Return ("Entropy input source failure", Null).
```

```
7.6 ctr = 0.
```

Else

- 7.7 *entropy input* = Null.
- 8. seed material = entropy input || additional input.
- 9. If (seed material \neq Null), then (K, V) =Update (seed material, K, V).
- 10. temp = Null.
- 11. While (len (temp) < requested_no_of_bits) do:

11.1
$$V = HMAC(K, V)$$
.

- 11.2 $temp = temp \parallel V$.
- 12. pseudorandom bits = Leftmost (requested no of bits) of temp.
- 13. If (seed_material \neq Null), then (K, V) = Update (seed_material, K, V) Else

```
13.1 K = HMAC(K, V || 0x00).
```

13.2
$$V = HMAC(K, V)$$
.

- 14. If $(ctr \ge max \ updates)$, then
 - 14.1 status = Reseed HMAC DRBG (usage class, mode).
 - 14.2 If (status ≠ "Success"), then Return (status, Null).
 - 14.3 Go to step 16.
- 15. state(usage_class) = {V, K, strength, ctr, prediction_resistance_flag, transformed entropy bits).
- 16. Return ("Success", pseudorandom bits).

If an implementation will never provide *additional_input*, then the *additional_input* input parameter may be omitted, and step 8 becomes seed material = entropy input.

If an implementation does not need the *prediction_resistance_flag*, then the *prediction_resistance_flag* may be omitted as an input parameter, and step 6 may be omitted. If prediction resistance is never used, then step 7 becomes *entropy input* = Null.

If an implementation does not have a reseeding capability, then step 14 is omitted, and step 3 takes effect during the next call to the DRBG.

10.1.3.3.6 Removing a KHF_DRBG (...) Instantiation

The following or an equivalent process shall be used to remove a HMAC_DRBG (...) instantiation:

Uninstantiate HMAC DRBG (...):

Input: integer usage_class.

Output: string status.

Process:

- 1. If (usage_class > max_no_of_states), then **Return** ("Invalid usage_class").
- 2. $state(usage_class) = \{Null, Null, 0, 0, 0, Null\}.$
- 3. Return ("Success").

10.1.3.3.7 Self Testing of the HMAC_DRBG (...)

[To be added later]

10.1.3.4 Generator Strength and Attributes

10.1.3.5 Reseeding and Optional Input

Comment [ebb1]: Do we even need these sections any more?