ESC/Java2 Warnings

David Cok, Joe Kiniry, and Erik Poll

Eastman Kodak Company, University College Dublin, and Radboud University Nijmegen

- warnings about possible runtime exceptions: (Cast, Null, NegSize, IndexTooBig, IndexNegative, ZeroDiv, ArrayStore)
 - These are the most common runtime exceptions caused by coding problems (that is, not by explicitly throwing an exception)
 - They do not include nearly all of the possible runtime exceptions
 - Most of the others are explicitly thrown by various library methods

Cast Warning

The Cast warning occurs when ESC/Java2 cannot verify that a ClassCastException will not be thrown:

```
public class CastWarning {
  public void m(Object o) {
    String s = (String)o;
  }
}
```

results in

```
CastWarning.java:3: Warning: Possible type cast error (Cast)
    String s = (String)o;
    ^
```

But this is OK:

```
public class CastWarningOK {
   public void m(Object o) {
     if (o instanceof String) { String s = (String)o; }
   }
}
```

Cast Warning

So is this:

```
public class CastWarningOK2 {
    //@ requires o instanceof String;
   public void m(Object o) {
       String s = (String)o;
    }
}
```

Null Warning

The Null warning occurs when ESC/Java2 cannot verify that a NullPointerException will not be thrown:

```
public class NullWarning {
  public void m(Object o) {
   int i = o.hashCode();
  }
}
```

results in

```
NullWarning.java:3: Warning: Possible null dereference (Null)
  int i = o.hashCode();
  ^
```

But this is OK:

```
public class NullWarningOK {
   public void m(/*@ non_null */ Object o) {
    int i = o.hashCode();
   }
}
```

ArrayStore Warning

The ArrayStore warning occurs when ESC/Java2 cannot verify that the assignment of an object to an array element will not result in an ArrayStoreException:

```
public class ArrayStoreWarning {
  public void m(Object o) {
    Object[] s = new String[10];
    s[0] = o;
results in
ArrayStoreWarning.java:4: Warning: Type of right-hand side possibly not
a subtype of array element type (ArrayStore)
    s[0] = o;
But this is OK:
public class ArrayStoreWarningOK {
  public void m(Object o) {
    Object[] s = new String[10];
    if (o instanceof String) s[0] = o;
```

ZeroDiv, index Warnings

- ZeroDiv issued when a denominator (integer division) may be 0
- NegSize issued when the array size in an array allocation expression may be negative
- IndexNegative issued when an array index may be negative
- IndexTooBig issued when an array index may be greater than or equal to the array length

```
public class Index {
  void m() {
    int i = 0;
    int j = 8/i; // Causes a ZeroDiv warning
    Object[] oo = new Object[i-1]; // NegSize warning
    oo = new Object[10];
    i = oo[-1].hashCode(); // IndexNegative warning
    i = oo[20].hashCode(); // IndexTooBig warning
  }
}
```

- warnings about possible runtime exceptions: (Cast, Null, NegSize, IndexTooBig, IndexNegative, ZeroDiv, ArrayStore)
- warnings about possible method specification violations: (Precondition, Postcondition, Modifies)
 - These are all caused by violations of explicit user-written method specifications

Pre, Post warnings

These warnings occur in response to user-written preconditions (requires), postconditions (ensures, signals), or assert statements.

```
public class PrePost {
  //@ requires i >= 0;
  //@ ensures \result == i;
  public int m(int i);
  //@ ensures \result > 0;
  public int mm() {
    int j = m(-1); // Pre warning - argument must be >= 0
  //@ ensures \result > 0;
  public int mmm() {
    int j = m(0);
    return j;
  } // Post warning - result is 0 and should be > 0
```

Frame conditions

- To reason (modularly) about a call of a method, one must know what that method might modify: this is specified by
 - assignable clauses

```
//@ assignable x, o.x, this.*, o.*, a[*], a[3], a[4..5];
```

- modifies clauses (a synonym)
- pure modifier

```
//@ pure
public int getX() { return x; }
```

- Assignable clauses state what fields may be assigned within a method - this is the set of what might be modified
- The default assignable clause is assignable \everything; (but it is better to be explicit because \everything; is not fully implemented and ESC/Java2 can reason better with more explicit frame conditions)
- A pure method is assignable \nothing;

Frame conditions

- A Modifies warning indicates an attempt to assign to an object field that is not in a modifies clause
- Note: Some violations of modifies clauses can be detected at typecheck time.
- Note also: Handling of frame conditions is an active area of research.

Modifies warnings

For example, in

```
public class ModifiesWarning {
  int i;

  //@ assignable i;
  void m(/*@ non_null */ ModifiesWarning o) {
   i = 1;
   o.i = 2; // Modifies warning
  }
}
```

we don't know if o equals this; since only this.i may be assigned, ESC/Java2 produces

- warnings about possible runtime exceptions: (Cast, Null, NegSize, IndexTooBig, IndexNegative, ZeroDiv, ArrayStore)
- warnings about possible specification violations: (Precondition, Postcondition, Modifies)
- non null violations (NonNull, NonNullInit)
 - These warnings relate to explicit non_null field or parameter specifications

NonNullInit warning

Class fields declared non_null must be initialized to values that are not null in each constructor, else a NonNullInit warning is produced.

```
public class NonNullInit {
    /*@ non_null */ Object o;

   public NonNullInit() { }
}
```

produces

NonNull warning

A NonNull warning is produced whenever an assignment is made to a field or variable that has been declared non_null but ESC/Java2 cannot determine that the right-hand-side value is not null.

```
public class NonNull {
   /*@ non_null */ Object o;

public void m(Object oo) { o = oo; } // NonNull warning
}
```

produces

NonNull warning

But this is OK

```
public class NonNull {
   /*@ non_null */ Object o;
   public void m(/*@ non_null */ Object oo) { o = oo; }
}
```

So is this

```
public class NonNull {
   /*@ non_null */ Object o;
   public void m(Object oo) {
     if (oo != null) o = oo;
   }
}
```

So is this

```
public class NonNull {
   /*@ non_null */ Object o;
   public void m() {
      o = new Object();
   }
}
```

non_null can be applied to

- a field
- a formal parameter
- a return value
- a local variable
- ghost and model variables

- warnings about possible runtime exceptions: (Cast, Null, NegSize, IndexTooBig, IndexNegative, ZeroDiv, ArrayStore)
- warnings about possible method specification violations: (Precondition, Postcondition, Modifies)
- non null violations (NonNull, NonNullInit)
- loop and flow specifications (Assert, Reachable, LoopInv, DecreasesBound)
 - These are caused by violations of specifications in a routine body

Body assertions

- Assert: warning occurs when an assert annotation may not be satisfied
- Reachable: not in JML, only in ESC/Java2; occurs with the //@ unreachable; annotation, which is equivalent to //@ assert false;

Example:

```
public class AssertWarning {
  //@ requires i >= 0;
  public void m(int i) {
    //@ assert i >= 0; // OK
    --i;
    //@ assert i >= 0; // FAILS
  public void n(int i) {
    switch (i) {
      case 0,1,2: break;
      default: //@ unreachable; // FAILS
```

Loop assertions

- A loop_invariant assertion just before a loop asserts a predicate that is true prior to each iteration and at the termination of the loop (or a Looplnv warning is issued).
- A decreases assertion just before a loop asserts a (int) quantity that is non-negative and decreases with each iteration (or a DecreasesBound warning is issued).
- Caution: Loops are checked by unrolling a few times.

Example:

- warnings about possible runtime exceptions: (Cast, Null, NegSize, IndexTooBig, IndexNegative, ZeroDiv, ArrayStore)
- warnings about possible method specification violations: (Precondition, Postcondition, Modifies)
- non null violations (NonNull, NonNullInit)
- loop and flow specifications (Assert, Reachable, LoopInv, DecreasesBound)
- warnings about possible class specification violations: (Invariant, Constraint, Initially)

class invariant warnings

Invariant and constraint clauses generate additional postconditions for every method. If they do not hold, appropriate warnings are generated:

```
public class Invariant {
  public int i,j;
  //@ invariant i > 0;
  //@ constraint j > \old(j);

public void m() {
  i = -1; // will provoke an Invariant error
  j = j-1; // will provoke a Constraint error
}
```

Initially warning

An initially clause is a postcondition for every constructor:


```
public class Initially {
  public int i; //@ initially i == 1;
  public Initially() { } // does not set i - Initially warning
}
```

produces

- warnings about possible runtime exceptions: (Cast, Null, NegSize, IndexTooBig, IndexNegative, ZeroDiv, ArrayStore)
- warnings about possible method specification violations: (Precondition, Postcondition, Modifies)
- non null violations (NonNull, NonNullInit)
- loop and flow specifications (Assert, Reachable, LoopInv, DecreasesBound)
- warnings about possible class specification violations: (Invariant, Constraint, Initially)
- exception problems (Exception)
 - These warnings are caused by undeclared exceptions

Exceptions - Errors

- Java Errors (e.g. OutOfMemoryError) can be thrown at any time
 - No declarations are needed in throws clauses
 - No semantics are implied by JML
 - No checking is performed by ESC/Java2



Checked Exceptions

- Java checked exceptions (e.g. FileNotFoundException) are Exceptions that are not RuntimeExceptions:
 - Declarations of exceptions mentioned in the body are required in throws clauses
 - ESC/Java2 checks during typechecking that throws declarations are correct (as a Java compiler does)
 - Typically specified in signals clauses in JML
 - ESC/Java2 checks via reasoning that signals conditions hold
 - Default specification is that declared exceptions may occur: signals (Exception) true;
 - ESC/Java2 presumes that checked exceptions not declared in a throws clause will not occur.

Unchecked Exceptions

- Java unchecked exceptions (e.g. NoSuchElementException) are RuntimeExceptions:
 - Java does not require these to be declared in throws clauses
 - ESC/Java2 is stricter than Java it will issue an Exception warning if an unchecked exception might be explicitly thrown but is not declared in a throws declaration
 - Caution: currently ESC/Java2 will assume that an undeclared unchecked exception will not be thrown, even if it is specified in a signals clause -

Declare all unchecked exceptions that might be thrown!

(e.g. especially when there is no implementation to check).

Exception warning

```
public class Ex {
  public void m(Object o) {
    if (!(o instanceof String)) throw new ClassCastException();
  }
}
```

produces

```
Ex.java:4: Warning: Possible unexpected exception (Exception)
}
^
Execution trace information:
    Executed then branch in "Ex.java", line 3, col 32.
    Executed throw in "Ex.java", line 3, col 32.
```

Turn off this warning by

- declaring the exception in a throws clause
- using //@ nowarn Exception; on the offending line
- using a -nowarn Exception command-line option

- warnings about possible runtime exceptions: (Cast, Null, NegSize, IndexTooBig, IndexNegative, ZeroDiv, ArrayStore)
- warnings about possible method specification violations: (Precondition, Postcondition, Modifies)
- non null violations (NonNull, NonNullInit)
- loop and flow specifications (Assert, Reachable, LoopInv, DecreasesBound)
- warnings about possible class specification violations: (Invariant, Constraint, Initially)
- exception problems (Exception)
- multithreading (Race, RaceAllNull, Deadlock)
 - These warnings are caused by potential problems with monitors
 - Multithreading problems caused by the absence of any synchronization are not detected.

Race conditions

- Java defines monitors associated with any object and allows critical sections to be guarded by synchronization statements.
- ESC/Java permits fields to be declared as monitored by one or more objects.
- To read a monitored field, at least one monitor must be held (or a Race warning is issued).
- To write a monitored field, all non-null monitors must be held (or a Race warning is issued).
- To write a monitored field, at least one of its monitors must be non-null (or a RaceAllNull warning is issued).

Race warnings

For example,

```
public class RaceWarning {
    //@ monitored
    int i;

    void m() {
        i = 0; // should have a synchronization guard
    }
}
```

produces

```
RaceWarning.java:6: Warning: Possible race condition (Race)
   i = 0; // should have a synchronization guard
   ^
Associated declaration is "RaceWarning.java", line 2, col 6:
   //@ monitored
   ^
```

Deadlocks

- Deadlocks occur when each thread of a group of threads needs monitors held by another thread in the group.
- One way to avoid this is to always acquire monitors in a specific order.
- This requires
 - the user state a (partial) order for monitors (typically using an axiom)
 - that it be clear before acquiring a monitor that the thread does not hold any 'larger' monitors (typically a precondition)
- Checking for Deadlock warnings is off by default but can be turned on with -warn Deadlock.

Deadlock warnings

For example:

```
public class DeadlockWarning {
  /*@ non_null */ final static Object o = new Object();
  /*@ non_null */ final static Object oo = new Object();
  //@ axiom o < oo;
  //@ requires \max(\lockset) < o;</pre>
  public void m() {
      synchronized(o) { synchronized(oo) { }}
  //@ requires \max(\lockset) < o;</pre>
  public void mm() {
      synchronized(oo) { synchronized(o)
                                                  Deadlock warning
```

- warnings about possible runtime exceptions: (Cast, Null, NegSize, IndexTooBig, IndexNegative, ZeroDiv, ArrayStore)
- warnings about possible method specification violations: (Precondition, Postcondition, Modifies)
- non null violations (NonNull, NonNullInit)
- loop and flow specifications (Assert, Reachable, LoopInv, DecreasesBound)
- warnings about possible class specification violations: (Invariant, Constraint, Initially)
- exception problems (Exception)
- multithreading (Race, RaceAllNull, Deadlock)
- a few others (OwnerNull, Uninit, Unreadable, Writable)

Other warnings

- Uninit: used with the uninitialized annotation
- OwnerNull: see the ESC/Java User Manual for a description
- Unreadable: occurs with the readable_if annotation on shared variables. [JML's change of syntax from readable_if to readable is not complete in ESC/Java2.]
- Writable: occurs with the writable_if annotation on shared variables. [JML's change of syntax from writable_if to writable is not complete in ESC/Java2.]

trace information

For complicated bodies, the warning messages give some information about which if-then-else branches caused the warning:

```
public class Trace {
  //@ ensures \result > 0;
  int m(int i) {
    if (i == 0) return 1;
    if (i == 2) return 0;
    return 4;
produces
Trace.java:8: Warning: Postcondition possibly not established (Post)
Associated declaration is "Trace.java", line 2, col 6:
  //@ ensures \result > 0;
Execution trace information:
    Executed else branch in "Trace.java", line 4, col 4.
    Executed then branch in "Trace.java", line 5, col 16.
    Executed return in "Trace.java", line 5, col 16, Joe Kiniry & Erik Poll - ESC/Java2 & JML Tutorial - p.35/?
```

Counterexamples

- Sometimes when a specification is found to be invalid, ESC/Java2 will produce a counterexample context.
- A full context will be produced with the -counterexample option
- These are difficult to read, but can give information about the reason for failure.
- They state formulae that the prover believes to be true; if there is something you think should not be true, that is a hint about the problem.
- Note also: Typically only one warning will be issued in a given run.