Chapter 8: Memory Management

Prof. Li-Pin Chang
National Chiao Tung University

Chapter 8: Memory Management


- Memory hierarchy and caching
- Address Binding
- Contiguous Memory Allocation
- Paging
- Structure of the Page Table
- Swapping
- Segmentation
- Example: The Intel Pentium

Memory Hierarchy

Memory Hierarchy

- Main memory the only large storage media that the CPU can access directly
 - RAM (random access)
- Secondary storage extension of main memory that provides large nonvolatile storage capacity
 - No random access, Magnetic disks rigid metal or glass platters covered with magnetic recording material
 - Disk surface is logically divided into tracks, which are subdivided into sectors
 - The disk controller determines the logical interaction between the device and the computer

Storage Structure (Memory hierarchy)



Storage Structure (Memory hierarchy)

- Storage systems organized in hierarchy
 - Speed
 - Cost
 - Volatility
- Caching copying information into faster storage system; main memory can be viewed as a last cache for secondary storage

Caching


- Important principle, performed at many levels in a computer (in hardware, operating system, software)
- Information in use copied from slower to faster storage temporarily
- Faster storage (cache) checked first to determine if information is there
 - If it is, information used directly from the cache (fast)
 - If not, data copied to cache and used there
- Cache smaller than storage being cached
 - Cache management important design problem
 - Cache size and replacement policy
- What we need?
 - An efficient lookup service
 - A replacement policy that minimizes cache misses

Performance of Various Levels of Storage

Moving data among storage levels can be explicit or implicit

Level	1	2	3	4
Name	registers	cache	main memory	disk storage
Typical size	< 1 KB	> 16 MB	> 16 GB	> 100 GB
Implementation technology	custom memory with multiple ports, CMOS	on-chip or off-chip CMOS SRAM	CMOS DRAM	magnetic disk
Access time (ns)	0.25 - 0.5	0.5 – 25	80 – 250	5,000.000
Bandwidth (MB/sec)	20,000 - 100,000	5000 - 10,000	1000 – 5000	20 – 150
Managed by compiler		hardware	operating system	operating system
Backed by	cache	main memory	disk	CD or tape

Migration of Integer A from Disk to Register




Address Binding

Address Binding

- Assigning memory addresses to instructions and data
- Program must be brought into memory and placed within a process for it to be run
- Input queue collection of processes on the disk that are waiting to be brought into memory to run the program
- User programs go through several steps before running

Binding of Instructions and Data to Memory

- Address binding of instructions and data to memory addresses can happen at three different stages
 - Compile time
 - Load time
 - Execution time



Binding of Instructions and Data to Memory

• Compile time: If memory location known a priori, absolute code can be generated; must recompile code if the starting location changes


Binding of Instructions and Data to Memory

• Execution time: Binding delayed until run time if the process can be moved during its execution from one memory segment to another.

Execution Time Binding

- The concept of a logical address space that is bound to a separate physical address space is central to proper memory management
 - Logical address generated by the CPU; also referred to as virtual address
 - Physical address address seen by the memory unit
- The user program deals with logical addresses; it never sees the real physical addresses
- Need hardware support to translate logical addresses into physical addresses during runtime
 - Relocation registers (base/limit)


Execution Time Binding/Relocating using a Relocation Register



Memory-Management Unit (MMU)

• A hardware component in the CPU that translates logical addresses into physical addresses

- Paging
 - Address mapping
 - Virtual memory
- Segmentation
 - Memory protection
- To be explained later



Project Denver 64-bit CPU core

CONTIGOUS MEMORY ALLOCATION


Process B Process C Process A OS


- Process are allocated to contiguous memory space
- •Processes can be loaded into any contiguous and sufficiently large memory space
- •As processes arrive and leave, free space may be fragmented into many pieces

Contiguous Allocation

- Main memory usually into two partitions:
 - Resident operating system, usually held in low memory with interrupt vector
 - User processes then held in high memory
- Single-partition allocation
 - Relocation-register scheme used to protect user processes from each other, and from changing operating-system code and data
 - Relocation register contains value of smallest physical address; limit register contains range of logical addresses – each logical address must be less than the limit register

Memory Mapping and Protection






Memory Allocation

How to satisfy a request of size *n* from a list of free holes

- First-fit: Allocate the first hole that is big enough
- Best-fit: Allocate the smallest hole that is big enough; must search entire list, unless ordered by size. Produces the smallest leftover hole.
- Worst-fit: Allocate the *largest* hole; must also search entire list. Produces the largest leftover hole.

First-fit and best-fit better than worst-fit in terms of speed and storage utilization



A20		20	108						
A15		20	15	93					
A10		20	15	10	10 83				
A25		20	15	10	25	25 58			
D20		20	15	10	25	25 58			
D10		20 15		10	25	58			
A 8	8	12	15	10	25	58			
A30	8	12	15	10	25	30	28		
D15	8		37		25	30	28		
A15	8	15	5 22		25	30	28		

First fit


D10	20	15	10		25	58			
A8	20	15	8	2	25	58			
A8 A30	20	15	8	2	25	30 28		3	
D15	35	8	2	25	30 28		3		
A15	35	8	2	25	30	15	13		

Best fit

D10	20	15	10	25	58			
A8	20	20 15 10		25	8	50		
A30	20	15	10	25	8	30	20	
D15	45			25	8	30	20	
A15	15	15 30			8	30	20	

Worst fit

Buddy System



Fragmentation

- External Fragmentation total memory space exists to satisfy a request, but it is not contiguous
- Internal Fragmentation allocated memory may be slightly larger than requested memory; this size difference is memory internal to a partition, but not being used

Comparison




Figure 8: Total fragmentation values of techniques




Figure 9: Allocation duration of techniques (micro second)

Karabiber, Fethullah & Sertbaş, Ahmet & Zaim, A.. (2005). Dynamic memory allocator algorithms simulation and performance analysis. 5. 1435-1441.


Slab Allocation

- The root cause of external fragmentation is that allocation sizes are not uniform
- Idea: allocate objects of the same size from the same memory pool
- Solution: slab allocation

Linux Kernel Memory Allocation

- Kernel objects (of different sizes) are small, frequently allocated/deallocated
 - E.g., inode, dentry, page structure, etc
- Fragmentation is a crucial problem

Linux kernel slab cache



Benefits:

- No fragmentation
- Quick memory allocation
- Objects get physically contiguous memory

[cache[obj][obj][obj]]
[page][page] [page]

Case Study

- malloc() of glibc 2.28
 - A variation of Best Fit
- Linux kernel provide slab allocator and buddy system
 - Frequent allocation/deallocation of objects of the same size, use slab cache
 - Allocation/deallocation of objects of various sizes, use buddy system

PAGING


External Fragmentation

- Compaction
 - Migrate allocated memory chunks together to make free space contiguous
 - Will relocate programs—need execution time binding
 - Occasionally slows down the system
- A better approach: What if memory can be logically continuous but not physically continuous?


Paging

- Divide physical memory into fixed-sized blocks called frames (size is power of 2, between 512 bytes and 8192 bytes)
- Divide logical memory into blocks of same size called pages.
- Keep track of all free frames
- To run a program of size n pages, need to find n free frames and load program
- Set up a page table to translate logical to physical addresses


Paging Model of logical and physical memory



Paging hardware




Paging Example



Q: how many bits are required to represent

- 1. The page number
- 2. The frame number
- 3. The displacement
- 4. A logical address
- 5. A physical address
- 6. A page-table entry?

Free Frames




After allocation

Implementation of Page Table


- Page table is kept in main memory
- A table per process
 - Page-table base register (PTBR) points to the page table
 - Page-table length register (PRLR) indicates size of the page table
- In this scheme every data/instruction access requires two memory accesses. One for the page table and one for the data/instruction.
- The two memory access problem can be solved by the use of a special fast-lookup hardware cache called associative memory or translation look-aside buffers (TLBs)

Paging Hardware With TLB



TLB hit ratio vs. Locality of Reference

- TLB is small, usually holds 64~1024 entries
 - A replacement policy should be used.
 - E.g., random policy or LRU
 - Page references have temporal localities and spatial localities
- Important entries can be wired down (nailed)
 - E.g., kernel code



Effective Access Time

- Associative Lookup = ε time unit
- Assume memory cycle time is 1 microsecond
- Hit ratio percentage of times that a page number is found in the associative registers; ratio related to number of associative registers
- Hit ratio = α
- Effective Access Time (EAT)

$$EAT = (1 + \varepsilon) \alpha + (2 + \varepsilon)(1 - \alpha)$$
$$= 2 + \varepsilon - \alpha$$

The overhead of updating page table is ignored

Let the TLB hit ratio be 98%

20ns to lookup the TLB 100 ns to access memory

TLB hit: 20+100

TLB miss: 20 + 100 (page table) + 100 (target address)

EAT= 0.98*120+0.02*220=122 ns

The overhead of updating page table is ignored here

STRUCTURE OF THE PAGE TABLE

Structure of Page Table

- Hierarchical Paging
- Hashed Page Tables
- Inverted Page Tables

Hierarchical Page Tables

- A per-process page table could be very large and sparse
- Allocating Large and contiguous page tables for processes is inconvenient and may under-utilize memory space (of page tables)
- Breaking up the logical address space into multiple page tables
 - Page table can be divided into pieces
 - Page table pieces are allocated on demand
- A simple technique is a two-level page table
 - Example: Intel 80386

Two-Level Paging Example


- A logical address (on 32-bit machine with 4K page size) is divided into:
 - a page number consisting of 20 bits
 - a page offset consisting of 12 bits
- Since the page table is paged, the page number is further divided into:
 - a 10-bit outer-page number
 - a 10-bit displacement of the outer page
- Thus, a logical address is as follows:

page number			page offset
	p_{i}	p_2	d
	10	10	12

where pi is an index into the outer page table, and p2 is the displacement within the page of the outer page table


Two-Level Page-Table Scheme

[p1][p2][d]



Address-Translation Scheme


 Address-translation scheme for a two-level 32-bit paging architecture



Pros: page tables need not to be contiguous, and need not all present in memory Cons: multiple memory accesses on TLB miss. 7-level paging in UltraSparc 64

Think about it...


• Logical address or physical address?



Hashed Page Tables

- Replace the radix-based multi-level table with a hash table
- Common in address spaces > 32 bits
 - The logical address footprint of a process << the logical address space
- The page number is hashed into a page table. This page table contains a chain of elements hashing to the same location
- Page numbers are compared in this chain searching for a match. If a match is found, the corresponding physical frame is extracted
- Example: 64-bit PowerPC CPUs

Hashed Page Table



How many extra memory references are needed on TLB miss is related to the quality of the hash function


Inverted Page Table

- Consider that there can be up to 16K processes, and the logical addressing space of each process can be of 220 pages. If each entry is of 4B, the total size of page tables is: very large
- The size of an inverted page table is bounded by the size of physical memory and is irrelevant to # of processes

Inverted Page Table


- One entry for each real page (frame) of memory
 - Entry index number is the frame number
- Each table entry stores a page number and the process ID owns that owns the page
- One global page table shared among all processes
- On memory reference, find the table entry that stores the current process ID and the referenced page number
 - Use hash table to limit the search to one or at most a few — page-table entries
- Example: PowerPC 603

Inverted Page Table Architecture



Think about it...

• Why pid is necessary in inverted page tables?



Design Considerations of Paging

- Increased memory references
 - Solution: Use TLB
- Space requirement of the page table (in main memory)
- Multilevel page tables
 - Break the entire table into small pieces, allocate on demand
- Hash page tables
 - Small hash table with overflow handling (linked lists)
- Inverted page tables
 - Table size is bounded by the physical memory size and is independent of the total number of active processes


SEGMENTATION

Segmentation


- Memory-management scheme that supports user view of memory
- A program is a collection of segments. A segment is a logical unit such as:

```
main program,
procedure,
function,
method,
object,
local variables, global variables,
common block,
stack,
symbol table, arrays
```

User's View of a Program



Logical View of Segmentation




User programs do not know where in physical memory a segment is placed.


Hardware

- Logical address consists of a two tuple:
 <segment-number, offset>,
- Segment table maps two-dimensional physical addresses; each table entry has:
 - base contains the starting physical address where the segments reside in memory
 - limit specifies the length of the segment
- Segment-table base register (STBR) points to the segment table's location in memory
- Segment-table length register (STLR) indicates number of segments used by a program;
 - segment number s is legal if s < STLR

Segmentation hardware



Example of Segmentation



Segment Protection

- Segments storing execution code normally do not allow modification
 - Allow read, execute but not write
 - Avoid self-modifying malicious code, such as polymorphic viruses
- Stack segments normally do not allow execution
 - Allow read, write but not execute
 - Avoid malicious code injection

Stack Overrun Attack




Figure 1. Ruffer averrun evalait

What is the result of executing the program below?

```
#include<stdio.h>
#include<stdlib.h>

int main()
{
      char *p = "hello world";
      p[0] = 'H';
}
```

Hardware Support for Segmentation

- Provided by MMU
- Segment Limit
 - Segment base register
 - Segment limit register
- Segment Protection
 - With each entry in segment table associate:
 - Permissions of read, write, and/or execute
 - Access privileges of user mode or kernel mode


Comparison

- Paging solves the external *fragmentation* problem at the process level
- Segmentation provides memory protection according to the purposes (r,w,x) of memory regions
- Segmented paging (more common)
- Paged segmentation

EXAMPLE: THE INTEL 80386+


Segmented Paging

- Intel 80386
 - Segmentation
 - 2-level paging




Logical Address to Linear Address

- Logical address format
 - [Selector:16]:[offset:32]
 - Selector format is [s:13][g:1][p:2]



Linear Address to Physical Address

- Once logical address is translated into linear address, it is handled by paging
- Linear address format
 - [p1:10][p2:10][d:12]



Linux on Intel 80386

- Uses minimal segmentation to keep memory management implementation more portable
- Uses 6 global segments: (80386 has many)

Shared by all processes:

- Kernel code
- Kernel data
- User code
- User data
- The default LDT (usually not used)

Per-core

- Task-state (TSS, used to switch from user mode to kernel mode)
- Uses 2 protection levels: (80386 has 4)
 - Kernel mode
 - User mode
- Use three-level paging (80386 has only 2)
 - The mid-level paging is disabled

End of Chapter 8