The Pi of Archimedes

R (Chandra) Chandrasekhar

2004-01-14 | 2024-06-30

This blog began life more than two decades ago, as part of a series of lectures I delivered to very bright first-year engineering students at an Australian university.

The number π (pronounced "pie") has been recognized from time immemorial because its physical significance can be grasped easily: it is the ratio of the circumference of a circle to its diameter. But who would have thought that such an innocent ratio would exercise such endless fascination because of the complexities enfolded into it?

Not surprisingly, some students I met recently wanted to know more about π . Accordingly, I have substantially recast and refreshed my original presentation to better accord with the form and substance of a blog. The online references have also been updated to keep up with a rapidly changing Web.

My original intention was to write a single blog on π . But because I did not want it to become another overly long *slog*, I have decided to divide it into two parts.

If there are any errors or omissions, please email me your feedback.

Circumference, diameter, and π

The straight line or geodesic is the shortest distance between any two points on a plane, sphere, or other space. The circle is the locus traversed by a moving point that is equidistant from another fixed point on a two-dimensional plane. It is the most symmetrical figure on the plane. The diameter is the name given both to any straight line passing through the centre of the circle—intersecting it at two points—as well as to its length. When we divide the perimeter of circle, more properly called its circumference, C, by its diameter, d, we get the enigmatic constant π , which has a value between 3.141 and 3.142:

$$\frac{C}{d} = \pi. (1)$$

The diameter d is twice the radius r, and substituting for d into Equation (1), we get the well-known school formula:

$$C = \pi d = 2\pi r \approx 2 \left[\frac{22}{7} \right] r \approx 6.28r. \tag{2}$$

Note, however, that π is *not exactly equal* to $\frac{22}{7}$. This value is a convenient *rational fraction approximation* for π that serves well in elementary contexts.¹

You might reasonably wonder whether the ratio of the circumference to the diameter of *any* circle is *always* π . The answer is "Yes", because *all circles are similar*. The ratios of corresponding lengths of similar figures are equal. This idea is also covered in my blog "A tale of two measures: degrees and radians".

¹See "A tale of two measures: degrees and radians".

The symbol π is the lowercase version of the sixteenth letter of the Greek alphabet. For the history of its use in mathematics, see adoption of the symbol π in Wikipedia.




Figure 1: The ratio of the circumference to the diameter of *any* circle is π .

Figure 1 shows the relationships in Equation (1) and Equation (2) pictorially. The circumference of a circle is about 6.28 times its radius. Why this should be so is a secret, a mystery of Nature.

Is $\pi = 22/7$ an exact value?

Is π really equal to $\frac{22}{7}$, as it has been drummed into our heads at school? A wonderfully revealing story lies behind this mysterious relationship, and it is due to the labours of one man, in the days when calculators could not be dreamed of, and when neither the decimal system of numbers nor trigonometry were known. That is the story we look at next.

Archimedes of Syracuse

Archimedes of Syracuse² (Ἡρχιμήδης, 287–212 BCE) was a polymath and genius of the ancient world. He was one of the greatest mathematicians the world has ever known. By today's standards, he would be called a mathematician, physicist, engineer, and astronomer, all rolled into one. He is perhaps most famous for running out of his bathtub naked exclaiming "Eureka"—Greek for "I have found it"—oblivious of those around him. The principle that he had then discovered—that the upthrust on a body submerged in a fluid is equal to the weight of fluid displaced—is known as Archimedes' Principle.

²His very name, Archimedes, means "master thinker" in Greek.




Figure 2: Archimedes of Syracuse.³

Among the many accomplishments of Archimedes is his method for estimating π , which was the best approximation for almost 1900 years. And it was not based on using a length of string, superimposing it on a circle, and getting an estimate! s

What is even more remarkable is that Archimedes made his discovery without the benefit of:

- (a) the real numbers;
- (b) algebra;
- (c) trigonometry;
- (d) decimal (positional) notation; and
- (e) calculators.

Instead he applied the theorem of Pythagoras and extracted rational values for square roots laboriously by hand. His method is also an excellent geometrical illustration of the idea of a *limit*, with which he was doubtless familiar. It is known that Archimedes was familiar with what we now know as integral calculus, and it is possible that he may have anticipated differential calculus as well.

Archimedes devised an ingenious method for estimating the circumference of a circle. He used a sophisticated algorithm that allowed him to obtain successively more accurate values for the circumference of a circle, and therefore of π .

³Domenico Fetti's 1620 painting entitled *Archimedes Thoughtful*. Public domain.




Figure 3: Portrait of Archimedes generated by AI and available at the Craiyon website here. All portraits of Archimedes are flights of fancy rather than true likenesses.

Principles used by Archimedes

The method that Archimedes devised is instructive because it is a synthesis of several principles by which the greatest human minds have furthered scientific progress over time. The abstract principles that Archimedes used to estimate π were these:

- 1. Start with the known and progress to the unknown;
- 2. Initialize variables;
- 3. Devise a method of increasing the accuracy of the estimate by recursion or iteration;
- 4. Stop when the desired accuracy is reached.

These principles constitute what is known as an algorithm. Once such a systematic framework has been put in place, it can be applied in many research domains to aid rapid scientific progress. The algorithm is the basis of modern computing.

Of polygons and circles

Archimedes considered a circle, containing an inscribed regular polygon with n sides, and circumscribed by a regular polygon with the same n sides. Figure 4 illustrates this for the case n = 6, i.e., with a regular hexagon.




Figure 4: The circumference of the circle in darkolivegreen is bounded from below by the perimeter of the inscribed regular hexagon in maroon and bounded from above by the perimeter of the circumscribed regular hexagon in midnightblue. The circumference of the circle must lie between the perimeters of these two hexagons. The value r is the radius of the circle and the height h—from the centre to the mid-point of a side—is called the apothem.

Let us tabulate below the variables arising from Figures 4 and 5.




Figure 5: The relationship between the circle and its inscribed and circumscribed regular polygons. The symbol h is used for the apothem in both cases. Note that $OD = h = r \cos \theta$ for the inscribed polygon, whereas OC = h = r for the circumscribed polygon.

Parameter	Circle	Inscribed	Circumscribed
Radius	r		
Sides		n	n
Length		$2r\sin\theta$	2r an heta
Angle		$\theta(n) = \frac{\pi}{n} = \frac{180^{\circ}}{n}$	$\theta(n) = \frac{\pi}{n} = \frac{180^{\circ}}{n}$
Apothem		$h = r\cos\theta$	h = r
Area	$A = \pi r^2$	a(n) =	$A(n) = n \tan \theta r^2$
		$n \sin \theta \cos \theta r^2$	
Perimeter	$C = 2\pi r$	$c(n) = 2n\sin\theta r$	$C(n) = 2n \tan \theta r$

Table 1: Circle, inscribed, and circumscribed regular polygons (*n*-gons).

When n varies, so do the values of θ and the areas and perimeters; they are therefore shown as functions of n in Table 1.

Lower and upper bounds for π

We assume that r=1 without loss of generality. Table 1 and Figure 5 together give us these inequalities for regular n-gons where $\theta=\frac{180}{n}$ degrees or $\theta=\frac{\pi}{n}$ radians.

$$a(n) < A < A(n) \implies n \sin \theta \cos \theta < \pi < n \tan \theta$$

$$c(n) < C < C(n) \implies n \sin \theta < \pi < n \tan \theta$$
(3)

From the right hand side of Equation (3), using the inequalities for perimeters, we have

$$n \sin \frac{180^{\circ}}{n} = n \sin \frac{\pi}{n}$$
, for the lower bound. (4)

$$n \tan \frac{180^{\circ}}{n} = n \tan \frac{\pi}{n}$$
, for the lower bound. (5)

Equations (4) and (5) represent respectively the lower and upper bounds on the value of π obtained through the method of Archimedes.

Obviously, the circle may be viewed as a regular polygon whose number of sides, n has become exceedingly large, or *infinite*. So, as n is increased, we should expect the two bounds to converge to the limiting value of π .

Table 2: The values of $n \sin \frac{\pi}{n}$ and $n \tan \frac{\pi}{n}$ as n increases. {#tbl:large-n-pi}

n	$n \sin \frac{\pi}{n}$	$n \tan \frac{\pi}{n}$
6	3.0000000000	3.4641016151
12	3.1058285412	3.2153903092
24	3.1326286133	3.1596599421
48	3.1393502030	3.1460862151
96	3.1410319509	3.1427145996
100	3.1410759078	3.1426266043

n	$n\sin\frac{\pi}{n}$	$n \tan \frac{\pi}{n}$
1000	3.1415874859	3.1416029891
10000	3.1415926019	3.1415927569
100000	3.1415926531	3.1415926546
1000000	3.1415926536	3.1415926536

The upper and lower bounds are equal up to ten decimal digits when $n=10^6$, and we might declare the problem of estimating pi solved. But in the time of Archimedes, trigonometry was not known; only geometry was. Moreover, the decimal system and calculators were also in the future. We now have to backtrack and attempt to retrace the steps Archimedes used to estimate π .

Trigonometry and half angles

But before we leave trigonometry altogether, let us explore how a recurrence relation may be established among successive estimates of c(n) and C(n) when n is doubled.

Once we have calculated, say, c(6), ideally we would like to calculate c(12) using the estimate of c(6). This process of chaining successive results is called recursion and is vital in developing efficient algorithms.

The trigonometry of half angles in terms of the full angle [1] helps relate the successive values of θ .

We now introduce a slight change in notation. Since our focus is on side doubling and angle halving, we introduce a subscript k to denote the number of doublings/halvings. We start with k=0 denoting no doubling, which is the base case, with $n=n_0=6$. After that, k doublings are denoted by 2^k .

$$k = 0$$

$$n = n_0$$

$$\theta_0 = \frac{\pi}{n_0}$$

$$n_k = 2^k n_0$$

$$\theta_k = \theta(n_k)$$

$$= \theta(2^k n_0)$$

$$= \frac{\pi}{2^k n_0}$$

$$= \frac{\theta_0}{2^k}.$$
(6)

The half-angle formulae are:

$$\sin\frac{\theta}{2^{k}} = \left[\frac{1 - \cos\left[\frac{\theta}{2^{k-1}}\right]}{2}\right]^{\frac{1}{2}}$$

$$\cos\frac{\theta}{2^{k}} = \left[\frac{1 + \cos\left[\frac{\theta}{2^{k-1}}\right]}{2}\right]^{\frac{1}{2}}$$

$$\tan\frac{\theta}{2^{k}} = \left[\frac{1 - \cos\left[\frac{\theta}{2^{k-1}}\right]}{1 + \cos\left[\frac{\theta}{2^{k-1}}\right]}\right]^{\frac{1}{2}}$$
(7)

Once we have the base case for the regular hexagon, we can relate successive angles and their sines via Equation (7) and descend that binary staircase, according to Equations (6) to (8):

$$n_k \sin \theta_k = 2^k n_0 \sin \frac{\theta_0}{2^k}$$

$$= 2^k n_0 \left[\frac{1 - \cos \left[\frac{\theta_0}{2^{k-1}} \right]}{2} \right]^{\frac{1}{2}}$$

$$n_k \tan \theta_k = 2^k n_0 \tan \frac{\theta_0}{2^k}$$

$$= \left[\frac{1 - \cos \left[\frac{\theta_0}{2^{k-1}} \right]}{1 + \cos \left[\frac{\theta_0}{2^{k-1}} \right]} \right]^{\frac{1}{2}}$$
(8)

The recurrence relation linking θ_k to θ_{k-1} has now been established.

This has been a digression because these techniques were not available to Archimedes in his day. I have added it for completeness, and to demonstrate the use of recurrence relations with the trigonometric approach [2].

We now return to the main theme of how Archimedes used geometry to relate current values to previous values.

The angle bisector theorem

Without using the half-angle formulae of trigonometry, how can we successively obtain expressions for the values of c(n) and C(n) as we halve the angles and double the sides each time? We have to rely on something called the **angle bisector theorem** from geometry. This was something Archimedes already knew.

This derivation might seem tedious, but it is closer to what Archimedes did in order to establish the recurrence relation that tied the current value to the previous value.




Figure 6: The angle bisector theorem. The relative lengths of the two segments that a triangle's side is divided into by a line that bisects the opposite angle equals the relative lengths of the other two sides of the triangle, as shown on the diagram.

Referring to Figure 6, if the line *OC* bisects the angle *BOA*, then the base *AB* is divided in the same ratio as the corresponding sides. This means

$$\frac{AO}{OB} = \frac{AC}{CB}$$
 which in turn means that
$$\frac{a}{b} = \frac{p}{q}$$
 (9)

Before we can apply this to the regular hexagons we need to become aware of what I call the thirty, sixty, ninety triangle, which is considered next.

The thirty, sixty, ninety right triangle

Archimedes applied the principle "of starting from the known" to initiate his algorithm using a *regular hexagon*, which is a mosaic of six juxtaposed equilateral triangles. We know from symmetry that each angle of an equilateral triangle is 60°. When an equilateral triangle is bisected, we get two right-angled triangles with angles of thirty and sixty degrees, as shown in Figure 7.

The inscribed hexagon, within a circle of radius one unit, also has a side of one unit. Thus, the hypotenuse of the circle OAP in Figure 7 has unit length. Moreover, the base OP, resulting from a bisected side, has a length of half a unit. By applying the theorem of Pythagoras, the third side, AP is

$$\sqrt{1^2 - \left(\frac{1}{2}\right)^2} = \frac{\sqrt{3}}{2}.\tag{10}$$




Figure 7: This right-angled, obtained by bisecting an equilateral triangle, must be familiar to all school students. These lengths—obtainable from symmetry and the theorem of Pythagoras—allowed Archimedes to start off his process for estimating π .

The next thing Archimedes needed and knew how to do was to compute $\sqrt{3}$ which figures in Equation (10). Finding square roots is a tedious process, not unlike long division, and prone to human error. The patience and doggedness of Archimedes that must have gone into the process is astounding.

Extracting square roots by hand

Archimedes must have known how to extract square roots by hand. Perhaps, he used one of the methods described in my blog "How Are Numbers Built?". He should have known the value of $\sqrt{3}$ as a rational fraction. With remarkable accuracy, he stated that:

$$\sqrt{3} \approx \frac{265}{153} \approx 1.732.$$
 (11)

Numerical results

WHERE TO PUT THIS?

Evaluating the bounds given in Table 1 and Equation (3) by setting r = 1, n = 6, and $\theta = \frac{180}{n} = 30^{\circ 4}$ gives us these values:

$$C_i = 2n \sin \theta r = 12(\sin 30^\circ) = 12(0.5)$$
 = 6.0000.
 $C = 2\pi r$ = 6.2381.
 $C_c = 2n \tan \theta r = 12(\tan 30^\circ) = 12\left(\frac{\sqrt{3}}{3}\right) = 4\sqrt{3} \approx 6.9282.$ (12)

Archimedes doubled n four times to compute values for regular polygons with 12, 24, 48, and 96 sides. For his last calculation with n = 96 and $\theta = \frac{180}{96}$ ° ≈ 1.875 °, we have:

$$C_i = 2n \sin \theta r = 2(96) \sin 1.875^{\circ} \approx 192(0.0327) \approx 6.2820.$$
 $C = 2\pi r = 6.2381.$
 $C_c = 2n \tan \theta r = 2(96) \tan 1.875^{\circ} \approx 192(0.0327) \approx 6.2854.$
(13)

Note that in the case of 96 sides, we have a *very small angle* θ whose sin and tan are almost equal. This is what gives us tight bounds on the estimate of π . If you know the power series for $\sin \theta$ and $\tan \theta$, you will appreciate even better how the value of π is trapped and squeezed between these two rather close limits.

Remember Equation (13) because it helps us to estimate lower and upper bounds for the value of the circumference. Archimedes's application of the squeeze theorem nineteen centuries before the calculus was invented is illustrated in the series of figures, Figures 8 to 12.

Sanity check: Does $2\pi = 6.2820$, from a calculator, lie within the bounds of Equation (13)? Yes, indeed, and we are home and dry.

Second sanity check: When n is very large, we expect $n\sin\frac{180^\circ}{n}$ to be closer and closer to the true value. Setting $n=10^6$ and evaluating on a calculator we get $10^6\sin\frac{180^\circ}{10^6}=3.14159$ which is reassuring. This deep connection between the circle and the trigonometric functions also explains why they are sometimes called the *circular functions*. Indeed, the values $n\sin\frac{\pi}{n}$ and $n\sin\tan\pi n$ both converge to π for very large n. The interested reader should plot these two curves.

WHERE SHOULD THIS GO?

Imagine the mathematical fortitude of Archimedes to plough on—without algebra or trigonometry or the decimal number system—to establish the value of π .

Before we consider numerical results, there are two aspects of the problem and the approach taken by Archimedes that I wish to discuss.

⁴Rather than use radians with π entering the proceedings, I decided to stick with degrees as units to avoid confusion. If one uses power series to probe further, of course, radians are called for.

Recursion and Iteration

Archimedes started with regular hexagons and successively *doubled* the number of sides, until he had the circle closely sandwiched between two 96-gons—one circumscribe; the other inscribed. Successively doubling or halving is a fast-converging technique used in numerical estimation, called the bisection method, that is applied to solving a variety of problems. That Archimedes was aware of it shows how far ahead of his time his thinking was.

When he moved from n=6 to n=12 sides, how did Archimedes estimate the respective perimeters without the aid of trigonometry? He used geometry and the Pythagorean theorem, as described here online [3] to obtain recurrence relations that gave the current result from the previous one.

For an English translation of the book *Measurement of a Circle* by Archimedes click on this link. It is the original source material from the man himself, and will give you a sense of completeness in your understanding of his method.

He repeatedly calculated rational approximations to π until he was satisfied with the accuracy. The principle of the method is clearly seen in Figures 8 to 12.




Figure 8: The estimate for π lies between $C_i = 3.0000 < \pi < C_c = 3.4641$.

Is π really 22/7?

The answer is a qualified "Yes and no". Because π is irrational, it cannot be expressed precisely in a finite number of digits. Consequently, we use rational approximations, or a decimal representation at the desired accuracy for π . Thanks to Archimedes, $\frac{22}{7}$ is a serviceable overestimate for π that has survived for centuries.




Figure 9: The estimate for π lies between $C_i = 3.1058 < \pi < C_c = 3.2153$.




Figure 10: The estimate for π lies between $C_i = 3.1326 < \pi < C_c = 3.1596$.




Figure 11: The estimate for π lies between $C_i = 3.1393 < \pi < C_c = 3.1460$.

A closer look at π as a number

Pi is both an irrational and a transcendental number. Let us see what each of these appelations mean.

Recurring decimals.

To explore further

A well-written, accessible article on how Archimedes estimated that π is approximately $\frac{22}{7}$ is available online: "How Archimedes showed that pi is approximately 22 by 7". I urge you to read it. 5 You will then appreciate for yourselves how arduous the process must have been in an age without the benefit of: #. Trigonometry; he used the theorem of pythagors instead; #. Algebra; he used geometry and the ratios of the lengths of well-known triangles; #. Decimal numbers for division; he used fractions instead; square roots by hand; similar and congruent figures; bisection theorems; exhaustion methods

In Figures 8 to 12 below, which illustrate the approach Archimedes took to estimate π , we see very clearly that the perimeter of the *inscribed polygon* c_n and the perimeter of the *circumscribed polygon* C_n represent respectively the *lower bound* and *upper bound* of the estimated value of π . As the number of sides, n, of the polygon increases, the estimates become increasingly accurate.

https://publications.azimpremjiuniversity.edu.in/3356/1/02-DaminiAndAbhishek_PiIs22By7_Final.pdf

⁵This article is all the more remarkable because its first author is a Grade 8 student: proof that deep mathematics is not beyond the school student.




Figure 12: The estimate for π lies between $C_i=3.1410<\pi< C_c=3.1427$. Notice in this sequence of images how the circumference of the circle approaches the perimeter of the inscribed and circumscribed heaxgons to the point of being indistinguishable from them. The final estimate of Archimedes was $\frac{223}{71}<\pi<\frac{22}{7}$.

https://azimpremjiuniversity.edu.in/at-right-angles

How did Archimedes arrive at $\pi = 22/7$?

22/7 = 3.142857 142857 142857 (recurring decimal)

Formulae involving π

Quest for the endless digits of π

Buffon's Needle

π Trivia

Web links

https://www.pbs.org/wgbh/nova/physics/approximating-pi.html

https://demonstrations.wolfram.com/ArchimedesApproximationOfPi/ John Tucker "Archimedes' Approximation of Pi" http://demonstrations.wolfram.com/ArchimedesApproximationOfPi/ Wolfram Demonstrations Project Published: March 5 2009

https://math.stackexchange.com/questions/4851929/archimedes-method-to-estimate-pi

http://arxiv.org/pdf/2008.07995

https://mathsciencehistory.com/2019/10/01/archimedes-and-his-pi-the-great-numerical-hope/

https://carmamaths.org/resources/jon/pi-culture.pdf

https://nonagon.org/ExLibris/archimedes-pi

https://www.exploratorium.edu/pi/history-of-pi

https://en.wikipedia.org/wiki/Approximations_of_%CF%80

https://www.joyofpi.com/

Book References

Web resources

Teaser: are of circle half radius multiplied by circumference. How?

Appendix: Circumscribed and inscribed polygons of circle

Archimedes devised his ingenious *squeeze* method for computing the upper and lower bounds of the perimeter of a circle by computing instead the perimeters of the polygons that inscribe and circumscribe the circle. The approximations become more accurate as the number of sides, n, of the polygon is increased. This YouTube presentation might help you understand the algorithm of Archimedes better, but remember that he did not have trigonometry to aid hm.

Feedback

Please email me your comments and corrections.

A PDF version of this article is available for download here:

https://swanlotus.netlify.app/blogs/the-pi-of-archimedespdf-blog.pdf

References

- [1] OpenStax. Algebra and Trigonometry. Double-Angle, Half-Angle, and Reduction Formulas. Retrieved 6 July 2024 from https://math.libretexts.org/Bookshelves/Algebra/Algebra_and_ Trigonometry_1e_(OpenStax)/09:_Trigonometric_Identities_and_Equations/9.03:_Double-Angle_Half-Angle_and_Reduction_Formulas
- [2] Damini D B and Abhishek Dhar. 2022. How archimedes showed that pi is approximately 22 by 7. *Azim Premji University At Right Angles*. Retrieved 2 July 2024 from https://publications.azimpremjiuniversity.edu.in/3356/1/02-DaminiAndAbhishek_Pils22By7_Final.pdf
- [3] Mike Bertrand. 2014. Archimedes and Pi. Ex libris. Retrieved 5 July 2024 from https://nonagon.org/ExLibris/archimedes-pi