

### **Basic Addressing Modes**

- Processor instructions often need to access memory to read values and store results
- So far, we have used registers to read and store single values
- However, we need to:
  - · access items in an array
  - · follow pointers
  - · and more!

3

Sacramento State - Cook - CSc 3



### **Basic Addressing Modes**

- How the processor can locate and read data from memory is called an addressing mode
- Information combined from registers, immediates, etc... to create a target address
- Modes vary greatly between processors



002 Sacramento Stata - Cook - CS

4

### 4 Basic Addressing Modes


- 1. Immediate Addressing
- 2. Register Addressing
- 3. Direct Addressing
- 4. Indirect Addressing





### Immediate Addressing

- Immediate addressing is one of the most basic modes found on a processor
- Often a value is stored as part of the instruction
- As the result, it is immediately available
- Very common for assigning constants

5







Register & Immediate in Java
The following, for comparison, is the equivalent code in Java
The register file (for rcx) is set to the value 1947.
// rcx = 1947;
mov rcx, 1947

9 10

Example: Immediate & Register

Immediate

mov rcx, 1947

register addressing

Register & Immediate in Java

• This is the also the case with labels
• Remember: labels are addresses (numbers)

// rcx = label;
lea rcx, label

11 12

### In direct addressing, the processor reads data directly from the an address Commonly used to: get a value from a "variable" read items in an array etc...

Instruction

Memory

Value

Value

13 14

### Register Indirect Addressing Register Indirect reads data from an address stored in register Same concept as a pointer Because the address is in a register... it is just as fast as direct addressing the processor already had the address ... and very common


Register Indirect Addressing

Instruction
Register File
Wemory
Value
Address

15 16

```
    The following, for comparison, is the equivalent code in Java
    The value in rbx is used as the address to read from memory.
    The brackets here are necessary!

// rcx = Memory[rbx];
mov rcx, [rbx]
Street Memory [rbx] # December 100 - CD & December 200 - CD & Dece
```



17 18

### Relative Addressing

- In relative addressing, a value is added to a instruction pointer (e.g. program counter)
- Advantages:
  - instruction can just store the *difference* (in bytes) from the current instruction address
  - · takes less storage than a full 64-bit address
  - it allows a program to be stored anywhere in memory and it will still work!

Spring 2

acramento State - Cook - CSc 35

### Relative Addressing

- Often used in conditional jump statements
  - only need the to store the number of bytes to jump either up or down
  - so, the instruction only stores the value to add to the program counter
  - · practically all processors us this approach
- Also used to access local data load/store

Sacramento State - Cook - (

19

20



Arrays

- Computers do not have an 'array' data type
- So, how do you have array variables?
- When you create an array...
  - · you allocate a block of memory
  - each element is located sequentially in memory – one right after each other

Sacramento State - Cook - CSc 35

21

22

24

### Arrays

- Every byte in memory has an address
- This is just like an array
- To get an array element
  - we merely need to compute the address
  - we must also remember that some values take multiple bytes – so there is math

Spring 2

Sacramento State - Cook - CSc 35

Array Math Example

Let's again assume that our buffer starts at address 2000

The first array element is located at address 2000

Arrays consists of bytes...

the second is 2001

the third is 2002

the fourth 2003

etc...

Array Math Example – 16 bit First element uses 2000... 2001 F0A3 Since each array 042B element is 2 bytes... C1F1 2004 • second address is 2002 • third address is 2004 2006 0D0B • fourth address is 2006 2008 9C2A • etc...

Array Math Example - 64 bit First element uses 2000 to 2007 446576696E20436F Second address is 2008 6F6B0000000000000 2008 53616372616D656E Third address is 2016 746F205374617465 2024 Fourth address is 2024 4353433335000000 2032 etc...

25 26

Behind the Scenes...

So, when an array element is read, internally, a mathematical equation is used

It uses the start of the first element, the array index, and the size of each element

start address + (index × size)

Behind the Scenes...

This is why the C Programming Languages uses zero as the first array element

If zero is used with this formula, it gets the start of the buffer

start address + (index × size)

27 28

Behind the Scenes...

Java uses zero-indexing because C does

... and C does so it can create efficient assembly!

start address + (index × size)



29 30

### Indexing on the x64

- The Intel x64 supports direct, indirect, indexing and scaling
- So, the Intel is very versatile in how it can access memory
- This is typical of CISC-ish architectures



31

### **Effective Addresses**

- Processors have the ability to create the effective address by combining data
- How it works:
  - · starts with a base address
  - · then adds a value (or values)
  - finally, uses this temporary value as the actual address



32

### **Effective Addresses**

- Using the addresses stored in memory, registers, etc... is useful in programs
- Often programs contain groups of data
  - · fields in an abstract data type
  - · elements in an array
  - · entries in a large table etc...

pring 2022 Sacramento State - Cook - CSc



33

### **Terminology**

- Base-address is the initial address
- Displacement (aka offset) is a constant (immediate) that is added to the address
- Index is a register added to the address
- Scale used to multiply the index before adding it to the address

Sacramento State - Cook - CSc 35

34

# x64 Effective Address Formula Signed Constant 1,2,4 or 8 displacement + base + (index × scale) Any Register Any Register

But wait, doesn't that formula look familiar?

The addressing term "scale" is basically equivalent to "size" in this example

Addressing and arrays work together flawlessly

start address + (index × size)


35 36

### Addressing Notation in Assembly

- Intel Notation (Microsoft actually created it) allows you to specify the full equation
- The notation is very straight forward and mimics the equation used to compute the effective address
- Parts of the equation can be omitted, and the assembler will understand

uping year.

37



- -

### Notation (reg = register) Immediate Register register register Direct Memory[label] Memory[label + reg] Direct Indexed [label + reg] [reg] Memory[reg] Indirect Indirect Indexed [reg + reg] Memory[reg + reg] [reg + reg \* scale] Memory[reg + reg × scale] Indirect Indexed Scale

Addressing Notation in Assembly
 When you write an assembly instruction...

 you specify all 4 four addressing features
 however, notation fills in the "missing" items

 For example: for direct addressing...

 Displacement → Address of the data
 Base → Not used
 Index → Not used
 Scale → 1, irrelevant without an Index

39 40

# Indexing Examples The following examples use addressing modes modify an ASCII buffer Let's <u>assume</u> that the start of the buffer Talk is 5000 Expression From the following examples use addressing modes modify an ASCII buffer 5000 48 H 5001 65 e 5002 6c 1 5003 6c 1 5004 6F o

Using the RDI register for indexing, but you can use any register

mov rdi, 1
movb [Talk + rdi], 33

ASCII 33 → 1


Formation


ASCII 33 → 1


Formation


Comparison

41 42












45 46






47 48








Tables of Integers
Tables can contain anything!
Often, they are used to store integers & addresses (8 bytes on a 64-bit system)
Just make sure to use the scale feature!


51 52


Table of Long Integers


Years:
 . quad 1776
 . quad 1783
 . quad 1846
 . quad 1850
 . quad 1947



53 54









57 58


When you use arrays in Java, often the index is a variable
This allows you to use a For Loop to analyze very element in the array
This is more common than you think in assembly


Addressing & Loops


So, processors allow a register to be used as an index


This allows you to:
copy strings (copying arrays)
search through a list
and much more...

59 60










63




Operating systems protect programs from having their memory / code damaged by other programs
 However...operating systems don't protect programs from damaging themselves


65 66

# In memory, a running program's data is often stored next to its instructions This means... if the end of a buffer of exceeded, the program can be read/written this is a common hacker technique to modify a program while it is running!




67 68





69



It is possible to accidentally change data stored in the different buffers
 In assembly, you have full control over your allocated memory
 With great power comes great responsibility

71 72

