MPICH2 Windows Development Guide*

Version 1.0.3

Mathematics and Computer Science Division Argonne National Laboratory

David Ashton

December 13, 2006

^{*}This work was supported by the Mathematical, Information, and Computational Sciences Division subprogram of the Office of Advanced Scientific Computing Research, Sci-DAC Program, Office of Science, U.S. Department of Energy, under Contract W-31-109-ENG-38.

Contents

1	Intr	roduction	1
2	Bui	ld machine	1
3	Test machine		1
4	Soft	tware	1
	4.1	Packages	1
5	Bui	lding MPICH2	3
	5.1	Developer Studio automated 32bit build	3
		5.1.1 Automated build from the source distribution	5
		5.1.2 Building without Fortran	5
	5.2	Platform SDK builds	5
6	Dis	tributing MPICH2 builds	7
7	Tes	ting MPICH2	7
	7.1	Testing from scratch	7
	7.2	Testing a built mpich2 directory	7
	7.3	Testing an existing installation	8
8	Dev	velopment issues	8
9	Rui	ntime environment	9
	9.1	User credentials	9
	9.2	MPICH2 channel selection	10
	9.3	MPI apps with GUI	11

9.4	Security	11
9.5	Firewalls	13
9.6	MPIEXEC options	14
9.7	SMPD process manager options	19
9.8	Debugging jobs by starting them manually	22
9.9	Environment variables	23
9.10	Compiling	28
	9.10.1 Visual Studio 6.0	28
	9.10.2 Developer Studio NET 2003	29

1

1 Introduction

This manual describes how to set up a Windows machine to build and test MPICH2 on.

2 Build machine

Build a Windows XP or Windows Server 2003 machine. Place this machine in the MPICH domain and create a user in the domain with the same name as your MCS user name. Use your MCS password for this new account. This isn't a requirement; you can create any username you want with any password you want and it doesn't have to be part of the MPICH domain. But it makes life a lot easier if you do.

3 Test machine

Build a Windows XP or Windows Server 2003 machine on a 32bit CPU. Also build a Windows Server 2003 X64 machine to test the Win64 distribution.

4 Software

This section describes the software necessary to build MPICH2.

4.1 Packages

To build MPICH2 you will need:

- 1. Microsoft Developer Studio .NET 2003
- 2. Microsoft Platform SDK
- 3. cygwin full installation
- 4. Intel Fortran compiler IA32
- 5. Intel Fortran compiler EMT64

4 SOFTWARE 2

6. Java SDK

Microsoft Developer Studio can be found on the CDs from an MSDN subscription. The 2003 version is needed to get a compiler that is up to date on standards compliance. This is needed to compile the C++ interface and handle types like "long long".

The Platform SDK can also be found on the MSDN CDs or downloaded from Microsoft.com. The latest version as of the writing of this document was Platform SDK - Windows Server 2003 SP1. This package needs to be installed to get the Win64 compilers.

The Intel Fortran compilers need to be installed after Developer Studio and the PSDK because they integrate themselves into those two products. The regular IA32 compiler needs to be installed and the EMT64 compiler needs to be installed. They are two separate packages and they require a license file to use. The license file is for a single user on a single machine.

cygwin needs to be installed to get cvs, perl and ssh. MPICH2 can also be built completely under cygwin just like a Unix build so I install all of cygwin. The latest cygwin packages are needed to build MPICH2 under cygwin and the MCS mirror site for cygwin does not contain the latest versions. So I would select a download site other than the mcs mirror site during the cygwin install. I also select to use the DOS file format during the install process for cygwin.

After installing cygwin, bring up a cygwin bash shell and generate some ssh keys. I believe the command is: ssh-keygen -t dsa. Then copy the public key generated to your mcs /home/you/.ssh/authorized_keys file. This will allow you to ssh from this machine to harley.mcs.anl.gov without typing a password. This is important in order for the automated scripts to run without user intervention.

Assuming you installed cygwin to the default c:\cygwin directory, add c:\cygwin\bin to your path environment variable. This is required so the automated scripts can run tools like ssh and perl without specifying the full path.

The Java SDK needs to be installed so the logging library can be compiled. This can be a problem because MPICH2 needs to know the include path for jni.h. Since the JSDK can be installed anywhere and the path includes the version there isn't a standard path that can be added

to the MPICH2 projects. Currently c:\j2sdk1.4.2_06\include is used in mpich2\src\util\logging\rlog\TraceInput\TraceInput.vcproj. This will have to be modified if you install a different version of the JSDK.

Run the following command from a command prompt to change the Windows script engine from GUI mode to console mode:

cscript //H:cscript

5 Building MPICH2

This section describes how to make various packages once you have a working build machine.

5.1 Developer Studio automated 32bit build

The easist way to build an MPICH2 distribution is to use the Developer Studio environment and the makewindist.bat script from the top level of the mpich2 source tree. You can check out mpich2 from CVS or you can simply copy this batch file from the distribution. The batch file knows how to check out mpich2 so it the only file required to make a distribution.

The product GUIDs need to be changed when a new release is created. To do this run "perl update_windows_version <new_version>". Run this script with mpich2/maint as the current directory so the project files can be found. Example:

perl update_windows_version 1.0.3

Or you can modify the project files by hand. Edit mpich2/maint/mpich2i.vdproj. The ProductCode and PackageCode entries need to be changed to use new GUIDs. Under Unix or Windows, unidgen can be used to generate a new GUID. The ProductVersion entry needs to be changed to match the version of MPICH2.

Once the version and GUIDs have been updated, commit the changes to mpich2i.vdproj to CVS.

Then you can build a distribution.

Bring up a build command prompt by selecting Start \rightarrow Progams \rightarrow Microsoft Visual Studio .NET 2003 \rightarrow Visual Studio .NET Tools \rightarrow Visual Studio .NET 2003 Command Prompt.

Change directories to wherever you want to create the distribution. mpich2 will be checked out under the current directory. Run the makewindist batch file:

makewindist.bat --with-checkout

Since there are no bugs in MPICH2 everything will work automatically. The batch file does the following steps:

- 1. check out mpich2allWithMPE and change into the mpich2 directory
- 2. ssh to harley.mcs.anl.gov and checkout mpich2. Then run maint/updatefiles on harley, collect all the generated .h.in files and copy them back to the Windows machine.
- 3. run "winconfigure.wsf --cleancode" to configure mpich2 for Windows and output all the generated files like mpi.h and the fortran interface files, etc.
- 4. run the Developer Studio command line tool to build all the pieces of MPICH2. This includes each of the channels sock, ssm, shm, sshm, and the multi-threaded sock channel. Two versions of each channel are built, the regular release build and the rlog profiled version. The mpi wrapper channel selector dll is built and three Fortran interfaces are built, one for each set of common symbol types and calling conventions. mpiexec and smpd are built along with the Windows GUI tools and the cygwin libraries. (These are the cygwin link libraries to use the Windows native build of MPICH2, not a Unix-style build of MPICH2 under cygwin.)
- 5. package up everthing into maint\ReleaseMSI\mpich2.msi.

When the batch file is finished you will be left with a mpich2.msi file that can be used to install MPICH2 on any Win32 machine. This file can be re-named to match our release naming conventions.

5

5.1.1 Automated build from the source distribution

If you don't have access to the CVS repository but you have the MPICH2 source distribution you can still use the makewindist batch file. Follow these steps:

- 1. unzip/untar the source distribution
- 2. bring up a Visual Studio Command Prompt
- 3. cd into the mpich2xxx directory
- 4. execute "winconfigure.wsf --cleancode"
- 5. execute "makewindist.bat --with-curdir"

5.1.2 Building without Fortran

If you don't have a Fortran compiler you can use winconfigure.wsf to remove the Fortran projects. Execute winconfigure.wsf --remove-fortran --cleancode Then you can build the projects without Fortran support. If you want to use the makewindist.bat script you will need to remove the Fortran lines from it before executing it.

5.2 Platform SDK builds

The makefile in the mpich2\winbuild directory builds a distribution based on what compilers are specified in the environment so it can be used to compile any version of MPICH2. The following targets can all be built with this mechanism:

- Win64 X64
- Win64 IA64
- Win32 x86

But first you need to have mpich2 checked out and configured before building.

- 1. bring up a command prompt and check out mpich2:
 cvs -d :ext:ashton@harley.mcs.anl.gov:/home/MPI/cvsMaster co
 mpich2allWithMPE. Replace ashton with your own username.
- 2. cd into mpich2
- 3. run getdotin.bat
- 4. run winconfigure.wsf --cleancode

To build the Win64 X64 distribution do the following:

- Bring up a build command prompt from the PSDK. It can be found here: Start→Programs →Microsoft Platform SDK for Windows Server 2003 SP1→Open Build Environment Window→ Windows Server 2003 64-bit Build Environment→Set Win Svr 2003 x64 Build Env (Retail)
- 2. Run \Program Files\Intel\Fortran\compiler80\Ia32e\Bin\ifortvars.bat
- 3. cd into mpich2\winbuild
- 4. run build.bat 2>&1 | tee build.x64.out

To build the Win64 IA64 distribution do the following:

- Bring up a build command prompt from the PSDK. It can be found here: Start→Programs →Microsoft Platform SDK for Windows Server 2003 SP1→Open Build Environment Window→ Windows Server 2003 64-bit Build Environment→Set Win Svr 2003 IA64 Build Env (Retail)
- 2. Run \Program Files\Intel\Fortran\compiler80\Itanium\Bin\ifortvars.bat
- 3. cd into mpich2\winbuild
- 4. run build.bat 2>&1 | tee build.ia64.out

To build the Win32 x86 distribution do the following:

1. Bring up a build command prompt from the PSDK. It can be found here: Start→Programs →Microsoft Platform SDK for Windows Server 2003 SP1→Open Build Environment Window→ Windows 2000 Build Environment→Set Windows 2000 Build Environment (Retail)

- 2. Run \Program Files\Intel\Fortran\compiler80\Ia32\Bin\ifortvars.bat
- 3. cd into mpich2\winbuild
- 4. run build.bat 2>&1 | tee build.x86.out

6 Distributing MPICH2 builds

If you built an .msi file using the Developer Studio build process 5.1 then all you have to do is rename the mpich2.msi file to something appropriate like mpich2-1.0.3-1-win32-ia32.msi

If you built using the Platform SDK build process 5.2 then the output files are left in their build locations and need to be collected and put in a zip file for distributing. This process should be automated with a script.

7 Testing MPICH2

Run the testmpich2.wsf script to checkout mpich2, build it, install it, checkout the test suites, build them, run the test suites, and collect the results in a web page.

7.1 Testing from scratch

Explain the use of testmpich2.wsf.

Run "testmpich2.wsf" without any parameters and it will create a testmpich2 subdirectory and check out into that directory mpich2 and the test suites - c++, mpich, intel and mpich2. It will then build mpich2 and all the tests from the test suites. Then it will run the tests and place a summary in testmpich2\summary\index.html.

7.2 Testing a built mpich2 directory

Explain how to run testmpich2.wsf if you have the mpich2 source tree on a machine and you have already built all of mpich2.

Here is a sample batch file to test mpich2 that has already been built in c:\mpich2:

```
testmpich2.wsf /mpich2:c:\mpich2 /make- /configure- /buildbatch
pushd testmpich2\buildMPICH
call mpich_cmds.bat
popd
pushd testmpich2\buildCPP
call cpp_cmds.bat
popd
pushd testmpich2\buildINTEL
call intel_cmds.bat
popd
pushd testmpich2\buildMPICH2
call mpich2_cmds.bat
popd
pushd testmpich2\buildMPICH2
call mpich2_cmds.bat
popd
testmpich2.wsf /mpich2:c:\mpich2 /make- /configure- /summarize
```

7.3 Testing an existing installation

Explain the use of testmpich2.wsf to test an existing installation, one that was installed with the .msi distribution.

8 Development issues

This section describes development issues that are particular to the Windows build.

Whenever a .h.in file is created on the Unix side, winconfigure.wsf needs to be updated to create the .h file from the .h.in file. Copy and paste an existing section in winconfigure.wsf that already does this and rename the file names.

When new definitions are added to the .h.in files these definitions, usually in the form HAVE_FOO or USE_FOO, need to be added to the AddDefinitions function in winconfigure.wsf. Simply add new cases to the big case statement as needed. winconfigure.wsf warns you of definitions that are not in the case statement.

Whenever a @FOO@ substitution is added on the Unix side, winconfigure.wsf needs to be updated to handle the substitution. Find the ReplaceAts function in winconfigure.wsf and add the substitution to the big case statement. winconfigure.wsf warns you of new substitutions that have not been added to the case statement.

9 Runtime environment

This section describes the MPICH2 environment that is particular to Windows.

9.1 User credentials

mpiexec must have the user name and password to launch MPI applications in the context of that user. This information can be stored in a secure encrypted manner for each user on a machine. Run mpiexec -register to save your username and password. Then mpiexec will not prompt you for this information.

This is also true for a nightly build script. The user context under which the script is run must have saved credentials so mpiexec doesn't prompt for them. So scripts won't hang, mpiexec provides a flag, -noprompt, that will cause mpiexec to print out errors in cases when it normally would prompt for user input. This can also be specified in the environment with the variable MPIEXEC_NOPROMPT.

You can also save more than one set of user credentials. Add the option -user n to the -register, -remove, -validate, and mpiexec commands to specify a saved user credential other than the default. The parameter n is a non-zero positive number. For example this will save credentials in slot 1:

```
mpiexec -register -user 1
```

And this command will use the user 3 to launch a job:

```
mpiexec -user 3 -n 4 cpi.exe
```

User credentials can also be specified in a file using the -pwdfile filename option to mpiexec. Put the username on the first line of the file and the password on the second line. If you choose this option you should make sure the file is only readable by the current user.

9.2 MPICH2 channel selection

MPICH2 for Windows comes with multiple complete implementations of MPI. These are called channels and each build represents a different transport mechanism used to move MPI messages. The default channel uses sockets for communication. There are two channels that use only shared memory. There is a channel that uses both sockets and shared memory. There is a channel that uses Infiniband. And there is a thread-safe version of the sockets channel.

The short names for the channels are: sock, shm, sshm, ssm, mt.

These channels can be selected at runtime with an environment variable: MPICH2_CHANNEL. The following is an example that uses the Infiniband channel instead of the default sockets channel:

```
mpiexec -env MPICH2_CHANNEL ib -n 4 myapp.exe
or
mpiexec -channel ib -n 4 myapp.exe
```

If you specify auto for the channel then mpiexec will automatically choose a channel for you.

```
mpiexec -channel auto -n 4 myapp.exe
```

The rules are:

- 1. If numprocs is less than 8 on one machine, use the shm channel
- 2. If numprocs is greater than 7 on one machine, use the sshm channel
- 3. If running on multiple machines, use the ssm channel. This channel can be changed using winconfigure.

9.3 MPI apps with GUI

Many users on Windows machines want to build GUI apps that are also MPI applications. This is completely acceptable as long as the application follows the rules of MPI. MPI.Init must be called before any other MPI function and it needs to be called soon after each process starts. The processes must be started with mpiexec but they are not required to be console applications.

The one catch is that MPI applications are hidden from view so any Windows that a user application brings up will not be able to be seen. mpiexec has an option to allow the MPI processes on the local machine to be able to bring up GUIs. Add -localroot to the mpiexec command to enable this capability. But even with this option, all GUIs from processes on remote machines will be hidden.

So the only GUI application that MPICH2 cannot handle by default would be a video-wall type application. But this can be done by running smpd.exe by hand on each machine instead of installing it as a service. Log on to each machine and run "smpd.exe -stop" to stop the service and then run "smpd.exe -d 0" to start up the smpd again. As long as this process is running you will be able to run applications where every process is allowed to bring up GUIs.

9.4 Security

MPICH2 can use Microsoft's SSPI interface to launch processes without using any user passwords. This is the most secure way to launch MPI jobs but it requires the machines to be configured in a certain way.

- All machines must be part of a Windows domain.
- Each machine must have delegation enabled.
- Each user that will run jobs must be allowed to use delegation.

If the machines are set up this way then an administrator can set up MPICH2 for passwordless authentication. On each node, a domain administrator needs to execute the following: "smpd -register_spn".

Then a user can add the -delegate flag to their mpiexec commands and the job startup will be done without any passwords. Example:

mpiexec -delegate -n 3 cpi.exe

With SSPI enabled you can also control access to nodes with job objects.

First the nodes need to be set up so that only SSPI authentication is allowed. An administrator can run the following on each node:

- 1. smpd.exe -set sspi_protect yes
- 2. smpd.exe -set jobs_only yes
- 3. smpd.exe -restart

These settings mean that authentication must be done through SSPI and mpiexec commands will only be accepted for registered jobs.

To register jobs an administrator or a scheduler running with administrator privileges can execute the following command:

```
mpiexec.exe -add_job <name> <domain\username> [-host <hostname>]
```

This adds a job called "name" for the specified user on either the local or specified host. Any name can be used but it must not collide with another job with the same name on the same host. The command must be executed for each host that is to be allocated to the user.

Then when the job has finished or the allotted time has expired for the user to use the nodes the following command can be executed:

```
mpiexec.exe -remove_job <name> [-host <hostname>]
```

This command removes the job from the local or specified host. Any processes running on the host under the specified job name will be terminated by this command.

So -add_job and -remove_job can be used by a scheduler to create a window when a user is allowed to start jobs on a set of nodes.

When the window is open the user can run jobs using the job name. First the user must run:

```
mpiexec.exe -associate_job <name> [-host <hostname>]
```

This will associate the user's token with the job object on the local or specified host. This must be done for all of the hosts allocated to the user. Then the user can issue mpiexec commands. The mpiexec commands are of the usual format except they must contain one extra option - "-job <name>". This job name must match the job allocated by the -add_job command. So a typical command would look like this:

mpiexec.exe -job foo -machinefile hosts.txt -n 4 myapp.exe

Multiple mpiexec commands can be issued until the <code>-remove_job</code> command is issued. This allows the users to issue multiple mpiexec commands and multiple MPI_Comm_spawn commands all using the same job name until the job is removed from the nodes.

The rationale for the design where an administrator can create and destroy jobs but the user must first associate the job with his own token before running jobs is so that the administrator does not need to know the user's password. In order for an administrator to do both the job allocation and association he would have to call LogonUser with the user name and password for each user that submits a job request.

9.5 Firewalls

Windows comes with a default firewall that is usually turned on by default. Firewalls block all TCP ports by default which renders MPICH2 applications inoperable because the default communication mechanism used by MPICH2 are sockets on arbitrary ports assigned by the operating system. This can be solved in several ways:

- Turn off the firewall completely.
- MPICH2 applications can be limited to a range of TCP ports using the MPICH_PORT_RANGE environment variable. If you set your firewall to allow the same port range then MPICH2 applications will run.
- Leave the Windows firewall on and allow exceptions for your MPICH2 applications. This can be done through the Security Center module of the Windows Control Panel. Click the Windows Firewall option in the Security Center to bring up the properties page and select the Exceptions tab. Here you can add each MPICH2 application to exempt.

Note that this exception includes the path to the executable so if you move the executable you will have to exempt the new location. This solution obviously only will work for a small number of applications since managing a large list would be difficult. Make sure you add mpiexec.exe and the smpd.exe process manager to this exception list.

9.6 MPIEXEC options

This section describes all the options to mpiexec.exe

- -n x or -np x Specify the number of processes to launch.
- -localonly x or -localonly Specify that the processes should only be launched on the local host. This option can replace the -n x option or be used in conjunction with it when it is only a flag.
- -machinefile filename Use the specified file to get host names to launch processes on. Hosts are selected from this file in a round robin fashion. One host is specified per line. Extra options can be specified. The number of desired processes to launch on a specific host can be specified with a colon followed by a number after the host name: hostname:n. This is usefull for multi-CPU hosts. If you want to specify the interface that should be used for MPI communication to the host you can add the -ifhn flag. Here is an example: hostname:4-ifhn 192.168.1.100
- -configfile filename Use the specified job configuration file to launch the job. Each line in the file represents a set of options just like you would enter them on the mpiexec command line. The one difference is that there are no colons in the file. The colons are replaced by new-lines.
- -file filename Use the specified implementation specific job configuration file. For Windows this option is used to specify the old MPICH 1.2.5 configuration file format. This is useful for users who have existing configuration files and want to upgrade to MPICH2.
- -host hostname Specify that the processes should be launched on a specific host.

- -hosts n host1 host2 host3 ... Specify that the processes should be launched on a list of hosts. This option replaces the -n x option.
- ullet -hosts n host1 m1 host2 m2 host3 m3 ... Specify that the processes should be launched on a list of hosts and how many processes should be launched on each host. The total number of processes launched is m1 + m2 + m3 + ... mn.
- -map drive:\\host\share Specify a network mapped drive to create on the hosts before launching the processes. The mapping will be removed when the processes exit. This option can be specified multiple times.
- -dir drive:\my\working\directory Specify the working directory for the processes.
- -wdir drive:\my\working\directory -wdir and -dir are synonyms.
- -env variable value Specify an environment variable and its value to set in the processes' environments. This option can be specified multiple times.
- -genvlist a,b,c,d... Specify a list of environment variables to taken from the environment local to mpiexec and propagated to the launched processes.
- -logon Prompt for user credentials to launch the job under.
- -pwdfile filename Specify a file to read the user name and password from. The user name should be on the first line and the password on the second line.
- -exitcodes Specify that the exit code of each process should be printed to stdout as each processes exits.
- -noprompt Prevent mpiexec for prompting for information. If user credentials are needed to launch the processes mpiexec usually prompts for this information but this flag causes an error to be printed out instead.
- -priority class[:level] Specify the priority class and optionally the thread priority of the processes to be launched. The class can be 0,1,2,3, or 4 corresponding to idle, below, normal, above, and high. The level can be 0,1,2,3,4, or 5 corresponding to idle, lowest, below, normal, above, highest. The default is 2:3.

- -localroot Specify that the root process should be launched on the local machine directly from mpiexec bypassing the smpd process manager. This is useful for applications that want to create windows from the root process that are visible to the interactive user. The smpd process manager creates processes in a hidden service desktop where you cannot interact with any GUI.
- -channel channel name This option is only available under Windows and allows the user to select which channel implementation of MPICH2 to select at runtime. The current channels supported are sock, mt, ssm, shm, and sshm. These represent the sockets, multi-threaded sockets, sockets plus shared memory, shared memory, and scalable shared memory channels. The shared memory channels only work on one node. The sockets, multi-threaded sockets, and sockets plus shared memory channels work on multiple nodes. There are also profiled versions of the channels that produce RLOG files for each process when selected. They are named p, mtp, ssmp, shmp, and sshmp. See the section on channel selection for additional information.
- -log This option is a short cut to selecting the MPE wrapper library to log the MPI application. When the job finishes there will be a .clog2 file created that can be viewed in Jumpshot.
- -1 This flag causes mpiexec to prefix output to stdout and stderr with the rank of the process that produced the output. (This option is the lower-case L not the number one)
- -port port Specify the port where the smpd process manager is listening.
- -p port Short version of the -port option.
- -smpdfile filename Specify the location of the smpd configuration file. The default is 7.smpd. This is a Unix only option. Under Windows the settings are stored in the Windows Registry.
- -phrase passphrase Specify the passphrase used to authenticate with the smpd process managers.
- -path search_path Specify the search path used to locate executables. Separate multiple paths with semicolons. The path can be mixed when using both Windows and Linux machines. For example: -path c:\temp;/home/user is a valid search path.

- -register [-user n] Encrypt a user name and password into the Windows registry so that it can be automatically retrieved by mpiexec to launch processes with. If you specify a user index then you can save more than one set of credentials. The index should be a positive non-zero number and does not need to be consecutive.
- -remove [-user n] Remove the encrypted credential data from the Registry. If multiple entries are saved then use the -user option to specify which entry to remove. -user all can be specified to delete all entries.
- -validate [-user n] [-host hostname] Validate that the saved credentials can be used to launch a process on the local or specified host.

 If more that one credentials has been saved then the -user option can be used to select which user credentials to use.
- -user n Specify which encrypted credentials to retrieve from the Registry. The corresponding entry must have been previously saved using the -register -user n option.
- -timeout seconds Specify the maximum number of seconds the job is allowed to run. At the end of the timeout period, if the job has not already exited then all processes will be killed.
- -plaintext Specify that user credentials should go over the wire unencrypted. This is required if both Linux and Windows machines are used in the same job because the Linux machines cannot encrypt and decrypt the data created by the Windows machines.
- -delegate Specify that you want to use passwordless SSPI delegation to launch processes. The machines must be configured to use SSPI as described in the section on security.
- -impersonate Specify that you want to use passwordless SSPI impersonation to launch processes. This will create processes on the remote machines with limited access tokens. They wil not be able to open files on remote machines or access mapped network drives.
- -add_job job_name domain\user [-host hostname] Create a job object on the local or specified host for the specified user. Administrator privileges are required to execute this command.

- -remove_job job_name [-host hostname] Remove a job object on the local or specified host. Any processes running under this job will be terminated. Administrator privileges are required to execute this command.
- -associate_job job_name [-host hostname] Associate the current user token with the specified job on the local or specified host. The current user must match the user specified by the -add_job job_name username command.
- -job job_name Specify that the processes should be launched under the specifed job object. This can only be used after successful calls to -add_job and -associate_job.
- -whoami Print out the current user name in the format that mpiexec and smpd expect it to be. This is useful for users who use a screen name that is different from their user name.
- -hide_console Detach from the console so that no command prompt window will appear and consequently not output will be seen.
- -quiet_abort Use this flag to prevent extensive abort messages to appear. Instead the job will simply exit with minimal error output.
- -rsh or -ssh Use the remote shell command to execute the processes in the job instead of using the smpd process manager. The default command is "ssh -x" no matter whether -rsh or -ssh is used. If this is the only flag specified then an smpd process manager must be running on the local host where mpiexec is executed. mpiexec contacts the local smpd process to start a PMI service required by the MPI job and then starts the processes using the remote shell command. On the target machines the application "env" must be available since it is used to set the appropriate environment variables and then start the application. The remote shell command can be changed using the environment variable MPIEXEC_RSH. Any command can be used that takes a host name and then everything after that as the user command to be launched.
- -nopm This flag is used in conjunction with the -rsh flag. With this flag specified there need not be any smpd process manager running on any of the nodes used in the job. mpiexec provides the PMI interface and the remote shell command is used to start the processes. Using

these flags allows jobs to be started without any process managers running but the MPI-2 dynamic process functions like MPI_Comm_spawn are consequently not available.

- -verbose Output trace data for mpiexec. Only useful for debugging.
- -pmi_server num_processes or -pmiserver num_processes This option specified by itself connects to the local smpd process manager and starts a PMI service. This service is used by MPICH2 processes to communicate connection information to each other. This option is only good for a single MPICH2 job. The input parameter is the number of processes in the job. mpiexec immediately outputs three lines of data. The first line is the host name. The second line is the port it is listening on and the third line is the name of the PMI KVS. A process manager that can set environment variables and launch processes but does not implement the PMI service can use this option to start jobs. Along with the other PMI environment variables the process manager must set PMI_HOST to the host name provided, PMI_PORT to the port provided and PMI_KVS and PMI_DOMAIN to the KVS name provided. It is the responsibility of the process manager to set the other environment variables correctly like PMI_RANK and PMI_SIZE. See the document on the smpd PMI implementation for a complete list of the environment variables. When the job is finished the PMI server will exit. This option can be executed in separate command simultaneously so that multiple jobs can be executed at the same time.

9.7 SMPD process manager options

This section describes some of the options for the smpd process manager.

smpd.exe runs as a service under Windows. This is required so that it can start processes under multiple user credentials. Only services have the privileges necessary to log on users and start processes for them. Since this is a privileged operation administrator rights are required to install the smpd service. This is what the default installer package does.

But smpd can be run in other ways for debugging or single user use.

If you have smpd.exe installed first execute smpd.exe -stop to stop the service.

Then you can run it by hand for single user mode or for debugging. The flag for debugging single user mode is -d debug_output_level.

If you run it like this you will get full trace output:

```
smpd.exe -d
```

If you run it like this you will get no output except for errors:

```
smpd.exe -d 0
```

Here are all the options to smpd.exe:

- -install or -regserver Install the smpd service. Requires administrator privileges.
- -remove or -uninstall or -unregserver Uninstall the smpd service. Requires administrator privileges.
- -start Start the smpd service. Requires administrator privileges.
- -stop Stop the smpd service. Requires administrator privileges.
- -restart Stop and restart the smpd service. Requires administrator privileges.
- -register_spn Register the Service Prinicipal Name for the smpd service of the local machine on the domain controller. Requires DOMAIN administrator privileges. This is used in conjunction with passwordless SSPI authentication described in the section on security.
- -remove_spn Remove the Service Prinicipal Name from the domain controller for the smpd service of the local machine. Requires DO-MAIN administrator privileges.
- -traceon filename [hostA hostB ...] Turn on the trace logging of the smpd service on the local or specified hosts and set the output to the specified file. The file location must be available on the local drive of each of the hosts. It cannot be located on a remote machine.
- -traceoff [hostA hostB ...] Turn off the trace logging of the smpd service on the local or specified hosts.

- -port n Listen on the specified port number. If this option is not specified then smpd listens on the default port (8676).
- -anyport Listen on any port assigned by the OS. smpd immediately prints out the port that it has been assigned.
- -phrase passphrase Use the specified passphrase to authenticate connections to the smpd either by mpiexec or another smpd process.
- -getphrase Prompt the user to input the passphrase. This is useful if you don't want to specify the phrase on the command line.
- -noprompt Don't prompt the user for input. If there is missing information, print an error and exit.
- -set option value Set the smpd option to the specified value. For example, smpd -set logfile c:\temp\smpd.log will set the log file to the specified file name. smpd -set log yes will turn trace logging on and smpd -set log no will turn it off.
- -get option Print out the value of the specified smpd option.
- -hosts Print the hosts that mpiexec and this smpd will use to launch
 processes on. If the list is empty then processes will be launched on
 the local host only.
- -sethosts hostA hostB ... Set the hosts option to a list of hosts that mpiexec and smpd will use to launch processes on.
- -d [level] or -debug [level] Start the smpd in debug or single user mode with the optionally specified amount of output. For example, smpd -d will start the smpd will lots of trace output and smpd -d 0 will start the smpd with no output except for errors.
- -s Only available on Unix systems. This option starts the smpd in single user daemon mode for the current user.
- -smpdfile filename On Unix systems the smpd options are stored in a file that is readable only by the current user (chmod 600). This file stores the same information that would be stored in the Windows registry like the port and passphrase. The default file is named 7.smpd if this option is not specified.
- -shutdown Shutdown a running smpd that was started by smpd -s or smpd -d.

- -printprocs On a Windows machine you can run smpd -printprocs and it will print out the processes started and stopped by smpd on the current host. The format of the output is +/-pid cmd. Plus means a process was started and minus means the process has exited. The process id is specified next and then the rest of the line is the command that was launched.
- -enum or -enumerate Print the smpd options set on the local host.
- -version Print the smpd version and exit.
- -status [-host hostname] Print the status of the smpd on the local or specified host.
- -help Print a brief summary of the options to smpd.

9.8 Debugging jobs by starting them manually

This section describes how to start a job by hand without the use of a process manager so the job can be stepped through with a debugger.

You can launch an MPICH2 job by hand if you set the minimum required environment variables for each process and then start the processes yourself (or in a debugger).

Here is a script that sets the environment variables so that a job can be started on the local machine: The file is called setmpi2.bat

```
if ''%1'' == '''' goto HELP
if ''%2'' == '''' goto HELP
set PMI_ROOT_HOST=%COMPUTERNAME%
set PMI_ROOT_PORT=9222
set PMI_ROOT_LOCAL=1
set PMI_RANK=%1
set PMI_SIZE=%2
set PMI_KVS=mpich2
goto DONE
:HELP
REM usage: setmpi2 rank size
:DONE
```

For example, to debug a two process job bring up two separate command prompts. In the first prompt execute setmpi2.bat 0 2 and in the second prompt execute setmpi2.bat 1 2. Then run your application always starting the root process first. The root process must call MPI_Init before any of the other processes because it is the process that listens on the port specifed by the environment variable PMI_ROOT_PORT. Simply execute myapp.exe from each command prompt to run your job. Or better yet run each process in a debugger. If you have the Microsoft developer studio installed you can run the following from each command prompt: devenv.exe myapp.exe. This will bring up a debugger for each process. Then you can step through each process and debug it. Remember that the first process must call MPI_Init before any of the rest of the processes do. You can restart the processes at any time as long as you restart all of them.

The script can be modified to launch on multiple hosts by changing the line:

set PMI_ROOT_HOST=%COMPUTERNAME%

to set the variable to the hostname where the root process will be started instead of the local host name.

The limitation of this method of starting processes is that MPI-2 spawning operations are not supported. If your application calls MPI_Comm_spawn it will produce an error.

9.9 Environment variables

This section describes the environment variables used by MPICH2 and smpd.

- MPICH_ABORT_ON_ERROR Call abort() when an error happens instead of returning an error and calling MPID_Abort. useful for unix where calling abort() creates a core file.
- MPICH_PRINT_ERROR_STACK Print the entire error stack when an error occurs (currently this is the default)
- MPICH_CHOP_ERROR_STACK Split the error stack output at the character position specified. A value of 79 would cause carriage returns to be inserted after the 79th character.

- MPICH_WARNINGS Print runtime warnings (unmatched messages at MPI_Finalize, unreleased resources, etc)
- MPICH_SOCKET_BUFFER_SIZE socket buffer size
- MPICH_SOCKET_RBUFFER_SIZE socket receive buffer size
- MPICH_SOCKET_SBUFFER_SIZE socket send buffer size
- MPICH_SOCKET_NUM_PREPOSTED_ACCEPTS number of accepts posted for MPIDU_Sock_listen
- MPICH_PORT_RANGE Range of ports to use for sockets: min..max or min,max
- MPICH_INTERFACE_HOSTNAME hostname to use to connect sockets
- MPICH_NETMASK bitmask to select an ip subnet: ip/numbits, ie 192.0.0.0/8
- MPIEXEC_TIMEOUT job timeout in seconds
- MPIEXEC_LOCALONLY launch job processes on the local machine only
- MPIEXEC_NOPROMPT Don't prompt for user input for missing information, print an error instead.
- MPIEXEC_SMPD_PORT Connect to smpd on the specified port.
 The following two only affect mpiexec for smpd if -rsh is on the command line:
- MPIEXEC_RSH rsh command to use, default is "ssh -x"
- MPIEXEC_RSH_NO_ESCAPE create an rsh command compatible with cygwin's ssh
- MPICH_SPN Service Principal Name used for passwordless authentication
- SMPD_DBG_OUTPUT Print debugging output
- SMPD_DBG_LOG_FILENAME name of logfile to send output to
- SMPD_MAX_LOG_FILE_SIZE maximum number of bytes the logfile can grow to before it is truncated

- MPICH_DBG_OUTPUT stdout, memlog or file. determines where debugging output goes
- MPI_DLL_NAME name of the dll that contains the MPI and PMPI interfaces
- MPICH2_CHANNEL short name of the channel used to create the full name of the MPI dll (ie. ib becomes mpich2ib.dll)
- MPI_WRAP_DLL_NAME name of the dll that contains only the MPI interface, not the PMPI interface
- MPICH_TRMEM_INITZERO used by the memory tracing package
- MPICH_TRMEM_VALIDATE used by the memory tracing package
- MPITEST_DEBUG used by the test suite
- MPITEST_VERBOSE used by the test suite
- PATH used by smpd to search for executables under Unix.

SMPD options specified on the command line can also be specified in the environment by prefixing SMPD_OPTION_ to the option name and saving it as an environment variable.

- SMPD_OPTION_app_path
- SMPD_OPTION_logfile
- SMPD_OPTION_nocache
- SMPD_OPTION_phrase
- SMPD_OPTION_sspi_protect
- SMPD_OPTION_max_logfile_size
- SMPD_OPTION_plaintext
- SMPD_OPTION_port
- SMPD_OPTION_timeout
- SMPD_OPTION_exitcodes

- SMPD_OPTION_priority
- SMPD_OPTION_localonly
- SMPD_OPTION_noprompt
- SMPD_OPTION_channel
- SMPD_OPTION_hosts
- SMPD_OPTION_delegate
- SMPD_OPTION_internode_channel
- SMPD_OPTION_log
- SMPD_OPTION_no_dynamic_hosts

Variables to control debugging output when enabled:

- MPICH_DBG
- MPICH_DBG_CLASS
- MPICH_DBG_FILENAME
- MPICH_DBG_LEVEL
- MPICH_DBG_OUTPUT
- MPICH_DBG_RANK
- MPICH_DEBUG_ITEM

The following variables affect the MPE logging library:

- MPE_LOGFILE_PREFIX name of the clog file to create without the extension
- MPE_DELETE_LOCALFILE true, false delete or not the local clog file
- MPE_LOG_OVERHEAD I think this one adds an event to the clog files representing the time it takes to write a clog buffer to disk
- CLOG_BLOCK_SIZE number of bytes in a clog block

27

- CLOG_BUFFERED_BLOCKS number of blocks
- MPE_CLOCKS_SYNC yes/no synchronize clocks directories to store temporary files:
- MPE_TMPDIR
- TMPDIR
- TMP
- TEMP

PMI environment variables created by smpd are described in the smpd documentation:

- PMI_DLL_NAME name of the PMI dll to load (replaces the default smpd functions)
- PMI_NAMEPUB_KVS name of the key-val-space where MPI service names are stored for MPI_Lookup_name()
- PMI_ROOT_HOST
- PMI_ROOT_PORT
- PMI_ROOT_LOCAL
- PMI_SPAWN
- PMI_KVS
- PMI_DOMAIN
- PMI_RANK
- PMI_SIZE
- PMI_CLIQUE
- PMI_APPNUM
- PMI_SMPD_ID
- PMI_SMPD_KEY

- PMI_SMPD_FD
- PMI_HOST
- PMI_PORT
- PMI_APPNUM

Used by the process managers other than smpd:

- MPIEXEC_DEBUG
- MPIEXEC_MACHINES_PATH
- MPIEXEC_PORTRANGE
- MPIEXEC_PREFIX_STDERR
- MPIEXEC_PREFIX_STDOUT
- MPIEXEC_REMSHELL
- MPIEXEC_USE_PORT

9.10 Compiling

This section describes how to set up a project to compile an MPICH2 application using MS Visual Studio 6.0 or MS Developer Studio .NET 2003.

9.10.1 Visual Studio 6.0

Visual C++ 6.0 cannot handle multiple functions with the same type signature that only differ in their return type. So you must define HAVE_NO_VARIABLE_RETURN_TYPE_SUPPORT in your project.

- 1. Create a project and add your source files.
- 2. Bring up the settings for the project by hitting Alt F7. Select the Preprocessor Category from the C/C++ tab. Enter HAVE_NO_VARIABLE_RETURN_TYPE_SUPPORT into the Preprocessor box. Enter C:\Program Files\MPICH2\include into the "Additional include directories" box.

- 3. Select the Input Category from the Link tab. Add cxx.lib and mpi.lib to the Object/library modules box. Add C:\Program Files\MPICH2\lib to the "Additional library path" box.
- 4. Compile your application.

9.10.2 Developer Studio .NET 2003

For Developer Studio .NET 2003 or newer you can use the example projects provided with the release as a guide to creating your own projects.

- 1. Create a project and add your source files.
- 2. Bring up the properties dialog for your project by right clicking the project name and selecting Properties.
- 3. Navigate to Configuration Properties::C/C++::General
- 4. Add C:\Program Files\MPICH2\include to the "Additional Include Directories" box.
- 5. Navigate to Configuration Properties::Linker::General
- 6. Add C:\Program Files\MPICH2\lib to the "Aditional Library Directories" box.
- 7. Navigate to Configuration Properties::Linker::Input
- 8. Add cxx.lib and mpi.lib and fmpich2.lib to the "Additional Dependencies" box. If your application is a C application then it only needs mpi.lib. If it is a C++ application then it needs both cxx.lib and mpi.lib. If it is a Fortran application then it only needs one of the fmpich2[s,g].lib libraries. The fortran library comes in three flavors fmpich2.lib, fmpich2s.lib and fmpich2s.lib. fmpich2.lib contains all uppercase symbols and uses the C calling convention like this: MPI_INIT. fmpich2s.lib contains all uppercase symbols and uses the stdcall calling convention like this: MPI_INIT@4. fmpich2g.lib contains all lowercase symbols with double underscores and the C calling convention like this: mpi_init_.. Add the library that matches your Fortran compiler.
- 9. Compile your application.