## PS 46: Problem 4.25

The Boltzmann distribution is given by

$$P_S = \frac{1}{Z}e^{-\beta E_s} \tag{1}$$

where  $Z \equiv \sum_s e^{-\beta E_s}$  is the partition function. The probability that a system is in any microstate with energy E is

$$p(E) = \frac{\Omega(E)e^{-\beta E}}{\sum_{\text{levels}} \Omega(E)e^{-\beta E}}$$
 (2)

In the limit  $N, V \to \infty$ , the gap between adjacent energy levels becomes infinitesimal, so E can be considered a continuous variable. The probability that a system is in any microstate with energy between E and  $E + \mathrm{d}E$  is  $p(E)\,\mathrm{d}E$ . Let  $g(E)\,\mathrm{d}E$  be the number of microstates between E and  $E + \mathrm{d}E$ . The form of the probability distribution of the energy of a system in the canonical ensemble is

$$p(E) dE = \frac{g(E)e^{-\beta E} dE}{\int_0^\infty g(E)e^{-\beta E} dE}$$
(3)

where  $\beta \equiv \frac{1}{kT}$ .