# Sqitch-configuration - Hierarchical engine and target configuration - V1.0.0

## **Contents**

Description	3
Project Initialization	
Global Configuration	3
8	
Engine Configuration	3

#### **Description**

Simple description

The specification of database targets is core to Sqitch database change management. A target consists of a database connection URI, a plan file, change script directories, a registry schema or database name, and the path to a database engine command-line client. Sqitch determines the values for these attributes via a hierarchical evaluation of the runtime configuration, examining and selecting from these values:

- 1. Command-line options
- 2. Target-specific configuration
- 3. Engine-specific configuration
- 4. Core configuration
- 5. A reasonable default

This document explains how this evaluation works, and how to use the init, config, engine, and target commands to configure these values for various deployment scenarios

#### **Project Initialization**

- 1. Open your terminal
- 2. Run the command: sqitch init widgets --engine pg.
- 3. This command initializes a new project named "widgets" configured to manage PostgreSQL databases.

### **Global Configuration**

- 1. Open your terminal.
- 2. If the psql client is not in the path, specify its location: sqitch config --user engine.pg.client /usr/local/pgsql/bin/psql
- 3. This command sets the PostgreSQL client for all Sqitch projects you manage on your host.
- **4.** To configure this setting for all accounts on your host, run: sqitch config --system engine.pg.client /usr/local/pgsql/bin/psql
- 5. This will add the values to the global Sqitch configuration file located at sqitch --etc-path/sqitch.conf.

#### **Engine Configuration**

- 1. Create a subdirectory (e.g., pg) and move PostgreSQL-related files there. Create a subdirectory (e.g., pg) and move PostgreSQL-related files there.
- 2. Open your terminal.
- 3. Add the PostgreSQL engine to the configuration: sqitch engine add pg --client /usr/local/pgsql/bin/psql
- **4.** Set the top directory for the PostgreSQL engine: This command configures Sqitch to use the newly-created pg directory for PostgreSQL-related scripts.
- 5. To verify and view all the settings for the PostgreSQL engine, run: sqitch engine show pg
- 6. The show action displays the fully-evaluated configuration, showing the top directory and client settings.
- 7. To add SQLite support, run the command: sqitch engine add sqlite --client /path/to/sqlite3