Set 6
The Link Layer and LANs

implemented in nic

deliver packet to next physical

pdu called packet at this layer

mac address - physical address, added by link layer

Set 6: Link layer and LANs

our goals:

- understand principles behind link layer services:
  - error detection, correction
  - sharing a broadcast channel: multiple access
  - link layer addressing
  - local area networks: Ethernet, VLANs
- instantiation, implementation of various link layer technologies

Link layer, LANs: outline

6.1 introduction, services

6.2 error detection, correction

6.3 multiple access protocols

6.4 LANs

- addressing, ARP
- Ethernet
- switches
- VLANS

6.6 data center networking

6.7 a day in the life of a web request

Link layer: introduction

terminology:

- nodes: hosts and routers
- links: communication channels that connect adjacent nodes along communication path
  - wired links
  - wireless links
  - LANs
- layer-2 packet: frame, encapsulates datagram



data-link layer has responsibility of transferring datagram from one node to *physically adjacent* node over a link

Link layer: context

- datagram transferred by different link protocols over different links:
  - e.g., Ethernet on first link, frame relay on intermediate links, 802.11 on last link
- each link protocol provides different services

transportation analogy:

- trip from Princeton to Lausanne
  - limo: Princeton to JFK
  - plane: JFK to Geneva
  - train: Geneva to Lausanne
- tourist = datagram
- transport segment = communication link
- transportation mode = link layer protocol
- travel agent = routing algorithm

Link layer services

- basic service of the link layer is to move a datagram from one node to an adjacent node over a single link. Possible services offered by a link-layer protocol:
- *framing, link access*
  - encapsulate datagram into frame, adding header, trailer
  - channel access if shared medium
  - "MAC" addresses used in frame headers to identify source, destination
    - different from IP address!
- *reliable delivery between adjacent nodes*
  - we learned how to do this already (set 3)!
  - seldom used on low bit-error link (fiber, some twisted pair)
  - wireless links: high error rates
    - *Q:* why both link-level and end-end reliability?

Link layer services (more)

- *flow control:*
  - pacing between adjacent sending and receiving nodes
- *error detection:*
  - errors caused by signal attenuation, noise.
  - receiver detects presence of errors:
    - signals sender for retransmission or drops frame
- *error correction:*
  - receiver identifies *and corrects* bit error(s) without resorting to retransmission
- *half-duplex and full-duplex* walkie talkie vs phone call
  - with half duplex, nodes at both ends of link can transmit, but not at same time

Where is the link layer implemented?

- in each and every host
- link layer implemented in "adapter" (aka *network interface card* NIC) or on a chip
  - Ethernet card, 802.11 card; Ethernet chipset
  - implements link, physical layer
- attaches into host's system buses
- combination of hardware, software, firmware



Adapters communicating



- sending side:
  - encapsulates datagram in frame
  - adds error checking bits, rdt, flow control, etc.
- receiving side
  - looks for errors, rdt, flow control, etc.
  - extracts datagram, passes to upper layer at receiving side

Link layer, LANs: outline

6.1 introduction, services

6.2 error detection, correction

6.3 multiple access protocols

6.4 LANs

- addressing, ARP
- Ethernet
- switches
- VLANS

6.6 data center networking

6.7 a day in the life of a web request

three classes of error detection algorithms:

- parity
  - single parity
  - matrix parity
- checksum
- cyclic redundancy code

Error detection

larger edc = more error catching BUT higher overhead

NO algorithm can 100% detect errors

EDC= Error Detection and Correction bits (redundancy)
D = Data protected by error checking, may include header fields

- Error detection not 100% reliable!
  - protocol may miss some errors, but rarely
  - larger EDC field yields better detection and correction



Parity checking

single bit parity can only detect an odd amount of

rectangular error pattern will go undetected in 2d bit parity

single bit parity:

- detect single bit errors



two-dimensional bit parity:

- detect and correct single bit errors





Uncorrectable error pattern



no errors



correctable single bit error

Internet checksum (review)

goal: detect "errors" (e.g., flipped bits) in transmitted packet (note: used at transport layer only)

Internet checksum

- Typically, the checksum is included as a field in the header of a protocol data unit.
- To compute the checksum
  1. The checksum field is first set to all **zeros**
  2. Perform *ones-complement addition* of all the ***words*** (2 bytes) in the header
  3. Take *the ones-complement* of the result. This result is the checksum
- To verify a checksum
  1. Perform ones-complement addition of all the ***words*** (2 bytes) in the header *including the checksum field*
  2. If the result is all 1 bits (11111..111, *i*.e., FF…..FF in hex format), the check succeeds and no errors occur

1 hex digit is 4 binary bits, so 2 hex digit is 1 byte. we add 2 bytes at a time in chekcsum

Internet checksum

- Example: consider a header that consists of 10 octets (bytes), with the checksum in the last two octets with the following content (in hexadecimal)

  00 01 F2 03 F4 F5 F6 F7 **00 00**

  - Checksum result = 220D (compute and verify it!)

- The internet checksum provides greater error-detection capability than parity bit or two-dimensional parity scheme, but it less effective than cyclic redundancy check (CRC)

0000 0000 0000 0001 - 00 01
1111 0010 0000 0011 - F2 03

1111 0010 0000 0100
1111 0100 1111 0101 - F4 F5

1110 0110 1111 1001
1

1110 0110 1111 1010
1111 0110 1111 0111 - F6 F7

1101 1101 1111 0001
1

1101 1101 1111 0010 - take ones complement

0010 0010 0000 0010 - final checksum

Cyclic redundancy check

- It is one of the most common, and one of the most powerful error-detecting codes
- Given ***k***-bit message, the transmitter generates (***n-k***)-bit sequence known as frame check sequence (FCS), so the resulting frame consists of ***n*** bits
- The resulting ***n***-bit frame is *exactly divisible by* (i.e., no reminder) some predetermined number
- The receiver divides the incoming frame by that number and, if there is no reminder assumes no error

P -> length of this pattern is n - k + 1

long division and remainder -> CRC



Cyclic redundancy check

Modulo 2 Arithmetic

- Addition and subtraction operations are done using XOR operation

```
  1111          1111
+               -
  1010          1010
 ------        ----------
  0101          0101
```

```
   11001
x     11
 --------
   11001
  11001
 ----------
  101011
```

Cyclic redundancy check

Modulo 2 Arithmetic (cont.)

- Define
  - *D* = ***k***-bit block of data or message
  - *T* = ***n***-bit frame to be transmitted
  - *R* = (***n-k***)-bit FCS
  - *P* = pattern of (***n-k+1***) bits; this is the predetermined divisor
  - *T* is constructed as
- Steps
  1. Determine *k*, *n*, *n-k*
  2. Construct D00…0 (*n-k* zeros)
  3. Compute frame check sequence (**FCS**) *R* as the remainder of (D00…0)/P

Cyclic redundancy check

Modulo 2 Arithmetic (cont.)

- Example:
  - Message *D* = **10100011101** (10 bits) *k* = 10
  - Pattern *P* = **110101** (6 bits) *n-k+1* = 6
  - FCS *R*= ??? (After calculations FCS = **01110**). Note that *n-k* = 5 bits
  - Transmitted frame *T* = **10100011010110**
- If there are no errors, then divide *T* = **10100011010110** /*P* = 110101 gives no reminder
- Notes
  - The pattern *P* is chosen to be one bit longer than the FCS *R*
  - The receiver will fail to detect errors if and only if the received frame *that has errors* is divisible by *P*. Intuitively, this seems an unlikely occurrence.

Link layer, LANs: outline

6.1 introduction, services

6.2 error detection, correction

6.3 multiple access protocols

6.4 LANs

- addressing, ARP
- Ethernet
- switches
- VLANS

6.6 data center networking

6.7 a day in the life of a web request

Multiple access links, protocols

two types of "links":

- point-to-point
  - PPP for dial-up access
  - point-to-point link between Ethernet switch, host
- *broadcast (shared wire or medium)*
  - old-fashioned Ethernet
  - upstream HFC
  - 802.11 wireless LAN

shared wire (e.g., cabled Ethernet)

shared RF (e.g., 802.11 WiFi)



shared RF (satellite)

humans at a cocktail party (shared air, acoustical)

Multiple access protocols

- single shared broadcast channel
- two or more simultaneous transmissions by nodes: interference
  - *collision* if node receives two or more signals at the same time

multiple access protocol

- distributed algorithm that determines how nodes share channel, i.e., determine when node can transmit
- communication about channel sharing must use channel itself!
  - no out-of-band channel for coordination

MAC protocols: taxonomy

three broad classes:

- *channel partitioning*
  - divide channel into smaller "pieces" (time slots, frequency, code)
  - allocate piece to node for exclusive use
- *random access*
  - channel not divided, allow collisions
  - "recover" from collisions
- *"taking turns"*
  - nodes take turns, but nodes with more to send can take longer turns

channel partitioning: no possibility of collision
- TDMA
- FDMA

random access:
- ALOHA
- CSMA
- CSMA/CD, CSMA/CA

taking turns
- polling
- token

when many nodes have high load -> channel partitioning

when many nodes with low load -> random access

Channel partitioning MAC protocols: TDMA

TDMA: time division multiple access

- access to channel in "rounds"
- each station gets fixed length slot (length = packet transmission time) in each round
- unused slots go idle
- example: 6-station LAN, 1,3,4 have packets to send, slots 2,5,6 idle



slots can go unused

Channel partitioning MAC protocols: FDMA

FDMA: frequency division multiple access

- channel spectrum divided into frequency bands
- each station assigned fixed frequency band
- unused transmission time in frequency bands go idle



Random access protocols

- when node has packet to send
  - transmit at full channel data rate R.
  - no *a priori* coordination among nodes
- two or more transmitting nodes ➜ "collision",
- random access MAC protocol specifies:
  - how to detect collisions
  - how to recover from collisions (e.g., via delayed retransmissions)
- examples of random access MAC protocols:
  - slotted ALOHA
  - ALOHA
  - CSMA, CSMA/CD, CSMA/CA

Slotted ALOHA

assumptions:

- all frames same size
- time divided into equal size slots (time to transmit 1 frame)
- nodes start to transmit only slot beginning
- nodes are synchronized
- if 2 or more nodes transmit in slot, all nodes detect collision

operation:

- when node obtains fresh frame, transmits in next slot
  - *if no collision:* node can send new frame in next slot
  - *if collision:* node retransmits frame in each subsequent slot with prob. ***p*** until success

in aloha we do not
listen to link

Slotted ALOHA



Pros:

- single active node can continuously transmit at full rate of channel
- highly decentralized: only slots in nodes need to be in sync
- simple

Cons:

- collisions, wasting slots
- idle slots
- nodes may be able to detect collision in less than time to transmit packet
- clock synchronization

in csma we listen to
link before seding

CSMA (carrier sense multiple access)

CSMA: listen before transmit:

- if channel sensed idle: transmit entire frame
- if channel sensed busy, defer transmission

- human analogy: don't interrupt others!

CSMA collisions

- collisions *can* still occur: propagation delay means two nodes may not hear each other's transmission
- collision: entire packet transmission time wasted
  - distance & propagation delay play role in in determining collision probability



in normal csma transmission does not stop when collision occurs, only in CD, CA are collisions handled

CD used in wired networks
CA used in wireless networks

CSMA/CD (collision detection)

CSMA/CD: carrier sensing, deferral as in CSMA

- collisions *detected* within short time
- colliding transmissions aborted, reducing channel wastage

- collision detection:
  - easy in wired LANs: measure signal strengths, compare transmitted, received signals
  - difficult in wireless LANs: received signal strength overwhelmed by local transmission strength
- human analogy: the polite conversationalist

CSMA/CD (collision detection)



Ethernet CSMA/CD algorithm

1. NIC receives datagram from network layer, creates frame
2. If NIC senses channel idle, starts frame transmission. If NIC senses channel busy, waits until channel idle, then transmits.
3. If NIC transmits entire frame without detecting another transmission, NIC is done with frame !
4. If NIC detects another transmission while transmitting, aborts and sends jam signal
5. After aborting, NIC waits a random amount of time and then returns to step 2

collision detection: NIC has hardware that can detect that there is garbage on the link

"Taking turns" MAC protocols

channel partitioning MAC protocols:

- share channel *efficiently* and *fairly* at high load
- inefficient at low load: delay in channel access, 1/N bandwidth allocated even if only 1 active node!

random access MAC protocols

- efficient at low load: single node can fully utilize channel
- high load: collision overhead

"taking turns" protocols

look for best of both worlds!

"Taking turns" MAC protocols

taking turns algorithm 1

polling:

- master node "invites" slave nodes to transmit in turn
- typically used with "dumb" slave devices
- concerns:
  - polling overhead
  - latency
  - single point of failure (master)



"Taking turns" MAC protocols

taking turns algorithm 2

token passing:

- control *token* passed from one node to next sequentially.
- token message
- concerns:
  - token overhead
  - latency
  - single point of failure (token)

starvation



Summary of MAC protocols

- *channel partitioning,* by time, frequency or code
  - Time Division, Frequency Division
- *random access* (dynamic),
  - ALOHA, S-ALOHA, CSMA, CSMA/CD
  - carrier sensing: easy in some technologies (wire), hard in others (wireless)
  - CSMA/CD used in Ethernet
  - CSMA/CA used in 802.11
- *taking turns*
  - polling from central site, token passing
  - Bluetooth, FDDI, token ring

Link layer, LANs: outline

6.1 introduction, services

6.2 error detection, correction

6.3 multiple access protocols

6.4 LANs

- addressing, ARP
- Ethernet
- switches
- VLANS

6.6 data center networking

6.7 a day in the life of a web request

mac address to ssn like ip address to zip code

MAC addresses and ARP

- 32-bit IP address:
  - *network-layer* address for interface
  - used for layer 3 (network layer) forwarding
- MAC (or LAN or physical or Ethernet) address:
  - function: *used "locally" to get frame from one interface to another physically-connected interface (same network, in IP-addressing sense)*
  - 48 bit MAC address (for most LANs) burned in NIC ROM, also sometimes software settable
  - e.g.: 1A-2F-BB-76-09-AD

hexadecimal (base 16) notation
(each "numeral" represents 4 bits)

IEEE -> manufacturer -> NIC gives mac addresses
ICANN -> ISP -> network gives the IP addresses

LAN addresses and ARP

each node on LAN has unique *LAN/MAC* address



ARP is to DNS as
link layer is to
network layer

LAN addresses (more)

- MAC address allocation administered by IEEE
- manufacturer buys portion of MAC address space (to assure uniqueness)
- analogy:
  - MAC address: like Social Security Number
  - IP address: like postal address
- MAC flat address ➜ portability
  - can move LAN card from one LAN to another
- IP hierarchical address *not* portable
  - address depends on IP subnet to which node is attached

ARP: address resolution protocol

Question: how to determine the MAC address, knowing the IP address?



ARP table: each IP node (host, router) on LAN has table

- IP/MAC address mappings for some LAN nodes:

  < IP address; MAC address; TTL>

- TTL (Time To Live): time after which address mapping will be forgotten (typically 20 min)

ARP protocol: same LAN

- A wants to send datagram to B
  - B's MAC address not in A's ARP table.
- A broadcast ARP query packet, containing B's IP address
  - destination MAC address = FF-FF-FF-FF-FF-FF
  - all nodes on LAN receive ARP query
- B receives ARP packet, replies to A with its (B's) MAC address
  - frame sent to A's MAC address (unicast)
- A caches (saves) IP-to-MAC address pair in its ARP table until information becomes old (times out)
  - soft state: information that times out (goes away) unless refreshed
- ARP is "plug-and-play":
  - nodes create their ARP tables *without intervention from net administrator*

Addressing: routing to another LAN

walkthrough: send datagram from A to B via R

- focus on addressing – at IP (datagram) and MAC layer (frame)
- assume A knows B's IP address (*how*?)
- assume A knows IP address of first hop router, R (*how*?)
- assume A knows R's MAC address (*how*?)



Addressing: routing to another LAN

- A creates IP datagram with IP source A, destination B
- A creates link-layer frame with R's MAC address as destination address, frame contains A-to-B IP datagram



Addressing: routing to another LAN

- frame sent from A to R
- frame received at R, datagram removed, passed up to IP



Addressing: routing to another LAN

- R forwards datagram with IP source A, destination B
- R creates link-layer frame with B's MAC address as destination address, frame contains A-to-B IP datagram



Addressing: routing to another LAN

- R forwards datagram with IP source A, destination B
- R creates link-layer frame with B's MAC address as destination address, frame contains A-to-B IP datagram



Addressing: routing to another LAN

- R forwards datagram with IP source A, destination B
- R creates link-layer frame with B's MAC address as dest, frame contains A-to-B IP datagram



* Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose_ross/interactive/

Link layer, LANs: outline

6.1 introduction, services

6.2 error detection, correction

6.3 multiple access protocols

6.4 LANs

- addressing, ARP
- Ethernet
- switches
- VLANS

6.6 data center networking

6.7 a day in the life of a web request

Ethernet

"dominant" wired LAN technology:

- single chip, multiple speeds (e.g., Broadcom BCM5761)
- first widely used LAN technology
- simpler, cheap
- kept up with speed race: 10 Mbps – 10 Gbps



Metcalfe's Ethernet sketch

Ethernet: physical topology

- *bus:* popular through mid 90s
  - all nodes in same collision domain (can collide with each other)
- *star:* prevails today
  - active *switch* in center
  - each "spoke" runs a (separate) Ethernet protocol (nodes do not collide with each other)



bus: coaxial cable



star

Ethernet frame structure

sending adapter encapsulates IP datagram (or other network layer protocol packet) in Ethernet frame

preamble:

- 7 bytes with pattern 10101010 followed by one byte with pattern 10101011
- used to synchronize receiver, sender clock rates

Ethernet frame structure (more)

- *addresses:* 6 byte source, destination MAC addresses
  - if adapter receives frame with matching destination address, or with broadcast address (e.g. ARP packet), it passes data in frame to network layer protocol
  - otherwise, adapter discards frame
- *type:* indicates higher layer protocol (mostly IP but others possible, e.g., Novell IPX, AppleTalk)
- *CRC:* cyclic redundancy check at receiver
  - error detected: frame is dropped

Ethernet: unreliable, connectionless

- *connectionless:* no handshaking between sending and receiving NICs
- *unreliable:* receiving NIC doesn't send acks or nacks to sending NIC
  - data in dropped frames recovered only if initial sender uses higher layer rdt (e.g., TCP), otherwise dropped data lost
- Ethernet's MAC protocol: unslotted *CSMA/CD with binary backoff*

802.3 Ethernet standards: link & physical layers

- *many* different Ethernet standards
  - common MAC protocol and frame format
  - different speeds: 2 Mbps, 10 Mbps, 100 Mbps, 1Gbps, 10 Gbps, 40 Gbps
  - different physical layer media: fiber, cable



Link layer, LANs: outline

6.1 introduction, services

6.2 error detection, correction

6.3 multiple access protocols

6.4 LANs

- addressing, ARP
- Ethernet
- switches
- VLANS

6.6 data center networking

6.7 a day in the life of a web request

Ethernet switch

- link-layer device: takes an *active* role
  - store, forward Ethernet frames
  - examine incoming frame's MAC address, selectively forward frame to one-or-more outgoing links when frame is to be forwarded on segment, uses CSMA/CD to access segment
- *transparent*
  - hosts are unaware of presence of switches
- *plug-and-play, self-learning*
  - switches do not need to be configured

Switch: *multiple* simultaneous transmissions

- hosts have dedicated, direct connection to switch
- switches buffer packets
- Ethernet protocol used on *each* incoming link, but no collisions; full duplex
  - each link is its own collision domain
- *switching:* A-to-A' and B-to-B' can transmit simultaneously, without collisions



switch with six interfaces (1,2,3,4,5,6)

Switch forwarding table

Q: how does switch know A' reachable via interface 4, B' reachable via interface 5?

- A: each switch has a switch table, each entry:
  - (MAC address of host, interface to reach host, time stamp)
  - looks like a routing table!

Q: how are entries created, maintained in switch table?

- something like a routing protocol?



switch with six interfaces (1,2,3,4,5,6)

Switch: self-learning

- switch *learns* which hosts can be reached through which interfaces
  - when frame received, switch "learns" location of sender: incoming LAN segment
  - records sender/location pair in switch table



MAC addr	interface	TTL
A	*1*	*60*

Switch table (initially empty)

Switch: frame filtering/forwarding

when frame received at switch:

1. record incoming link, MAC address of sending host
2. index switch table using MAC destination address
3. if entry found for destination
   then {
   if destination on segment from which frame arrived
      then drop frame
      else forward frame on interface indicated by entry
   }
   else flood /* forward on all interfaces except arriving
                 interface */

Self-learning, forwarding: example

- frame destination, A', location unknown: *flood*
- destination A location known: selectively send on just one link



MAC addr	interface	TTL
A	*1*	*60*
A'	*4*	*60*

switch table (initially empty)

Institutional network



Switches vs. routers

both are store-and-forward:

- *routers:* network-layer devices (examine network-layer headers)
- *switches*: link-layer devices (examine link-layer headers)

both have forwarding tables:

- *routers:* compute tables using routing algorithms, IP addresses
- *switches:* learn forwarding table using flooding, learning, MAC addresses



Switches vs. routers

Comparison of the typical features of popular interconnection devices

	Hubs	Routers	Switches
Traffic isolation	No	Yes	Yes
Plug and play	Yes	No	Yes
Optimal routing	No	Yes	No

- Typically, small networks ⟶ switches
- Typically, large networks ⟶ routers (in addition to switches)

VLANs: motivation



consider:

- CS user moves office to EE, but wants connect to CS switch?
- single broadcast domain:
  - all layer-2 broadcast traffic (ARP, DHCP, unknown location of destination MAC address) must cross entire LAN
  - security/privacy, efficiency issues
- use of switches: at least 1 per department

VLANs

Virtual Local Area Network

switch(es) supporting VLAN capabilities can be configured to define multiple ***virtual*** LANS over single physical LAN infrastructure.

port-based VLAN: switch ports grouped (by switch management software) so that *single* physical switch ……



… operates as multiple virtual switches



Port-based VLAN

- *traffic isolation:* frames to/from ports 1-8 can *only* reach ports 1-8
  - can also define VLAN based on MAC addresses of endpoints, rather than switch port
- dynamic membership: ports can be dynamically assigned among VLANs
- forwarding between VLANS: done via routing (just as with separate switches)
  - in practice vendors sell combined switches plus routers



VLANS spanning multiple switches



Electrical Engineering
(VLAN ports 1-8)

Computer Science
(VLAN ports 9-15)

Ports 2,3,5 belong to EE VLAN
Ports 4,6,7,8 belong to CS VLAN

- *trunk port:* carries frames between VLANS defined over multiple physical switches.
- How does a switch know that a frame arriving on a trunk port belongs to a particular VLAN?
  - frames forwarded within VLAN between switches can't be vanilla 802.1 frames (must carry VLAN ID info)
  - 802.1q protocol adds/removes additional header fields for frames forwarded between trunk ports

802.1Q VLAN frame format



Link layer, LANs: outline

6.1 introduction, services

6.2 error detection, correction

6.3 multiple access protocols

6.4 LANs

- addressing, ARP
- Ethernet
- switches
- VLANS

6.6 data center networking

6.7 a day in the life of a web request

Data center networks

- 10's to 100's of thousands of hosts, often closely coupled, in close proximity:
  - e-business (e.g. Amazon)
  - content-servers (e.g., YouTube, Akamai, Apple, Microsoft)
  - search engines, data mining (e.g., Google)
- challenges:
  - multiple applications, each serving massive numbers of clients
  - managing/balancing load, avoiding processing, networking, data bottlenecks

Inside a 40-ft Microsoft container, Chicago data center

Data center networks

load balancer: application-layer routing

- receives external client requests
- directs workload within data center
- returns results to external client (hiding data center internals from client)



Data center networks

- rich interconnection among switches, racks:
  - increased throughput between racks (multiple routing paths possible)
  - increased reliability via redundancy



Link layer, LANs: outline

6.1 introduction, services

6.2 error detection, correction

6.3 multiple access protocols

64 LANs

- addressing, ARP
- Ethernet
- switches
- VLANS

6.6 data center networking

6.7 a day in the life of a web request

Synthesis: a day in the life of a web request

- journey down protocol stack complete!
  - application, transport, network, link
- putting-it-all-together: synthesis!
  - *goal:* identify, review, understand protocols (at all layers) involved in seemingly simple scenario: requesting www page
  - *scenario:* student attaches laptop to campus network, requests/receives www.google.com

A day in the life: scenario



A day in the life… connecting to the Internet



- connecting laptop needs to get its own IP address, addr of first-hop router, addr of DNS server: use *DHCP*
- DHCP request encapsulated in UDP, encapsulated in IP, encapsulated in 802.3 Ethernet
- Ethernet frame broadcast (dest: FFFFFFFFFFFF) on LAN, received at router running DHCP server
- Ethernet demuxed to IP demuxed, UDP demuxed to DHCP

A day in the life… connecting to the Internet



- DHCP server formulates *DHCP ACK* containing client's IP address, IP address of first-hop router for client, name & IP address of DNS server
- encapsulation at DHCP server, frame forwarded (switch learning) through LAN, demultiplexing at client
- DHCP client receives DHCP ACK reply

Client now has IP address, knows name & addr of DNS server, IP address of its first-hop router

A day in the life… ARP (before DNS, before HTTP)



- before sending *HTTP* request, need IP address of www.google.com: *DNS*
- DNS query created, encapsulated in UDP, encapsulated in IP, encapsulated in Eth. To send frame to router, need MAC address of router interface: ARP
- ARP query broadcast, received by router, which replies with ARP reply giving MAC address of router interface
- client now knows MAC address of first hop router, so can now send frame containing DNS query

A day in the life… using DNS



- IP datagram containing DNS query forwarded via LAN switch from client to 1st hop router
- IP datagram forwarded from campus network into Comcast network, routed (tables created by RIP, OSPF, IS-IS and/or BGP routing protocols) to DNS server
- demuxed to DNS server
- DNS server replies to client with IP address of www.google.com

A day in the life…TCP connection carrying HTTP



- to send HTTP request, client first opens TCP socket to web server
- TCP SYN segment (step 1 in 3-way handshake) inter-domain routed to web server
- web server responds with TCP SYNACK (step 2 in 3-way handshake)
- TCP connection established!

A day in the life… HTTP request/reply



- web page finally (!!!) displayed

- HTTP request sent into TCP socket
- IP datagram containing HTTP request routed to www.google.com
- web server responds with HTTP reply (containing web page)
- IP datagram containing HTTP reply routed back to client

Set 6: Summary

- principles behind data link layer services:
  - error detection, correction
  - sharing a broadcast channel: multiple access
  - link layer addressing
- instantiation and implementation of various link layer technologies
  - Ethernet
  - switched LANS, VLANs
- synthesis: a day in the life of a web request

Set 6: let's take a breath

- journey down protocol stack *complete* (except PHY)
- solid understanding of networking principles, practice
- ….. could stop here …. but *lots* of interesting topics!
  - wireless
  - multimedia
  - security