



PDS - The Swiss Army Knife of Utilities

Session 2837

August 14, 2006

Thomas Conley

Pinnacle Consulting Group, Inc. (PCG)

59 Applewood Drive

Rochester, NY 14612-3501

P: (585)720-0012

F: (585)723-3713

pinncons@rochester.rr.com

http://home.rochester.rr.com/pinncons

© Pinnacle Consulting Group, Inc., 2006. All rights reserved.. Permission granted to SHARE to distribute for SHARE 107.









Wish I Had One!







Legal & Acknowledgement

- Swiss Army[™] is the registered trademark of Victorinox AG and subsidiaries, and is used here with their kind permission
- Thanks to John Kalinich at Computer Sciences Corporation; this presentation is largely based on material he prepared





- History
- Installing PDS
- Learning to Use PDS
- PDSE Support
- Member Groups
- Getting Started
- PDS Subcommands





- Miscellaneous Commands
- Summary
- Finally...



History

- PDS was designed to manipulate partitioned data sets (PDS's)
- Originally written in 1972 at Fireman's Fund Insurance by Tom Springer
- From 1977 to 1990, Bruce Leland and Steve Smith made extensive modifications to PDS
- In 1997, John Kalinich contributed modifications to the PDS command for Year 2000



History

- In 2005, Greg Price and John Kalinich added PDSE support
- The PDS command code base has grown from 3,500 to over 50,000 lines of code
- John Kalinich currently supports PDS; send him an Email at <u>ikalinic@csc.com</u> with your comments, concerns, suggestions, enhancements, etc. for PDS



- Download File 182 from http://www.cbttape.org
 to obtain the PDS to install PDS
- Binary FTP or upload to MVS bin file with attributes (DSORG=PS,LRECL=80).
- Issue TSO RECEIVE INDATASET(bin) and respond to prompts to create install PDS
- Review and follow instructions in the \$\$\$\$INST member.



- Edit member #PDSGEN (and #PDSGENB if required) to set PDS global assembler variables according to instructions in each member
- An alternative to updating #PDSGEN is to uncomment the COPY statement for #PDSGENU (at the end of #PDSGEN) and make your changes in that user member (this is the current default)



- Run job PDSJCLHL to assemble and link edit the PDS load module into a PDS load library
- Run job PDSPJCL to copy the ISPF panels and message members
- Copy member PDSHELP to a SYSHELP dataset. Rename it to PDS86 with aliases of PDS and PDSE



 To install the PDS related command processors, issue RECEIVE INDS(install.pds(UTILXMIT)) and respond to prompts to create the following load modules in the PDS load library:

BLKDISK, COMPARE*, DELINKI, DISASM, DSAT, DVOL, HEL, OFFLOAD, RELEASE, REVIEW and VTOC

 While not required, the above commands offer significant extended functions for PDS



- Tailor PDS LIBDEF CLIST in PDSLIBDF member
- Add Option P to an ISPF selection panel:

)BODY
P PDS Command - Invoke PDS
)PROC
P,'CMD(%PDSLIBDF) SCRNAME(PDS)'

 Can run as TSO command processor if placed in TSOLIB/STEPLIB/LINKLIST (e.g. TSO %PDS)



Learning to Use PDS

- Read "Effective use of the PDS command" (member \$\$\$PROSE on the install PDS) by Bruce Leland
- Read "Public MVS Software The PDS Program" by Sam Golob (members \$PDSART1-3)
- Read the TSO Help member for PDS (member PDSHELP)
- This presentation (member \$\$\$2837)



PDSE Support

- PDSE's have been difficult to support due to IBM's proprietary IGWFAMS interface
- In 2005, Greg Price and John Kalinich added PDSE support using standard access methods
- PDS uses QSAM to read PDSE directories and BPAM to read/write PDSE members
- Apply OA13747 to fix S0C4's in PDSE dataspace (thanks to Greg Price for this APAR)



PDSE Support

- Apply OA13224 to allow DISP=SHR for STOW INITIALIZE (thanks to John Kalinich for this APAR)
- STOW INITIALIZE will reset a PDS directory, but it requires exclusive access for a PDS
- PDSE provides its own serialization, so this APAR relaxes the exclusive requirement for PDSE datasets



PDSE Support

 The following subcommands are not supported for PDSE data sets:

| Subcommand | PDSE Type | Reason |
|-----------------|----------------|------------|
| | | |
| RESTORE | Data | IBM design |
| RESTORE | Program Object | IBM design |
| REPLACE | Program Object | IBM design |
| ALIAS | Program Object | Binder API |
| ATTRIB lkedattr | Program Object | Binder API |
| REPRO | Program Object | Binder API |



- Many PDS commands allow lists or groups of members to be specified
- You can specify ranges of members, matching patterns, discrete member names, or any combination of the above



- ":" (colon) represents all members
- memlist :

| – DS | N=SYS2.PD | S.INSTALL, | VOL=SER=O | S39M1 MEM | =: | | | | |
|------|----------------|------------|-----------|-----------|----------|-------|------|------|--------|
| CMD | NAME | DATA | VER.MOD | CREATED | LAST MOD | IFIED | SIZE | INIT | ID |
| | \$\$\$\$\$\$\$ | | 01.00 | 97/11/24 | 97/11/24 | 7:38 | 6 | 6 | TRIDJK |
| | \$\$\$\$READ | | | | | | | | |
| | \$\$\$\$REA1 | | ALIAS | | | | | | |
| | \$\$\$BUGS | | 01.05 | 03/04/08 | 03/08/04 | 12:09 | 531 | 530 | TRIDJK |
| | \$\$\$CTBL | | 01.10 | 92/01/29 | 05/08/10 | 8:34 | 174 | 174 | TRIDJK |
| | \$\$\$CUSTM | Ι | 01.40 | 98/03/16 | 05/12/28 | 10:45 | 384 | 336 | TRIDJK |
| | \$\$\$CUT | | 01.03 | 98/01/27 | 98/06/17 | 8:02 | 105 | 100 | TRIDJK |



- "*" (asterisk) represents the current sublist
- sublist a*;memlist *



- "mem1:mem2" defines a range starting with mem1, ending with names starting with mem2
- memlist @al:@cl reset

| - DS | - DSN=SYS2.PDS.INSTALL, VOL=SER=OS39M1 MEM=@AL:@CL | | | | | | | | |
|------|--|------|---------|----------|----------------|------|------|--------|--|
| CMD | NAME | DATA | VER.MOD | CREATED | LAST MODIFIED | SIZE | INIT | ID | |
| | @ALIAS | | 01.19 | 99/07/16 | 06/01/03 15:20 | 169 | 158 | TRIDJK | |
| | @ATTRIB | | 01.79 | 98/01/15 | 06/01/04 13:58 | 1579 | 1413 | TRIDJK | |
| | @BROWSE | | 01.06 | 99/07/16 | 06/01/11 8:14 | 520 | 515 | TRIDJK | |
| | @CHANGE | | 01.00 | 99/07/16 | 99/07/16 9:34 | 35 | 35 | TRIDJK | |
| | @CLEAR | | 01.00 | 99/07/16 | 99/07/16 9:34 | 45 | 45 | TRIDJK | |



- "mem1/mem2" defines a pattern where mem1 and mem2 are anywhere in the member name
- memlist @/pds reset

| - DS | - DSN=SYS2.PDS.INSTALL, VOL=SER=OS39M1 MEM=@/PDS | | | | | | | | |
|------|--|------|---------|----------|----------------|------|------|--------|--|
| CMD | NAME | DATA | VER.MOD | CREATED | LAST MODIFIED | SIZE | INIT | ID | |
| | @FIXPDS | | 01.34 | 99/07/16 | 06/02/22 14:14 | 1000 | 906 | TRIDJK | |
| | @PDSMAIN | Ī | 01.99 | 98/10/13 | 06/02/22 14:32 | 5378 | 4869 | TRIDJK | |
| | @PDSMODS | | 01.99 | 02/12/18 | 06/02/22 14:22 | 212 | 35 | TRIDJK | |
| | PDS@PRIM | I | 01.24 | 00/03/20 | 05/09/30 7:38 | 261 | 223 | TRIDJK | |



- "mem1*mem2" defines a pattern where mem1 precedes mem2 in the member name
- memlist @*pds reset

| - DSN=SYS2.PDS.INSTALL, VOL=SER=OS39M1 MEM=@*PDS | | | | | | | | | |
|--|----------|------|---------|----------|----------------|------|------|--------|--|
| CMD | NAME | DATA | VER.MOD | CREATED | LAST MODIFIED | SIZE | INIT | ID | |
| | @FIXPDS | | 01.34 | 99/07/16 | 06/02/22 14:14 | 1000 | 906 | TRIDJK | |
| | @PDSMAIN | Ī | 01.99 | 98/10/13 | 06/02/22 14:32 | 5378 | 4869 | TRIDJK | |
| | @PDSMODS | | 01.99 | 02/12/18 | 06/02/22 14:22 | 212 | 35 | TRIDJK | |



- Combinations can also be specified
- memlist (a:b, tso/, pdshelp) reset

| - DS | SN=SYS2.PD | S.INSTALL, | , VOL=SER=O | S39M1 MEM | =(A:B | | | | | |
|------|------------|------------|-------------|-----------|----------|-------|------|------|--------|--|
| CMD | NAME | DATA | VER.MOD | CREATED | LAST MOD | IFIED | SIZE | INIT | ID | |
| | @TSO | | 01.00 | 99/07/16 | 99/07/16 | 9:34 | 175 | 175 | TRIDJK | |
| | @TSOEDIT | | 01.00 | 99/07/16 | 99/07/16 | 9:34 | 156 | 156 | TRIDJK | |
| | ABEHELP | | | | | | | | | |
| | PDSHELP | | 01.99 | 97/09/25 | 06/01/13 | 11:59 | 6359 | 5972 | TRIDJK | |
| | P85VTSO | | | | | | | | | |
| | P86VTSO | | | | | | | | | |
| | VTSOPCF | | | | | | | | | |
| | VTSORACF | | 01.00 | 05/11/17 | 05/11/17 | 9:51 | 234 | 234 | TRIDJK | |
| | | | | | | | | | | |





SHARE. ORG

Execute the PDSLIBDF CLIST to start PDS

```
RefList RefMode Options Help
                     PDS Version 8.6
Option ===>
   I - Enter ISPMODE
   M - Enter MEMLIST with the identified MEMBERS
   L - Enter Line mode
 SET - Set default options prompt
blank - Enter MEMLIST if any member data is entered; ISPMODE otherwise
ISPF Library:
  Project ===> TCONLEY
  Library ===> TSO
  Type ===> JCL
  Members ===>
                            (set to * or a member group to use MEMLIST)
Other Partitioned or Sequential Data Set or FILE(ddname):
  Data Set Name ===> sys2.pds.install
  Volume Serial ===> (If not cataloged)
  MEMLIST Prompt ===> NO (yes/no for a MEMLIST prompt panel)
  PDS PGM Name ===> PDS86 (latest: PDS86)
```

SHARE Technology · Connections · Results

SHARE. ORG

PDS log is displayed

Getting Started

PDS300A ENTER OPTION -- DSN=SYS2.PDS.INSTALL, VOL=SER=OS39M1 MEM=

Getting Started



SHARE. ORG

Enter "6" for MEMLIST all

```
COMMAND ===>
                                               SCROLL ===> CSR
Enter an ISPF command, a PDS subcommand or a special control code:
  8 View log 1 Suspend ISPF 6 MEMLIST all F Find R Recall
 LA Lista 4 Sublist = 7 Output table L Locate SO Sort
 LV Listv 5 Check aliases 9 Swap panels 0 Options X Above/Below/Al
- DSN=SYS2.PDS.INSTALL, VOL=SER=OS39M1 MEM=: ------
CMD NAME
           DATA
                 VER MOD
                          CREATED LAST MODIFIED
                                             SIZE
                01.00 97/11/24 97/11/24 7:38 6 6 TRIDJK
    $$$$$$$$
    $$$READ
    $$$$REA1
                  ALIAS
    $$$BUGS
             01.05 03/04/08 03/08/04 12:09 531 530
                                                      TRIDJK
```

© Pinnacle Consulting Group, Inc., 2006. All rights reserved. Permission granted to SHARE to distribute for SHARE 107.



 ATTRIB displays and modifies load module attributes or member statistics

Attributes for load modules:

AMODE 24/AMODE 31/AMODE 64/AMODE ANY

AUTH/NOAUTH or APF/NOAPF

DC/NODC EDIT/NOEDIT

ENTRY (entryname) EXEC/NOEXEC

LOADONLY/NOLOADONLY PAGE/NOPAGE

REFR/NOREF RENT/NORENT

REUS/NOREUS RLDFIX/NORLDFIX

RMODE24/RMODEANY SSI(hexdata)/NOSSI

UNALIAS NONE

ALIASINFO/NOALIASINFO LKEDDATE/NOLKEDDATE



Attributes for regular PDS members:

```
ADDSTATS
            - create ISPF statistics if none are present
VER(num) - reset the ISPF version number
MOD(num) - reset the ISPF modification level
ID(userid) - reset the ISPF userid
CREATED(mm/dd/yy) - reset the ISPF creation date
LAST(mm/dd/yy) - reset the ISPF last modification date
TIME(hhmm) - reset the ISPF last modification time
               - reset the ISPF last modification time
SECS(ss)
UNALIAS - remove any alias attribute
SSI(hexval) - assign the hexadecimal SSI information
NOSSI
        - remove any existing SSI information
NONE - remove any existing SSI or ISPF attribute information
ALIASINFO - provide alias name information
NOALIASINFO - do not provide alias name information
```



attrib pds86



attrib pds86 norent noreus norefr

```
- DSN=SYS2.PDS.LOAD, VOL=SER=OS39M2 MEM=PDS86
>attrib pds86 norent

PDS020I PDS86 ATTRIBUTES ARE: NONE
PDS024I PAGE ALIGNMENT IS REQUIRED
PDS102I ENTRY POINT AT 000000

PDS104I MODULE LENGTH 040C10 -- 260K
PDS064I LAST LINK-EDITED ON 3/04/06 BY LKED 5695PMB01 V01 M03 AT 15:18:54
PDS160I ALIASES FOR THIS MEMBER ARE: PDS
```



attrib pdsjclhl

attrib pdsjclhl ver(2) mod(02) id(tconley)



PDS Subcommands - ALIAS

- ALIAS can assign an ALIAS name to a main member in a PDS
- alias \$\$\$\$read \$\$\$\$rea1



PDS Subcommands - BROWSE

- BROWSE opens a PDS member in ISPF BROWSE mode
- browse \$\$\$\$read



PDS Subcommands - CHANGE

- CHANGE changes the dataset that PDS is working on
- c 'sys2.pds.load'



PDS Subcommands - COMPARE

- COMPARE compares two members using SUPERC
- compare adyset01 adyset02

```
- DSN=ADCD.ZOSV14W.PARMLIB,VOL=SER=W4RES1 MEM=ADYSET02
>compare adyset01 adyset02
1 ISRSUPC - MVS/PDF FILE/LINE/WORD/BYTE/SFOR COMPARE UTILITY- ISPF FOR z/OS
                                                                                     2006/03/08 2.00 PAGE
NEW: ADCD.ZOSV14W.PARMLIB(ADYSET02)
                                                           OLD: ADCD.ZOSV14W.PARMLIB(ADYSET01)
                    LISTING OUTPUT SECTION (LINE COMPARE)
ID
         SOURCE LINES
                                                                                  TYPE LEN N-LN# O-LN#
                                                                             MAT=
 I - * START PARAMETERS.
                                                                          00100000 RPL=
                                                                                          1 00002 00002
D - * STOP PARAMETER.
                                                                          00100000
```



PDS Subcommands - COMPRESS

SHARE. ORG

- COMPRESS performs an IEBCOPY compress
- compress shr (undocumented option "SHR" bypasses ENQ, good for hosing LINKLIST)




PDS Subcommands - CONTROL

- CONTROL specifies PDS processing options, like sysout class, prompting, etc.
- control noprompt (turns off prompting for PDS)



PDS Subcommands - CONTROL

control mods (shows PDS enhancements)





PDS Subcommands - COPY

- COPY copies member(s) to another dataset
- Copy ady* tconley.tso.jcl

```
- DSN=ADCD.ZOSV14W.PARMLIB,VOL=SER=W4RES1 MEM=ADY*
>copy ady* tconley.tso.jcl
PDS484W COPY IS IN PROGRESS
IEB11351 IEBCOPY FMID HDZ11GO SERVICE LEVEL UA05363 DATED 20030923 DFSMS 01.03.00 z/OS 01.04.00 HBB7707 CPU 7490
IEB10351 TCONLEY ISPFPROC ISPFPROC 02:11:56 WED 08 MAR 2006 PARM="
        O=SYS00019, I=SYS00006
S M=ADYSET00, ADYSET01, ADYSET02
IEB1013I COPYING FROM PDS INDD=SYS00006 VOL=W4RES1 DSN=ADCD.ZOSV14W.PARMLIB
TEB1014T
                  TO PDS OUTDD=SYS00019 VOL=XS39M1 DSN=TCONLEY.TSO.JCL
IEB1671 FOLLOWING MEMBER(S) COPIED FROM INPUT DATA SET REFERENCED BY SYS00006
IEB154I ADYSET00 HAS BEEN SUCCESSFULLY COPIED
IEB154I ADYSET01 HAS BEEN SUCCESSFULLY COPIED
IEB154I ADYSET02 HAS BEEN SUCCESSFULLY COPIED
IEB1098I 3 OF 3 MEMBERS COPIED FROM INPUT DATA SET REFERENCED BY SYS00006
IEB1441 THERE ARE 11 UNUSED TRACKS IN OUTPUT DATA SET REFERENCED BY SYS00019
IEB1491 THERE ARE 23 UNUSED DIRECTORY BLOCKS IN OUTPUT DIRECTORY
TEB147T END OF JOB - 0 WAS HIGHEST SEVERITY CODE
```



PDS Subcommands - DCF

DCF prints a hardcopy using TSO SCRIPT

```
SCRIPT Subcommand -----
               ---- O.DCF
OPTION ===>
Enter the member group name and any operands below for DCF:
Operands: memgroup
                        (e.g., *; start:end; start:; first*pat; range*; part/)
BIND(obind {ebind})
                                      PAGE{({PROMPT}{{FROM} p {TO} q}
 CHARS (font1..font4)
                                            {{FROM} p FOR n}{{FROM} p ONLY})}
 CONTINUE/NOCONT
                                      PRINT{(copies, class, fcb, ucs)}
                                      PROFILE { (fileid) } / NOPROFILE
 CTF
 DDUT/NODDUT
                                      OUIET
 DEST(station-id)
                                      SEARCH(libname) (opnum...)
 DEVICE (devtype)
                                      SEGLIB/NOSEGLIB
 FILE{(fileid)}
                                      SPELLCHK
 FONTLIB({filetype}{filemodel})
                                      STOP
FPASSES n
                                      SYON/SYOFF
                                      SYSVAR(n value...)
 INDEX
LIB(libename...) (opnum...)
                                      TERM
MESSAGE({DELAY}{D}{TRACE})
                                      TLIB
NOSPIE
                                      TWOPASS
 NOWAIT
                                      UNFORMAT
 NUMBER
                                      UPCASE
 OPTIONS { (fileid) }
                                      @user-option
```



PDS Subcommands - DELETE

- DELETE deletes members from a PDS
- del tom*

```
- DSN=TCONLEY.TSO.JCL, VOL=SER=XS39M1 MEM=TOM* ------>del tom*

PDS162I MEMBERS TO BE DELETED ARE: TOMNEW, TOMOLD

PDS394A SHOULD ALL OF THESE MEMBERS BE DELETED (Y/N) ?

>y

PDS040I TOMOLD HAS BEEN DELETED

PDS040I TOMNEW HAS BEEN DELETED
```



dir pds (for a load module)



| PDS262I | 10 | PDS2TTRN | 000000,00 | (NOT USED FOR THIS MEMBER) |
|---------|----|----------|-----------|--|
| PDS262I | 14 | PDS2ATR1 | C2 | REENTRANT; REUS; NOT OVERLAY; NOT TEST |
| PDS262I | | | | NOT ONLY LOAD; NOT SCATTER; EXEC; NOT 1 TEXT |
| PDS262I | 15 | PDS2ATR2 | E3 | NOT DC; TEXT ORG=0; EP=0; HAS RLDS |
| PDS262I | | | | EDIT; NOT TEST; LKED F; REFRESHABLE |
| PDS262I | 16 | PDS2STOR | 260K | TOTAL CONTIGUOUS MAIN STORAGE REQUIRED |
| PDS262I | 19 | PDS2FTBL | 31,032. | LENGTH OF FIRST BLOCK OF TEXT |
| PDS262I | 1B | PDS2EPA | 000000 | ENTRY POINT ADDRESS |
| PDS262I | 1E | PDS2FTB1 | A8 | PROCESSED BY OS/VS LINKAGE EDITOR |
| PDS262I | | | | PAGE ALIGNMENT REQUIRED |
| PDS262I | | | | APF INFORMATION IS VALID |
| PDS262I | 1F | PDS2FTB2 | 00 | RMODE 24; ALIAS AMODE 24; MAIN AMODE 24 |
| PDS262I | 20 | PDS2FTB3 | 02 | RLD/CONTROL RECORDS AFTER FIRST TEXT BLOCK |
| PDS262I | 21 | PDS2EPM | 000000 | ENTRY POINT OF MAIN MEMBER |
| PDS262I | 24 | PDS2MNM | PDS86 | MEMBER NAME OF MAIN MEMBER |
| PDS262I | 2C | PDSAPFCT | 01 | LENGTH OF PROGRAM AUTHORIZATION CODE |
| PDS262I | 2D | PDSAPFAC | 00 | PROGRAM AUTHORIZATION CODE |

[©] Pinnacle Consulting Group, Inc., 2006. All rights reserved. Permission granted to SHARE to distribute for SHARE 107.



 New for PDS 8.6.04, Large Program Object (LPO) support

```
22 PDSSSIWD 01117795 SSI INFORMATION
26 PDS2LPOL 0D LENGTH OF LARGE PROGRAM OBJECT SECTION
27 PDS2VSTR 02686040 VIRTUAL STORAGE REQUIREMENT FOR THIS MODULE
28 PDS2MEPA 00000000 MAIN ENTRY POINT OFFSET
2F PDS2AEPA 00000000 ALIAS ENTRY POINT OFFSET
```



PDS262I 08 PDS2TTRP 00A603 TTR OF FIRST BLOCK OF DATA

dir pds (for a source member)



| PDS262I OB | PDS2INDC OF | 0 TTRS FOLLOW; 15 HALFWORDS OF DATA |
|------------|-------------------|-------------------------------------|
| PDS262I OC | DIRSPFV 1. | MEMBER VERSION NUMBER |
| PDS262I OD | DIRSPFR 9. | MEMBER REVISION NUMBER |
| PDS262I OE | DIRSPFSC 00 | SCLM INDICATOR X'80' |
| PDS262I OF | DIRSPFCS 48 | LAST CHANGE TIME FORMAT: SS |
| PDS262I 10 | DIRSPFCR 0105334F | CREATION DATE FORMAT: OCYYDDDF |
| PDS262I 14 | DIRSPFCD 0105343F | LAST CHANGE DATE FORMAT: OCYYDDDF |
| PDS262I 18 | DIRSPFCT 1331 | LAST CHANGE TIME FORMAT: HHMM |
| PDS262I 1A | DIRSPFSI 9. | NUMBER OF LINES CURRENTLY |
| PDS262I 1C | DIRSPFIN 7. | NUMBER OF LINES INITIALLY |
| PDS262I 1E | DIRSPFMD 0. | NUMBER OF MODIFIED LINES |
| PDS262I 20 | DIRSPFID TRIDJK | USERID OF LAST PERSON TO UPDATE |



PDS Subcommands - DISPLAY

- DISPLAY creates a list of members matching a start/end pattern
- DISPLAY is no longer recommended, use MEMBERS instead



PDS Subcommands - DSNAME

- DSNAME displays current dataset stats in format you wish (TSO, JCL, or MSG)
- dsname tso



PDS Subcommands - DSPRINT

DSPRINT prints a hardcopy listing of a member

```
DSPRINT Subcommand -----
  ----- O.DSP
OPTION ===>
Enter the member group name, the printer name and operands for DSPRINT:
Operands: memgroup
                       (e.q., *; start:end; start:; first*pat; range*; part/)
          printername
          DDNAME (ddname) DIRECT (KEEP/DELETE)
          LINES(linenum1:linenum2)
          NUM(loc, length)/SNUM(loc, length)/NONUM
          FCB(fcbname) FORMS(formname)
          CLASS(c) HOLD/NOHOLD COL(col1:col2, ...) COPIES(number)
          PAGELEN (num) TMARGIN (num) BMARGIN (num)
          SINGLE/DOUBLE/CCHAR
          FOLD(width)/TRUNCATE(width)
          EJECT/NOEJECT NOEJMESS NOHEADER
          TERMINAL TRACE WTR(wtrname)
Required: printername
Defaults: NUM, CLASS(A), COPIES(1), NOHOLD, SINGLE, HEADER, NOEJECT, MEMBERS
          The above parameters are actually for the VPSPRINT product.
Note:
```



PDS Subcommands - EDIT

- EDIT opens a PDS member in ISPF EDIT mode
- edit \$\$\$\$read



PDS Subcommands - FIND

- FIND displays portions of a member which contain a search string
- FIND has a myriad of options, including, but not limited to, the format of the FIND, how many records you want to skip before the FIND, or a THEN/ELSE clause to determine what to do with a member if the string is found or not found within it



PDS Subcommands - FIND

find: /fixpds/ then(sublist)

>mem *

PDS1651 MEMBERS ARE: \$\$\$BUGS, \$\$\$CUSTM, \$\$\$MODS, \$\$\$PDSE, \$\$\$PROSE, \$\$\$SECUR, \$\$\$UNDOC, \$\$PDSMAN, \$PDSARTH, \$PDSART1, \$PDSART2, \$PDSART3, #MDSECT, #PDSGEN, #PDSMODS, #PDSTBL, @DIAFUN, @DIALOG, @DIATBL, @FIXPDS, @GLOBAL, @LIST, @PARSE, @PDSMAIN, @PDSMODS, @REPRO, @SUBS, @VERIFY, NOTES, PDSHELP, P86ART1, P86ART2B, P86ART3, P86CUST, P86EXPAN, P86LOHE, P86OPFX, P86OPHE, P86OPUX, P86OSFX, P86PN5E, P86RLSE, P86UNDOC, SMPFIXES, SMPINST, VSUBCMD

PDS1931 THIS GROUP CONTAINS 46 MEMBERS



PDS Subcommands - FIXPDS

- FIXPDS can perform several utility functions for a PDS to repair or change it
- Expand and free directory blocks
- Modify DCB attributes
- Reset the directory (empty the PDS)
- Release or add space (extents)



PDS Subcommands - FIXPDS

PDS392A SHOULD THIS DATA SET BE MODIFIED (Y/N) ?

fixpds expanddir(45)

© Pinnacle Consulting Group, Inc., 2006. All rights reserved. Permission granted to SHARE to distribute for SHARE 107.



PDS Subcommands - FIXPDS

fixpds expanddir(45) (reply 'Y')

PDS2001 DISP UNIT OPT RECFM LRECL BLKSIZE ALLOCTRK FREETRK SECONDARY FREEDIR
PDS2001 SHR 3390 C FB 80 27920 6X 90 10 1 CYL 68



PDS Subcommands - HISTORY

- The HISTORY subcommand displays the last linkage edit date for a module and lists any CSECT IDR data assigned to a load module
- history pds



PDS Subcommands - IF

IF searches for members meeting certain criteria

```
Enter the member group name and any operands for IF:
===>
                         (e.g., *; start:end; start:; first*pat; range*; part/)
Operands:
          memgroup
           SINCE/BEFORE
           TODAY/YESTERDAY/WEEK/CURRENT/BIWEEK/MONTH/BIMONTH/OUARTER/
                 HALFYEAR/YEAR/BIYEAR/LAST(numdays)/DATE(mm/dd/yy)
           CHANGED (mm/dd/yy:mm/dd/yy) CREATED (mm/dd/yy:mm/dd/yy)
           ABOVE (Count 1) BELOW (Count 2)
                                              NULL/NONULL
           ALIAS/NOALIAS APPARENTALIAS/NOAPP ORPHAN/NOORPHAN
                                                                 HASALTAS/NOHAS
           BLOCKERR/NOBL IOERR/NOIOERR
                                        LRECLERR/NOLRECL NAMEERR/NONAME
          MAXBLK(size) SPFEDIT/NOSPFEDIT TTR(Lttr:Httr)
           ID(Puid)/NOID/NOTID(Puid)
                                               SSI(hx)/SSI/NOSSI/PARTSSI(hx)
                       / BROWSE
                                  / DIRENTRY / DELETE / EDIT
         THEN (ATTRIB
                                                                 / END
                       / FSE
                                             / MEMBERS / MEMLIST /OUTCOPY
              FIND
                                  / LIST
              PRINTOFF / REVIEW
                                  / SUBMIT
                                             / SUBLIST / VIEW
                                                                 /VERIFY)
         ELSE(as above for THEN)
Defaults: memgroup, THEN(ATTRIB) if neither THEN nor ELSE is entered, SINCE
```



PDS Subcommands - IF

if: id(tconley) then(sublist)

PDS1931 THIS GROUP CONTAINS 29 MEMBERS

© Pinnacle Consulting Group, Inc., 2006. All rights reserved. Permission granted to SHARE to distribute for SHARE 107.



PDS Subcommands - LIST

- LIST displays the data in a member
- list \$\$\$\$\$\$\$\$

Ah-ha, you must have come here because of your curiosity, thats good. This member is an attention getter as first member in this file, but the starting point is \$\$\$READ. If you have not been there, now is the time. Have fun.

PDS142I 6 LINES IN THIS MEMBER



PDS Subcommands - MAP

- MAP lists CSECT structure of a load module
- map iefbr14



PDS Subcommands - MEMBERS

- MEMBERS lists member names from the PDS
- members a:b

```
- DSN=SYS2.PDS.INSTALL, VOL=SER=OS39M1 MEM=A:B ----->members a:b

PDS165I MEMBERS ARE: ABEHELP

PDS193I THIS GROUP CONTAINS 1 MEMBERS
```



PDS Subcommands - MEMLIST

MEMLIST creates member selection list

```
MEMLIST Subcommand (source members) ---
            ---- O.MEML
OPTION ===>
Enter the member group specification and any operands for MEMLIST:
Operands: memgroup - (e.g., *; start:end; start:; first*pat; range*; part/)
           SINCE/BEFORE
           TODAY/YESTERDAY/WEEK/CURRENT/BIWEEK/MONTH/BIMONTH/OUARTER/
                 HALFYEAR/YEAR/BIYEAR/LAST (numdays) / DATE (mm/dd/yy)
           CHANGED(mm/dd/yy:mm/dd/yy)
CREATED(mm/dd/yy:mm/dd/yy)
           ABOVE (count)
           ALIAS/NOALIAS
           BELOW (count)
           HASALIAS/NOHASALIAS
           ID (pname) /NOID/NOTID (pname)
           ORPHAN/NOORPHAN
           SSI(hexdata)/SSI/NOSSI/PARTSSI(hexdata)
           TTR(lttr:httr)
           RESET/NORESET
Defaults: NORESET, SINCE
```



PDS Subcommands - MEMLIST

- MEMLIST is cumulative, so use RESET to create a new MEMLIST
- memlist a* reset



PDS Subcommands - OPTIONS

- OPTIONS lists available PDS subcommands
- options



PDS Subcommands - OUTCOPY

- OUTCOPY can create IEBCOPY or IEBUPDTE control cards for selected members
- DD PDSOUT must be allocated to an FB 80 file
- outcopy \$\$\$\$\$\$\$\$

```
- DSN=SYS2.PDS.INSTALL, VOL=SER=OS39M1 MEM=$$$$$$$ -------
>outcopy $$$$$$$ echo

COPY OUTDD=OUTPUT, INDD=INSTALL

S M=$$$$$$$, $$$$$$$))

>outcopy $$$$$$$ iebupdte echo

./ ADD NAME=$$$$$$$
```



PDS Subcommands - PATTERN

- PATTERN lists members matching the patterns
- PATTERN is no longer recommended, use MEMBERS instead



PDS Subcommands - PRINTOFF

PRINTOFF prints a hardcopy list of a member

```
---- O.PR
                                 PRINTOFF Subcommand -----
OPTION ===>
Enter the member group name and any operands below for PRINTOFF:
===>
                        (e.g., *; start:end; start:; first*pat; range*; part/)
Operands:
          memgroup
                             DEST(destname)
           CLASS(c)
                             HOLD/NOHOLD
           COPIES (num)
           LIST/NOLIST
                             PRINT/NOPRINT
           FORMS (formname)
                            UCS(ucsname)
                             FCB(fcbname)
          PROG (progname)
           HEADING/NOHEADING SNUM
           CAPS/ASIS
                             TEXT
          NOMSG
                             ASA
           VOLUME (volname)
Defaults: memgroup, CLASS(A), COPIES(1), NOHOLD, LIST, PRINT, ASIS, HEADING
```



PDS Subcommands - RENAME

 RENAME will rename, swap, or replace members or groups of members in a PDS



PDS Subcommands - RENAME

Rename tomold tomnew swap

- DSN=TCONLEY.TSO.JCL, VOL=SER=XS39M1 MEM=TOMNEW ------>
>rename tomold tomnew swap

PDS090I TOMOLD HAS BEEN RENAMED TO TOMNEW

PDS090I TOMNEW HAS BEEN RENAMED TO TOMOLD



PDS Subcommands - REPLACE

REPLACE finds and replaces strings in members

```
------ O.REP REPLACE Subcommand -----
OPTION ===>
Enter the member group name, search/replace strings and operands for REPLACE:
Operands: memgroup (e.g., *; start:end; start:; first*pat; range*; part/)
                   -search-replace / 'search' 'replace'
                   NUM / SNUM / NONUM / LBLOCK / LDUMP / BLOCK / DUMP
                   WRITE/NOWRITE
                   CAPS/ASIS/IGNORE
                   STATS/NOSTATS
                   OFFSET (hex)
                                  MODULE (Partname)
                   MAXIN(num)
                                  MAXLEN (num)
                   MAXOUT (num)
                                  MAXFIND(num)
                                  SKIPREC(num)
                   SKIPCOL(num)
Defaults: memgroup; NUM or previous REPLACE/FIND/LIST format;
```

Defaults: memgroup; NUM or previous REPLACE/FIND/LIST format; NOWRITE; CAPS; STATS



PDS Subcommands - REPLACE

replace ady* /tom/new/ (write)



PDS Subcommands - REPRO

- REPRO can rebuild or add members to a PDS
- Repro iefbr14 to(iefbr15)



PDS Subcommands - RESTORE

- RESTORE resurrects deleted members in PDS
- restore zmem repeat noprompt ttr(0)

```
- DSN=TCONLEY.TSO.JCL, VOL=SER=XS39M1 MEM=ZMEM:ZMEM
>restore zmem repeat noprompt ttr(0)
PDS101I DELETED MEMBER FOUND AT TTR: 00020D
PDS144I DATA LINE 1:
//TCONLEYA JOB (TCONLEY), 'ADD USER', CLASS=A,
                                                                   00010000
PDS144I DATA LINE 2:
             MSGCLASS=H, NOTIFY=&SYSUID
                                                                   00020000
PDS144I DATA LINE 3:
//**************
                                                                   00030000
PDS144T DATA LINE 4:
//ADDUSER EXEC PGM=IKJEFT01
                                                                   00040000
PDS144I DATA LINE 5:
//SYSTSPRT DD SYSOUT=*
                                                                   00050000
```

© Pinnacle Consulting Group, Inc., 2006. All rights reserved. Permission granted to SHARE to distribute for SHARE 107.

PDS091I ZMEM0001 HAS BEEN RESTORED



PDS Subcommands - RESTORE

SHARE. ORG

 Options CAPS/ASIS (for FIND) and TEST to simulate RESTORE added with version 8.6.04

```
RESTORE Subcommand ---
              ---- O.RES
OPTION ===>
Enter the member name desired and any operands below for RESTORE:
Operands: member - name to use for the restored member
          TTR(ttr) - one to six hex digit ttr address or search start address
          REPEAT - restore multiple members (mbr00001, mbr00002, ...)
          NOREPEAT - restore only a single member
          DISPLAY - display data from deleted members
          NODISPLAY - display no data from deleted members
          PROMPT - prompt before restoring a member
          NOPROMPT - do not prompt before restoring a member
          COUNT(nm) - number of lines to display from a member
          LIKE(xyz) - take attributes from member XYZ
          FIND('s') - a character string which must be found before a restore
          MODULE(n) - a partial CSECT or entry name which must be present
          CAPS/ASIS - case of the FIND argument
                    - simulate the resurrection of deleted members
Defaults: TTR(0), DISPLAY, PROMPT, COUNT(5), CAPS
```



PDS Subcommands - SRCHFOR

SRCHFOR invokes SuperC to search the PDS

```
------O.SRCH SRCHFOR Subcommand ------
OPTION ===>
Enter the member group name, the string and any operands for SCRHFOR:
===>
Operands:
                    (e.g., *; start:end; start:; first*pat; range*; part/)
         memgroup
         'string'
         ALIAS/NOALIAS
                           - to include associated members
         HEX
                           - string is hexadecimal
         PREFIX/SUFFIX/WORD - type of search
         COL(start)
                           - start search in this column
         COL(start:end) - limit search to these columns
```

Required: memgroup, string

Defaults: ALIAS

Process options: ANYC, LONGLN (IBM SuperC Search-For)



PDS Subcommands - SRCHFOR

 srchfor \$* 'pdsjcl' noslist (undocumented option NOSLIST suppresses SELECT <member> display if not processing ':' for all members)

| >srchfor \$* 'pdsjcl' | PDF FILE/LINE/WORD/BYTE | /SFOR COMPARE | UTILITY- ISPF I | FOR z/OS | 2006/03/09 | 2.26 | PAGE | 1 |
|---|--------------------------|----------------|-----------------|-------------------|------------|------|------|---|
| \$\$\$DOC | STRI | NG(S) FOUND | | | | | | |
| 36 PDSJCL | JCL to install PDS | | | | | | | |
| | PDF FILE/LINE/WORD/BYTE | | | FOR z/OS | 2006/03/09 | 2.26 | PAGE | 2 |
| LINES-FOUND LINES-F | PROC MEMBERS-W/LNS MEM | | COMPARE-COLS LO | DNGEST-LINE 80 | | | | |
| PROCESS OPTIONS USE | : LONGLN ANYC | | | | | | | |
| THE FOLLOWING PROCES SRCHFOR 'pdsjcl' SLIST OFF | SS STATEMENTS (USING COL | UMNS 1:72) WEF | RE PROCESSED: | | | | | |
| PDS171I SRCHFOR HAS | COMPLETED; RC= 1 | | | | | | | |



PDS Subcommands - SUBLIST

- SUBLIST creates member sublists
- sublist \$\$*

PDS193I THIS GROUP CONTAINS 33 MEMBERS



PDS Subcommands - SUBMIT

- SUBMIT will submit a member or group of members to the internal reader for execution
- sub iefbr14
- sub tconley*
- sub a:b



- USAGE displays stats for current dataset
- usage all

```
- DSN=SYS2.PDS.INSTALL, VOL=SER=OS39M1 MEM=PDSHELP
>USAGE ALL
PDS2001 DISP UNIT OPT RECFM LRECL BLKSIZE
                                            ALLOCTRK FREETRK SECONDARY FREEDIR
PDS200I SHR 3390 C
                      FB
                                    27920
                                             5X
                                                  401
                                                          167
                                                                 50 TRK
                                                                             43
PDS1801 DATA SET: CREATED EXPIRES LAST USE
                                              UPDATED
                                                        SECURITY
                  5/11/05 0/00/00
                                     3/09/06 YES
PDS180I
                                                        NONE
PDS181I EXTENTS IN TRACKS: 201, 50, 50, 50, 50
PDS182I TRACKS: ALLOCATED
                             USED
                                     FREE
PDS182I
                      401
                              234
                                      167
PDS183I DIRECTORY: BLOCKS
                             USED
                                     FREE
                                             TRACKS
                                                     MEMBERS ALIASES
                              137
                                       43
                                                        1011
PDS183I
                      180
```



SHARE.ORG

usage all (cont'd).

| PDS184I EXTENT | UCB LO TT-HI TT | TRACKS | LOW CCHH-HIGH CCHH | BOUNDARY |
|-----------------|----------------------|-----------|---------------------------|--------------|
| PDS184I | | | | |
| PDS184I 0 | 0A82 00.00 00.C8 | 201 | 05.FD.00.0C 06.0B.00.02 | TRK |
| PDS184I 1 | 0A82 00.C9 00.FA | 50 | 06.C3.00.00 06.C6.00.04 | TRK |
| PDS184I 2 | 0A82 00.FB 01.2C | 50 | 06.C6.00.05 06.C9.00.09 | TRK |
| PDS184I 3 | 0A82 01.2D 01.5E | 50 | 06.C9.00.0A 06.CC.00.0E | TRK |
| PDS184I 4 | 0A82 01.5F 01.90 | 50 | 06.CD.00.00 06.D0.00.04 | TRK |
| | | | | |
| | | | | |
| PDS185I FORMAT | 1 DSCB: | | | |
| PDS185I 0 4 | 8 C 10 14 18 | 1C 20 | 24 28 2C 30 34 38 | 3C 40 44 |
| PDS185I SYS2.PI | OS.INSTALL | | 10S39M1c | IBMOSVS2 |
| PDS185I EEEF4DC | CE4CDEECDD4444444444 | 44444444 | 14444444444FDEFFDF0060800 | 0000CCDDEEEF |
| PDS185I 2822B74 | 42B952313300000000 | 000000000 | 000000000016239410190300 | 050092462522 |
| | | | | |
| PDS185I 48 40 | C 50 54 58 5C | 60 64 6 | 58 6C 70 74 78 7C 8 | 0 84 88 |
| PDS185I . | & b& | Z | | FI |
| | | | 0000F000000000C000C00000 | |
| PDS185I 00000AC | 0400D02000D00000020 | 004092200 | 00105D0C6B021163006604126 | 605690900022 |
| | | | | |



usage all (cont'd).

| PDS186I | LOC | NAME | VALUE | DESCRIPTION |
|---------|-----|----------|---------------|--|
| PDS186I | | | | |
| PDS186I | 00 | DS1DSNAM | SYS2.PDS.INST | TALL |
| PDS186I | 2C | DS1FMTID | F1 | FORMAT IDENTIFIER |
| PDS186I | 2D | DS1DSSN | OS39M1 | DATA SET SERIAL NUMBER |
| PDS186I | 33 | DS1VOLSQ | 1. | VOLUME SEQUENCE NUMBER |
| PDS186I | 35 | DS1CREDT | 690083 | CREATION DATE |
| PDS186I | 38 | DS1EXPDT | 000000 | EXPIRATION DATE |
| PDS186I | 3B | DS1NOEPV | 5. | NUMBER OF EXTENTS ON VOLUME |
| PDS186I | 3C | DS1NOBDB | 0. | NUMBER OF BYTES USED IN LAST DIRECTORY BLOCK |
| PDS186I | 3D | DS1FLAG1 | 00 | FLAG 1 |
| PDS186I | 3E | DS1SYSCD | C9C2D4D6E2E5E | C2F24040404040 |
| PDS186I | 4B | DS1REFD | 6A0044 | DATE LAST REFERENCED |
| PDS186I | 4E | DS1SMSFG | 00 | SYSTEM MANAGED STORAGE INDICATORS |
| PDS186I | 4F | DS1SCEXT | 806D10 | SECONDARY SPACE EXTENSION |
| PDS186I | 52 | DS1DSORG | 0200 | DATA SET ORGANIZATION |
| PDS186I | 54 | DS1RECFM | 90 | RECORD FORMAT |
| PDS186I | 55 | DS10PTCD | 20 | OPTION CODE |
| PDS186I | 56 | DS1BLKL | 27,920. | BLOCK LENGTH |
| | | | | |



usage all (cont'd).

```
PDS186I 58 DS1LRECL 80.
                                 LOGICAL RECORD LENGTH
PDS186I 5A DS1KEYL 0.
                                 KEY LENGTH
PDS186I 5B DS1RKP
                    0.
                                 RELATIVE KEY POSITION
PDS186I 5D DS1DSIND 82
                                 DATA SET INDICATORS
PDS186I 5E DS1SCALO 50000064
                                 SECONDARY ALLOCATION
PDS186T 62 DS1LSTAR 00E902
                                 TTR OF LAST USED TRACK AND BLOCK ON TRACK
PDS186I 65 DS1TRBAL 45,696.
                                 BYTES REMAINING ON LAST TRACK USED
PDS186I 67
                    0.0
                                 RESERVED (ONE BYTE)
PDS186T 68 DS1TTTHI 00
                                 HIGH ORDER BYTE OF TRACK NUMBER IN DS1LSTAR
PDS186I 69 DS1EXT1 0100.05FD000C.060B0002 FIRST EXTENT DESCRIPTION
PDS186I 73 DS1EXT2 0101.06C30000.06C60004 SECOND EXTENT DESCRIPTION
PDS186I 7D DS1EXT3 0102.06C60005.06C90009 THIRD EXTENT DESCRIPTION
PDS186I 87 DS1PTRDS 0000000232 CCHHR OF ANY ASSOCIATED FORMAT 2 OR 3 DSCB
```



PDS Subcommands - VERIFY

- VERIFY runs a validity check on the PDS
- verify:

PDS117I 1,010 MEMBERS COUNTED; CUMULATIVE SIZE IS 131,889 RECORDS



PDS Subcommands - VIEW

- VIEW opens a PDS member in ISPF VIEW mode
- view \$\$\$\$read



PDS Subcommands - VPSPRINT

VPSPRINT prints hardcopy listing of a member

```
----- O.VPS
                              VPSPRINT Subcommand -----
OPTION ===>
Enter the member group name, the printer name and operands for VPSPRINT:
Operands: memgroup
                      (e.g., *; start:end; start:; first*pat; range*; part/)
          printername
          DDNAME (ddname) DIRECT (KEEP/DELETE)
          LINES(linenum1:linenum2)
          NUM(loc, length)/SNUM(loc, length)/NONUM
          FCB(fcbname) FORMS(formname)
          CLASS(c) HOLD/NOHOLD COL(col1:col2, ...) COPIES(number)
          PAGELEN (num) TMARGIN (num) BMARGIN (num)
          SINGLE/DOUBLE/CCHAR
          FOLD(width)/TRUNCATE(width)
          EJECT/NOEJECT NOEJMESS NOHEADER
          TERMINAL TRACE WTR(wtrname)
Required: printername
Defaults: NUM, CLASS(A), COPIES(1), NOHOLD, SINGLE, HEADER, NOEJECT, MEMBERS
```



PDS Subcommands - XMIT (new!)

 XMIT uses the TSO TRANSMIT command to act on members in the PDS (new in 8.6.03)

```
XMIT Subcommand -----
                ----- O.XMIT
OPTION ===>
Enter the member group name, the addressee and any operands for XMIT:
===>
Operands: memgroup
                        (e.g., *; start:end; start:; first*pat; range*; part/)
                              - node.userid, nickname, or distribution list
          addressee
          OUTDSN (dsname)
                              - direct output to a file instead of JES
          OUTFILE (ddname)
                              - direct output to a file instead of JES
          ALIAS/NOALIAS
                              - to include associated members
                              - request notification of delivery
          NOTIFY/NONOTIFY
          LOG/NOLOG
                              - log all transmissions in the log data set
          SYSOUT(class)
                              - direct utility messages to a sysout class
```

Required: memgroup, addressee Defaults: ALIAS, NOTIFY, LOG



PDS Subcommands - XMIT (new!)

xmit \$\$\$* a.a outda('tconley.xmit')

```
IEBCOPY MESSAGES AND CONTROL STATEMENTS
IEB1135I IEBCOPY FMID HDZ11GO SERVICE LEVEL UA05363 DATED 20030923 DFSMS 01.03.00 z/OS 01.04.00 HBB7707 CPU 2066
IEB1035I TCONLEY ISPFPROC ISPFPROC 18:27:57 SUN 14 MAY 2006 PARM="
COPY OUTDD=SYS00008, INDD=((SYS00004, R))
SELECT MEMBER=($$$$$$$,$$$READ,$$$REA1,$$$BUGS,$$$CTBL,$$$CUSTM)
SELECT MEMBER=($$$CUT,$$$DOC,$$$EQUAL,$$$HERC,$$$INST,$$$ISODT)
SELECT MEMBER=($$$MODS,$$$PDSE,$$$PROSE,$$$SECUR,$$$TRAP,$$$UCB)
SELECT MEMBER=($$$UNDOC,$$$Y2K)
IEB1013I COPYING FROM PDS INDD=SYS00004 VOL=OS39M1 DSN=SYS2.PDS.INSTALL
                  TO PDSU OUTDD=SYS00008 VOL=OS39M1 DSN=SYS06134.T182757.RA000.TCONLEY.R0100257
IEB1671 FOLLOWING MEMBER(S) UNLOADED FROM INPUT DATA SET REFERENCED BY SYS00004
IEB154I $$$$$$$ HAS BEEN SUCCESSFULLY UNLOADED
IEB154I $$$$READ HAS BEEN SUCCESSFULLY UNLOADED
IEB154I $$$REA1 HAS BEEN SUCCESSFULLY UNLOADED
IEB154I $$$PDSE HAS BEEN SUCCESSFULLY UNLOADED
IEB154I $$$PROSE HAS BEEN SUCCESSFULLY UNLOADED
IEB154I $$$SECUR HAS BEEN SUCCESSFULLY UNLOADED
IEB154I $$$TRAP HAS BEEN SUCCESSFULLY UNLOADED
IEB154I $$$UCB HAS BEEN SUCCESSFULLY UNLOADED
IEB154I $$$UNDOC HAS BEEN SUCCESSFULLY UNLOADED
IEB154I $$$Y2K HAS BEEN SUCCESSFULLY UNLOADED
IEB1098I 20 OF 20 MEMBERS UNLOADED FROM INPUT DATA SET REFERENCED BY SYS0000
IEB147I END OF JOB - 0 WAS HIGHEST SEVERITY CODE
INMX000I 0 message and 54 data records sent as 7272 records to A.A
```

INMX001I Transmission occurred on 05/14/2006 at 18:27:56.



Miscellaneous Commands

- CAX Display active catalogs (CAXWA)
- DISASM Run a disassembler
- DLINK De-link and breakdown a load module
- FSE Full Screen Edit
- H Online help (HEL command)
- LISTA List TSO allocations
- LISTC/LISTF List files w/DSAT or VTOC



Miscellaneous Commands

- LISTV LSPACE list of volumes
- MXIBAT MXI interface to PDS
- REV REVIEW file browser



Summary

- Discussed the history of PDS
- Installing and learning to use PDS
- Talked about PDSE support
- Discussed member groups
- Showed how to get started
- Reviewed PDS subcommands
- Covered miscellaneous commands



Finally...

- I'm interested in hearing about your experiences with PDS; if you discover any unique ways to use PDS, please let me know about them
- Feel free to Email me at <u>pinncons@rochester.rr.com</u> if you have any questions or concerns regarding this presentation or PDS in general

ERROR: undefined OFFENDING COMMAND:

STACK: