inst.eecs.berkeley.edu/~cs61c **CS61C: Machine Structures**

> Lecture 15 **Floating Point**



Senior Lecturer SOE Dan Garcia

www.cs.berkeley.edu/~ddgarcia

Dr. John Gustafson, Senior Fellow at AMD has proposed a new format for floating-point number representation that "promises to be to floating point what floating point is to fixed point". You specify the number of

exponent and fraction bits. Claims to save power! sites.ieee.org/scv-cs/files/2013/03/Right-SizingPrecision1.pdf

UNUM, Float replacement? ⇒

Quote of the day

"95% of the folks out there are completely clueless about floating-point."

James Gosling Sun Fellow Java Inventor 1998-02-28





Review of Numbers

- · Computers are made to deal with numbers
- What can we represent in N bits?
 - 2N things, and no more! They could be...
 - · Unsigned integers:

to 2N-1

(for N=32, $2^{N}-1 = 4,294,967,295$)

· Signed Integers (Two's Complement)

-2^(N-1)

2(N-1) - 1 to

(for N=32, $2^{(N-1)} = 2,147,483,648$)

Garcia, Fall 2014 © UCB

What about other numbers?

- Very large numbers? (seconds/millennium) \Rightarrow 31,556,926,000₁₀ (3.1556926₁₀ x 10¹⁰)
- 2. Very small numbers? (Bohr radius) \Rightarrow 0.0000000000529177₁₀m (5.29177₁₀ x 10⁻¹¹)
- 3. Numbers with both integer & fractional parts?

First consider #3.


...our solution will also help with 1 and 2.



Representation of Fractions

"Binary Point" like decimal point signifies boundary between integer and fractional parts:

Example 6-bit representation:




 $10.1010_2 = 1x2^1 + 1x2^{-1} + 1x2^{-3} = 2.625_{10}$

If we assume "fixed binary point", range of 6-bit representations with this format:

0 to 3.9375 (almost 4)





Representation of Fractions with Fixed Pt.

What about addition and multiplication?

01.100 1.510 Addition is + 00.100 0.5₁₀ straightforward: 10.000 2.0₁₀ 01.100 1.5₁₀ 00.100 0.510 00 000 Multiplication a bit more complex: 000 00 0110 0 00000 00000 0000110000

Where's the answer, 0.11? (need to remember where point is) Cal

Representation of Fractions

So far, in our examples we used a "fixed" binary point what we really want is to "float" the binary point. Why?

Floating binary point most effective use of our limited bits (and thus more accuracy in our number representation):

example: put 0.1640625 into binary. Represent as in 5-bits choosing where to put the binary point. ... 000000.001010100000...

> Store these bits and keep track of the binary point 2 places to the left of the MSB

Any other solution would lose accuracy!

With floating point rep., each numeral carries a exponent field recording the whereabouts of its binary point.

The binary point can be outside the stored bits, so very large and small numbers can be represented.

Scientific Notation (in Decimal)

mantissa exponent 6,02₁₀ x 10²³ radix (base) decimal point

- Normalized form: no leadings 0s (exactly one digit to left of decimal point)
- Alternatives to representing 1/1,000,000,000

· Normalized: 1.0 x 10-9

0.1 x 10⁻⁸,10.0 x 10⁻¹⁰ · Not normalized:

<u>Col</u> (2810 L15

Scientific Notation (in Binary)

mantissa ~1.01_{two} x <mark>2</mark>-1 radix (base) "binary point"

- Computer arithmetic that supports it called floating point, because it represents numbers where the binary point is not fixed, as it is for integers
 - · Declare such variable in C as float



Floating Point Representation (1/2)

- Normal format: +1.xxx...x_{two}*2^{yyy...y}two
- Multiple of Word Size (32 bits)

S Exponent Significand 1 bit 8 bits 23 bits

 S represents Sign Exponent represents y's Significand represents x's

• Represent numbers as small as 2.0 x 10⁻³⁸ to as large as 2.0 x 10³⁸

Floating Point Representation (2/2)


What if result too large?

 $(> 2.0 \times 10^{38}, < -2.0 \times 10^{38})$

- Overflow! ⇒ Exponent larger than represented in 8bit Exponent field
- · What if result too small?

(>0 & < 2.0x10⁻³⁸, <0 & > -2.0x10⁻³⁸)

• <u>Underflow!</u> ⇒ Negative exponent larger than represented in 8-bit Exponent field



· What would help reduce chances of overflow and/or underflow?

IEEE 754 Floating Point Standard (1/3) Single Precision (DP similar): 3130 23 22 Significand 1 bit 8 bits 23 bits • Sign bit: 1 means negative 0 means positive Significand: · To pack more bits, leading 1 implicit for normalized numbers · 1 + 23 bits single, 1 + 52 bits double always true: 0 < Significand < 1 (for normalized numbers)


• Note: 0 has no leading 1, so reserve exponent value 0 just for number 0


IEEE 754 Floating Point Standard (2/3)

- IEEE 754 uses "biased exponent" representation.
 - · Designers wanted FP numbers to be used even if no FP hardware; e.g., sort records with FP numbers using integer compares
- · Wanted bigger (integer) exponent field to represent bigger numbers.
- · 2's complement poses a problem (because negative numbers look bigger)
- · We're going to see that the numbers are ordered EXACTLY as in sign-magnitude
 - I.e., counting from binary odometer 00...00 up to 11...11 goes from 0 to +MAX to -0 to -MAX to 0

IEEE 754 Floating Point Standard (3/3)

- Called Biased Notation, where bias is number subtracted to get real number
 - IEEE 754 uses bias of 127 for single prec.
 - Subtract 127 from Exponent field to get actual value for exponent





Representation for ±∞

- In FP, divide by 0 should produce ± ∞, not overflow.
- ·Why?
 - · OK to do further computations with ∞ E.g., X/0 > Y may be a valid comparison
 - · Ask math majors
- •IEEE 754 represents ±∞
 - Most positive exponent reserved for ∞
 - · Significands all zeroes



Representation for 0

- Represent 0?
 - exponent all zeroes
 - · significand all zeroes
 - · What about sign? Both cases valid.



Special Numbers

 What have we defined so far? (Single Precision)

Exponent	Significand	Object
0	0	0
0	nonzero	???
1-254	anything	+/- fl. pt. #
255	0	+/- ∞
255	nonzero	???

 Professor Kahan had clever ideas; "Waste not, want not"



· Wanted to use Exp=0,255 & Sig!=0

0------

Representation for Not a Number

- •What do I get if I calculate sqrt(-4.0) or 0/0?
 - If ∞ not an error, these shouldn't be either
 - · Called Not a Number (NaN)
 - Exponent = 255, Significand nonzero
- · Why is this useful?
 - · Hope NaNs help with debugging?
 - They contaminate: op(NaN, X) = NaN
 - · Can use the significand to identify which!



cia Eall 2014 © HC

Representation for Denorms (1/2)

- Problem: There's a gap among representable FP numbers around 0
 - · Smallest representable pos num:

 $a = 1.0..._{2} * 2^{-126} = 2^{-126}$

· Second smallest representable pos num:

$$\begin{array}{lll} b = 1.000.....1 & 2 & 2^{-126} \\ & = (1 + 0.00...1) & 2^{-126} \\ & = (1 + 2^{-23}) & 2^{-126} \\ & = 2^{-126} + 2^{-149} & \text{And implicit 1} \\ a - 0 = 2^{-126} & \text{is to blame!} \\ b - a = 2^{-149} & \text{Gaps!} \\ & - \infty & & & & & & & & & \\ \end{array}$$

Representation for Denorms (2/2)

- •Solution:
 - We still haven't used Exponent = 0, Significand nonzero
 - <u>DEnormalized number</u>: no (implied) leading 1, implicit exponent = -126.
 - · Smallest representable pos num:

a = 2⁻¹⁴⁹

Second smallest representable pos num:



iarcia, Fall 2014 © UCE

Special Numbers Summary

Reserve exponents, significands:

Exponent	Significand	Object
0	0	0
0	nonzero	Denorm
1-254	anything	+/- fl. pt. #
255	0	+/- ∞
255	nonzero	NaN



