

Assembly Language: Part 1




Context of this Lecture



First half lectures: "Programming in the large"

Second half lectures: "Under the hood"



Goals of this Lecture



Help you learn:

- Language levels
- The basics of IA-32 architecture
 - Enough to understand IA-32 assembly language
- The basics of IA-32 assembly language
 - Instructions to define global data
 - Instructions to transfer data and perform arithmetic

Lectures vs. Precepts



Approach to studying assembly language:

Precepts	Lectures
Study complete pgms	Study partial pgms
Begin with small pgms; proceed to large ones	Begin with simple constructs; proceed to complex ones
Emphasis on writing code	Emphasis on reading code

Agenda



Language Levels

Architecture

Assembly Language: Defining Global Data

Assembly Language: Performing Arithmetic

High-Level Languages



Characteristics

- Portable
 - To varying degrees
- Complex
 - One statement can do much work
- Expressive
 - To varying degrees
 - Good (code functionality / code size) ratio
- Human readable

```
count = 0;
while (n>1)
{    count++;
    if (n&1)
        n = n*3+1;
    else
        n = n/2;
}
```

Machine Languages



Characteristics

- Not portable
 - Specific to hardware
- Simple
 - Each instruction does a simple task
- Not expressive
 - Each instruction performs little work
 - Poor (code functionality / code size) ratio
- Not human readable
 - Requires lots of effort!
 - Requires tool support

00	00	0000	0000	0000	0000	0000	0000	0000	
00	00	0000	0000	0000	0000	0000	0000	0000	
92	22	9120	1121	A120	1121	A121	7211	0000	
00	00	0001	0002	0003	0004	0005	0006	0007	
00	08	0009	000A	000B	000C	000D	000E	000F	
00	00	0000	0000	FE10	FACE	CAFE	ACED	CEDE	
12	34	5678	9ABC	DEF0	0000	0000	F00D	0000	
00	00	0000	EEEE	1111	EEEE	1111	0000	0000	
B1	В2	F1F5	0000	0000	0000	0000	0000	0000	

Assembly Languages



Characteristics

- Not portable
 - Each assembly lang instruction maps to one machine lang instruction
- Simple
 - Each instruction does a simple task
- Not expressive
 - Poor (code functionality / code size) ratio
- Human readable!!!

	movl	\$0, %ecx
loop:	——————————————————————————————————————	\$1, %edx endloop
	addl	\$1, %ecx
	movl	%edx, %eax
	andl	\$1, %eax
	je	else
	movl	%edx, %eax
	addl	%eax, %edx
	addl	%eax, %edx
	addl	\$1, %edx
else:	jmp	endif
	sarl	\$1, %edx
endif:		
endloop		loop

Why Learn Assembly Language?



Q: Why learn assembly language?

A: Knowing assembly language helps you:

- Write faster code
 - In assembly language
 - In a high-level language!
- Understand what's happening "under the hood"
 - Someone needs to develop future computer systems
 - Maybe that will be you!

Why Learn IA-32 Assembly Lang?



Why learn IA-32 assembly language?

Pros

- IA-32 is the most popular processor
- Nobel computers are IA-32 computers
 - Program natively on nobel instead of using an emulator

Cons

- IA-32 assembly language is big
 - Each instruction is simple, but...
 - There are many instructions
 - Instructions differ widely

We'll study a popular subset

As defined by Bryant & O'Hallaron Ch 3 and precept IA-32
 Assembly Language document

Agenda



Language Levels

Architecture

Assembly Language: Defining Global Data

Assembly Language: Performing Arithmetic

John Von Neumann (1903-1957)



In computing

- Stored program computers
- Cellular automata
- Self-replication

Other interests

- Mathematics
- Nuclear physics (hydrogen bomb)



Princeton connection


Princeton Univ & IAS, 1930-death

Known for "Von Neumann architecture"

In contrast to less successful "Harvard architecture"


Von Neumann Architecture





RAM






Registers



Registers

- Small amount of storage on the CPU
- Much faster than RAM
- Top of the storage hierarchy
 - Above RAM, disk, ...



Registers



General purpose registers

31	15 8	7 0	16-bit	32-bit
	AH	AL	AX	EAX
	ВН	BL	ВХ	EBX
	СН	CL	CX	ECX
	DH	DL	DX	EDX
	S	I		ESI
	D	I		EDI
	В	P		EBP
	S	P		ESP

ESP and EBP Registers




low memory

ESP (Stack Pointer) register

 Contains address of top (low address) of current function's stack frame

EBP (Base Pointer) register

 Contains address of bottom (high address) of current function's stack frame



high memory

Allow effective use of the STACK section of memory

(See Assembly Language: Function Calls lecture)

EFLAGS Register



Special-purpose register...

EFLAGS (Flags) register

- Contains CC (Condition Code) bits
- Affected by compare (cmp) instruction
 - And many others
- Used by conditional jump instructions
 - je, jne, jl, jg, jle, jge, jb, jbe, ja, jae, jb

(See Assembly Language: Part 2 lecture)


EIP Register



Special-purpose register...

EIP (Instruction Pointer) register

- Stores the location of the next instruction
 - Address (in TEXT section) of machine-language instructions to be executed next
- Value changed:
 - Automatically to implement sequential control flow
 - By jump instructions to implement selection, repetition



Registers and RAM



Typical pattern:


- Load data from RAM to registers
- Manipulate data in registers
- Store data from registers to RAM

Many instructions combine steps

ALU



21




Control Unit



Control Unit

- Fetches and decodes each machine-language instruction
- Sends proper data to ALU




CPU



CPU (Central Processing Unit)

- Control unit
 - Fetch, decode, and execute
- ALU
 - Execute low-level operations
- Registers
 - High-speed temporary storage



Agenda



Language Levels

Architecture

Assembly Language: Defining Global Data

Assembly Language: Performing Arithmetic

Defining Data: DATA Section 1



```
static char c = 'a';
static short s = 12;
static int i = 345;
```

```
.section ".data"
c:
    .byte 'a'
s:
    .word 12
i:
    .long 345
```

Note:

.section instruction (to announce DATA section)

label definition (marks a spot in RAM)

- .byte instruction (1 byte)
- .word instruction (2 bytes)
- .long instruction (4 bytes)

Note:

Best to avoid "word" (2 byte) data

Defining Data: DATA Section 2



```
char c = 'a';
short s = 12;
int i = 345;
```

```
.section ".data"
   .globl c
c: .byte 'a'
   .globl s
s: .word 12
   .globl i
i: .long 345
```

Note:

Can place label on same line as next instruction .glob1 instruction

Defining Data: BSS Section



```
static char c;
static short s;
static int i;
```

```
.section ".bss"
c:
    .skip 1
s:
    .skip 2
i:
    .skip 4
```

Note:

- .section instruction (to announce BSS section)
- .skip instruction

Defining Data: RODATA Section



```
...
..."hello\n"...;
...
```

```
.section ".rodata"
helloLabel:
    .string "hello\n"
```

Note:

- .section instruction (to announce RODATA section)
- .string instruction

Agenda



Language Levels

Architecture

Assembly Language: Defining Global Data

Assembly Language: Performing Arithmetic

Instruction Format



Many instructions have this format:

- name: name of the instruction (mov, add, sub, and, etc.)
- byte => operands are one-byte entities
- word => operands are two-byte entities
- long => operands are four-byte entities

Instruction Format



Many instructions have this format:

```
name{b,w,l} src, dest
```

- src: source operand
 - The source of data
 - Can be
 - Register operand: %eax, %ebx, etc.
 - Memory operand: 5 (legal but silly), someLabel
 - Immediate operand: \$5, \$someLabel

Instruction Format



Many instructions have this format:

name{b,w,l} src, dest

- dest: destination operand
 - The destination of data
 - Can be
 - Register operand: %eax, %ebx, etc.
 - Memory operand: 5 (legal but silly), someLabel
 - Cannot be
 - Immediate operand

Performing Arithmetic: Long Data



```
static int length;
static int width;
static int perim;
...
perim =
  (length + width) * 2;
```

Note:

```
movl instruction
addl instruction
sall instruction
Register operand
Immediate operand
Memory operand
.section instruction (to announce TEXT section)
```

```
.section ".bss"
length: .skip 4
width: .skip 4
perim: .skip 4
...
    .section ".text"
...
    movl length, %eax
    addl width, %eax
    sall $1, %eax
    movl %eax, perim
```

Performing Arithmetic: Byte Data



```
static char grade = 'B';
...
grade--;
```

Note:

Comment

movb instruction
subb instruction
decb instruction

What would happen if we use mov1 instead of movb?

```
.section ".data"
grade: .byte 'B'
   .section ".text"
   # Option 1
   movb grade, %al
   subb $1, %al
   movb %al, grade
   # Option 2
   subb $1, grade
   # Option 3
   decb grade
```

Generalization: Operands



Immediate operands

- \$5 => use the number 5 (i.e. the number that is available immediately within the instruction)
- \$i => use the address denoted by i (i.e. the address that is available immediately within the instruction)
- · Can be source operand; cannot be destination operand

Register operands

- %eax => read from (or write to) register EAX
- Can be source or destination operand

Memory operands

- 5 => load from (or store to) memory at address 5 (silly; seg fault)
- i => load from (or store to) memory at the address denoted by i
- Can be source or destination operand (but not both)
- There's more to memory operands; see next lecture

Generalization: Notation



Instruction notation:

I => long (4 bytes); w => word (2 bytes); b => byte (1 byte)

Operand notation:

- src => source; dest => destination
- R => register; I => immediate; M => memory

Generalization: Data Transfer



Data transfer instructions

mov is used often; others rarely

Generalization: Arithmetic



Arithmetic instructions

```
add{1,w,b} srcIRM, destRM dest += src
sub{1,w,b} srcIRM, destRM dest -= src
inc{1,w,b} destRM dest++
dec{1,w,b} destRM dest--
neg{1,w,b} destRM dest = -dest
```

Generalization: Signed Mult & Div



Signed multiplication and division instructions

See Bryant & O'Hallaron book for description of signed vs. unsigned multiplication and division

Generalization: Unsigned Mult & Div



Unsigned multiplication and division instructions

```
        mull srcRM
        reg[EDX:EAX] = reg[EAX]*src

        mulw srcRM
        reg[DX:AX] = reg[AX]*src

        mulb srcRM
        reg[AX] = reg[AL]*src

        divl srcRM
        reg[EAX] = reg[EDX:EAX]/src

        reg[EDX] = reg[EDX:EAX]*src
        reg[AX] = reg[DX:AX]/src

        divw srcRM
        reg[AX] = reg[DX:AX]*src

        divb srcRM
        reg[AL] = reg[AX]/src

        reg[AH] = reg[AX]*src
```

See Bryant & O'Hallaron book for description of signed vs. unsigned multiplication and division

Generalization: Bit Manipulation



Bitwise instructions

```
and{1,w,b} srcIRM, destRM dest = src & dest
or{1,w,b} srcIRM, destRM dest = src | dest
xor{1,w,b} srcIRM, destRM dest = src ^ dest
not{1,w,b} destRM dest = ~dest
sal{1,w,b} srcIR, destRM dest = dest << src
sar{1,w,b} srcIR, destRM dest = dest >> src (sign extend)
shl{1,w,b} srcIR, destRM (Same as sal)
shr{1,w,b} srcIR, destRM dest = dest >> src (zero fill)
```

Summary



Language levels

The basics of computer architecture

Enough to understand IA-32 assembly language

The basics of IA-32 assembly language

- Instructions to define global data
- Instructions to perform data transfer and arithmetic

To learn more

- Study more assembly language examples
 - Chapter 3 of Bryant and O' Hallaron book
- Study compiler-generated assembly language code
 - gcc217 -S somefile.c

Appendix



Big-endian vs little-endian byte order

Byte Order



Intel is a little endian architecture

 Least significant byte of multi-byte entity is stored at lowest memory address

 "Little end goes first" 	1000	00000101
TI ' (F () 1 4000	1001	0000000
The int 5 at address 1000:	1002	

1002

0000000

0000000

Some other systems use big endian

- Most significant byte of multi-byte entity is stored at lowest memory address
- "Big end goes first"

		0000000
The int 5 at address 1000:		
	1003	00000101

Byte Order Example 1



```
#include <stdio.h>
int main(void)
{ unsigned int i = 0x003377ff;
 unsigned char *p;
 int j;
 p = (unsigned char *)&i;
 for (j=0; j<4; j++)
    printf("Byte %d: %2x\n", j, p[j]);
}</pre>
```

Output on a little-endian machine

```
Byte 0: ff

Byte 1: 77 Output on a

Byte 2: 33 big-endian

Byte 3: 00 machine
```

Byte 0: 00
Byte 1: 33
Byte 2: 77
Byte 3: ff

Byte Order Example 2



Note:

Flawed code; uses "b" instructions to manipulate a four-byte memory area

Intel is **little** endian, so what will be the value of grade?

What would be the value of grade if Intel were **big** endian?

```
.section ".data"
grade: .long 'B'
   .section ".text"
   # Option 1
   movb grade, %al
   subb $1, %al
   movb %al, grade
   # Option 2
   subb $1, grade
```

Byte Order Example 3



Note:

Flawed code; uses "I" instructions to manipulate a one-byte memory area

What would happen?

```
.section ".data"
grade: .byte 'B'
   .section ".text"
   # Option 1
   movl grade, %eax
   subl $1, %eax
   movl %eax, grade
   # Option 2
   subl $1, grade
```