Quagga Software Routing Suite

Internet core routers

- Powerful
- Handling large amounts of traffic
- Built by Huawei, Juniper or Cisco
- They use proprietary operating systems
 - such as Cisco IOS, or JunOS







Quagga

- Free routing software suite
- Similar commands to the ones in Cisco's IOS

- MiniNExT
 - Mininet Extended
 - An extension layer to Mininet
 - Integrates Quagga into Mininet's virtual environment

Quagga

- Implementations of several routing protocols (namely OSPF, RIP and BGP-4)
- Important Quagga processes (daemons):
 - zebra
 - Manage the network interfaces
 - ripd
 - Handles RIP version 2 implementation
 - ripngd
 - Handles RIP routing for IPv6
 - quagga
 - The main service, which is used to call the three daemons above

• 4 files:

- 1. daemons
- 2. debian.conf
- 3. zebra.conf
- 4. ripd.conf

1. daemons:

zebra=yes

bgpd=no

ospfd=no

ospf6d=no

ripd=no

ripngd=no

isisd=no

2. debian.confvtysh enable=no

```
zebra options=" --daemon -A 127.0.0.1 -u quagga -g quagga" bgpd options=" --daemon -A 127.0.0.1 -u quagga -g quagga" ospfd options=" --daemon -A 127.0.0.1 -u quagga -g quagga" ospf6d options="--daemon -A ::1 -u quagga -g quagga" ripd options=" --daemon -A 127.0.0.1 -u quagga -g quagga" ripngd options=" --daemon -A ::1 -u quagga -g quagga" isisd options=" --daemon -A 127.0.0.1 -u quagga -g quagga"
```

```
3. zebra.conf
                                  ! Zebra configuration file for r1
                                  hostname r1
                                  password quagga
                                  enable password quagga
                                  log file /home/mininet/Desktop/shared/lab7/configs/r1/logs/zebra.log
                                  debug zebra packet
                                  interface r1-eth1
                                  no shutdown
                                  ip address 10.10.12.1/24
                                  line vty
```

4. ripd.conf

hostname r1

password quagga

enable password quagga

log file /home/mininet/Desktop/shared/lab7/configs/r1/logs/ripd.log

!log stdout

debug rip events

debug rip packet

router rip

version 2

redistribute connected


network 10.10.11.0/24

network 10.10.12.0/24

network 10.10.14.0/24

line vty

Network topology



• \$ sudo python lab7.py

mininext> net

```
mininext> net
h1 h1-eth1:SW1-eth1
h2 h2-eth1:SW2-eth1
rl rl-eth3:SW1-eth2 rl-eth1:SW2-eth2 rl-eth2:SW4-eth1
r2 r2-eth1:SW2-eth3 r2-eth2:SW3-eth1 r2-eth3:SW5-eth1
r3 r3-eth1:SW3-eth2 r3-eth2:SW7-eth1
r4 r4-eth1:SW4-eth2 r4-eth2:SW6-eth1
r5 r5-eth1:SW5-eth2 r5-eth2:SW7-eth2 r5-eth3:SW6-eth2
SW1 lo: SW1-eth1:h1-eth1 SW1-eth2:r1-eth3
        SW2-eth1:h2-eth1 SW2-eth2:r1-eth1 SW2-eth3:r2-eth1
SW3 lo: SW3-eth1:r2-eth2 SW3-eth2:r3-eth1
SW4 lo: SW4-eth1:r1-eth2 SW4-eth2:r4-eth1
SW5 lo: SW5-eth1:r2-eth3 SW5-eth2:r5-eth1
SW6 lo: SW6-eth1:r4-eth2 SW6-eth2:r5-eth3
SW7 lo: SW7-eth1:r3-eth2 SW7-eth2:r5-eth2
c0
mininext>
```

root@r1:/# ping 10.10.12.2

```
mode: r1 (r1) — + ×
root@r1:/# ping 10.10.12.2
connect: Network is unreachable
root@r1:/# ■
```

- Create/edit the configuration files for other routers:
 - \$ sudo leafpad configs/r2/daemons
 - \$ sudo leafpad configs/r2/debian.conf
 - \$ sudo leafpad configs/r2/zebra.conf
 - \$ sudo leafpad configs/r2/ripd.conf
- Start Quagga service on each router:
 - root@r1:/# /etc/init.d/quagga start

```
root@r1:/# /etc/init.d/quagga start
Loading capability module if not yet done.
Starting Quagga daemons (prio:10): zebra.
root@r1:/# 
root@r2:/# /etc/init.d/quagga start
Loading capability module if not yet done.
Starting Quagga daemons (prio:10): zebra.
```

root@r2:/# [

```
node: r1 (r1) — + ×

root@r1:/# ping 10.10.12.2

PING 10.10.12.2 (10.10.12.2) 56(84) bytes of data.
64 bytes from 10.10.12.2: icmp_seq=1 ttl=64 time=5.79 ms
64 bytes from 10.10.12.2: icmp_seq=2 ttl=64 time=0.670 ms
64 bytes from 10.10.12.2: icmp_seq=3 ttl=64 time=0.088 ms
64 bytes from 10.10.12.2: icmp_seq=4 ttl=64 time=0.086 ms

^C
--- 10.10.12.2 ping statistics ---
4 packets transmitted, 4 received, 0% packet loss, time 3003ms
rtt min/avg/max/mdev = 0.086/1.660/5.798/2.400 ms
root@r1:/#
```

Quagga monitoring mode

- Connect to the Quagga process running on router:
 - root@r1:/# telnet localhost zebra

```
root@r1:/# telnet localhost zebra
Trying 127.0.0.1...
Connected to localhost.
Escape character is '^]'.
Hello, this is Quagga (version 0.99.22.4).
Copyright 1996-2005 Kunihiro Ishiguro, et al.
```

- Inspect the contents of the routing table:
 - r1> show ip route

```
r1> show ip route

Codes: K - kernel route, C - connected, S - static, R - RIP,

0 - OSPF, I - IS-IS, B - BGP, A - Babel,

> - selected route, * - FIB route

C>* 10.10.11.0/24 is directly connected, r1-eth3

C>* 10.10.12.0/24 is directly connected, r1-eth1

C>* 10.10.14.0/24 is directly connected, r1-eth2

C>* 127.0.0.0/8 is directly connected, lo
```

- Check the status of the network interfaces:
 - r3> show interface

```
r3> show interface
Interface lo is up, line protocol detection is disabled
 index 1 metric 1 mtu 65536
 flags: <UP,LOOPBACK,RUNNING>
 inet 127.0.0.1/8
 inet6 ::1/128
Interface r3-eth1 is up, line protocol detection is disabled
 index 913 metric 1 mtu 1500
 flags: <UP,BROADCAST,RUNNING,MULTICAST>
 HWaddr: fe:5e:63:a3:f1:59
 inet 10.10.23.3/24 broadcast 10.10.23.255
 inet6 fe80::fc5e:63ff:fea3:f159/64
Interface r3-eth2 is up, line protocol detection is disabled
 index 927 metric 1 mtu 1500
 flags: <UP,BROADCAST,RUNNING,MULTICAST>
 HWaddr: 6a:aa:d8:e7:77:4d
 inet 10.10.35.3/24 broadcast 10.10.35.255
```

Quagga configuration mode

- Enable the configuration mode:
 - r3> enable
 - (Password: quagga)

```
r3> enable
Password:
r3# █
```

- Inspect the running configuration of router:
 - r3# show running-config

```
r3# show running-config
Current configuration:
hostname r3
password quagga
enable password quagga
 og file /home/mininet/Downloads/lab7/configs/r3/logs/zebra.log
debug zebra packet
interface lo
 interface r3-eth1
 ip address 10.10.23.3/24
 ipv6 nd suppress-ra
 interface r3-eth2
 ip address 10,10,35,3/24
 ipv6 nd suppress-ra
line vty
 no login
```

On the fly configuration

- Enter the fly configuration mode:
 - r4# configure terminal
- Enter the configuration mode of interface:
 - r4(config)# interface r4-eth2
- Edit interface:
 - r4(config-if)# ip address 10.10.45.4/24

```
r4# configure terminal
r4(config)# interface r4-eth2
r4(config-if)# ip address 10.10.45.4/24
r4(config-if)#
```