value column to run report-generating queries on that column using SQL. See Section 15.22, "InnoDB Limits" for details.

- The maximum size for the key-value combination is 1 MB.
- If you share configuration files across MySQL servers of different versions, using the latest configuration options for the daemon\_memcached plugin could cause startup errors on older MySQL versions. To avoid compatibility problems, use the loose prefix with option names. For example, use loose-daemon\_memcached\_option='-c 64' instead of daemon\_memcached\_option='-c 64'.
- There is no restriction or check in place to validate character set settings. memcached stores and retrieves keys and values in bytes and is therefore not character set sensitive. However, you must ensure that the memcached client and the MySQL table use the same character set.
- memcached connections are blocked from accessing tables that contain an indexed virtual column.

  Accessing an indexed virtual column requires a callback to the server, but a memcached connection does not have access to the server code.

## 15.21 InnoDB Troubleshooting

The following general guidelines apply to troubleshooting InnoDB problems:

- When an operation fails or you suspect a bug, look at the MySQL server error log (see Section 5.4.2, "The Error Log"). Server Error Message Reference provides troubleshooting information for some of the common InnoDB-specific errors that you may encounter.
- If the failure is related to a deadlock, run with the <code>innodb\_print\_all\_deadlocks</code> option enabled so that details about each deadlock are printed to the MySQL server error log. For information about deadlocks, see Section 15.7.5, "Deadlocks in InnoDB".
- If the issue is related to the InnoDB data dictionary, see Section 15.21.3, "Troubleshooting InnoDB Data Dictionary Operations".
- When troubleshooting, it is usually best to run the MySQL server from the command prompt, rather than through mysqld\_safe or as a Windows service. You can then see what mysqld prints to the console, and so have a better grasp of what is going on. On Windows, start mysqld with the --console option to direct the output to the console window.
- Enable the Innobe Monitors to obtain information about a problem (see Section 15.17, "Innobe Monitors"). If the problem is performance-related, or your server appears to be hung, you should enable the standard Monitor to print information about the internal state of Innobe. If the problem is with locks, enable the Lock Monitor. If the problem is with table creation, tablespaces, or data dictionary operations, refer to the Innobe Information Schema system tables to examine contents of the Innobe internal data dictionary.

InnoDB temporarily enables standard InnoDB Monitor output under the following conditions:

- · A long semaphore wait
- InnoDB cannot find free blocks in the buffer pool
- Over 67% of the buffer pool is occupied by lock heaps or the adaptive hash index
- If you suspect that a table is corrupt, run CHECK TABLE on that table.

## 15.21.1 Troubleshooting InnoDB I/O Problems