## Step 2: Install MongoDB for Windows.

Change to the directory containing the .msi installation binary of your choice and invoke:

You can specify the installation location for the executable by modifying the INSTALLLOCATION value.

By default, this method installs all MongoDB binaries. To install specific MongoDB component sets, you can specify them in the ADDLOCAL argument using a comma-separated list including one or more of the following component sets:

<b>Component Set</b>	Binaries
Server	mongod.exe
Router	mongos.exe
Client	mongo.exe
MonitoringTools	mongostat.exe, mongotop.exe
ImportExportTools	mongodump.exe, mongorestore.exe, mongoexport.exe,
	mongoimport.exe
MiscellaneousTools	bsondump.exe, mongofiles.exe, mongooplog.exe, mongoperf.exe

For instance, to install *only* the MongoDB utilities, invoke:

## Run MongoDB

Warning: Do not make mongod.exe visible on public networks without running in "Secure Mode" with the auth setting. MongoDB is designed to be run in trusted environments, and the database does not enable "Secure Mode" by default.

## Step 1: Set up the MongoDB environment.

MongoDB requires a *data directory* to store all data. MongoDB's default data directory path is \data\db. Create this folder using the following commands from a *Command Prompt*:

```
md \data\db
```

You can specify an alternate path for data files using the --dbpath option to mongod. exe, for example:

```
C:\mongodb\bin\mongod.exe --dbpath d:\test\mongodb\data
```

If your path includes spaces, enclose the entire path in double quotes, for example:

```
C:\mongodb\bin\mongod.exe --dbpath "d:\test\mongo db data"
```

You may also specify the dbpath in a configuration file.

2.3. Installation Guides