

Hortonworks Data Platform

Ambari User's Guide

(Dec 21, 2015)

Hortonworks Data Platform : Ambari User's Guide

Copyright © 2012-2015 Hortonworks, Inc. Some rights reserved.

The Hortonworks Data Platform, powered by Apache Hadoop, is a massively scalable and 100% open source platform for storing, processing and analyzing large volumes of data. It is designed to deal with data from many sources and formats in a very quick, easy and cost-effective manner. The Hortonworks Data Platform consists of the essential set of Apache Hadoop projects including MapReduce, Hadoop Distributed File System (HDFS), HCatalog, Pig, Hive, HBase, Zookeeper and Ambari. Hortonworks is the major contributor of code and patches to many of these projects. These projects have been integrated and tested as part of the Hortonworks Data Platform release process and installation and configuration tools have also been included.

Unlike other providers of platforms built using Apache Hadoop, Hortonworks contributes 100% of our code back to the Apache Software Foundation. The Hortonworks Data Platform is Apache-licensed and completely open source. We sell only expert technical support, [training](#) and partner-enablement services. All of our technology is, and will remain free and open source.

Please visit the [Hortonworks Data Platform](#) page for more information on Hortonworks technology. For more information on Hortonworks services, please visit either the [Support](#) or [Training](#) page. Feel free to [Contact Us](#) directly to discuss your specific needs.



Except where otherwise noted, this document is licensed under
Creative Commons Attribution ShareAlike 3.0 License.
<http://creativecommons.org/licenses/by-sa/3.0/legalcode>

Table of Contents

1. Overview: Ambari User's Guide	1
1.1. Architecture	1
1.1.1. Sessions	1
1.2. Accessing Ambari Web	2
2. Monitoring and Managing Your Cluster	3
2.1. Viewing the Cluster Dashboard	3
2.1.1. Scanning Service Status	3
2.1.2. Widget Descriptions	4
2.1.3. Widget Details	5
2.1.4. Linking to Service UIs	5
2.1.5. Viewing Cluster-Wide Metrics	6
2.2. Modifying the Cluster Dashboard	7
2.2.1. Adding a Widget to the Dashboard	7
2.2.2. Resetting the Dashboard	7
2.2.3. Customizing Widget Display	8
2.3. Viewing Cluster Heatmaps	8
3. Managing Hosts	10
3.1. Working with Hosts	10
3.2. Determining Host Status	10
3.3. Filtering the Hosts List	11
3.4. Performing Host-Level Actions	11
3.5. Viewing Components on a Host	12
3.6. Decommissioning Masters and Slaves	13
3.6.1. How to Decommission a Component	13
3.7. How to Delete a Component	14
3.8. Deleting a Host from a Cluster	14
3.8.1. How to Delete a Host from a Cluster	15
3.9. Setting Maintenance Mode	15
3.9.1. Setting Maintenance Mode for Services, Components, and Hosts	15
3.9.2. How to Turn On Maintenance Mode for a Service	16
3.9.3. How to Turn On Maintenance Mode for a Host	16
3.9.4. How to Turn On Maintenance Mode for a Host (alternative using filtering for hosts)	16
3.9.5. Maintenance Mode Use Cases	17
3.10. Adding Hosts to a Cluster	18
3.11. Rack Awareness	18
4. Managing Services	20
4.1. Starting and Stopping All Services	20
4.2. Selecting a Service	21
4.3. Adding a Service	21
4.3.1. Adding a Service to your Hadoop cluster	21
4.4. Editing Service Config Properties	24
4.5. Viewing Service Summary and Alerts	25
4.5.1. Alerts and Health Checks	26
4.5.2. Modifying the Service Dashboard	26
4.6. Performing Service Actions	28
4.7. Monitoring Background Operations	29
4.8. Using Quick Links	30

4.9. Rolling Restarts	30
4.9.1. Setting Rolling Restart Parameters	31
4.9.2. Aborting a Rolling Restart	31
4.10. Refreshing YARN Capacity Scheduler	32
4.10.1. How to refresh the YARN Capacity Scheduler	32
4.11. Rebalancing HDFS	32
4.11.1. How to rebalance HDFS	32
5. Managing Service High Availability	34
5.1. NameNode High Availability	34
5.1.1. How To Configure NameNode High Availability	34
5.1.2. How to Roll Back NameNode HA	39
5.2. ResourceManager High Availability	47
5.2.1. How to Configure ResourceManager High Availability	47
5.2.2. How to Disable ResourceManager High Availability	48
5.3. HBase High Availability	50
5.3.1. Adding an HBase Master Component	50
5.4. Hive High Availability	50
5.4.1. Adding a Hive Metastore Component	50
5.4.2. Adding a HiveServer2 Component	50
5.4.3. Adding a WebHCat Component	51
5.5. Storm High Availability	51
5.5.1. Adding a Nimbus Component	51
5.6. Oozie High Availability	51
5.6.1. Adding an Oozie Server Component	52
6. Managing Configurations	53
6.1. Configuring Services	53
6.1.1. Updating Service Properties	53
6.1.2. Restarting Components	53
6.2. Using Host Config Groups	53
6.3. Customizing Log Settings	55
6.4. Downloading Client Configs	56
6.5. Service Configuration Versions	56
6.5.1. Basic Concepts	56
6.5.2. Terminology	57
6.5.3. Saving a Change	57
6.5.4. Viewing History	58
6.5.5. Comparing Versions	59
6.5.6. Reverting a Change	60
6.5.7. Versioning and Host Config Groups	60
7. Administering the Cluster	62
7.1. Managing Stack and Versions	62
7.1.1. Register a Version	62
7.1.2. Install the Version	63
7.1.3. Perform Upgrade	63
7.1.4. Upgrade Prerequisites	64
7.2. Service Accounts	65
7.3. Kerberos	65
7.3.1. How To Regenerate Keytabs	65
7.3.2. How To Disable Kerberos	66
8. Monitoring and Alerts	67
8.1. Managing Alerts	67

8.1.1. Alert Types	68
8.2. Configuring Notifications	70
8.2.1. Customizing Notification Templates	72
8.3. List of Predefined Alerts	74
8.3.1. HDFS Service Alerts	75
8.3.2. YARN Alerts	77
8.3.3. MapReduce2 Alerts	78
8.3.4. HBase Service Alerts	78
8.3.5. Hive Alerts	79
8.3.6. Oozie Alerts	79
8.3.7. ZooKeeper Alerts	80
8.3.8. Ambari Alerts	80
8.3.9. Ambari Metrics Alerts	80

1. Overview: Ambari User's Guide

Hadoop is a large-scale, distributed data storage and processing infrastructure using clusters of commodity hosts networked together. Monitoring and managing such complex distributed systems is a non-trivial task. To help you manage the complexity, Apache Ambari collects a wide range of information from the cluster's nodes and services and presents it to you in an easy-to-read and use, centralized web interface, Ambari Web.


Ambari Web displays information such as service-specific summaries, graphs, and alerts. You use Ambari Web to create and manage your HDP cluster and to perform basic operational tasks such as starting and stopping services, adding hosts to your cluster, and updating service configurations. You also can use Ambari Web to perform administrative tasks for your cluster such as enabling Kerberos security and performing Stack upgrades.

For more information on administering Ambari users, groups and views, refer to the [Ambari Administration Guide](#).

1.1. Architecture

The Ambari Server serves as the collection point for data from across your cluster. Each host has a copy of the Ambari Agent - either installed automatically by the Install wizard or manually - which allows the Ambari Server to control each host.

Figure - Ambari Server Architecture



1.1.1. Sessions

Ambari Web is a client-side JavaScript application, which calls the Ambari REST API (accessible from the Ambari Server) to access cluster information and perform cluster operations. After authenticating to Ambari Web, the application authenticates to the Ambari Server. Communication between the browser and server occurs asynchronously via the REST API.

The Ambari Web UI periodically accesses the Ambari REST API, which resets the session timeout. Therefore, by default, Ambari Web sessions do not timeout automatically. You can configure Ambari to timeout after a period of inactivity. Refer to [Ambari Web Inactivity Timeout](#) in the Ambari Security Guide for more information.

1.2. Accessing Ambari Web

Typically, you start the Ambari Server and Ambari Web as part of the installation process. If Ambari Server is stopped, you can start it using a command line editor on the Ambari Server host machine. Enter the following command:


```
ambari-server start
```

To access Ambari Web, open a supported browser and enter the Ambari Web URL:

```
http://<your.ambari.server>:8080
```

Enter your user name and password. If this is the first time Ambari Web is accessed, use the default values, admin/admin.


These values can be changed, and new users provisioned, using the Manage Ambari option.



For more information about managing users and other administrative tasks, see [Administering Ambari](#).

2. Monitoring and Managing Your Cluster

This topic describes how to use Ambari Web features to monitor and manage your HDP cluster. To navigate, select one of the following feature tabs located at the top of the Ambari main window.



- [Viewing the Cluster Dashboard](#)
- [Modifying the Cluster Dashboard](#)
- [Viewing Cluster Heatmaps](#)

2.1. Viewing the Cluster Dashboard

Ambari Web displays the **Dashboard** page as the home page. Use the **Dashboard** to view the operating status of your cluster. Each metrics widget displays status information for a single service in your HDP cluster. The Dashboard displays all metrics for the HDFS, YARN, HBase, and Storm services, and cluster-wide metrics by default. You can add and remove individual widgets, and rearrange the Dashboard by dragging and dropping each widget to a new location in the dashboard. Status information appears as simple pie and bar charts, more complex charts showing usage and load, sets of links to additional data sources, and values for operating parameters such as uptime and average RPC queue wait times. Most widgets display a single fact by default. For example, HDFS Disk Usage displays a load chart and a percentage figure.



Note

Each Service installed in your cluster also has a Service-specific dashboard. Refer to the [Managing Services > Modifying the Service Dashboard](#) section for more information.

2.1.1. Scanning Service Status

Notice the color of the dot appearing next to each component name in a list of components, services or hosts. The dot color and blinking action indicates operating status of each component, service, or host. For example, in the [Summary View](#), notice green dot next to each service name. The following colors and actions indicate service status:

Status Indicators

Color	Status
Solid Green	All masters are running
Blinking Green	Starting up
Solid Red	At least one master is down
Blinking Red	Stopping

Click the service name to open the **Services** screen, where you can see more detailed information on each service.

2.1.2. Widget Descriptions

The Dashboard includes metrics for the following services:

View **Metrics** that indicate the operating status of your cluster on the Ambari Dashboard. Each metrics widget displays status information for a single service in your HDP cluster. The Ambari Dashboard displays all metrics for the HDFS, YARN, HBase, and Storm services, and cluster-wide metrics by default.



Note

Metrics data for Storm is buffered and sent as a batch to Ambari every five minutes. After adding the Storm service, anticipate a five-minute delay for Storm metrics to appear.

You can add and remove individual widgets, and rearrange the dashboard by dragging and dropping each widget to a new location in the dashboard.

Status information appears as simple pie and bar charts, more complex charts showing usage and load, sets of links to additional data sources, and values for operating parameters such as uptime and average RPC queue wait times. Most widgets display a single fact by default. For example, HDFS Disk Usage displays a load chart and a percentage figure. The Ambari Dashboard includes metrics for the following services:

Ambari Service Metrics and Descriptions


Metric:	Description:
HDFS	
HDFS Disk Usage	The Percentage of DFS used, which is a combination of DFS and non-DFS used.
Data Nodes Live	The number of DataNodes live, as reported from the NameNode.
NameNode Heap	The percentage of NameNode JVM Heap used.
NameNode RPC	The average RPC queue latency.
NameNode CPU WIO	The percentage of CPU Wait I/O.
NameNode Uptime	The NameNode uptime calculation.
YARN (HDP 2.1 or later Stacks)	
ResourceManager Heap	The percentage of ResourceManager JVM Heap used.
ResourceManager Uptime	The ResourceManager uptime calculation.
NodeManagers Live	The number of DataNodes live, as reported from the ResourceManager.

Metric:	Description:
YARN Memory	The percentage of available YARN memory (used vs. total available).
HBase	
HBase Master Heap	The percentage of NameNode JVM Heap used.
HBase Ave Load	The average load on the HBase server.
HBase Master Uptime	The HBase Master uptime calculation.
Region in Transition	The number of HBase regions in transition.
Storm (HDP 2.1 or later Stacks)	
Supervisors Live	The number of Supervisors live, as reported from the Nimbus server.

2.1.3. Widget Details

To see more detailed information about a service, hover your cursor over a Metrics widget.


More detailed information about the service displays, as shown in the following example:



- To remove a widget from the mashup, click the white X.
- To edit the display of information in a widget, click the pencil icon. For more information about editing a widget, see [Customizing Metrics Display](#).

2.1.4. Linking to Service UIs

The HDFS Links and HBase Links widgets list HDP components for which links to more metrics information, such as thread stacks, logs and native component UIs are available. For example, you can link to NameNode, Secondary NameNode, and DataNode components for HDFS, using the links shown in the following example:




Choose the More drop-down to select from the list of links available for each service. The Ambari Dashboard includes additional links to metrics for the following services:

Links to More Metrics for HDP Services

Service:	Metric:	Description:
HDFS	NameNode UI	Links to the NameNode UI.
	NameNode Logs	Links to the NameNode logs.
	NameNode JMX	Links to the NameNode JMX servlet.
	Thread Stacks	Links to the NameNode thread stack traces.
HBase	HBase Master UI	Links to the HBase Master UI.
	HBase Logs	Links to the HBase logs.
	ZooKeeper Info	Links to ZooKeeper information.
	HBase Master JMX	Links to the HBase Master JMX servlet.
	Debug Dump	Links to debug information.
	Thread Stacks	Links to the HBase Master thread stack traces.

2.1.5. Viewing Cluster-Wide Metrics

Cluster-wide metrics display information that represents your whole cluster. The Ambari Dashboard shows the following cluster-wide metrics:




Ambari Cluster-Wide Metrics and Descriptions

Metric:	Description:
Memory Usage	The cluster-wide memory utilization, including memory cached, swapped, used, shared.
Network Usage	The cluster-wide network utilization, including in-and-out.
CPU Usage	Cluster-wide CPU information, including system, user and wait IO.
Cluster Load	Cluster-wide Load information, including total number of nodes, total number of CPUs, number of running processes and 1-min Load.

- To remove a widget from the dashboard, click the white X.
- Hover your cursor over each cluster-wide metric to magnify the chart or itemize the widget display.
- To remove or add metric items from each cluster-wide metric widget, select the item on the widget legend.
- To see a larger view of the chart, select the magnifying glass icon.

Ambari displays a larger version of the widget in a pop-out window, as shown in the following example:



Use the pop-up window in the same ways that you use cluster-wide metric widgets on the dashboard.

To close the widget pop-up window, choose OK.

2.2. Modifying the Cluster Dashboard

You can customize the Ambari Dashboard in the following ways:

- [Adding a Widget to the Dashboard](#)
- [Resetting the Dashboard](#)
- [Customizing Widget Display](#)

2.2.1. Adding a Widget to the Dashboard

To replace a widget that has been removed from the dashboard:

1. Select the Metrics drop-down, as shown in the following example:




2. Choose Add.
3. Select a metric, such as Region in Transition.
4. Choose Apply.

2.2.2. Resetting the Dashboard

To reset all widgets on the dashboard to display default settings:

1. Select the Metrics drop-down, as shown in the following example:




2. Choose Edit.
3. Choose Reset all widgets to default.

2.2.3. Customizing Widget Display

To customize the way a service widget displays metrics information:

1. Hover your cursor over a service widget.
2. Select the pencil-shaped, edit icon that appears in the upper-right corner.

The Customize Widget pop-up window displays properties that you can edit, as shown in the following example.



3. Follow the instructions in the Customize Widget pop-up to customize widget appearance.

In this example, you can adjust the thresholds at which the HDFS Capacity bar chart changes color, from green to orange to red.

4. To save your changes and close the editor, choose Apply.
5. To close the editor without saving any changes, choose Cancel.



Note

Not all widgets support editing.


2.3. Viewing Cluster Heatmaps

Heatmaps provides a graphical representation of your overall cluster utilization using simple color coding.



A colored block represents each host in your cluster. To see more information about a specific host, hover over the block representing the host in which you are interested. A pop-

up window displays metrics about HDP components installed on that host. Colors displayed in the block represent usage in a unit appropriate for the selected set of metrics. If any data necessary to determine state is not available, the block displays "Invalid Data". Changing the default maximum values for the heatmap lets you fine tune the representation. Use the Select Metric drop-down to select the metric type.



Heatmaps supports the following metrics:

Metric	Uses
Host/Disk Space Used %	disk.disk_free and disk.disk_total
Host/Memory Used %	memory.mem_free and memory.mem_total
Host/CPU Wait I/O %	cpu.cpu_wio
HDFS/Bytes Read	dfs.datanode.bytes_read
HDFS/Bytes Written	dfs.datanode.bytes_written
HDFS/Garbage Collection Time	jvm.gcTimeMillis
HDFS/JVM Heap MemoryUsed	jvm.memHeapUsedM
YARN/Garbage Collection Time	jvm.gcTimeMillis
YARN / JVM Heap Memory Used	jvm.memHeapUsedM
YARN / Memory used %	UsedMemoryMB and AvailableMemoryMB
HBase/RegionServer read request count	hbase.regionserver.readRequestsCount
HBase/RegionServer write request count	hbase.regionserver.writeRequestsCount
HBase/RegionServer compaction queue size	hbase.regionserver.compactionQueueSize
HBase/RegionServer regions	hbase.regionserver.regions
HBase/RegionServer memstore sizes	hbase.regionserver.memstoreSizeMB

3. Managing Hosts

Use Ambari Hosts to manage multiple HDP components such as DataNodes, NameNodes, NodeManagers and RegionServers, running on hosts throughout your cluster. For example, you can restart all DataNode components, optionally controlling that task with rolling restarts. Ambari Hosts supports filtering your selection of host components, based on operating status, host health, and defined host groupings.

3.1. Working with Hosts

Use Hosts to view hosts in your cluster on which Hadoop services run. Use options on **Actions** to perform actions on one or more hosts in your cluster.

View individual hosts, listed by fully-qualified domain name, on the Hosts landing page.

Name	IP Address	Cores (CPUs)	RAM	Disk Usage	Load Avg	Versions	Components
c6401.ambari.apache.org	10.0.2.15	1 (1)	1.8GB	0.04	2.2.1.1-20 (Current)	+ 7 Components	
c6402.ambari.apache.org	10.0.2.15	1 (1)	1.8GB	0.10	2.2.1.1-20 (Current)	+ 22 Components	
c6403.ambari.apache.org	10.0.2.15	1 (1)	1.8GB	0.85	2.2.1.1-20 (Current)	+ 21 Components	

3.2. Determining Host Status

A colored dot beside each host name indicates operating status of each host, as follows:

- Red - At least one master component on that host is down. Hover to see a tooltip that lists affected components.
- Orange - At least one slave component on that host is down. Hover to see a tooltip that lists affected components.
- Yellow - Ambari Server has not received a heartbeat from that host for more than 3 minutes.
- Green - Normal running state.

A red condition flag overrides an orange condition flag, which overrides a yellow condition flag. In other words, a host having a master component down may also have other issues. The following example shows three hosts, one having a master component down, one having a slave component down, and one healthy. Warning indicators appear next to hosts having a component down.

Name
Any
c6401.ambari.apache.org
c6402.ambari.apache.org
c6403.ambari.apache.org

3.3. Filtering the Hosts List

Use Filters to limit listed hosts to only those having a specific operating status. The number of hosts in your cluster having a listed operating status appears after each status name, in parenthesis. For example, the following cluster has one host having healthy status and three hosts having Maintenance Mode turned on.

- All (3)
- Healthy (1)
- Master Down (2)
- Slave Down (0)
- Lost Heartbeat (0)
- Alerts (2)
- Restart (2)
- Maintenance Mode (0)

For example, to limit the list of hosts appearing on Hosts home to only those with Healthy status, select Filters, then choose the Healthy option. In this case, one host name appears on Hosts home. Alternatively, to limit the list of hosts appearing on Hosts home to only those having Maintenance Mode on, select Filters, then choose the Maintenance Mode option. In this case, three host names appear on Hosts home.

Use the general filter tool to apply specific search and sort criteria that limits the list of hosts appearing on the Hosts page.

3.4. Performing Host-Level Actions


Use Actions to act on one, or multiple hosts in your cluster. Actions performed on multiple hosts are also known as bulk operations.

Actions comprises three menus that list the following option types:

- Hosts - lists selected, filtered or all hosts options, based on your selections made using Hosts home and Filters.
- Objects - lists component objects that match your host selection criteria.
- Operations - lists all operations available for the component objects you selected.

For example, to restart DataNodes on one host:

1. In Hosts, select a host running at least one DataNode.
2. In Actions, choose Selected Hosts > DataNodes > Restart, as shown in the following image.



3. Choose OK to confirm starting the selected operation.
4. Optionally, use [Monitoring Background Operations](#) to follow, diagnose or troubleshoot the restart operation.


3.5. Viewing Components on a Host

To manage components running on a specific host, choose a FQDN on the Hosts page. For example, choose c6403.ambari.apache.org in the default example shown. Summary-Components lists all components installed on that host.

Summary	Config	Alerts	Versions
Components	Host Actions		
Metric Collector / AMS ZooKeeper Server / ZooKeeper DataNode / HDFS Flume / Flume RegionServer / HBase Metric Monitor / AMS NodeManager / YARN Supervisor / Storm	Started Started Started Started Started Started Started Installed		
Clients / Falcon Client, HBase Client, HCat Client, HDFS Client, Hive Client, MapReduce2 Client, Oozie Client, Pig, Slider, Sqoop, Tez Client, YARN Client, ZooKeeper Client			
Summary			
Hostname: c6403.ambari.apache.org IP Address: 10.0.2.15 OS: centos6 (x86_64) Cores (CPU): 1 (1) Disk: 30.94GB/489.68GB (6.32% used) Memory: 1.83GB Load Avg: 0.78 Heartbeat: a moment ago Current Version: 2.2.1.1-20			

Choose options in **Host Actions**, to start, stop, restart, delete, or turn on maintenance mode for all components installed on the selected host.

Alternatively, choose action options from the drop-down menu next to an individual component on a host. The drop-down menu shows current operation status for each component. For example, you can decommission, restart, or stop the DataNode component (started) for HDFS, by selecting one of the options shown in the following example:



3.6. Decommissioning Masters and Slaves

Decommissioning is a process that supports removing a component from the cluster. You must decommission a master or slave running on a host before removing the component or host from service. Decommissioning helps prevent potential loss of data or service disruption. Decommissioning is available for the following component types:

- DataNodes
- NodeManagers
- RegionServers

Decommissioning executes the following tasks:


- For DataNodes, safely replicates the HDFS data to other DataNodes in the cluster.
- For NodeManagers, stops accepting new job requests from the masters and stops the component.
- For RegionServers, turns on drain mode and stops the component.

3.6.1. How to Decommission a Component

To decommission a component using Ambari Web, browse **Hosts** to find the host FQDN on which the component resides.

Using **Actions**, select **HostsComponent Type**, then choose **Decommission**.

For example:



The UI shows "Decommissioning" status while steps process, then "Decommissioned" when complete.

● DataNode / HDFS	Decommissioning ▾
● RegionServer / HBase	Started ▾
● NodeManager / YARN	Decommissioned ▾

3.7. How to Delete a Component

To delete a component using Ambari Web, on Hosts choose the host FQDN on which the component resides.

1. In Components, find a decommissioned component.
2. Stop the component, if necessary.



Note

A decommissioned slave component may restart in the decommissioned state.

3. For a decommissioned component, choose **Delete** from the component drop-down menu.



Note

Restarting services enables Ambari to recognize and monitor the correct number of components.

Deleting a slave component, such as a DataNode does not automatically inform a master component, such as a NameNode to remove the slave component from its exclusion list. Adding a deleted slave component back into the cluster presents the following issue; the added slave remains decommissioned from the master's perspective. Restart the master component, as a work-around.

3.8. Deleting a Host from a Cluster

Deleting a host removes the host from the cluster. Before deleting a host, you must complete the following prerequisites:


- Stop all components running on the host.
- Decommission any DataNodes running on the host.
- Move from the host any master components, such as NameNode or ResourceManager, running on the host.

- Turn Off Maintenance Mode, if necessary, for the host.

3.8.1. How to Delete a Host from a Cluster

1. In Hosts, click on a host name.
2. On the Host-Details page, select Host Actions drop-down menu.
3. Choose Delete.

If you have not completed prerequisite steps, a warning message similar to the following one appears:



3.9. Setting Maintenance Mode

Maintenance Mode supports suppressing alerts and skipping bulk operations for specific services, components and hosts in an Ambari-managed cluster. You typically turn on Maintenance Mode when performing hardware or software maintenance, changing configuration settings, troubleshooting, decommissioning, or removing cluster nodes. You may place a service, component, or host object in Maintenance Mode before you perform necessary maintenance or troubleshooting tasks.

Maintenance Mode affects a service, component, or host object in the following two ways:

- Maintenance Mode suppresses alerts, warnings and status change indicators generated for the object
- Maintenance Mode exempts an object from host-level or service-level bulk operations

Explicitly turning on Maintenance Mode for a service implicitly turns on Maintenance Mode for components and hosts that run the service. While Maintenance Mode On prevents bulk operations being performed on the service, component, or host, you may explicitly start and stop a service, component, or host having Maintenance Mode On.

3.9.1. Setting Maintenance Mode for Services, Components, and Hosts

For example, examine using Maintenance Mode in a 3-node, Ambari-managed cluster installed using default options. This cluster has one data node, on host c6403. This example describes how to explicitly turn on Maintenance Mode for the HDFS service, alternative procedures for explicitly turning on Maintenance Mode for a host, and the implicit effects of turning on Maintenance Mode for a service, a component and a host.

3.9.2. How to Turn On Maintenance Mode for a Service

1. Using Services, select HDFS.
2. Select Service Actions, then choose Turn On Maintenance Mode.
3. Choose OK to confirm.

Notice, on Services Summary that Maintenance Mode turns on for the NameNode and SNameNode components.

3.9.3. How to Turn On Maintenance Mode for a Host

1. Using Hosts, select c6401.ambari.apache.org.
2. Select Host Actions, then choose Turn On Maintenance Mode.
3. Choose OK to confirm.

Notice on Components, that Maintenance Mode turns on for all components.

3.9.4. How to Turn On Maintenance Mode for a Host (alternative using filtering for hosts)

1. Using Hosts, select c6403.ambari.apache.org.
2. In Actions > Selected Hosts > Hosts choose Turn On Maintenance Mode.
3. Choose OK to confirm.

Notice that Maintenance Mode turns on for host c6403.ambari.apache.org.

Your list of Hosts now shows Maintenance Mode On for hosts c6401 and c6403.

Name	IP Address	Cores (CPU)	RAM	Disk Usage	Load Avg	Components
c6401.ambari.apache.org	10.0.2.15	1 (1)	1.83GB	0.14	> 6 Components	
c6402.ambari.apache.org	10.0.2.15	1 (1)	1.83GB	0.11	> 27 Components	
c6403.ambari.apache.org	10.0.2.15	1 (1)	1.83GB	0.02	> 17 Components	

3 of 3 hosts showing - clear filters 1 host selected - clear selection Show: [10] [5] 1 - 3 of 3

- Hover your cursor over each Maintenance Mode icon appearing in the Hosts list.
- Notice that hosts c6401 and c6403 have Maintenance Mode On.
- Notice that on host c6401; HBaseMaster, HDFS client, NameNode, and ZooKeeper Server have Maintenance Mode turned On.
- Notice on host c6402, that HDFS client and Secondary NameNode have Maintenance Mode On.
- Notice on host c6403, that 15 components have Maintenance Mode On.
- The following behavior also results:
 - Alerts are suppressed for the DataNode.

- DataNode is skipped from HDFS Start/Stop/Restart All, Rolling Restart.
- DataNode is skipped from all Bulk Operations except Turn Maintenance Mode ON/OFF.
- DataNode is skipped from Start All and / Stop All components.
- DataNode is skipped from a host-level restart/restart all/stop all/start.

3.9.5. Maintenance Mode Use Cases

Four common Maintenance Mode Use Cases follow:

1. You want to perform hardware, firmware, or OS maintenance on a host.

You want to:

- Prevent alerts generated by all components on this host.
- Be able to stop, start, and restart each component on the host.
- Prevent host-level or service-level bulk operations from starting, stopping, or restarting components on this host.

To achieve these goals, turn On Maintenance Mode explicitly for the host. Putting a host in Maintenance Mode implicitly puts all components on that host in Maintenance Mode.

2. You want to test a service configuration change. You will stop, start, and restart the service using a rolling restart to test whether restarting picks up the change.

You want:

- No alerts generated by any components in this service.
- To prevent host-level or service-level bulk operations from starting, stopping, or restarting components in this service.

To achieve these goals, turn on Maintenance Mode explicitly for the service. Putting a service in Maintenance Mode implicitly turns on Maintenance Mode for all components in the service.

3. You turn off a service completely.

You want:

- The service to generate no warnings.
- To ensure that no components start, stop, or restart due to host-level actions or bulk operations.

To achieve these goals, turn On Maintenance Mode explicitly for the service. Putting a service in Maintenance Mode implicitly turns on Maintenance Mode for all components in the service.

4. A host component is generating alerts.


You want to:

- Check the component.
- Assess warnings and alerts generated for the component.
- Prevent alerts generated by the component while you check its condition.

To achieve these goals, turn on Maintenance Mode explicitly for the host component. Putting a host component in Maintenance Mode prevents host-level and service-level bulk operations from starting or restarting the component. You can restart the component explicitly while Maintenance Mode is on.

3.10. Adding Hosts to a Cluster

To add new hosts to your cluster, browse to the Hosts page and select Actions >+Add New Hosts. The Add Host Wizard provides a sequence of prompts similar to those in the Ambari Install Wizard. Follow the prompts, providing information similar to that provided to define the first set of hosts in your cluster.



3.11. Rack Awareness


Ambari can manage Rack information for hosts. By setting the Rack ID, Ambari can display the hosts in heatmaps by Rack ID, as well users can filter & find hosts based on Rack ID on the Hosts page.

If HDFS is installed in your cluster, Ambari will pass this Rack ID information to HDFS via a topology script. Ambari generates a topology script at /etc/hadoop/conf/topology.py and sets the net.topology.script.file.name property in core-site automatically. This topology script reads a mappings file /etc/hadoop/conf/topology_mappings.data that Ambari automatically generates. When you make changes to Rack ID assignment in Ambari, this mappings file will be updated when you push out the HDFS configuration. HDFS uses this topology script to obtain Rack information about the DataNode hosts.


Setting Rack ID

There are two methods in Ambari Web for setting the Rack ID. You can set the Rack ID for hosts in bulk on the Hosts page using the Actions menu; and you can set the Rack ID on an individual host by viewing the Host page using the Host Actions menu.

To set the Rack ID in bulk on the Hosts page, use the Actions menu and select Hosts > Set Rack (for All, Filtered or Selected hosts).



To set the Rack ID on an individual host, browse to the Host page, use the Host Actions menu and select Set Rack.



Using a Custom Topology Script


It is possible to not have Ambari manage the Rack information for hosts. Instead, you can use a custom topology script to provide rack information to HDFS and not use the Ambari-generated topology.py script. If you choose to manage Rack information on your own, you will need to **create your own topology script and manage distributing the script to all hosts**. Ambari will also not have any knowledge of host Rack information so heatmaps will not display by Rack in Ambari Web.

To manage Rack information on your own, in the Services > HDFS >Configs, modify the net.topology.script.file.name property. Set this property value to your own custom topology script (for example /etc/hadoop/conf/topology.sh). Distribute that topology script to your hosts and manage the Rack mapping information for your script outside of Ambari.

4. Managing Services

Use Services to monitor and manage selected services running in your Hadoop cluster.

All services installed in your cluster are listed in the leftmost Services panel.




Services supports the following tasks:

- Starting and Stopping All Services
- Selecting a Service
- Editing Service Config Properties
- Performing Service Actions
- Viewing Summary, Alert, and Health Information
- Rolling Restarts
- Refreshing YARN Capacity Scheduler
- Rebalancing HDFS

4.1. Starting and Stopping All Services

To start or stop all listed services at once, select Actions, then choose Start All or Stop All, as shown in the following example:



4.2. Selecting a Service

Selecting a service name from the list shows current summary, alert, and health information for the selected service. To refresh the monitoring panels and show information about a different service, select a different service name from the list.

Notice the colored dot next to each service name, indicating service operating status and a small, red, numbered rectangle indicating any alerts generated for the service.

4.3. Adding a Service

The Ambari install wizard installs all available Hadoop services by default. You may choose to deploy only some services initially, then add other services at later times. For example, many customers deploy only core Hadoop services initially. Add Service supports deploying additional services without interrupting operations in your Hadoop cluster. When you have deployed all available services, Add Service displays disabled.

For example, if you are using HDP 2.2 Stack and did not install Falcon or Storm, you can use the Add Service capability to add those services to your cluster.


To add a service, select Actions > Add Service, then complete the following procedure using the Add Service Wizard.

4.3.1. Adding a Service to your Hadoop cluster

This example shows the Falcon service selected for addition.

1. Choose Services.

Choose an available service. Alternatively, choose all to add all available services to your cluster. Then, choose Next. The Add Service wizard displays installed services highlighted green and check-marked, not available for selection.





Note

Ambari 2.0 supports adding Ranger and Spark services, using the Add Services Wizard.

<input checked="" type="checkbox"/> Ranger	0.4.0	Comprehensive security for Hadoop
<input type="checkbox"/> Slider	0.60.0.2.2	A framework for deploying, managing and monitoring existing distributed applications on YARN.
<input checked="" type="checkbox"/> Spark	1.2.0.2.2	Apache Spark is a fast and general engine for large-scale data processing.
<input type="checkbox"/> Kafka	0.8.1.2.2	A high-throughput distributed messaging system
<input checked="" type="checkbox"/> Ambari Metrics	0.1.0	A system for metrics collection that provides storage and retrieval capability for metrics collected from the cluster

For more information about installing Ranger, see [Installing Ranger](#).

For more information about Installing Spark, see [Installing Spark](#).

2. In Assign Masters, confirm the default host assignment. Alternatively, choose a different host machine to which master components for your selected service will be added. Then, choose Next.

The Add Services Wizard indicates hosts on which the master components for a chosen service will be installed. A service chosen for addition shows a grey check mark.

Using the drop-down, choose an alternate host name, if necessary.

- A green label located on the host to which its master components will be added, or
- An active drop-down list on which available host names appear.

3. In Assign Slaves and Clients, accept the default assignment of slave and client components to hosts. Then, choose Next.

Alternatively, select hosts on which you want to install slave and client components. You must select at least one host for the slave of each service being added.

Host Roles Required for Added Services

Service Added	Host Role Required
YARN	NodeManager
HBase	RegionServer


The Add Service Wizard skips and disables the Assign Slaves and Clients step for a service requiring no slave nor client assignment.

4. In Customize Services, accept the default configuration properties.

Alternatively, edit the default values for configuration properties, if necessary. Choose Override to create a configuration group for this service. Then, choose Next.

5. In Review, make sure the configuration settings match your intentions. Then, choose Deploy.

6. Monitor the progress of installing, starting, and testing the service. When the service installs and starts successfully, choose Next.



7. Summary displays the results of installing the service. Choose Complete.



8. Restart any other components having stale configurations.

4.4. Editing Service Config Properties

Select a service, then select **Configs** to view and update configuration properties for the selected service. For example, select **MapReduce2**, then select **Configs**. Expand a config category to view configurable service properties. For example, select **General** to configure Default virtual memory for a job's map task.

The screenshot shows the 'Configs' tab selected in the top navigation bar. The 'Manage Config Groups' dropdown is open, showing 'MapReduce2 Default (3)'. The main area displays the 'V1 Current' configuration, authored by 'admin' on 'Mon, Dec 29, 2014 21:28'. The 'General' section contains the following properties:

- Default virtual memory for a job's map-task: 688 MB
- Default virtual memory for a job's reduce-task: 682 MB
- Map-side sort buffer memory: 273 MB

Below the General section are collapsed sections for 'Advanced mapred-env', 'Advanced mapred-site', and 'Custom mapred-site'. A green arrow points to the 'Default virtual memory for a job's map-task' input field.

4.5. Viewing Service Summary and Alerts

After you select a service, the Summary tab displays basic information about the selected service.

The screenshot shows the 'Summary' tab for the NameNode service. The 'No alerts' indicator is visible at the top right. The summary includes the following information:


- NameNodes:** 1/1 Started
- SNameNodes:** 0/0 Started
- DataNodes:** 1/1 Started
- DataNodes Status:** 1 live / 0 dead / 0 decommissioning
- NameNode Uptime:** 9.92 days
- NameNode Heap:** 76.9 MB / 998.4 MB (7.7% used)
- Disk Usage (DFS Used):** 575.1 MB / 488.2 GB (0.12%)
- Disk Usage (Non DFS Used):** 29.4 GB / 488.2 GB (0.02%)
- Disk Usage (Remaining):** 458.3 GB / 488.2 GB (0.87%)
- Blocks (total):** 404
- Block Errors:** 0 corrupt / 0 missing / 404 under replicated
- Total Files + Directories:** 2389
- Upgrade Status:** No pending upgrade
- Safe Mode Status:** Not in safe mode

Select one of the `View Host` links, as shown in the following example, to view components and the host on which the selected service is running.

[NameNode](#) Started
[SNameNode](#) Started
[DataNodes](#) 1/1 DataNodes Live

4.5.1. Alerts and Health Checks

On each Service page, in the Summary area, click **Alerts** to see a list of all health checks and their status for the selected service. Critical alerts are shown first. Click the text title of each alert message in the list to see the alert definition. For example, On the HBase > Services, click **Alerts**. Then, in **Alerts for HBase**, click **HBase Master Process**.



4.5.2. Modifying the Service Dashboard

Depending on the Service, the Summary tab includes a Metrics section which is by default populated with important service metrics to monitor.



This section of Metrics is customizable. You can add and remove widgets from the Dashboard as well as create new widgets. Widgets can be **private** only to you and your dashboard or **shared** in a Widget Browser library for other Ambari users to add/remove the widget from their Dashboard.




Important

You must have the Ambari Metrics service installed to be able to view, create, and customize the Service Dashboard. Only HDFS, Hive, HBase, and YARN have customizable service dashboards.

4.5.2.1. Adding or Removing a Widget

1. Click on the “+” to launch the Widget Browser. Alternatively, you can choose the Actions menu in the Metrics header to **Browse Widgets**.

2. The Widget Browser displays the available widgets to add to your Service Dashboard. This is a combination of shared widgets and widgets you have created. Widgets that are shared are identified by the icon highlighted in the following example.




3. If you want to only display the widgets you have created, click the "Show only my widgets" checkbox to filter the Widget Browser.
4. If a widget is already added to your dashboard, it is shown as **Added**. Click to remove.
5. If a widget is not already added, you can click **Add**.

4.5.2.2. Creating a Widget

1. Click on the “+” to launch the Widget Browser. Click the **Create Widget** button. Alternatively, you can choose the Actions menu in the Metrics header to **Create Widget**. This launches the Create Widget wizard.
2. Select the type of widget to create.
3. Depending on the service and type of widget, you can select metrics and use operators to create an Expression that will be displayed in the widget. A preview of the widget is displayed as you build the expression.
4. Enter the widget name and description. Optionally choose to Share the widget. Sharing the widget makes the widget available to all Ambari users for this cluster. Once a widget is shared, other Ambari Admins or Cluster Operators can modify or delete the widget. This cannot be undone.

4.5.2.3. Deleting a Widget

1. Click on the “+” to launch the Widget Browser. Alternatively, you can choose the Actions menu in the Metrics header to **Browse Widgets**.
2. The Widget Browser displays the available widgets to add to your Service Dashboard. This is a combination of shared widgets and widgets you have created. Widgets that are shared are identified by the icon highlighted in the following example.



3. If a widget is already added to your dashboard, it is shown as **Added**. Click to remove.
4. For widgets that you created, you can select the **More...** option to delete.
5. For widgets that are shared, if you are an Ambari Admin or Cluster Operator, you will also have the option to delete.
6. Deleting a shared widget removes the widget from all users. This cannot be undone.

4.5.2.4. Export Widget Graph Data

You can export the metrics data from widget graphs using the **Export** capability. This capability is available for graph-type widgets.

1. Mouse over the widget graph. You will see an **Export** icon. Alternatively, if you click on the widget graph to zoom into the graph, the **Export** icon is present in the upper-right of the dialog.
2. Click on the **Export** icon. You can choose to export in CSV or JSON format.
3. Select the format and the download will begin.

4.5.2.5. Setting Display Timezone


You can set the timezone used for displaying metrics data in widget graphs.

1. In Ambari Web, click on your user name and select **Settings**.
2. In the **Locale** section, select the **Timezone**.
3. Click **Save**.

The Ambari Web UI will reload and graphs will be displayed using the timezone you have set.

4.6. Performing Service Actions

Manage a selected service on your cluster by performing service actions. In Services, select the **Service Actions** drop-down menu, then choose an option. Available options depend on the service you have selected. For example, HDFS service action options include:




Optionally, choose Turn On Maintenance Mode to suppress alerts generated by a service before performing a service action. Maintenance Mode suppresses alerts and status indicator changes generated by the service, while allowing you to start, stop, restart, move, or perform maintenance tasks on the service. For more information about how Maintenance Mode affects bulk operations for host components, see [Setting Maintenance Mode](#).

4.7. Monitoring Background Operations


Optionally, use Background Operations to monitor progress and completion of bulk operations such as rolling restarts.

Background Operations opens by default when you run a job that executes bulk operations.


1. Select the right-arrow for each operation to show restart operation progress on each host.



2. After restarts complete, Select the right-arrow, or a host name, to view log files and any error messages generated on the selected host.




3. Select links at the upper-right to copy or open text files containing log and error information.



Optionally, select the option to not show the bulk operations dialog.

4.8. Using Quick Links

Select Quick Links options to access additional sources of information about a selected service. For example, HDFS Quick Links options include the native NameNode GUI, NameNode logs, the NameNode JMX output, and thread stacks for the HDFS service. Quick Links are not available for every service.



4.9. Rolling Restarts

When you restart multiple services, components, or hosts, use rolling restarts to distribute the task. A rolling restart stops, then starts multiple, running slave components such as DataNodes, NodeManagers, RegionServers, or Supervisors, using a batch sequence. You set rolling restart parameter values to control the number of, time between, tolerance for failures, and limits for restarts of many components across large clusters.

To run a rolling restart:

1. Select a Service, then link to a lists of specific components or hosts that Require Restart.
2. Select Restart, then choose a slave component option.
3. Review and set values for Rolling Restart Parameters.
4. Optionally, reset the flag to only restart components with changed configurations.
5. Choose Trigger Restart.

Use [Monitor Background Operations](#) to monitor progress of rolling restarts.



Important

Rolling Restarts of DataNodes is recommended to only be performed during a cluster maintenance window.

4.9.1. Setting Rolling Restart Parameters

When you choose to restart slave components, use parameters to control how restarts of components roll. Parameter values based on ten percent of the total number of components in your cluster are set as default values. For example, default settings for a rolling restart of components in a 3-node cluster restarts one component at a time, waits two minutes between restarts, will proceed if only one failure occurs, and restarts all existing components that run this service.

If you trigger a rolling restart of components, Restart components with stale configs defaults to true. If you trigger a rolling restart of services, Restart services with stale configs defaults to false.

Restart DataNodes

This will restart a specified number of DataNodes at a time.
Note: This will trigger alerts. To suppress alerts, turn on Maintenance Mode for HDFS prior to triggering a rolling restart

Restart	<input type="text" value="1"/>	DataNodes at a time
Wait	<input type="text" value="120"/>	seconds between batches
Tolerate up to	<input type="text" value="1"/>	restart failures
<input type="checkbox"/> Only restart DataNodes with stale configs		
<input type="button" value="Cancel"/>		<input type="button" value="Trigger Rolling Restart"/>


Rolling restart parameter values must satisfy the following criteria:

Validation Rules for Rolling Restart Parameters

Parameter	Required	Value	Description
Batch Size	Yes	Must be an integer > 0	Number of components to include in each restart batch.
Wait Time	Yes	Must be an integer > = 0	Time (in seconds) to wait between queuing each batch of components.
Tolerate up to x failures	Yes	Must be an integer > = 0	Total number of restart failures to tolerate, across all batches, before halting the restarts and not queuing batches.

4.9.2. Aborting a Rolling Restart

To abort future restart operations in the batch, choose Abort Rolling Restart.



4.10. Refreshing YARN Capacity Scheduler

After you modify the Capacity Scheduler configuration, YARN supports refreshing the queues without requiring you to restart your ResourceManager. The “refresh” operation is valid if you have made no destructive changes to your configuration. Removing a queue is an example of a destructive change.

4.10.1. How to refresh the YARN Capacity Scheduler

This topic describes how to refresh the Capacity Scheduler in cases where you have added or modified existing queues.

- In Ambari Web, browse to Services > YARN > Summary.
- Select Service Actions, then choose Refresh YARN Capacity Scheduler.
- Confirm you would like to perform this operation.

The refresh operation is submitted to the YARN ResourceManager.



Important

The Refresh operation will fail with the following message: “Failed to re-init queues” if you attempt to refresh queues in a case where you performed a destructive change, such as removing a queue. In cases where you have made destructive changes, you must perform a ResourceManager restart for the capacity scheduler change to take effect.


4.11. Rebalancing HDFS

HDFS provides a “balancer” utility to help balance the blocks across DataNodes in the cluster.

4.11.1. How to rebalance HDFS

This topic describes how you can initiate an HDFS rebalance from Ambari.

1. In Ambari Web, browse to Services > HDFS > Summary.
2. Select Service Actions, then choose Rebalance HDFS.
3. Enter the Balance Threshold value as a percentage of disk capacity.



4. Click Start to begin the rebalance.
5. You can check rebalance progress or cancel a rebalance in process by opening the Background Operations dialog.

5. Managing Service High Availability

Ambari provides the ability to configure the High Availability features available with the HDP Stack services. This section describes how to enable HA for the various Stack services.

- [NameNode High Availability](#)
- [ResourceManager High Availability](#)
- [HBase High Availability](#)
- [Hive High Availability](#)
- [Oozie High Availability](#)

5.1. NameNode High Availability

To ensure that a NameNode in your cluster is always available if the primary NameNode host fails, enable and set up NameNode High Availability on your cluster using Ambari Web.

Follow the steps in the Enable NameNode HA Wizard.

For more information about using the Enable NameNode HA Wizard, see [How to Configure NameNode High Availability](#).

5.1.1. How To Configure NameNode High Availability

1. Check to make sure you have at least three hosts in your cluster and are running at least three ZooKeeper servers.
2. Check to make sure that the HDFS and ZooKeeper services are not in Maintenance Mode.

These services will be stopped and started when enabling NameNode HA. Maintenance Mode will prevent those start and stop operations from occurring. If the HDFS or ZooKeeper services are in Maintenance Mode the NameNode HA wizard will not complete successfully.

3. In Ambari Web, select Services > HDFS > Summary.
4. Select **Service Actions** and choose **Enable NameNode HA**.
5. The Enable HA Wizard launches. This wizard describes the set of automated and manual steps you must take to set up NameNode high availability.
6. **Get Started** : This step gives you an overview of the process and allows you to select a Nameservice ID. You use this Nameservice ID instead of the NameNode FQDN once HA has been set up. Click **Next** to proceed.

The screenshot shows the 'ENABLE NAMENODE HA WIZARD' interface. On the left, a sidebar lists steps: Get Started, Select Hosts, Review, Create Checkpoint, Configure Components, Initialize JournalNodes, Start Components, Initialize Metadata, and Finalize HA Setup. The 'Get Started' button is highlighted. The main panel title is 'Get Started'. It contains text about the wizard's purpose, the process involving automated and manual steps, and a warning about HBase. A text input field for 'Nameservice ID' is present, and a 'Next →' button is at the bottom right.

ENABLE NAMENODE HA WIZARD

Get Started

This wizard will walk you through enabling NameNode HA on your cluster. Once enabled, you will be running a Standby NameNode in addition to your Active NameNode. This allows for an Active-Standby NameNode configuration that automatically performs failover.

The process to enable HA involves a combination of **automated steps** (that will be handled by the wizard) and **manual steps** (that you must perform in sequence as instructed by the wizard).

You should plan a cluster maintenance window and prepare for cluster downtime when enabling NameNode HA.

If you have HBase running, please exit this wizard and stop HBase first.

Nameservice ID:

Next →

7. **Select Hosts** : Select a host for the additional NameNode and the JournalNodes. The wizard suggest options that you can adjust using the drop-down lists. Click Next to proceed.

Select Hosts

Select a host that will be running the additional NameNode.
In addition, select the hosts to run JournalNodes, which store NameNode edit logs in a fault tolerant manner.

Current NameNode: c6401.ambari.apache.org (1.8 Gi)

Additional NameNode: c6402.ambari.apache.org (1.8 Gi)

JournalNode: c6401.ambari.apache.org (1.8 Gi)

JournalNode: c6402.ambari.apache.org (1.8 Gi)

JournalNode: c6403.ambari.apache.org (1.8 Gi)

c6401.ambari.apache.org (1.8 GB, 1 cores)
 NameNode HBase Master ZooKeeper
 JournalNode

c6402.ambari.apache.org (1.8 GB, 1 cores)
 SNameNode History Server
 ResourceManager App Timeline Server
 Nagios Server Ganglia Server
 HiveServer2 Hive Metastore
 WebHCat Server Oozie Server
 ZooKeeper Falcon Server Nimbus
 Storm UI Server Logviewer Server
 DRPC Server Storm REST API Server
 JournalNode NameNode

c6403.ambari.apache.org (1.8 GB, 1 cores)
 ZooKeeper JournalNode

[← Back](#) [Next →](#)

8. Review : Confirm your host selections and click Next.

Review

Confirm your host selections.

Current NameNode: c6401.ambari.apache.org
 Secondary NameNode: c6402.ambari.apache.org **TO BE DELETED**
 Additional NameNode: c6402.ambari.apache.org **+ TO BE INSTALLED**
 JournalNode: c6401.ambari.apache.org **+ TO BE INSTALLED**
 c6402.ambari.apache.org **+ TO BE INSTALLED**
 c6403.ambari.apache.org **+ TO BE INSTALLED**

Review Configuration Changes.
 The following lists the configuration changes that will be made by the Wizard to enable NameNode HA. This information is for review only and is not editable except for the dfs.journalnode.edits.dir property.

[HDFS](#) [HBase](#)

[← Back](#) [Next →](#)

9. Create Checkpoints : Follow the instructions in the step. You need to log in to your current NameNode host to run the commands to put your NameNode into safe mode and create a checkpoint. When Ambari detects success, the message on the bottom of the window changes. Click Next.

Manual Steps Required: Create Checkpoint on NameNode

```

1. Login to the NameNode host c6401.ambari.apache.org.
2. Put the NameNode in Safe Mode (read-only mode):
   sudo su -l hdfs -c 'hdfs dfsadmin -safemode enter'
3. Once in Safe Mode, create a Checkpoint:
   sudo su -l hdfs -c 'hdfs dfsadmin -savemanagespace'
4. You will be able to proceed once Ambari detects that the NameNode is in Safe Mode and the Checkpoint has been created successfully.

If the Next button is enabled before you run the "Step 3: Create a Checkpoint" command, it means there is a recent Checkpoint already and you may proceed without running the "Step 3: Create a Checkpoint" command.

```

Checkpoint created

Next →

10.Configure Components : The wizard configures your components, displaying progress bars to let you track the steps. Click **Next** to continue.

Configure Components

Please proceed to the next step.

- ✓ Stop All Services
- ✓ Install Additional NameNode
- ✓ Install JournalNodes
- ✓ Reconfigure HDFS
- ✓ Start JournalNodes
- ✓ Disable Secondary NameNode

Next

11.Initialize JournalNodes : Follow the instructions in the step. You need to login to your **current NameNode host** to run the command to initialize the JournalNodes. When Ambari detects success, the message on the bottom of the window changes. Click **Next**.

Manual Steps Required: Initialize JournalNodes

```

1. Login to the NameNode host c6401.ambari.apache.org.
2. Initialize the JournalNodes by running:
   sudo su -l hdfs -c 'hdfs namenode -initializeSharedEdits'
3. You will be able to proceed once Ambari detects that the JournalNodes have been initialized successfully.

```

JournalNodes initialized

Next →

12.Start Components : The wizard starts the ZooKeeper servers and the NameNode, displaying progress bars to let you track the steps. Click **Next** to continue.

Start Components

Please proceed to the next step.

- ✓ Start ZooKeeper Servers
- ✓ Start NameNode

Next

13.Initialize Metadata : Follow the instructions in the step. For this step you must log in to both the **current NameNode** and the **additional NameNode**. Make sure you are logged in to the correct host for each command. Click **Next** when you have completed the two commands. A **Confirmation** pop-up window displays, reminding you to do both steps. Click **OK** to confirm.

Manual Steps Required: Initialize NameNode HA Metadata

1. Login to the NameNode host c6401.ambari.apache.org.
2. Initialize the metadata for NameNode automatic failover by running:
`sudo su -l hdfs -c 'hdfs zkfc -formatX'`

3. Login to the Additional NameNode host c6402.ambari.apache.org.
Important! Be sure to login to the Additional NameNode host.
This is a different host from the Steps 1 and 2 above.

4. Initialize the metadata for the Additional NameNode by running:
`sudo su -l hdfs -c 'hdfs namenode -bootstrapStandby'`

Please proceed once you have completed the steps above.

[Next →](#)

14.Finalize HA Setup : The wizard tracks the setup, displaying progress bars to let you track the steps. Click Done to finish the wizard. After the Ambari Web GUI reloads, you may see some alert notifications. Wait a few minutes until the services come back up. If necessary, restart any components using Ambari Web.

Finalize HA Setup

Please wait while the wizard finalizes the HA setup.

- ✓ Start Additional NameNode
- ✓ Install Failover Controllers
- ✓ Start Failover Controllers
- ✓ Reconfigure HBase
- ✓ Delete Secondary NameNode

[Start All Services](#)  72%

[Done](#)

15.If you are using Hive, you must manually change the Hive Metastore FS root to point to the Nameservice URI instead of the NameNode URI. You created the Nameservice ID in the Get Started step.

a. Check the current FS root. On the Hive host:

```
hive --config /etc/hive/conf.server --service metatool -  
listFSRoot
```

The output looks similar to the following: Listing FS Roots... hdfs://<namenode-host>/apps/hive/warehouse

b. Use this command to change the FS root:

```
$ hive --config /etc/hive/conf.server --service metatool -  
updateLocation <new-location><old-location>
```

For example, where the Nameservice ID is mycluster:

```
$ hive --config /etc/hive/conf.server --service metatool -  
updateLocation hdfs://mycluster/apps/hive/warehouse hdfs://  
c6401.ambari.apache.org/apps/hive/warehouse
```

The output looks similar to the following:

```
Successfully updated the following locations... Updated X  
records in SDS table
```

16 Adjust the ZooKeeper Failover Controller retries setting for your environment.

- a. Browse to Services > HDFS > Configs >Advanced core-site.
- b. Set ha.failover-controller.active-standby-elector.zk.op.retries=120

5.1.2. How to Roll Back NameNode HA

To roll back NameNode HA to the previous non-HA state use the following step-by-step manual process, depending on your installation.

1. Stop HBase
2. Checkpoint the Active NameNode
3. Stop All Services
4. Prepare the Ambari Host for Rollback
5. Restore the HBase Configuration
6. Delete ZooKeeper Failover Controllers
7. Modify HDFS Configurations
8. Recreate the standby NameNode
9. Re-enable the standby NameNode
10. Delete All JournalNodes
11. Delete the Additional NameNode
12. Verify the HDFS Components
13. Start HDFS

5.1.2.1. Stop HBase

1. From Ambari Web, go to the Services view and select HBase.
2. Choose Service Actions > Stop.
3. Wait until HBase has stopped completely before continuing.

5.1.2.2. Checkpoint the Active NameNode

If HDFS has been in use **after** you enabled NameNode HA, but you wish to revert back to a non-HA state, you must checkpoint the HDFS state before proceeding with the rollback.

If the `Enable NameNode HA` wizard failed and you need to revert back, you can skip this step and move on to [Stop All Services](#).

- If Kerberos security has **not** been enabled on the cluster:

On the Active NameNode host, execute the following commands to save the namespace. You must be the HDFS service user to do this.

```
sudo su -l <HDFS_USER> -c 'hdfs dfsadmin -safemode enter' sudo su -l <HDFS_USER> -c 'hdfs dfsadmin -saveNamespace'
```

- If Kerberos security **has** been enabled on the cluster:

```
sudo su -l <HDFS_USER> -c 'kinit -kt /etc/security/keytabs/nn.service.keytab nn/<HOSTNAME>@<REALM>;hdfs dfsadmin -safemode enter' sudo su -l <HDFS_USER> -c 'kinit -kt /etc/security/keytabs/nn.service.keytab nn/<HOSTNAME>@<REALM>;hdfs dfsadmin -saveNamespace'
```

Where <HDFS_USER> is the HDFS service user; for example hdfs, <HOSTNAME> is the Active NameNode hostname, and <REALM> is your Kerberos realm.

5.1.2.3. Stop All Services

Browse to Ambari Web > Services, then choose Stop All in the Services navigation panel. You must wait until all the services are completely stopped.

5.1.2.4. Prepare the Ambari Server Host for Rollback

Log into the Ambari server host and set the following environment variables to prepare for the rollback procedure:

Variable	Value
export AMBARI_USER=AMBARI_USERNAME	Substitute the value of the administrative user for Ambari Web. The default value is admin.
export AMBARI_PW=AMBARI_PASSWORD	Substitute the value of the administrative password for Ambari Web. The default value is admin.
export AMBARI_PORT=AMBARI_PORT	Substitute the Ambari Web port. The default value is 8080.
export AMBARI_PROTO=AMBARI_PROTOCOL	Substitute the value of the protocol for connecting to Ambari Web. Options are http or https. The default value is http.
export CLUSTER_NAME=CLUSTER_NAME	Substitute the name of your cluster, set during the Ambari Install Wizard process. For example: mycluster.
export NAMENODE_HOSTNAME=NN_HOSTNAME	Substitute the FQDN of the host for the non-HA NameNode. For example: nn01.mycompany.com.
export ADDITIONAL_NAMENODE_HOSTNAME=ANN_HOSTNAME	Substitute the FQDN of the host for the additional NameNode in your HA setup.
export SECONDARY_NAMENODE_HOSTNAME=SNN_HOSTNAME	Substitute the FQDN of the host for the standby NameNode for the non-HA setup.
export JOURNALNODE1_HOSTNAME=JOUR1_HOSTNAME	Substitute the FQDN of the host for the first Journal Node.
export JOURNALNODE2_HOSTNAME=JOUR2_HOSTNAME	Substitute the FQDN of the host for the second Journal Node.
export JOURNALNODE3_HOSTNAME=JOUR3_HOSTNAME	Substitute the FQDN of the host for the third Journal Node.

Double check that these environment variables are set correctly.

5.1.2.5. Restore the HBase Configuration

If you have installed HBase, you may need to restore a configuration to its pre-HA state.

1. To check if your current HBase configuration needs to be restored, on the Ambari Server host:

```
/var/lib/ambari-server/resources/scripts/configs.sh -u  
<AMARI_USER> -p <AMARI_PW> -port <AMARI_PORT> get localhost  
<CLUSTER_NAME> hbase-site
```

Where the environment variables you set up in [Prepare the Ambari Server Host for Rollback](#) substitute for the variable names.

Look for the configuration property `hbase.rootdir`. If the value is set to the NameService ID you set up using the `Enable NameNode HA` wizard, you need to revert the `hbase-site` configuration set up back to non-HA values. If it points instead to a specific NameNode host, it does not need to be rolled back and you can go on to [Delete ZooKeeper Failover Controllers](#).

For example:

```
"hbase.rootdir": "hdfs://<name-service-id>:8020/apps/hbase/data"  
The hbase.rootdir property points to the NameService ID and the value needs to be  
rolled back "hbase.rootdir": "hdfs://<nn01.mycompany.com>:8020/apps/  
hbase/data" The hbase.rootdir property points to a specific NameNode host and not  
a NameService ID. This does not need to be rolled back.
```

2. If you need to roll back the `hbase.rootdir` value, on the Ambari Server host, use the `config.sh` script to make the necessary change:

```
/var/lib/ambari-server/resources/scripts/configs.sh -  
u <AMARI_USER> -p <AMARI_PW> -port <AMARI_PORT> set  
localhost <CLUSTER_NAME> hbase-site hbase.rootdir hdfs://  
<NAMENODE_HOSTNAME>:8020/apps/hbase/data
```

Where the environment variables you set up in [Prepare the Ambari Server Host for Rollback](#) substitute for the variable names.

3. Verify that the `hbase.rootdir` property has been restored properly. On the Ambari Server host:

```
/var/lib/ambari-server/resources/scripts/configs.sh -u  
<AMARI_USER> -p <AMARI_PW> -port <AMARI_PORT> get localhost  
<CLUSTER_NAME> hbase-site
```

The `hbase.rootdir` property should now be set to the NameNode hostname, not the NameService ID.

5.1.2.6. Delete ZooKeeper Failover Controllers

You may need to delete ZooKeeper (ZK) Failover Controllers.

1. To check if you need to delete ZK Failover Controllers, on the Ambari Server host:

```
curl -u <AMBARI_USER>:<AMBARI_PW> -H "X-Requested-By: ambari"
-i <AMBARI_PROTO>://localhost:<AMBARI_PORT>/api/v1/clusters/
<CLUSTER_NAME>/host_components?HostRoles/component_name=ZKFC
```

If this returns an empty `items` array, you may proceed to [Modify HDFS Configuration](#). Otherwise you must use the following DELETE commands:

2. To delete all ZK Failover Controllers, on the Ambari Server host:

```
curl -u <AMBARI_USER>:<AMBARI_PW> -H "X-Requested-By: ambari"
-i -X DELETE <AMBARI_PROTO>://localhost:<AMBARI_PORT>/
api/v1/clusters/<CLUSTER_NAME>/hosts/<NAMENODE_HOSTNAME>/
host_components/ZKFC curl -u <AMBARI_USER>:<AMBARI_PW> -
H "X-Requested-By: ambari" -i -X DELETE <AMBARI_PROTO>://
localhost:<AMBARI_PORT>/api/v1/clusters/<CLUSTER_NAME>/hosts/
<ADDITIONAL_NAMENODE_HOSTNAME>/host_components/ZKFC
```

3. Verify that the ZK Failover Controllers have been deleted. On the Ambari Server host:

```
curl -u <AMBARI_USER>:<AMBARI_PW> -H "X-Requested-By: ambari"
-i <AMBARI_PROTO>://localhost:<AMBARI_PORT>/api/v1/clusters/
<CLUSTER_NAME>/host_components?HostRoles/component_name=ZKFC
```

This command should return an empty `items` array.

5.1.2.7. Modify HDFS Configurations

You may need to modify your `hdfs-site` configuration and/or your `core-site` configuration.

1. To check if you need to modify your `hdfs-site` configuration, on the Ambari Server host:

```
/var/lib/ambari-server/resources/scripts/configs.sh -u
<AMBARI_USER> -p <AMBARI_PW> -port <AMBARI_PORT> get localhost
<CLUSTER_NAME> hdfs-site
```

If you see **any** of the following properties, you must delete them from your configuration.

- `dfs.nameservices`
- `dfs.client.failover.proxy.provider.<NAMESERVICE_ID>`
- `dfs.ha.namenodes.<NAMESERVICE_ID>`
- `dfs.ha.fencing.methods`
- `dfs.ha.automatic-failover.enabled`
- `dfs.namenode.http-address.<NAMESERVICE_ID>.nn1`
- `dfs.namenode.http-address.<NAMESERVICE_ID>.nn2`

- dfs.namenode.rpc-address.<NAMESERVICE_ID>.nn1
- dfs.namenode.rpc-address.<NAMESERVICE_ID>.nn2
- dfs.namenode.shared.edits.dir
- dfs.journalnode.edits.dir
- dfs.journalnode.http-address
- dfs.journalnode.kerberos.internal.spnego.principal
- dfs.journalnode.kerberos.principal
- dfs.journalnode.keytab.file

Where <NAMESERVICE_ID> is the NameService ID you created when you ran the **Enable NameNode HA** wizard.

2. To delete these properties, execute the following **for each property** you found. On the Ambari Server host:

```
/var/lib/ambari-server/resources/scripts/configs.sh -u  
<AMBARI_USER> -p <AMBARI_PW> -port <AMBARI_PORT> delete  
localhost <CLUSTER_NAME> hdfs-site property_name
```

Where you replace property_name with the name of **each** of the properties to be deleted.

3. Verify that all of the properties have been deleted. On the Ambari Server host: /var/lib/ambari-server/resources/scripts/configs.sh -u <AMBARI_USER> -p <AMBARI_PW> -port <AMBARI_PORT> get localhost <CLUSTER_NAME> hdfs-site

None of the properties listed above should be present.

4. To check if you need to modify your core-site configuration, on the Ambari Server host: /var/lib/ambari-server/resources/scripts/configs.sh -u <AMBARI_USER> -p <AMBARI_PW> -port <AMBARI_PORT> get localhost <CLUSTER_NAME> core-site

5. If you see the property ha.zookeeper.quorum, it must be deleted. On the Ambari Server host:

```
/var/lib/ambari-server/resources/scripts/configs.sh -u  
<AMBARI_USER> -p <AMBARI_PW> -port <AMBARI_PORT> delete  
localhost <CLUSTER_NAME> core-site ha.zookeeper.quorum
```

6. If the property fs.defaultFS is set to the NameService ID, it must be reverted back to its non-HA value. For example:

```
"fs.defaultFS": "hdfs://<name-service-id>" The property  
fs.defaultFS needs to be modified as it points to a NameService  
ID "fs.defaultFS": "hdfs://<nn01.mycompany.com>" The property
```

`fs.defaultFS` does not need to be changed as it points to a specific NameNode, not to a NameService ID

7. To revert the property `fs.defaultFS` to the NameNode host value, on the Ambari Server host:

```
/var/lib/ambari-server/resources/scripts/configs.sh -u  
<AMBARI_USER> -p <AMBARI_PW> -port <AMBARI_PORT> set localhost  
<CLUSTER_NAME> core-site fs.defaultFS hdfs://<NAMENODE_HOSTNAME>
```

8. Verify that the `core-site` properties are now properly set. On the Ambari Server host:

```
/var/lib/ambari-server/resources/scripts/configs.sh -u  
<AMBARI_USER> -p <AMBARI_PW> -port <AMBARI_PORT> get localhost  
<CLUSTER_NAME> core-site
```

The property `fs.defaultFS` should be set to point to the NameNode host and the property `ha.zookeeper.quorum` should not be there.

5.1.2.8. Recreate the Standby NameNode

You may need to recreate your standby NameNode.

1. To check to see if you need to recreate the standby NameNode, on the Ambari Server host:

```
curl -u <AMBARI_USER>:<AMBARI_PW> -H "X-Requested-By:  
ambari" -i -X GET <AMBARI_PROTO>://localhost:<AMBARI_PORT>/  
api/v1/clusters/<CLUSTER_NAME>/host_components?HostRoles/  
component_name=SECONDARY_NAMENODE
```

If this returns an empty `items` array, you must recreate your standby NameNode. Otherwise you can go on to [Re-enable Standby NameNode](#).

2. Recreate your standby NameNode. On the Ambari Server host: `curl -u <AMBARI_USER>:<AMBARI_PW> -H "X-Requested-By: ambari" -i -X POST -d '{"host_components": [{"HostRoles": {"component_name": "SECONDARY_NAMENODE"} }]}' <AMBARI_PROTO>://localhost:<AMBARI_PORT>/api/v1/clusters/<CLUSTER_NAME>/hosts?Hosts/host_name=<SECONDARY_NAMENODE_HOSTNAME>`

3. Verify that the standby NameNode now exists. On the Ambari Server host:

```
curl -u <AMBARI_USER>:<AMBARI_PW> -H "X-Requested-By:  
ambari" -i -X GET <AMBARI_PROTO>://localhost:<AMBARI_PORT>/  
api/v1/clusters/<CLUSTER_NAME>/host_components?HostRoles/  
component_name=SECONDARY_NAMENODE
```

This should return a non-empty `items` array containing the standby NameNode.

5.1.2.9. Re-enable the Standby NameNode

To re-enable the standby NameNode, on the Ambari Server host:

```
curl -u <AMBARI_USER>:<AMBARI_PW> -H "X-Requested-By: ambari" -i -X '{
  "RequestInfo": {
    "context": "Enable Secondary NameNode"
  },
  "Body": {
    "HostRoles": {
      "state": "INSTALLED"
    }
  }
}' <AMBARI_PROTO>://localhost:<AMBARI_PORT>/api/v1/clusters/<CLUSTER_NAME>/hosts/<SECONDARY_NAMENODE_HOSTNAME>/host_components/SECONDARY_NAMENODE
```

- If this returns 200, go to [Delete All JournalNodes](#).
- If this returns 202, wait a few minutes and run the following command on the Ambari Server host:

```
curl -u <AMBARI_USER>:<AMBARI_PW> -H "X-Requested-By: ambari" -i -X "<AMBARI_PROTO>://localhost:<AMBARI_PORT>/api/v1/clusters/<CLUSTER_NAME>/host_components?HostRoles/component_name=SECONDARY_NAMENODE&fields=HostRoles/state"
```

When "state" : "INSTALLED" is in the response, go on to the next step.

5.1.2.10. Delete All JournalNodes

You may need to delete any JournalNodes.

1. To check to see if you need to delete JournalNodes, on the Ambari Server host:

```
curl -u <AMBARI_USER>:<AMBARI_PW> -H "X-Requested-By: ambari" -i -X GET <AMBARI_PROTO>://localhost:<AMBARI_PORT>/api/v1/clusters/<CLUSTER_NAME>/host_components?HostRoles/component_name=JOURNALNODE
```

If this returns an empty items array, you can go on to [Delete the Additional NameNode](#). Otherwise you must delete the JournalNodes.

2. To delete the JournalNodes, on the Ambari Server host:

```
curl -u <AMBARI_USER>:<AMBARI_PW> -H "X-Requested-By: ambari" -i -X DELETE <AMBARI_PROTO>://localhost:<AMBARI_PORT>/api/v1/clusters/<CLUSTER_NAME>/hosts/<JOURNALNODE1_HOSTNAME>/host_components/JOURNALNODE
curl -u <AMBARI_USER>:<AMBARI_PW> -H "X-Requested-By: ambari" -i -X DELETE <AMBARI_PROTO>://localhost:<AMBARI_PORT>/api/v1/clusters/<CLUSTER_NAME>/hosts/<JOURNALNODE2_HOSTNAME>/host_components/JOURNALNODE
curl -u <AMBARI_USER>:<AMBARI_PW> -H "X-Requested-By: ambari" -i -X DELETE <AMBARI_PROTO>://localhost:<AMBARI_PORT>/api/v1/clusters/<CLUSTER_NAME>/hosts/<JOURNALNODE3_HOSTNAME>/host_components/JOURNALNODE
```

3. Verify that all the JournalNodes have been deleted. On the Ambari Server host:

```
curl -u <AMBARI_USER>:<AMBARI_PW> -H "X-Requested-By: ambari" -i -X GET <AMBARI_PROTO>://localhost:<AMBARI_PORT>/api/v1/clusters/<CLUSTER_NAME>/host_components?HostRoles/component_name=JOURNALNODE
```

This should return an empty items array.

5.1.2.11. Delete the Additional NameNode

You may need to delete your Additional NameNode.

1. To check to see if you need to delete your Additional NameNode, on the Ambari Server host:

```
curl -u <AMBARI_USER>:<AMBARI_PW> -H "X-Requested-By: ambari" -i  
-X GET <AMBARI_PROTO>://localhost:<AMBARI_PORT>/api/v1/clusters/  
<CLUSTER_NAME>/host_components?HostRoles/component_name=NAMENODE
```

If the `items` array contains two NameNodes, the Additional NameNode must be deleted.

2. To delete the Additional NameNode that was set up for HA, on the Ambari Server host:

```
curl -u <AMBARI_USER>:<AMBARI_PW> -H "X-Requested-By: ambari"  
-i -X DELETE <AMBARI_PROTO>://localhost:<AMBARI_PORT>/api/v1/  
clusters/<CLUSTER_NAME>/hosts/<ADDITIONAL_NAMENODE_HOSTNAME>/  
host_components/NAMENODE
```

3. Verify that the Additional NameNode has been deleted:

```
curl -u <AMBARI_USER>:<AMBARI_PW> -H "X-Requested-By: ambari" -i  
-X GET <AMBARI_PROTO>://localhost:<AMBARI_PORT>/api/v1/clusters/  
<CLUSTER_NAME>/host_components?HostRoles/component_name=NAMENODE
```

This should return an `items` array that shows only one NameNode.

5.1.2.12. Verify the HDFS Components

Make sure you have the correct components showing in HDFS.

1. Go to Ambari Web UI > Services, then select HDFS.
2. Check the Summary panel and make sure that the first three lines look like this:
 - NameNode
 - SNameNode
 - DataNodes

You should **not** see any line for JournalNodes.

5.1.2.13. Start HDFS

1. In the Ambari Web UI, select Service Actions, then choose Start.

Wait until the progress bar shows that the service has completely started and has passed the service checks.

If HDFS does not start, you may need to repeat the previous step.

2. To start all of the other services, select Actions > Start All in the Services navigation panel.

5.2. ResourceManager High Availability




Note

This feature is available with HDP 2.2 or later.


The following topic explains [How to Configure ResourceManager High Availability](#).

5.2.1. How to Configure ResourceManager High Availability


1. Check to make sure you have at least three hosts in your cluster and are running at least three ZooKeeper servers.
2. In Ambari Web, browse to Services > YARN > Summary. Select Service Actions and choose Enable ResourceManager HA.
3. The Enable ResourceManager HA Wizard launches. The wizard describes a set of automated and manual steps you must take to set up ResourceManager High Availability.
4. **Get Started:** This step gives you an overview of enabling ResourceManager HA. Click Next to proceed.




5. **Select Host:** The wizard shows you the host on which the current ResourceManager is installed and suggests a default host on which to install an additional ResourceManager. Accept the default selection, or choose an available host. Click Next to proceed.



6. **Review Selections:** The wizard shows you the host selections and configuration changes that will occur to enable ResourceManager HA. Expand YARN, if necessary, to review all the YARN configuration changes. Click Next to approve the changes and start automatically configuring ResourceManager HA.



- 7. Configure Components:** The wizard configures your components automatically, displaying progress bars to let you track the steps. After all progress bars complete, click Complete to finish the wizard.



5.2.2. How to Disable ResourceManager High Availability

Use the following instructions to disable ResourceManager High Availability. You will be deleting one ResourceManager and keeping one ResourceManager. This requires using the Ambari API to modify the cluster configuration to delete the ResourceManager and using the ZooKeeper client to update the znode permissions.



Important

These steps involve using the Ambari REST API. Be sure to test and verify these steps in a test environment prior to executing against a production environment.

1. In Ambari Web, stop YARN and ZooKeeper services.
2. On the Ambari Server host, use the Ambari API to retrieve the YARN configurations into a JSON file. For example, `yarn-site.json`.

```
/var/lib/ambari-server/resources/scripts/configs.sh get ambari.server
cluster.name yarn-site yarn-site.json
```

where **ambari.server** is the hostname of your Ambari Server and **cluster.name** is the name of your cluster.

3. Modify the following priorities in the `yarn-site.json` file:

Property	Value
<code>yarn.resourcemanager.ha.enabled</code>	Change the value to <code>false</code> .
<code>yarn.resourcemanager.ha.rm-ids</code>	Delete this property.
<code>yarn.resourcemanager.hostname.rm1</code>	Delete this property.
<code>yarn.resourcemanager.hostname.rm2</code>	Delete this property.
<code>yarn.resourcemanager.webapp.address.rm1</code>	Delete this property.
<code>yarn.resourcemanager.webapp.address.rm2</code>	Delete this property.

Property	Value
yarn.resourcemanager.webapp.https.address.rm1	Delete this property.
yarn.resourcemanager.webapp.https.address.rm2	Delete this property.
yarn.resourcemanager.cluster-id	Delete this property.
yarn.resourcemanager.ha.automatic-failover.zk-base-path	Delete this property.

4. Verify the following properties in the `yarn-site.json` file are set to the ResourceManager hostname you will be keeping:

Property	Value
yarn.resourcemanager.hostname	<ResourceManager hostname>
yarn.resourcemanager.admin.address	<ResourceManager hostname>
yarn.resourcemanager.webapp.address	<ResourceManager hostname>
yarn.resourcemanager.resource-tracker.address	<ResourceManager hostname>
yarn.resourcemanager.scheduler.address	<ResourceManager hostname>
yarn.resourcemanager.webapp.https.address	<ResourceManager hostname>
yarn.timeline-service.webapp.address	<ResourceManager hostname>
yarn.timeline-service.webapp.https.address	<ResourceManager hostname>
yarn.timeline-service.address	<ResourceManager hostname>
yarn.log.server.url	<ResourceManager hostname>

5. Search the `yarn-site.json` file and remove any references to the ResourceManager hostname that you will be removing.
6. Search the `yarn-site.json` file and remove any properties that might still be set for ResourceManager IDs. For example, rm1 and rm2.
7. Save the `yarn-site.json` file and set that configuration against the Ambari Server.

```
/var/lib/ambari-server/resources/scripts/configs.sh set
ambari.server cluster.name yarn-site yarn-site.json
```

where **ambari.server** is the hostname of your Ambari Server and **cluster.name** is the name of your cluster.

8. Using the Ambari API, delete the ResourceManager host component for the host that you are deleting:

```
curl --user admin:admin -i -H "X-Requested-By: ambari" -X DELETE
http://ambari.server:8080/api/v1/clusters/cluster.name/hosts/
hostname/host_components/RESOURCEMANAGER
```

where **ambari.server** is the hostname of your Ambari Server and **cluster.name** is the name of your cluster and **hostname** is the hostname of the ResourceManager you are deleting.

9. In Ambari Web, start the ZooKeeper service. On a host that has the ZooKeeper client installed, use the ZooKeeper client to change znode permissions:

```
/usr/hdp/current/zookeeper-client/bin/zkCli.sh
getAcl /rmstore/ZKRMStateRoot
setAcl /rmstore/ZKRMStateRoot world:anyone:rwcdra
```

10.In Ambari Web, restart ZooKeeper service and start YARN service.

5.3. HBase High Availability

During the HBase service install, depending on your component assignment, Ambari installs and configures one HBase Master component and multiple RegionServer components. To setup high availability for the HBase service, you can run two or more HBase Master components by [adding an HBase Master component](#). Once running two or more HBase Masters, HBase uses ZooKeeper for coordination of the active Master.

5.3.1. Adding an HBase Master Component

1. In Ambari Web, browse to Services > HBase.
2. In Service Actions, select the + Add HBase Master option.
3. Choose the host to install the additional HBase Master, then choose Confirm Add.

Ambari installs the new HBase Master and reconfigure HBase to handle multiple Master instances.

5.4. Hive High Availability

The Hive service has multiple, associated components. The primary Hive components are: Hive Metastore and HiveServer2. To setup high availability for the Hive service, you can run two or more of each of those components.



Note

This feature is available with HDP 2.2 or later.



Important

The relational database that backs the Hive Metastore itself should also be made highly available using best practices defined for the database system in use and should be done after consultation with your in-house DBA.

5.4.1. Adding a Hive Metastore Component

1. In Ambari Web, browse to Services > Hive.
2. In Service Actions, select the + Add Hive Metastore option.
3. Choose the host to install the additional Hive Metastore, then choose Confirm Add.
4. Ambari installs the component and reconfigures Hive to handle multiple Hive Metastore instances.

5.4.2. Adding a HiveServer2 Component

1. In Ambari Web, browse to the host where you would like to install another HiveServer2.

2. On the Host page, choose +Add.
3. Select HiveServer2 from the list.
4. Ambari installs the new HiveServer2.

5.4.3. Adding a WebHCat Component

1. In Ambari Web, browse to the host where you would like to install another WebHCat Server.
2. On the Host page, choose +Add.
3. Select WebHCat from the list.
4. Ambari installs the new WebHCat.
5. Ambari installs the component and reconfigures Hive to handle multiple Hive Metastore instances.

5.5. Storm High Availability



Note

This feature is available with HDP 2.3 or later.

To setup high availability for the Storm Nimbus server, you can run two or more Nimbus components by adding a Nimbus component from Ambari.

5.5.1. Adding a Nimbus Component

1. In Ambari Web, browse to Services > Hive.
2. In Service Actions, select the + Add Nimbus option.
3. Choose the host to install the additional Nimbus, then choose Confirm Add.

Ambari installs the component and reconfigures Storm to handle multiple Nimbus instances.

5.6. Oozie High Availability



Note

This feature is available with HDP 2.2 or later.

To setup high availability for the Oozie service, you can run two or more instances of the Oozie Server component.



Important

The relational database that backs the Oozie Server should also be made highly available using best practices defined for the database system in use and

should be done after consultation with your in-house DBA. Using the default installed Derby database instance is not supported with multiple Oozie Server instances and therefore, you must use an existing relational database. When using Derby for the Oozie Server, you will not have an option to add Oozie Server components to your cluster.



Important

High availability for Oozie requires the use of an external Virtual IP Address or Load Balancer to direct traffic to the Oozie servers.

5.6.1. Adding an Oozie Server Component

1. In Ambari Web, browse to the host where you would like to install another Oozie Server.
2. On the Host page, click the "+Add" button.
3. Select "Oozie Server" from the list and Ambari will install the new Oozie Server.
4. After configuring your external Load Balancer, update the oozie configuration.
5. Browse to Services > Oozie > Configs and in oozie-site add the following:

Property	Value
oozie.zookeeper.connection.string	List of ZooKeeper hosts with ports. For example: c6401.ambari.apache.org:2181,c6402.ambari.apache.org:2181,c6403.ambari.apache.org:2181
oozie.services.ext	org.apache.oozie.service.ZKLocksService,org.apache.oozie.service.ZKXLogStreamService
oozie.base.url	http://<loadbalancer.hostname>:11000/oozie

6. In oozie-env, uncomment OOZIE_BASE_URL property and change value to point to the Load Balancer. For example:

```
export OOZIE_BASE_URL="http://<loadbalance.hostname>:11000/oozie"
```

7. Restart Oozie service for the changes to take affect.
8. Update HDFS configs for the Oozie proxy user. Browse to Services > HDFS > Configs and in core-site update the hadoop.proxyuser.oozie.hosts property to include the newly added Oozie Server host. Hosts should be comma separated.
9. Restart all needed services.

6. Managing Configurations

Use Ambari Web to manage your HDP component configurations. Select any of the following topics:

- [Configuring Services](#)
- [Using Host Config Groups](#)
- [Customizing Log Settings](#)
- [Downloading Client Configs](#)
- [Service Configuration Versions](#)

6.1. Configuring Services

Select a service, then select **Configs** to view and update configuration properties for the selected service. For example, select MapReduce2, then select **Configs**. Expand a config category to view configurable service properties.

6.1.1. Updating Service Properties


1. Expand a configuration category.
2. Edit values for one or more properties that have the **Override** option.
Edited values, also called stale configs, show an **Undo** option.
3. Choose **Save**.

6.1.2. Restarting Components

After editing and saving a service configuration, **Restart** indicates components that you must restart.

Select the **Components** or **Hosts** links to view details about components or hosts requiring a restart.


Then, choose an option appearing in **Restart**. For example, options to restart YARN components include:



6.2. Using Host Config Groups

Ambari initially assigns all hosts in your cluster to one, default configuration group for each service you install. For example, after deploying a three-node cluster with default


configuration settings, each host belongs to one configuration group that has default configuration settings for the HDFS service. In Configs, select Manage Config Groups, to create new groups, re-assign hosts, and override default settings for host components you assign to each group.



To create a Configuration Group:

1. Choose Add New Configuration Group.
2. Name and describe the group, then choose Save.
3. Select a Config Group, then choose Add Hosts to Config Group.
4. Select Components and choose from available Hosts to add hosts to the new group.

Select Configuration Group Hosts enforces host membership in each group, based on installed components for the selected service.



5. Choose OK.
6. In Manage Configuration Groups, choose Save.

To edit settings for a configuration group:

1. In Configs, choose a Group.
2. Select a Config Group, then expand components to expose settings that allow Override.
3. Provide a non-default value, then choose Override or Save.

Configuration groups enforce configuration properties that allow override, based on installed components for the selected service and group.

DataNode
DataNode directories: /hadoop/hdfs/data
DataNode maximum Java heap size: 1024 MB (Override)
DataNode volumes failure toleration: 0 (Override)
DataNode directories permission: 750 (Override)

4. Override prompts you to choose one of the following options:

HDFS Configuration Group
Select or create a HDFS Configuration Group where the configuration value will be overridden.
Select an existing HDFS Configuration Group: custom log 4j hosts
Create a new HDFS Configuration Group: new config group name
A new HDFS Configuration Group will be created with the given name. Initially there will be no hosts in the group, with only the selected property overridden.
Cancel OK

- a. Select an existing configuration group (to which the property value override provided in step 3 will apply), or
- b. Create a new configuration group (which will include default properties, plus the property override provided in step 3).
- c. Then, choose OK.

5. In Configs, choose Save.

6.3. Customizing Log Settings

Ambari Web displays default logging properties in Service Configs > Custom log 4j Properties. Log 4j properties control logging activities for the selected service.

```
# Define some custom values that can be overridden by custom properties
hadoop.root.logger=INFO,console
hadoop.log.dir=
hadoop.log.file=hadoop.log
# Define the root logger to the system property 'hadoop.root.logger'.
log4j.rootLogger=${hadoop.root.logger}, EventCounter
# Logging Threshold
log4j.threshold=ALL
#
# Daily Rolling File Appender
#
log4j.appenders.DRFA=org.apache.log4j.DailyRollingFileAppender
log4j.appenders.DRFA.File=${hadoop.log.dir}/${hadoop.log.file}
```

Custom log4j.properties
Override
Cancel Save


Restarting components in the service pushes the configuration properties displayed in Custom log 4j Properties to each host running components for that service. If you have customized logging properties that define how activities for each service are logged, you will see refresh indicators next to each service name after upgrading to Ambari 1.5.0 or higher. Make sure that logging properties displayed in Custom log 4j Properties include any customization. Optionally, you can create configuration groups that include custom logging

properties. For more information about saving and overriding configuration settings, see [Updating Service Config Properties](#).

6.4. Downloading Client Configs

For Services that include client components (for example Hadoop Client or Hive Client), you can download the client configuration files associated with that client from Ambari.

- In Ambari Web, browse to the Service with the client for which you want the configurations.
- Choose Service Actions.
- Choose Download Client Configs. You are prompted for a location to save the client configs bundle.



- Save the bundle.

6.5. Service Configuration Versions

Ambari provides the ability to manage configurations associated with a Service. You can make changes to configurations, see a history of changes, compare + revert changes and push configuration changes to the cluster hosts.

- [Basic Concepts](#)
- [Terminology](#)
- [Saving a Change](#)
- [Viewing History](#)
- [Comparing Versions](#)
- [Reverting a Change](#)
- [Versioning and Host Config Groups](#)

6.5.1. Basic Concepts

It's important to understand how service configurations are organized and stored in Ambari. Properties are grouped into Configuration Types (config types). A set of config types makes up the set of configurations for a service.

For example, the HDFS Service includes the following config types: hdfs-site, core-site, hdfs-log4j, hadoop-env, hadoop-policy. If you browse to Services > HDFS > Configs, the configuration properties for these config types are available for edit.

Versioning of configurations is performed at the service-level. Therefore, when you modify a configuration property in a service, Ambari will create a Service Config Version. The figure below shows V1 and V2 of a Service Configuration Version with a change to a property in Config Type A. After making the property change to Config Type A in V1, V2 is created.



6.5.2. Terminology

The following table lists configuration versioning terms and concepts that you should know.

Term	Description
Configuration Property	Configuration property managed by Ambari, such as NameNode heapsize or replication factor.
Configuration Type (Config Type)	Group of configuration properties. For example: hdfs-site is a Config Type.
Service Configurations	Set of configuration types for a particular service. For example: hdfs-site and core-site Config Types are part of the HDFS Service Configuration.
Change Notes	Optional notes to save with a service configuration change.
Service Config Version (SCV)	Particular version of configurations for a specific service. Ambari saves a history of service configuration versions.
Host Config Group (HCG)	Set of configuration properties to apply to a specific set of hosts. Each service has a default Host Config Group, and custom config groups can be created on top of the default configuration group to target property overrides to one or more hosts in the cluster. See Managing Configuration Groups for more information.

6.5.3. Saving a Change

1. Make the configuration property change.
2. Choose Save.
3. You are prompted to enter notes that describe the change.



- Click Save to confirm your change. Cancel will not save but instead returns you to the configuration page to continuing editing.

To revert the changes you made and not save, choose Discard.

To return to the configuration page and continue editing without saving changes, choose Cancel.

6.5.4. Viewing History

Service Config Version history is available from Ambari Web in two places: On the Dashboard page under the Config History tab; and on each Service page under the Configs tab.

The Dashboard > Config History tab shows a list of all versions across services with each version number and the date and time the version was created. You can also see which user authored the change with the notes entered during save. Using this table, you can filter, sort and search across versions.

The screenshot shows a table titled 'Config History' with the following data:

Service	Config Group	Created	Author	Notes
HDFS	HDFS Default	Thu, Nov 06, 2014 08:10	admin	Created from service config version V2
HDFS	HDFS Default	Thu, Nov 06, 2014 08:09	admin	adjusted NN haipize
ZooKeeper	deleted	Wed, Nov 05, 2014 19:02	admin	Created from service config version V4
ZooKeeper	ZooKeeper Default	Wed, Nov 05, 2014 19:01	admin	Created from service config version V1
ZooKeeper	deleted	Wed, Nov 05, 2014 19:00	admin	No notes
ZooKeeper	deleted	Wed, Nov 05, 2014 19:00	admin	No notes
ZooKeeper	ZooKeeper Default	Wed, Nov 05, 2014 19:00	admin	No notes
ZooKeeper	ZooKeeper Default	Wed, Nov 05, 2014 19:00	admin	sync time
Pig	Pig Default	Wed, Nov 05, 2014 17:21	admin	Initial configurations for Pig
Hive	Hive Default	Wed, Nov 05, 2014 17:21	admin	Initial configurations for Hive

The most recent configuration changes are shown on the Service > Configs tab. Users can navigate the version scrollbar left-right to see earlier versions. This provides a quick way to access the most recent changes to a service configuration.

The screenshot shows the 'Configs' tab for the 'ZooKeeper' service. The current version is 'Current' (admin, authored on Wed, Nov 06, 2014 18:01). Other versions listed are '16 hours ago', '18 hours ago', '18 hours ago', and '19 hours ago'. The detailed view for the current version shows the following configuration parameters:

- ZooKeeper Server hosts: c6401.ambari.apache.org
- ZooKeeper directory: /hadoop/zookeeper
- Length of single Tick: 2000 ms
- Ticks to allow for sync at Init: 10
- Ticks to allow for sync at Runtime: 5
- Port for running ZK Server: 2181

Click on any version in the scrollbar to view, and hover to display an option menu which allows you compare versions and perform a revert. Performing a revert makes any config version that you select the current version.

ZooKeeper Default
admin authored on **Wed, Nov 05, 2014 16:00**
Initial configurations for ZooKeeper

V1

View **Compare** **Make Current**

6.5.5. Comparing Versions

When navigating the version scroll area on the Services > Configs tab, you can hover over a version to display options to view, compare or revert.

To perform a compare between two service configuration versions:

1. Navigate to a specific configuration version. For example "V6".
2. Using the version scrollbar, find the version would you like to compare against "V6". For example, if you want to compare V6 to V2, find V2 in the scrollbar.
3. Hover over the version to display the option menu. Click "Compare".
4. Ambari displays a comparison of V6 to V2, with an option to revert to V2.
5. Ambari also filters the display by only "Changed properties". This option is available under the Filter control.

Filter...

Overridden properties
Final properties
Changed properties
Show property issues
Show property warnings

6.5.6. Reverting a Change

You can revert to an older service configuration version by using the “Make Current” feature. The “Make Current” will actually create a new service configuration version with the configuration properties from the version you are reverting – it is effectively a “clone”. After initiating the Make Current operation, you are prompted to enter notes for the new version (i.e. the clone) and save. The notes text will include text about the version being cloned.




There are multiple methods to revert to a previous configuration version:

- View a specific version and click the “Make V* Current” button.



- Use the version navigation dropdown and click the “Make Current” button.



- Hover on a version in the version scrollbar and click the “Make Current” button.




- Perform a comparison and click the “Make V* Current” button.




6.5.7. Versioning and Host Config Groups

Service configuration versions are scoped to a host config group. For example, changes made in the default group can be compared and reverted in that config group. Same with custom config groups.

The following example describes a flow where you have multiple host config groups and create service configuration versions in each config group.





7. Administering the Cluster

From the cluster dashboard, use the Admin options to view information about [Managing Stack and Versions](#), [Service Accounts](#), and to Enable [Kerberos](#) security.



Note

For more information about administering your Ambari Server, see the [Ambari Administration Guide](#).

7.1. Managing Stack and Versions

The **Stack** section includes information about the Services installed and available in the cluster Stack. Browse the list of Services and click **Add Service** to start the wizard to install Services into your cluster.

The **Versions** section shows what version of software is currently running and installed in the cluster. This section also exposes the capability to perform an automated cluster upgrade for maintenance and patch releases for the Stack. This capability is available for HDP 2.2 Stack only. If you have a cluster running HDP 2.2, you can perform Stack upgrades to later maintenance and patch releases. For example: you can upgrade from the GA release of HDP 2.2 (which is HDP 2.2.0.0) to the first maintenance release of HDP 2.2 (which is HDP 2.2.4.2).



Note

For more details on upgrading from HDP 2.2.0.0 to the latest HDP 2.2 maintenance release, see the [Ambari Upgrade Guide](#).

The process for managing versions and performing an upgrade is comprised of three main steps:

1. [Register a Version](#) into Ambari
2. [Install the Version](#) into the Cluster
3. [Perform Upgrade](#) to the New Version

7.1.1. Register a Version

Ambari can manage multiple versions of Stack software.

To register a new version:

1. On the Versions tab, click **Manage Versions**.
2. Proceed to register a new version by clicking **+ Register Version**.
3. Enter a two-digit version number. For example, enter **4.2**, (which makes the version HDP-2.2.4.2).

[Versions](#) / Register Version

Details	
Name	HDP-2.2.4.2 · 4.2

4. Select one or more OS families and enter the respective Base URLs.
5. Click Save.
6. You can click “Install On...” or you can browse back to Admin > Stack and Versions > Versions tab. You will see the version current running and the version you just registered. Proceed to [Install the Version](#).

7.1.2. Install the Version

To install a version in the cluster:

1. On the versions tab, click [Install Packages](#).


Version	Hosts	Current
HDP-2.2.0.0-2041 (2.2.0.0-2041)	0 Not Installed	0 Installed
HDP-2.2.4.2 (2.2.4.2)	3 Not Installed	0 Installed

2. Click OK to confirm.
3. The Install version operation will start and the new version will be installed on all hosts.
4. You can browse to Hosts and to each Host > Versions tab to see the new version is installed. Proceed to [Perform Upgrade](#).

7.1.3. Perform Upgrade

Once your target version has been [registered into Ambari](#), [installed on all hosts](#) in the cluster and you meet the [Prerequisites](#) you are ready to perform an upgrade.

The perform upgrade process switches over the services in the cluster to a new version in a rolling fashion. The process follows the flow below. Starting with ZooKeeper and the Core Master components, ending with a Finalize step. To ensure the process runs smoothly, this process includes some manual prompts for you to perform cluster verification and testing along the way. You will be prompted when your input is required.



Important

This process can take some time to complete. You should validate the upgrade process in a dev/test environment prior to performing in production, as well, plan a block of time to monitor the progress. And as always, be sure to perform backups of your service metadata (you will be prompted during the first-stages of the upgrade process).

7.1.4. Upgrade Prerequisites

To perform an automated cluster upgrade from Ambari, your cluster must meet the following prerequisites:

Item	Requirement	Description
Cluster	Stack Version	Must be running HDP 2.2 Stack. This capability is not available for HDP 2.0 or 2.1 Stacks.
Version	New Version	All hosts must have the new version installed.
HDFS	NameNode HA	NameNode HA must be enabled and working properly. See the Ambari User's Guide for more information Configuring NameNode High Availability .
HDFS	Decommission	No components should be in decommissioning or decommissioned state.
YARN	YARN WPR	Work Preserving Restart must be configured.
Hosts	Heartbeats	All Ambari Agents must be heartbeating to Ambari Server. Any hosts that are not heartbeating must be in Maintenance Mode.
Hosts	Maintenance Mode	Any hosts in Maintenance Mode must not be hosting any Service master components.
Services	Services Started	All Services must be started.
Services	Maintenance Mode	No Services can be in Maintenance Mode.


To perform an upgrade to a new version.

1. On the versions tab, click **Perform Upgrade** on the new version.

2. Follow the steps on the wizard.

7.2. Service Accounts

To view the list of users and groups used by the cluster services, choose Admin > Service Accounts.



The screenshot shows the Ambari interface with the 'Service Accounts' tab selected. A table lists various service users and their corresponding values. The columns are 'Name' and 'Value'. The data includes users like 'Ams User', 'Smoke Test User', 'Hadoop Group', etc., and groups like 'proxuser group', 'hbase', 'HCat Client User', etc.

Name	Value
Ams User	ams
Smoke Test User	ambari-qa
Hadoop Group	hadoop
Falcon User	falcon
Flume User	flume
HDFS User	hdfs
Proxyuser Group	users
HBase User	hbase
HCat Client User	hcat
Hive User	hive
WebHCat User	hcat
Kafka User	kafka
Knox Group	knox
Knox User	knox
MapReduce User	mapred
Oozie User	oozie
Sqoop User	sqoop
Storm User	storm
Tez User	tez
YARN User	yarn
ZooKeeper User	zookeeper

7.3. Kerberos

If Kerberos has not been enabled in your cluster, click the Enable Kerberos button to launch the Kerberos wizard. For more information on configuring Kerberos in your cluster, see the [Ambari Security Guide](#). Once Kerberos is enabled, you can:

- [Regenerate Keytabs](#)
- [Disable Kerberos](#)

7.3.1. How To Regenerate Keytabs

1. Browse to Admin > Kerberos.
2. Click the Regenerate Kerberos button.
3. Confirm your selection to proceed.
4. Optionally, you can regenerate keytabs for only those hosts that are missing keytabs. For example, hosts that were not online/available from Ambari when enabling Kerberos.
5. Once you confirm, Ambari will connect to the KDC and regenerate the keytabs for the Service and Ambari principals in the cluster.

6. Once complete, you must restart all services for the new keytabs to be used.



Note

Ambari requires the Kerberos Admin credentials in order to regenerate the keytabs. If the credentials are not available to Ambari, you will be prompted to enter the KDC Admin username and password. For more information on configuring Kerberos in your cluster, see the [Ambari Security Guide](#).

7.3.2. How To Disable Kerberos

1. Browse to Admin > Kerberos.
2. Click the Disable Kerberos button.
3. Confirm your selection to proceed. Cluster services will be stopped and the Ambari Kerberos security settings will be reset.
4. To re-enable Kerberos, click Enable Kerberos and follow the wizard steps. For more information on configuring Kerberos in your cluster, see the [Ambari Security Guide](#).

8. Monitoring and Alerts

Ambari monitors cluster health and can alert you in the case of certain situations to help you identify and troubleshoot problems. You manage how alerts are organized, under which conditions notifications are sent, and by which method. This section provides information on:

- [Managing Alerts](#)
- [Configuring Notifications](#)
- [List of Predefined Alerts](#)

8.1. Managing Alerts

Ambari predefines a set of alerts that monitor the cluster components and hosts. Each alert is defined by an **Alert Definition**, which specifies the **Alert Type** check interval and thresholds. When a cluster is created or modified, Ambari reads the Alert Definitions and creates **Alert Instances** for the specific items to watch in the cluster. For example, if your cluster includes HDFS, there is an alert definition to watch the "DataNode Process". An instance of that alert definition is created for each DataNode in the cluster.



Note

Refer to [List of Predefined Alerts](#) for a list of the alerts that are configured by Ambari by default.

Using Ambari Web, you can browse the list of alerts defined for your cluster under the **Alerts** tab. You can search and filter alert definitions by current status, by last status change and the service the alert definition is associated with among other things. Click on the **alert definition name** to view the details about that alert, modify the alert properties (such as check interval and thresholds) and the list of alert instances associated with that alert definition.

Each alert instance reports an **Alert Status** defined by severity. The most common severity levels are OK, WARNING, CRITICAL but there are also severities for UNKNOWN and NONE. Alert notifications will be sent on alert status changes (for example, going from OK to CRITICAL). See [Configuring Notifications](#) for more information about notifications.

Modifying an Alert

General properties for an alert include Name, Description and Check Interval. The Check Interval defines the frequency Ambari will check the alert status. For example, a "1 minute" interval means Ambari checks the alert status every "1 minute".

The configuration options for thresholds depend on the **Alert Type**. See [Alert Types](#) for more information.

1. Browse to the Alerts section in Ambari Web.
2. Find the alert definition and click to view the definition details.

3. Click **Edit** to modify the name, description, check interval and thresholds (as applicable).
4. Click **Save**.
5. Changes will take effect on all alert instances at the next check interval.

Enabling or Disabling Alerts

You can optionally disable alerts. When an alert is disabled, no alert instances are in effect and Ambari will no longer perform the checks for the alert. Therefore, no alert status changes will be recorded and no notifications (i.e. no emails or SNMP traps) will be dispatched.

1. Browse to the Alerts section in **Ambari Web**.
2. Find the alert definition. Click the **Enabled** or **Disabled** text to enable/disable the alert.
3. Alternatively, you can click on the alert to view the definition details and click **Enabled** or **Disabled** to enable/disable the alert.
4. You will be prompted to confirm enable/disable.

8.1.1. Alert Types

Alert thresholds and the threshold units are dependent on alert type. The following table lists the types of alerts, their possible status and if the thresholds are configurable:

Alert Type	Description	Thresholds Configurable	Threshold Units
WEB	Connects to a Web URL. Alert status is based on the HTTP response code.	No	n/a
PORT	Connects to a port. Alert status is based on response time.	Yes	seconds
METRIC	Checks the value of a service metric. Units vary, based on the metric being checked.	Yes	varies
AGGREGATE	Aggregates the status for another alert.	Yes	%
SCRIPT	Executes a script to handle the alert check.	No	n/a

WEB Alert Type

WEB alerts watch a Web URL on a given component and the alert status is determined based on the HTTP response code. Therefore, you cannot change what HTTP response codes determine the thresholds for WEB alerts. Although you can customize what the response text for each threshold. The response code and corresponding status for WEB alerts:

- OK status if Web URL responds with code under 400.
- WARNING status if Web URL responds with code 400 and above.
- CRITICAL status if Ambari cannot connect to Web URL.



Note

The connection timeout defaults to 5.0 seconds on the `connection_timeout` property on the alert definition when accessed from the Alerts API.

```
GET /api/v1/clusters/MyCluster/alert_definitions/42

"source" : {
    "reporting" : {
        ...
    },
    "type" : "WEB",
    "uri" : {
        ...
        "connection_timeout" : 5.0
    }
}
```

PORT Alert Type

PORT alerts check the response time to connect to a given port and the threshold units are based on seconds.

METRIC Alert Type

METRIC alerts check the value of a single or multiple metrics (if a calculation is performed). The metric is accessed from a URL endpoint available on a given component. The thresholds are adjustable and the units for each threshold are metric-dependent. For example, in the case of “CPU utilization” alerts, the unit is “%”. And in the case of “RPC latency” alerts, the unit is “milliseconds (ms)”.



Note

The connection timeout defaults to 5.0 seconds on the connection_timeout property on the alert definition when accessed from the Alerts API.

```
GET /api/v1/clusters/MyCluster/alert_definitions/32

"source" : {
    "reporting" : {
        ...
    },
    "type" : "METRIC",
    "uri" : {
        ...
        "connection_timeout" : 5.0
    }
}
```

AGGREGATE Alert Type

AGGREGATE alerts aggregate the alert status as a percentage of the alert instances affected. For example, the “Percent DataNode Process” alert aggregates the “DataNode Process” alert. The threshold units are “%”.

SCRIPT Alert Type

SCRIPT alerts execute a script and the script determines status such as OK, WARNING or CRITICAL. The thresholds and response text built-into the alert definitions but are not modifiable from the Ambari Web UI.



Note

The location of the script is available on the path property on the alert definition when accessed from the Alerts API.

```
GET /api/v1/clusters/MyCluster/alert_definitions/19

    "source" : {
        "parameters" : {
            ...
        },
        "path" : "HDFS/2.1.0.2.0/package/alerts/
alert_ha_namenode_health.py",
        "type" : "SCRIPT"
    }
```

8.2. Configuring Notifications

With Alert Groups and Notifications, you can create groups of alerts and setup notification targets for each group. This way, you can notify different parties interested in certain sets of alerts via different methods. For example, you might want your Hadoop Operations team to receive all alerts via EMAIL, regardless of status. And at the same time, have your System Administration team receive all RPC and CPU related alerts that are Critical only via SNMP. To achieve this scenario, you would have an Alert Notification that handles Email for all alert groups for all severity levels, and you would have a different Alert Notification group that handles SNMP on critical severity for an Alert Group that contains the RPC and CPU alerts.

Ambari defines a set of default Alert Groups for each service installed in the cluster. For example, you will see a group for HDFS Default. These groups cannot be deleted and the alerts in these groups are not modifiable. If you choose not to use these groups, just do not set a notification target for them.

Creating or Editing Notifications

1. Browse to the Alerts section in Ambari Web.
2. Under the **Actions** menu, click **Manage Notifications**.
3. The list of existing notifications is shown.
4. Click + to “Create new Alert Notification”. The Create Alert Notification dialog is displayed.
5. Enter the notification name, select the groups to which the notification should be assigned (all or a specific set), select the Severity levels that this notification responds to, include a description, and choose the method for notification (EMAIL or SNMP).
 - For **EMAIL**: provide information about your SMTP infrastructure such as SMTP Server, Port, To/From address and if authentication is required to relay messages through the server. You can add custom properties to the SMTP configuration based on the [Javamail SMTP options](#).

Parameter	Description
Email To	A comma-separated list of one or more email addresses to send the alert email.

Parameter	Description
SMTP Server	The FQDN or IP address of the SMTP server to use to relay the alert email.
SMTP Port	The SMTP port on the SMTP Server.
Email From	A single email address to be the "from" alert email.
Use Authentication	Check if your SMTP Server requires authentication in order to relay messages. Be sure to also provide the username and password credentials.

- For **SNMP**: select the SNMP version, Community, Host, and Port where the SNMP trap should be sent. Also, the OID parameter must be configured properly for SNMP trap context. If no custom, or enterprise-specific OID will be used, we recommend the following:

Parameter	Description
OID	1.3.6.1.4.1.18060.16.1.1
Hosts	A comma-separated list of one or more Host FQDNs of where to send the trap.
Port	The port where snmptrapd is listening on the Hosts.



Note

Only SNMPv1 and SNMPv2c should be chosen for SNMP Version. SNMPv3 is not supported nor functional at this time.

6. After completing the notification, click **Save**.

Creating or Editing Alert Groups

1. Browse to the Alerts section in Ambari Web.
2. From the Actions menu, choose Manage Alert Groups
3. The list of existing groups (default and custom) is shown.
4. Choose + to "Create Alert Group". Enter the Group a name and click Save.
5. By clicking on the custom group in the list, you can add or delete alert definitions from this group, and change the notification targets for the group.

Dispatching Notifications

When an alert is enabled and the alert status changes (for example, from OK to CRITICAL or CRITICAL to OK), Ambari will send a notification (depending on how the user has configured notifications).

For **EMAIL** notifications: Ambari will send an email digest that includes all alert status changes. For example: if two alerts go CRITICAL, Ambari sends one email that says "Alert A is CRITICAL and Ambari B alert is CRITICAL". Ambari will not send another email notification until status has changed again.

For **SNMP** notifications: Ambari will fire an SNMP trap per alert status change. For example: if two alerts go CRITICAL, Ambari will fire two SNMP traps, one for each alert going OK -> CRITICAL. When the alert changes status from CRITICAL -> OK, another trap is sent.

Viewing Alert Status Log

In addition to dispatching alert notifications, Ambari writes alert status changes to a log on the Ambari Server host. Alert status changes will be written to the log regardless if EMAIL or SNMP notifications are configured.

1. On the Ambari Server host, browse to the log directory:

```
cd /var/log/ambari-server/
```

2. View the ambari-alerts.log file.

3. Log entries will include the time of the status change, the alert status, the alert definition name and the response text. For example:

```
2015-08-10 22:47:37,120 [OK] [STORM] [storm_server_process] (Storm Server Process) TCP OK - 0.000s response on port 8744  
2015-08-11 11:06:18,479 [CRITICAL] [AMBIARI] [ambari_server_agent_heartbeat] (Ambari Agent Heartbeat) c6401.ambari.apache.org is not sending heartbeats  
2015-08-11 11:08:18,481 [OK] [AMBIARI] [ambari_server_agent_heartbeat] (Ambari Agent Heartbeat) c6401.ambari.apache.org is healthy
```

8.2.1. Customizing Notification Templates

The notification template content produced by Ambari is tightly coupled to a notification type. Email and SNMP both have customizable templates that can be used to generate content. This section describes the steps necessary to change the template used by Ambari when creating alert notifications.

Alert Templates XML Location

By default, an alert-templates.xml ships with Ambari bundled inside of Ambari Server JAR. This file contains all of the templates for every known type of notification (for example EMAIL and SNMP). This file is bundled in the Ambari Server JAR so the template is not exposed on the disk. But we can use that file as a reference example.

When you customize the alert template, you are effectively overriding the template bundled by default. To override the alert templates XML:

1. On the Ambari Server host, browse to /etc/ambari-server/conf directory.
2. Edit the ambari.properties file.
3. Add an entry for the location of your new template. Any notification types defined in the new template will override those bundled with Ambari. If you choose to provide your own template file, you only need to define notification templates for the types that you wish to override. If a notification template type is not found in the customized template, Ambari will default to the templates that ship with the JAR.

```
alerts.template.file=/foo/var/alert-templates-custom.xml
```

4. Save the file and restart Ambari Server.



Important

Some alert notification types, such as EMAIL, automatically combine all pending alerts into a single outbound notification ("digest"). Others, like

SNMP, never combine pending alerts and will always create a 1:1 notification for every alert in the system ("individual"). All alert notification types are specified in the same alert templates file, but the specific alert template for each notification type will most likely vary greatly.

Alert Templates XML Structure

The structure of the template file is defined as follows. Each `<alert-template>` element declares what type of alert notification it should be used for.

```
<alert-templates>
  <alert-template type="EMAIL">
    <subject>
      Subject Content
    </subject>
    <body>
      Body Content
    </body>
  </alert-template>
  <alert-template type="SNMP">
    <subject>
      Subject Content
    </subject>
    <body>
      Body Content
    </body>
  </alert-template>
</alert-templates>
```

Template Variables

The template uses Apache Velocity to render all tokenized content. The following variables are available for use in your template:

Variable	Description
<code>\$alert.getAlertDefinition()</code>	The definition that the alert is an instance of.
<code>\$alert.getAlertText()</code>	The specific alert text.
<code>\$alert.getAlertName()</code>	The name of the alert.
<code>\$alert.getAlertState()</code>	The alert state (OK WARNING CRITICAL UNKNOWN)
<code>\$alert.getServiceName()</code>	The name of the service that the alert is defined for.
<code>\$alert.hasComponentName()</code>	True if the alert is for a specific service component.
<code>\$alert.getComponentName()</code>	The component, if any, that the alert is defined for.
<code>\$alert.hasHostName()</code>	True if the alert was triggered for a specific host.
<code>\$alert.getHostName()</code>	The hostname, if any, that the alert was triggered for.
<code>\$ambari.getServerUrl()</code>	The Ambari Server URL.
<code>\$ambari.getServerVersion()</code>	The Ambari Server version.
<code>\$ambari.getServerHostName()</code>	The Ambari Server hostname.
<code>\$dispatch.getTargetName()</code>	The notification target name.
<code>\$dispatch.getTargetDescription()</code>	The notification target description.
<code>\$summary.getAlerts(service,alertState)</code>	A list of all alerts for a given service or alert state (OK WARNING CRITICAL UNKNOWN).
<code>\$summary.getServicesByAlertState(alertState)</code>	A list of all services for a given alert state (OK WARNING CRITICAL UNKNOWN).
<code>\$summary.getServices()</code>	A list of all services that are reporting an alert in the notification.

Variable	Description
\$summary.getCriticalCount()	The CRITICAL alert count.
\$summary.getOkCount()	The OK alert count.
\$summary.getTotalCount()	The total alert count.
\$summary.getUnknownCount()	The UNKNOWN alert count.
\$summary.getWarningCount()	The WARNING alert count.
\$summary.getAlerts()	A list of all of the alerts in the notification.

Example: Modify Alert EMAIL Subject

The following example illustrates how to change the subject line of all outbound email notifications to include a hard coded identifier:

1. Download the alert-templates.xml code as your starting point.
2. On the Ambari Server, save the template to a location such as /var/lib/ambari-server/resources/alert-templates-custom.xml .
3. Edit the alert-templates-custom.xml file and modify the subject link for the <alert-template type="EMAIL" > template:

```
<subject>
  <![CDATA[Petstore Ambari has $summary.getTotalCount() alerts!]]>
</subject>
```

4. Save the file.
5. Browse to /etc/ambari-server/conf directory.
6. Edit the ambari.properties file.
7. Add an entry for the location of your new template file.

```
alerts.template.file=/var/lib/ambari-server/resources/alert-templates-custom.xml
```

8. Save the file and restart Ambari Server.

8.3. List of Predefined Alerts

- [HDFS Service Alerts](#)
- [NameNode HA Alerts](#)
- [YARN Alerts](#)
- [MapReduce2 Alerts](#)
- [HBase Service Alerts](#)
- [Hive Alerts](#)
- [Oozie Alerts](#)
- [ZooKeeper Alerts](#)

- [Ambari Alerts](#)
- [Ambari Metrics Alerts](#)

8.3.1. HDFS Service Alerts

Alert	Description	Potential Causes	Possible Remedies
NameNode Blocks Health	This service-level alert is triggered if the number of corrupt or missing blocks exceeds the configured critical threshold.	Some DataNodes are down and the replicas that are missing blocks are only on those DataNodes. The corrupt/missing blocks are from files with a replication factor of 1. New replicas cannot be created because the only replica of the block is missing.	For critical data, use a replication of 3. Bring up the failed DataNodes with missing or corrupt blocks. Identify the files associated with missing or corrupt blocks by running Hadoop fsck command. Delete the corrupt files and recover from backup, if it exists.
NFS Gateway Process	This host-level alert is triggered if the NFS Gateway process cannot be confirmed to be up and listening on the network.	NFS Gateway is down.	Check for dead NFS Gateway in Ambari Web.
DataNode Storage	This host-level alert is triggered if storage capacity is full on the DataNode (90% critical). It checks the DataNode JMX Servlet for the Capacity and Remaining properties.	Cluster storage is full. If cluster storage is not full, DataNode is full.	If cluster still has storage, use Balancer to distribute the data to relatively less loaded datanodes. If the cluster is full, delete unnecessary data or add additional storage by either more DataNodes or more physical disks to the DataNodes. After adding more storage run Balancer.
DataNode Process	This host-level alert is triggered if the individual DataNode processes cannot be established to be up and listening on the network for the configured critical threshold, given in seconds.	DataNode process is down or not responding. DataNode are not down but is not listening to the correct network port/address.	Check for dead DataNodes in Ambari Web. Check for any errors in the DataNode logs (/var/log/hadoop/hdfs) and restart the DataNode, if necessary. Run the netstat-tuplpn command to check if the DataNode process is listening to the correct network port.
DataNode Web UI	This host-level alert is triggered if the DataNode Web UI is unreachable.	The DataNode process is not running.	Check whether the DataNode process is running.
NameNode Host CPU Utilization	This host-level alert is triggered if CPU utilization of the NameNode exceeds certain thresholds (200% warning, 250% critical). It checks the NameNode JMX Servlet for the SystemCPULoad property. This information is only available if you are running JDK 1.7.	Unusually high CPU utilization: Can be caused by a very unusual job/query workload, but this is generally the sign of an issue in the daemon.	Use the top command to determine which processes are consuming extra CPU. Reset the offending process.
NameNode Web UI	This host-level alert is triggered if the NameNode Web UI is unreachable.	The NameNode process is not running.	Check whether the NameNode process is running.
Percent DataNodes with Available Space	This service-level alert is triggered if the storage is full on a certain percentage of DataNodes (10% warn, 30% critical).	Cluster storage is full. If cluster storage is not full, DataNode is full.	If cluster still has storage, use Balancer to distribute the data to relatively less loaded DataNodes. If the cluster is full, delete unnecessary data or add additional storage by either more DataNodes or more physical disks to the DataNodes. After adding more storage run Balancer.
Percent DataNodes Available	This alert is triggered if the number of down DataNodes in the cluster is greater than the configured threshold.	DataNodes are down	Check for dead DataNodes in Ambari Web.

Alert	Description	Potential Causes	Possible Remedies
	than the configured critical threshold. This aggregates the DataNode process alert.	DataNodes are not down but are not listening to the correct network port/address.	Check for any errors in the DataNode logs (/var/log/hadoop/hdfs) and the DataNode hosts/processes. Run the netstat-tuplpn command to check if the DataNode process is listening to the correct network port.
NameNode RPC Latency	This host-level alert is triggered if the NameNode operations RPC latency exceeds the configured critical threshold. Typically an increase in the RPC processing time increases the RPC queue length, causing the average queue wait time to increase for NameNode operations.	A job or an application is performing too many NameNode operations.	Review the job or the application for potential bugs causing it to perform many NameNode operations.
NameNode Last Checkpoint	This alert will trigger if the last time that the NameNode performed a checkpoint was too long ago or if the number of uncommitted transactions is beyond a certain threshold.	Too much time elapsed since last NameNode checkpoint. Uncommitted transactions beyond threshold.	Set NameNode checkpoint. Review threshold for uncommitted transactions.
Secondary NameNode Process	If the Secondary NameNode process cannot be confirmed to be up and listening on the network. This alert is not applicable when NameNode HA is configured.	The Secondary NameNode is not running.	Check that the Secondary DataNode process is running.
NameNode Directory Status	This alert checks if the NameNode NameDirStatus metric reports a failed directory.	One or more of the directories are reporting as not healthy.	Check the NameNode UI for info about unhealthy directories.
HDFS Capacity Utilization	This service-level alert is triggered if the HDFS capacity utilization exceeds the configured critical threshold (80% warn, 90% critical). It checks the NameNode JMX Servlet for the CapacityUsed and CapacityRemaining properties.	Cluster storage is full.	Delete unnecessary data. Archive unused data. Add more DataNodes. Add more or larger disks to the DataNodes. After adding more storage, run E
DataNode Health Summary	This service-level alert is triggered if there are unhealthy DataNodes.	A DataNode is in an unhealthy state.	Check the NameNode UI for the dead DataNodes.
HDFS Pending Deletion Blocks	This service-level alert is triggered if the number of blocks pending deletion in HDFS exceeds the configured warning and critical thresholds. It checks the NameNode JMX Servlet for the PendingDeletionBlock property.	Large number of blocks are pending deletion.	
HDFS Upgrade Finalized State	This service-level alert is triggered if HDFS is not in the finalized state.	The HDFS upgrade is not finalized.	Finalize any upgrade you have in progress.
DataNode Unmounted Data Dir	This host-level alert is triggered if one of the data directories on a host was previously on a mount point and became unmounted.	If the mount history file does not exist, then report an error if a host has one or more mounted data directories as well as one or more unmounted data directories on the root partition. This may indicate that a data directory is writing to the root partition, which is undesirable.	Check the data directories to confirm they are mounted as expected.

8.3.1.1. NameNode HA Alerts

Alert	Description	Potential Causes	Possible Remedies
JournalNode Process	This host-level alert is triggered if the individual JournalNode process cannot respond.	The JournalNode process is down or not responding.	Check if the JournalNode process is running.

Alert	Description	Potential Causes	Possible Remedies
	be established to be up and listening on the network for the configured critical threshold, given in seconds.	The JournalNode is not down but is not listening to the correct network port/ address.	
NameNode High Availability Health	This service-level alert is triggered if either the Active NameNode or Standby NameNode are not running.	The Active, Standby or both NameNode processes are down.	On each host running NameNode check for any errors in the logs (/var/log/hadoop/hdfs/) and restart the NameNode host/process using Ambari Web. On each host running NameNode run the netstat-tuplpn command to check if the NameNode process is bound to the correct network port.
Percent JournalNodes Available	This service-level alert is triggered if the number of down JournalNodes in the cluster is greater than the configured critical threshold (33% warn, 50% crit.). It aggregates the results of JournalNode process checks.	JournalNodes are down. JournalNodes are not down but are not listening to the correct network port/ address.	Check for dead JournalNodes in Ambari Web.
ZooKeeper Failover Controller Process	This alert is triggered if the ZooKeeper Failover Controller process cannot be confirmed to be up and listening on the network.	The ZKFC process is down or not responding.	Check if the ZKFC process is running.

8.3.2. YARN Alerts

Alert	Description	Potential Causes	Possible Remedies
App Timeline Web UI	This host-level alert is triggered if the App Timeline Server Web UI is unreachable.	The App Timeline Server is down. App Timeline Service is not down but is not listening to the correct network port/ address.	Check for dead App Timeline Server using Ambari Web.
Percent NodeManagers Available	This alert is triggered if the number of down NodeManagers in the cluster is greater than the configured critical threshold. It aggregates the results of DataNode process alert checks.	NodeManagers are down. NodeManagers are not down but are not listening to the correct network port/ address.	Check for dead NodeManagers. Check for any errors in the NodeManager logs (/var/log/hadoop/yarn) and restart the NodeManager hosts/processes if necessary. Run the netstat-tuplpn command to check if the NodeManager process is bound to the correct network port.
ResourceManager Web UI	This host-level alert is triggered if the ResourceManager Web UI is unreachable.	The ResourceManager process is not running.	Check if the ResourceManager process is running.
ResourceManager RPC Latency	This host-level alert is triggered if the ResourceManager operations RPC latency exceeds the configured critical threshold. Typically an increase in the RPC processing time increases the RPC queue length, causing the average queue wait time to increase for ResourceManager operations.	A job or an application is performing too many ResourceManager operations.	Review the job or the application for potential bugs causing it to perform many ResourceManager operations.
ResourceManager CPU Utilization	This host-level alert is triggered if CPU utilization of the ResourceManager exceeds certain thresholds (200% warning, 250% critical). It checks the ResourceManager JMX Servlet for the SystemCPUload property. This information is only available if you are running JDK 1.7.	Unusually high CPU utilization: Can be caused by a very unusual job/query workload, but this is generally the sign of an issue in the daemon.	Use the top command to determine which processes are consuming excess CPU. Reset the offending process.

Alert	Description	Potential Causes	Possible Remedies
NodeManager Web UI	This host-level alert is triggered if the NodeManager process cannot be established to be up and listening on the network for the configured critical threshold, given in seconds.	NodeManager process is down or not responding. NodeManager is not down but is not listening to the correct network port/ address.	Check if the NodeManager is running. Check for any errors in the NodeManager logs (/var/log/hadoop/yarn) and restart the NodeManager, if necessary.
NodeManager Health Summary	This host-level alert checks the node health property available from the NodeManager component.	NodeManager Health Check script reports issues or is not configured.	Check in the NodeManager logs (/var/log/hadoop/yarn) for health check errors and restart the NodeManager, if necessary. Check in the ResourceManager UI (var/log/hadoop/yarn) for health errors.
NodeManager Health	This host-level alert checks the "nodeHealthy" property available from the NodeManager component.	The NodeManager process is down or not responding.	Check in the NodeManager logs (/var/log/hadoop/yarn) for health check errors and restart the NodeManager, if necessary.

8.3.3. MapReduce2 Alerts

Alert	Description	Potential Causes	Possible Remedies
HistoryServer Web UI	This host-level alert is triggered if the HistoryServer Web UI is unreachable.	The HistoryServer process is not running.	Check if the HistoryServer process is running.
HistoryServer RPC latency	This host-level alert is triggered if the HistoryServer operations RPC latency exceeds the configured critical threshold. Typically an increase in the RPC processing time increases the RPC queue length, causing the average queue wait time to increase for NameNode operations.	A job or an application is performing too many HistoryServer operations.	Review the job or the application for potential bugs causing it to perform many HistoryServer operations.
HistoryServer CPU utilization	This host-level alert is triggered if the percent of CPU utilization on the HistoryServer exceeds the configured critical threshold.	Unusually high CPU utilization: Can be caused by a very unusual job/query workload, but this is generally the sign of an issue in the daemon.	Use the top command to determine which processes are consuming excess CPU. Reset the offending process.
HistoryServer process	This host-level alert is triggered if the HistoryServer process cannot be established to be up and listening on the network for the configured critical threshold, given in seconds.	HistoryServer process is down or not responding. HistoryServer is not down but is not listening to the correct network port/ address.	Check the HistoryServer is running. Check for any errors in the HistoryServer logs (/var/log/hadoop/mapred) and restart the HistoryServer, if necessary.

8.3.4. HBase Service Alerts

Alert	Description	Potential Causes	Possible Remedies
Percent RegionServers Available	This service-level alert is triggered if the configured percentage of Region Server processes cannot be determined to be up and listening on the network for the configured critical threshold. The default setting is 10% to produce a WARN alert and 30% to produce a CRITICAL alert. It aggregates the results of RegionServer process down checks.	Misconfiguration or less-than-ideal configuration caused the RegionServers to crash. Cascading failures brought on by some workload caused the RegionServers to crash. The RegionServers shut themselves down because there were problems in the dependent services, ZooKeeper or HDFS.	Check the dependent services to ensure they are operating correctly. Look at the RegionServer log files (usually /var/log/hbase/*.log) for information. If the failure was associated with a particular workload, try to understand the workload better. Restart the RegionServers.

Alert	Description	Potential Causes	Possible Remedies
		GC paused the RegionServer for too long and the RegionServers lost contact with Zookeeper.	
HBase Master Process	This alert is triggered if the HBase master processes cannot be confirmed to be up and listening on the network for the configured critical threshold, given in seconds.	The HBase master process is down. The HBase master has shut itself down because there were problems in the dependent services, ZooKeeper or HDFS.	Check the dependent services. Look at the master log files (usually log/hbase/*.log) for further information. Look at the configuration files (/etc/hbase/conf). Restart the master.
HBase Master CPU Utilization	This host-level alert is triggered if CPU utilization of the HBase Master exceeds certain thresholds (200% warning, 250% critical). It checks the HBase Master JMX Servlet for the SystemCPULoad property. This information is only available if you are running JDK 1.7.	Unusually high CPU utilization: Can be caused by a very unusual job/query workload, but this is generally the sign of an issue in the daemon.	Use the top command to determine which processes are consuming excessive CPU Reset the offending process.
RegionServers Health Summary	This service-level alert is triggered if there are unhealthy RegionServers.	The RegionServer process is down on the host. The RegionServer process is up and running but not listening on the correct network port (default 60030).	Check for dead RegionServer in Ambari Web.
HBase RegionServer Process	This host-level alert is triggered if the RegionServer processes cannot be confirmed to be up and listening on the network for the configured critical threshold, given in seconds.	The RegionServer process is down on the host. The RegionServer process is up and running but not listening on the correct network port (default 60030).	Check for any errors in the logs (usually log/hbase/) and restart the RegionServer process using Ambari Web. Run the netstat-tulpn command to check if the RegionServer process is bound to the correct network port.

8.3.5. Hive Alerts

Alert	Description	Potential Causes	Possible Remedies
HiveServer2 Process	This host-level alert is triggered if the HiveServer cannot be determined to be up and responding to client requests.	HiveServer2 process is not running. HiveServer2 process is not responding.	Using Ambari Web, check status of the HiveServer2 component. Stop and restart it.
HiveMetastore Process	This host-level alert is triggered if the Hive Metastore process cannot be determined to be up and listening on the network for the configured critical threshold, given in seconds.	The Hive Metastore service is down. The database used by the Hive Metastore is down. The Hive Metastore host is not reachable over the network.	Using Ambari Web, stop the HiveMetastore process and then restart it.
WebHCat Server status	This host-level alert is triggered if the WebHCat server cannot be determined to be up and responding to client requests.	The WebHCat server is down. The WebHCat server is hung and not responding. The WebHCat server is not reachable over the network.	Restart the WebHCat server using Ambari Web.

8.3.6. Oozie Alerts

Alert	Description	Potential Causes	Possible Remedies
Oozie Server Web UI	This host-level alert is triggered if the Oozie server Web UI is unreachable.	The Oozie server is down.	Check for dead Oozie Server in Ambari Web.

Alert	Description	Potential Causes	Possible Remedies
		Oozie Server is not down but is not listening to the correct network port/address.	
Oozie status	This host-level alert is triggered if the Oozie server cannot be determined to be up and responding to client requests.	The Oozie server is down. The Oozie server is hung and not responding. The Oozie server is not reachable over the network.	Restart the Oozie service using Ambari Web.

8.3.7. ZooKeeper Alerts

Alert	Description	Potential Causes	Possible Remedies
Percent ZooKeeper Servers Available	This service-level alert is triggered if the configured percentage of ZooKeeper processes cannot be determined to be up and listening on the network for the configured critical threshold, given in seconds. It aggregates the results of Zookeeper process checks.	The majority of your ZooKeeper servers are down and not responding.	Check the dependent services to make sure they are operating correctly. Check the ZooKeeper logs (/var/log/hadoop/zookeeper.log) for further information. If the failure was associated with a particular workload, try to understand the workload better. Restart the ZooKeeper servers from the Ambari UI.
ZooKeeper Server process	This host-level alert is triggered if the ZooKeeper server process cannot be determined to be up and listening on the network for the configured critical threshold, given in seconds.	The ZooKeeper server process is down on the host. The ZooKeeper server process is up and running but not listening on the correct network port (default 2181).	Check for any errors in the ZooKeeper logs (/var/log/hbase/) and restart the ZooKeeper process using Ambari. Run the netstat-tuplpn command to check if the ZooKeeper server process is bound to the correct network port.

8.3.8. Ambari Alerts

Alert	Description	Potential Causes	Possible Remedies
Host Disk Usage	This host-level alert is triggered if the amount of disk space used on a host goes above specific thresholds (50% warn, 80% crit).	The amount of free disk space left is low.	Check host for disk space to free up more storage.
Ambari Agent Heartbeat	This alert is triggered if the server has lost contact with an agent.	Ambari Server host is unreachable from Agent host Ambari Agent is not running	Check connection from Agent host to Ambari Server Check Agent is running
Ambari Server Alerts	This alert is triggered if the server detects that there are alerts which have not run in a timely manner	Agents are not reporting alert status Agents are not running	Check that all Agents are running and heartbeating

8.3.9. Ambari Metrics Alerts

Alert	Description	Potential Causes	Possible Remedies
Metrics Collector Process	This alert is triggered if the Metrics Collector cannot be confirmed to be up and listening on the configured port for a number of seconds equal to threshold.	The Metrics Collector process is not running.	Check the Metrics Collector is running.

Alert	Description	Potential Causes	Possible Remedies
Metrics Collector – ZooKeeper Server Process	This host-level alert is triggered if the Metrics Collector ZooKeeper Server Process cannot be determined to be up and listening on the network.	The Metrics Collector process is not running.	Check the Metrics Collector is running.
Metrics Collector – HBase Master Process	This alert is triggered if the Metrics Collector HBase Master Processes cannot be confirmed to be up and listening on the network for the configured critical threshold, given in seconds.	The Metrics Collector process is not running.	Check the Metrics Collector is running.
Metrics Collector – HBase Master CPU Utilization	This host-level alert is triggered if CPU utilization of the Metrics Collector exceeds certain thresholds.	Unusually high CPU utilization generally is the sign of an issue in the daemon configuration.	Review Tuning Ambari Metrics for information on tuning the Ambari Metrics Collector.
Metrics Monitor Status	This host-level alert is triggered if the Metrics Monitor process cannot be confirmed to be up and running on the network.	The Metrics Monitor is down.	Check whether the Metrics Monitor is running on the given host.
Percent Metrics Monitors Available	This is an AGGREGATE alert of the Metrics Monitor Status.	Metrics Monitors are down.	Check the Metrics Monitors are running.
Metrics Collector - Auto-Start Status	This alert is triggered if the Metrics Collector has been auto-started for number of times equal to start threshold in a 1 hour timeframe. By default if restarted 2 times in an hour, you will receive a Warning alert. If restarted 4 or more times in an hour, you will receive a Critical alert.	The Metrics Collector is running but is unstable and causing restarts. This could be due to improper tuning.	Review Tuning Ambari Metrics for information on tuning the Ambari Metrics Collector.
Metrics Monitor Status	This host-level alert is triggered if the Metrics Monitor process cannot be confirmed to be up and running on the network.	The Metrics Monitor is down.	Check whether the Metrics Monitor is running on a given host.
Percent Metrics Monitors Available	This is an AGGREGATE alert of the Metrics Monitor Status.	Metrics Monitors are down.	Check the Metrics Monitors are running.