## Virtual Memory II



### Learning Outcomes

- An understanding of TLB refill:
  - in general, assignment 3 TLB refill handler
  - and as implemented on the R3000
- An understanding of <u>demand-paged virtual</u> memory in depth, including: keep a subset of the application in memory.
  - Locality and working sets
  - Page replacement algorithms
  - Thrashing



### TLB Recap

- Fast associative cache of page table entries
  - Contains a subset of the page table
  - What happens if required entry for translation is not present (a TLB miss)?



### TLB Recap

- TLB may or may not be under OS control
  - Hardware-loaded TLB
    - On miss, hardware performs PT lookup and
       reloads TLB
       the page table is a pre-defined format that hardware understands, and the hardware walks through to find the page table entry on a tlb miss
    - Example: Pentium
  - Software-loaded TLB
    - On miss, hardware generates a TLB miss exception, and exception handler reloads TLB
    - Example: MIPS

micro process raise an exception and gives the control of the OS, then the OS figures out what the appropriate page is, then the OS puts the page table entry into the TLB table



## Aside: even if filled by software

TLB still a hardware-based translator



# R3000 TLB Handling

kseg2

TLB refill is handled by software

0xA0000000

0xC000000

0xFFFFFFF

kseg1

An exception handler

0x80000000

kseg0

 TLB refill exceptions accessing kuseg are expected to be frequent

we need to ensure the handler performance is good

 CPU optimised for handling kuseg TLB refills by having a special exception handler just for TLB refills

kuseg



0x0000000

## **Exception Vectors**

Program address	"segment"	Physical Address	Description
		011 11 Have Const. No. 40 Have Decision	this exception is only for TLB miss
0000 0008x0	kseg0	0x0000 0000	TLB miss on <i>kuseg</i> reference only.
0x8000 008x0	kse	0x0000 0080	All other exceptions.
0xbfc0 0100	kseg1	0x1fc0 0100	Uncached alternative <i>kuseg</i> TLB miss entry point (used if <i>SR</i> bit BEV set).
0xbfc0 0180	kseg1		alternative for all other s, used if <i>SR</i> bit BEV set).
0xbfc0 0000 Table 4.1.	kseg1 Reset and ex	Special exe vector for TLB re	ception exception".



# Special Exception Vector

- Can be optimised for TLB refill only
  - Does not need to check the exception type
  - Does not need to save any registers
    - It uses a specialised assembly routine that only uses k0 and k1.
  - Does not check if PTE exists
    - Assumes virtual linear array see extended OS notes (if interested)
- With careful data structure choice, exception handler can be made very fast

An example routine

refill routine



### MIPS VM Related Exceptions

- TLB refill
  - Handled via special exception vector
  - Needs to be very fast
- Others handled by the general exception vector
  - TLB Mod
    - TLB modify exception, attempt to write to a read-only page
  - TLB Load
    - Attempt it load from a page with an invalid translation
  - TLB Store
    - Attempt to store to a page with an invalid translation
  - Note: these can be slower as they are mostly either caused by an error, or non-resident page.
    - We never optimise for errors, and page-loads from disk dominate the fault resolution cost.



### <Intermezzo>




### Amdahl's law

don't optimise for errors

 States that overall performance improvement is limited by the fraction of time an enhancement can be used

Law of diminishing returns



fraction in enhanced mode = 0.5 (based on old system)

Speedup of enhanced mode = 2

### Amdahl's law

• State the common case fast!

Make the common by the fraction of the common case fast!

 $Speedup = \frac{ExecutionTimeWithoutEnhancement}{ExecutionTimeWithEnhancement}$ 



### 



### c0 Registers

address of the instruction that causes the fault

- c0\_EPC
  - The address of where to restart after the exception
- c0 status which mode we come from
  - Kernel/User Mode bits, Interrupt control
- c0\_cause
  - What caused the exception
- c0 badvaddr bad virtual address, the address that triggers the fault
  - The address of the fault



## The TLB and EntryHi,EntryLo

search in parallel by the hardware

by using the c0 registers to include a particular entry of the tlb

### c0 Registers

c0\_EntryHi c0\_EntryLo c0\_Index

Used to read and write individual TLB entries

misp has 64 tlb

## Each TLB entry contains

- EntryHi to match page# and ASID
- EntryLo which contains frame# and protection

**TLB** 

EntryHi	EntryLo
EntryHi	EntryLo



### c0 Registers

31 6 5 12 11 0 entry high ASID **VPN** 0 EntryHi Register (TLB key fields) assignment 31 12 11 10 8 0 entry low PEN 0 N D G

EntryLo Register (TLB data fields)

- N = Not cacheable
- D = Dirty = Write protect
- G = Global (ignore ASID in lookup) shared library

- V = valid bit
- 64 TLB entries
- Accessed via software through Coprocessor 0 registers
  - EntryHi and EntryLo



### c0 Index Register

- Used as an index to TLB entries
  - Single TLB entries are manipulated/viewed through EntryHi and EntryLo0 registers
  - Index register specifies which TLB entry to change/view

index of the entry we want to access



Special TLB management

these instructions are wrapped

Instructions

- TLBR
  - TLB read
    - EntryHi and EntryLo are loaded from the entry pointer to by the index register.
- TLBP
  - TLB probe
  - Set EntryHi to the entry you wish to match, index register is loaded with the index to the matching entry
  - **TLBWR**

replace a random entry of a TLB table

Write EntryHi and EntryLo to a psuedo-random location in the

TLB

most expensive,
TLBWR >> TLBN

if we happen to overwritte another one we need, we just come back with a tlb miss? wouldn't this result in a deadlock??

 Write EntryHi and EntryLo to the location in the TLB pointed to by the Index register.



# Coprocessor 0 registers on a refill exception

```
c0.EPC \leftarrow PC c0.cause.ExcCode \leftarrow TLBL; if read fault c0.cause.ExcCode \leftarrow TLBS; if write fault c0.BadVaddr \leftarrow faulting address c0.EntryHi.VPN \leftarrow page number of faulting address c0.status \leftarrow kernel mode, interrupts disabled. c0.PC \leftarrow 0x8000 0000
```



### Outline of TLB miss handling

- Software does:
  - Look up PTE corresponding to the faulting address
  - If found:
    if we find it, we load entry low with the page table entry
    - load c0\_EntryLo with translation
    - load TLB using TLBWR instruction
    - return from exception
  - Else, page fault

use this as our page table entry

- The TLB entry (i.e. c0\_EntryLo) can be:
  - (theoretically) created on the fly, or
  - stored completely in the right format in page table
    - more efficient

in practice

what we need to do is load the 32-bit from page table directly into entry low, then tlb random



### OS/161 Refill Handler

- After switch to kernel stack, it simply calls the common exception handler
  - Stacks all registers
  - Can (and does) call 'C' code
  - Unoptimised

it's not optimized at all

- Goal is ease of kernel programming, not efficiency
- Does not have a page table
  - It uses the 64 TLB entries and then panics when it runs out.
    - Only support 256K user-level address space

dumb vm needs a refill handler

look at dumb vm



## **Demand Paging**



## Demand Paging need to load data from the disk into memory: In loading it's from this disk in the original location; in runtime it may be from

this not only appears at the loading stage, but also mid-runtime. In both cases you need to load data from the disk into memory: In loading it's from this disk in the original location; in runtime it may be from where the virtual pages are being stored on disk

- With VM, only parts of the program image need to be resident in memory for execution.
- Can transfer presently unused pages/segments to disk
- Reload non-resident pages/segment on demand.
  - Reload is triggered by a page or segment fault
  - Faulting process is blocked and another scheduled
  - When page/segment is resident, faulting process is restarted
  - May require freeing up memory first
    - Replace current resident page/segment
    - How determine replacement "victim"?
  - If victim is unmodified ("clean") can simply discard it
    - This is reason for maintaining a "dirty" bit in the PT



- Why does demand paging work?
  - Program executes at full speed only when accessing the resident set.
  - TLB misses introduce delays of several microseconds
  - Page/segment faults introduce delays of several milliseconds
  - Why do it?
- Answer
  - Less physical memory required per process
    - Can fit more processes in memory
    - Improved chance of finding a runnable one
  - Principle of locality



### Principle of Locality

- An important observation comes from empirical studies of the properties of programs.
  - Programs tend to reuse data and instructions they have used recently.
  - 90/10 rule
     "A program spends 90% of its time in 10% of its code"
- We can exploit this <u>locality of references</u>
- An implication of locality is that we can reasonably predict what <u>instructions</u> and <u>data</u> a program will use in the near future based on its accesses in the recent past.




Two different types of locality have been observed:

locality in time, if I access something in the past, I'm likely to access that resource in the near future

- Temporal locality: states that recently accessed items are likely to be accessed in the near future.
- Spatial locality: says that items whose addresses are near one another tend to be referenced close together in time. locality in space



### Locality In A Memory-Reference Pattern






### Working Set

- The pages/segments required by an application in a time window (Δ) is called its memory working set.
- Working set is an approximation of a programs' locality
  - if  $\Delta$  too small will not encompass entire locality.
  - if  $\Delta$  too large will encompass several localities.
  - if  $\Delta$  = ∞ ⇒ will encompass entire program.
  - $-\Delta$ 's size is an application specific tradeoff
- System should keep resident at least a process's working set
  - Process executes while it remains in its working set
- Working set tends to change gradually
  - Get only a few page/segment faults during a time window
  - Possible (but hard) to make intelligent guesses about which pieces will be needed in the future
    - May be able to pre-fetch page/segments



## Working Set Example






### Thrashing

- CPU utilisation tends to increase with the degree of multiprogramming
  - number of processes in system
- Higher degrees of multiprogramming less memory available per process
- Some process's working sets may no longer fit in RAM
  - Implies an increasing page fault rate
- Eventually many processes have insufficient memory
  - Can't always find a runnable process
  - Decreasing CPU utilisation
  - System become I/O limited
- This is called thrashing.



## Thrashing



- Why does thrashing occur?
- $\Sigma$  working set sizes > total physical memory size




### Recovery From Thrashing

- In the presence of increasing page fault frequency and decreasing CPU utilisation
  - Suspend a few processes to reduce degree of multiprogramming
  - Resident pages of suspended processes will migrate to backing store
  - More physical memory becomes available
    - Less faults, faster progress for runnable processes
  - Resume suspended processes later when memory pressure eases



### What is the difference?

```
/* reset array */
int array[10000][10000];
int i,j;
for (i = 0; i < 10000; i++) {
   for (j = 0; j < 10000; j ++) {
      array[i][j] = 0;
      /* array[j][i] = 0 */
   }
}</pre>
```



### VM Management Policies



### VM Management Policies

- Operation and performance of VM system is dependent on a number of policies:
  - Page table format (may be dictated by hardware)
    - Multi-level
    - Inverted/Hashed
  - Page size (may be dictated by hardware)
  - Fetch Policy
  - Replacement policy
  - Resident set size
    - Minimum allocation
    - Local versus global allocation
  - Page cleaning policy



### Page Size

### Increasing page size

- Increases internal fragmentation
  - reduces adaptability to working set size
- ✓ Decreases number of pages
  - Reduces size of page tables
- ✓ Increases TLB coverage
  - Reduces number of TLB misses
- Increases page fault latency
  - Need to read more from disk before restarting process
- ✓ Increases swapping I/O throughput
  - Small I/O are dominated by seek/rotation delays
- Optimal page size is a (work-load dependent) trade-off.



# Working Set Size Generally Increases with Increasing Page Size: True/False?



Atlas	512 words (48-bit)
Honeywell/Multics	1K words (36-bit)
IBM 370/XA	4K bytes
DEC VAX	512 bytes
IBM AS/400	512 bytes
Intel Pentium	4K and 4M bytes
ARM	4K and 64K bytes
MIPS R4000	4k – 16M bytes in powers of 4
DEC Alpha	8K - 4M bytes in powers of 8
UltraSPARC	8K – 4M bytes in powers of 8
PowerPC	4K bytes + "blocks"
Intel IA-64	4K – 256M bytes in powers of 4



## Page Size

- Multiple page sizes provide flexibility to optimise the use of the TLB
- Example:
  - Large page sizes can be use for code
  - Small page size for thread stacks
- Most operating systems have limited support for only a single page size
  - Dealing with multiple page sizes is hard!



## Fetch Policy

- Determines when a page should be brought into memory
  - Demand paging only loads pages in response to page faults
    - Many page faults when a process first starts
  - Pre-paging brings in more pages than needed at the moment
    - Pre-fetch when disk is idle
    - Wastes I/O bandwidth if pre-fetched pages aren't used
    - Especially bad if we eject pages in working set in order to pre-fetch unused pages.
    - Hard to get right in practice.



# Replacement **Policy**

Page fault on page 14, physical memory full, which page should we evict?

S

Disk

Virtual Memory

B THE UNIVERSITY OF **NEW SOUTH WALES** 

**Physical Address** Space

## Replacement Policy

- Which page is chosen to be tossed out?
  - Page removed should be the page least likely to be references in the near future
  - Most policies attempt to predict the future behaviour on the basis of past behaviour
- Constraint: locked frames
  - Kernel code
  - Main kernel data structure
  - I/O buffers
  - Performance-critical user-pages (e.g. for DBMS)
- Frame table has a lock (or pinned) bit



## Optimal Replacement policy

- Toss the page that won't be used for the longest time
- Impossible to implement
- Only good as a theoretic reference point:
  - The closer a practical algorithm gets to optimal, the better
- Example:
  - Reference string: 1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5
  - Four frames
  - How many page faults?



# FIFO Replacement Policy

- First-in, first-out: Toss the oldest page
  - Easy to implement
  - Age of a page is isn't necessarily related to usage
- Example:
  - Reference string: 1,2,3,4,1,2,5,1,2,3,4,5
  - Four frames



# Least Recently Used (LRU)


- Toss the least recently used page
  - Assumes that page that has not been referenced for a long time is unlikely to be referenced in the near future
  - Will work if locality holds
  - Implementation requires a time stamp to be kept for each page, updated on every reference
  - Impossible to implement efficiently
  - Most practical algorithms are approximations of LRU



# Clock Page Replacement


- Clock policy, also called second chance
  - Employs a usage or reference bit in the frame table.
  - Set to one when page is used
  - While scanning for a victim, reset all the reference bits
  - Toss the first page with a zero reference bit.






(a) State of buffer just prior to a page replacement

Figure 8.16 Example of Clock Policy Operation



(a) State of buffer just prior to a page replacement

Figure 8.16 Example of Clock Policy Operation



(b) State of buffer just after the next page replacement

Figure 8.16 Example of Clock Policy Operation

## Issue

- How do we know when a page is referenced?
- Use the valid bit in the PTE:
  - When a page is mapped (valid bit set), set the reference bit
  - When resetting the reference bit, invalidate the PTE entry
  - On page fault
    - Turn on valid bit in PTE
    - Turn on reference bit
- We thus simulate a reference bit in software



## Simulated Reference Bit

State: Page not referenced

Frame#

R=0

W

V=0

Uses "spare" bits in page table (ignored by hardware), or bit in frame table

Page fault on access, fault handler sets Ref. and Valid bit.

Frame#

R=1

W

V=1

Ref. and valid bit reset by Clock algorithm

State: Page referenced



## Hardware Reference Bit

State: Page not referenced

Page Accessed

Ref. bit reset by Clock algorithm

Frame# R=1 W V=1

State: Page referenced



#### Performance

- It terms of selecting the most appropriate replacement, they rank as follows
  - 1. Optimal
  - 2. LRU
  - 3. Clock
  - 4. FIFO
- Note there are other algorithms (Working Set, WSclock, Ageing, NFU, NRU)
  - We don't expect you to know them in this course



## Resident Set Size

- How many frames should each process have?
  - Fixed Allocation
    - Gives a process a fixed number of pages within which to execute.
    - Isolates process memory usage from each other
    - When a page fault occurs, one of the pages of that process must be replaced.
    - Achieving high utilisation is an issue.
      - Some processes have high fault rate while others don't use their allocation.
  - Variable Allocation
    - Number of pages allocated to a process varies over the lifetime of the process



## Variable Allocation, Global Scope

- Easiest to implement
- Adopted by many operating systems
- Operating system keeps global list of free frames
- Free frame is added to resident set of process when a page fault occurs
- If no free frame, replaces one from any process

#### Pro/Cons

- Automatic balancing across system
- Does not provide guarantees for important activities




## Variable Allocation, Local Scope

- Allocate number of page frames to a new process based on
  - Application type
  - Program request
  - Other criteria (priority)
- When a page fault occurs, select a page from among the resident set of the process that suffers the page fault
- Re-evaluate allocation from time to time!



# Page-Fault Frequency Scheme



- Establish "acceptable" page-fault rate.
  - If actual rate too low, process loses frame.
  - If actual rate too high, process gains frame.



# Cleaning Policy

#### Observation

Clean pages are much cheaper to replace than dirty pages

#### Demand cleaning

- A page is written out only when it has been selected for replacement
- High latency between the decision to replace and availability of free frame.

#### Precleaning

- Pages are written out in batches (in the background, the pagedaemon)
- Increases likelihood of replacing clean frames
- Overlap I/O with current activity

