CO211 - Operating Systems

4th October 2019

Outline of the Course

• overview and introduction structure, case studies

• processes and threads abstractions that an OS uses to execute code

• inter-process communication (IPC) allows multiple processes to communicate with each other

• memory management allocation, abstraction for virtual memory, paging

• device management types, drivers

• disk management scheduling, caching, RAID

• file systems basic abstractions for storage and implementation

• security authentication, access control

Note that this follows a similar structure to most OS courses, and therefore we can reference content from other sources. *Operating Systems: Three Easy Pieces* is recommended, as it bridges between this course and the PintOS lab.

Overview

The general overview is that there is a system bus that interconnects different hardware components (including CPU and memory), and allows for communication between them.

The operating system provides abstractions for programs to use, meaning that they do not have to deal with the complex hardware. For example, a process abstraction expects an interface to the hardware, which allows programs to be used on different hardware. This means that the OS will need how to to control the hardware with drivers. The operating system has the following goals;

(1) managing resources

The operating system must be able to expose the resources efficiently to the application, and also share these resources fairly. Some examples are;

• CPU (multiple cores) should decide what runs on each hardware thread

• memory cache, RAM

• I/O devices displays (GPUs), network interfaces

• internal devices clocks, timers, interrupt controllers

• persistent storage

OS uses both time and space multiplexing for sharing. An example for the former is how the effect of parallelism can be achieved with a single CPU core by splitting up the time allocated per process, and an example for the latter is splitting up memory for each process.

On the other hand, with allocation, the OS must also support simultaneous resource access (such as to disks, RAM, network etc.). Continuing from this, it must also offer mutual exclusion, thus protecting risky operations (such as file writing). Generally, the OS aims to protect against corruption.

Finally, the operating system must also handle storing data, and enforce access control.

(2) clean interfaces

The OS should hide away the hardware, and applications use the hardware through an interface provided by the operating system. We can think of this as a virtual machine abstraction on top of the bare machine - similar to how the JVM works (but at a lower layer).

(3) concurrency and non-determinism

The operating system must be able to deal with concurrency, for example overlapping I/O and computation. This is because I/O devices tend to be slower, and while the device is working on the task, it shouldn't prevent the CPU from doing other work. An operating system may switch activities at arbitrary times, and this must be done safely - by offering synchronisation primitives. It should also protect processes by giving each program its own space, thus preventing interference.

Similarly, the OS is fundamentally non-deterministic, as it needs to handle interrupts (such as the network card receiving a packet, user interrupts, etc.).

Tutorial Questions

- 1) List the most important resources that must be managed by an operating system in the following settings;
 - (a) supercomputer
 - computation time

primarily used for intensive computations

- memory
- (b) networked workstations connected to a server
 - bandwidth

must handle packet processing and network traffic

- (c) smartphone
 - \bullet energy
 - mobile network
 - other sensors

limited power, can power off unused hardware (including other communication technology) issues of privacy, when to expose GPS etc.

As this highlights, some uses will need specially designed operating systems. We also have general-process OS, as it takes a large amount of effort to implement a new operating system.

2) What is the **kernel** of an operating system?

The part of the OS is always in memory, and runs in the privileged part of the CPU (user mode cannot access all functionality). Implements commonly used functions of the OS and has complete access to all hardware.

Kernel Design

• monolithic kernel

Consider it as one large program that has all the functionality that you want an OS to perform.

The kernel is a single executable with its own address space. There exists a **system call** interface that allows user mode applications to access the hardware. Software invokes functionality from the kernel by issuing system calls - the CPU must switch from user mode to kernel mode to support this. The kernel then executes some instruction on behalf of the application. Device drivers are part of the monolithic kernel.

advantages

- efficient calls within the kernel, as there it remains in kernel mode
- flexible to write kernel components due to the shared memory (direct access with no limit to APIs)

disadvantages

- complex design
- no protection between bits of kernel functionality, therefore any bugs within the kernel will crash the entire machine

• microkernels

Only includes functionality that **requires** direct access to the hardware (or to be run in kernel mode). This is a minimalistic design and has the advantage of fewer bugs (due to the smaller amount of code).



Note that both the application and servers run in user mode, and the kernel is in kernel mode. The kernel performs IPC between the servers, which are separated for device I/O, scheduling. file access etc.

advantages

- less complex kernel
- clean interfaces for the servers
- more reliable; one of the servers could crash and then restart, without bringing the entire kernel down

disadvantages

performance overhead due to the requirement of message passing and transitioning between user mode and kernel mode (checks must be done to maintain the separation) - less of an issue now due to better hardware (e.g Android)

hybrid kernel

many modern designs use a combination of both

This is a more structured design, however user-level servers can incur a performance penalty.

Linux Kernel

The structure of Linux system calls is to put arguments into registers Or on the stack, and then issue a trap to switch the CPU from user to kernel mode.

While C is the dominant language for the Linux kernel, the interrupt handlers are written in assembly, as they are low level pieces of code, and require fast performance (hence a low instruction count). Interrupt handlers are the primary means to interact with devices, it initiates dispatching which stops proxies, saves the state, starts the driver and returns.

Typically, we can split the Linux kernel into three parts;

• I/O

One of the design philosophies under UNIX style operating system is to treat everything as a file, and use this file abstraction to expose different resources. Therefore, a lot of I/O resources can be hidden under this virtual file system.

memory management

Includes virtual memory with paging (and the abstractions associated with that).

• process management

Includes process and thread abstraction, as well as synchronisation and scheduling between them.

In addition to this, Linux supports dynamically loaded modules into the kernel. This support was important as it allowed for the hardware configuration to change (new devices drivers could be loaded into the kernel, without recompiling).

Windows Kernel

The NTOS kernel layer implements Windows system call interface. This is an example of a hybrid kernel, as programs build on dynamic code libraries (DLLs) - which also make the kernel modular, however the executive servers in the kernel adopted the server model of the microkernel, but still runs in kernel space for the performance benefits. At the lower levels, there still exists a microkernel. In addition, there is also a hardware abstraction layer (HAL), as this was designed for portability.

It's also important to note that there are environment subsystems running in user mode allowing for different APIs to be exposed, including Win32, POSIX, and OS/2. While the Windows kernel was designed with a lot of flexibility, due to its nature as proprietary software, it only really focused support (until recently) on Win32 (and also Intel in terms of the HAL).

9th October 2020

Tutorial Questions

1. Why is the separation into a user mode and a kernel mode considered good OS design?

Reduce the amount of code running in kernel mode, since a bug in user mode code should not bring down the entire system.

- 2. Which of the following instructions should only be allowed in kernel mode, and why?
 - (a) disable all interrupts

only kernel mode

if a user program were to disable interrupts, it would prevent the OS from scheduling processes

(b) read the time of day clock

not privileged

(c) change any memory

only kernel mode

typically programs can only access its own memory, such that it cannot accidentally or maliciously interfere with other memory

(d) set the time of day

typically kernel

most programs assume monotonicity of the clock, and changing to an earlier time can cause bugs

3. Give an example in which the execution of a user process switches from user mode to kernel mode, and then back to user mode.

Reading a file. Essentially anything that requires a system call, as it requires a switch from user mode to kernel mode, and then back.

4. A portable operating system is one that can be ported from one system architecture to another with little modification - explain why it is infeasible to build an OS that is portable without any modification.

At some point in the kernel, it will need to know about the ISA (instruction set architecture) of the CPU (hardware), and what instructions it can support. Some parts of the OS require assembly, and therefore requires modification. The hardware abstraction layer in the Windows kernel makes this easier.

Processes

One of the oldest abstractions in computing. This is an instance of a program being executed - this is useful as we can then execute multiple programs "simultaneously" on one processor, especially if not all resources are needed at the same time. This provides isolation between programs (own address space), and therefore doesn't interfere with other unrelated processes - if it needs to, then the IPC provided can be used. It also makes programming easier, as a programmer can assume it is the only process running.

Concurrency

It's important to note that there exists both pseudo-concurrency (on one CPU core), as well as real concurrency (across multiple CPU cores). The latter will still use the former per core, as the number of processes is much higher than the number of physical cores. In the case of multiple cores, we have to deal with conflicting accesses, whereas in the case with a single core, there is only one process really running at a time.

One method of creating the illusion of concurrency is time slicing. The OS switches the process currently running on the CPU with another runnable process, saving the original process' execution state, and then restoring it after it is switched back. Note that a runnable process isn't waiting for input, as we want to minimise the amount of time the CPU is idle. We also must ensure that the switching is fair - for example, if process A has a long execution time, compared to an interactive process B, letting A run for a long period would cause the interactive process to become unresponsive - therefore the time slice tends to be quite short (how often it lets a process run before switching).

1. If on average a process computes 20% of the time, then with 5 processes, we should have 100% CPU utilisation, right?

Only in the ideal case, when they never wait for I/O at the same time. A better estimate is to look at the probability (assuming independence), with n being the number of processes, and p being the fraction of time a process is waiting for I/O. The probability that all are waiting for I/O would be p^n , and therefore the CPU utilisation would be $1 - p^n$.

2. How many processes nee to be running to only waste 10% of CPU if they spend 80% waiting for I/O?

$$1-0.8^n=0.9\Rightarrow 0.8^n=0.1\Rightarrow n=\log_{0.8}(0.1)\approx 10$$
 concurrent processes

Context Switches

A context switch is when the processor switches execution from process A to process B. This is done as part of a scheduling decision. With timer interrupts, the currently executing program passes control back to the kernel, which can then make a scheduling decision, changing what is currently running, possibly a different program and performing a context switch. This causes the order of execution between processes to become non-deterministic, as these events cannot be pre-determined.

This needs to be transparent to the process, therefore the state needs to be restored exactly, including anything currently in registers (this is saved by the hardware to the stack, before the hardware invokes the interrupt handler). This data is stored in a process descriptor, or a process control block (PCB), kept in the process table. The process has its own virtual machine;

• own virtual CPU

- own address space (stack, heap, text, data, etc.)
- resources it has access to (open file descriptors, etc.)

The information in registers (such as the program counter, page table register, stack pointer, etc.), the process management information (process ID, parents, etc.), as well as file management information also needs to be stored (root directory, working directory, file descriptors, etc.).

It's also important to avoid unnecessary context switches as they are expensive, not just from the direct cost of managing state, but also the indirect cost to caching (as the old cache contents are no longer relevant). Therefore it has to balance fairness, and the frequency of context switches.

Process Lifecycle

Processes are created at the startup of a system, by the request of a user, or through a specific system call by a running process. These processes can be foreground processes, that the user interacts with, or background processes that provide services (such as printing or mail) or APIs that can be used by other processes (daemons).

A process can terminate under these conditions;

- normal completion, where the process completes execution
- through a system call (exit() in UNIX or ExitProcess() in Windows)
- abnormal exit, where the process has run into an error or unhandled exception this is the importance of user and kernel space separation
- aborted, due to another process overruling its execution (such as killing from terminal)
- never some processes such as daemons should run infinitely and never terminate (unless an error occurs)

UNIX allows for a process hierarchy (tree), by running init (typically), and all processes then form a tree. On the other hand, Windows has no notion of hierarchy, and rather the parent of a child process is given a token (a handle) to control it. This handle can be passed to another process.

10th October 2019

UNIX Processes (fork)

In UNIX int fork(void) creates a new child process, which is an exact copy of the parent process, inheriting all resources, and executed concurrently - however, different virtual address space. fork will return twice, however in the parent process it will return the child's process ID, but in the child it will return 0, thus the child knows it's the child. Additionally, if there is an error (such as exceeding the global process limit, or running out of memory when copying the parent), -1 will be returned to the parent.

```
#include <unistd.h>
#include <stdio.h>

int main() {
   if (fork() != 0) {
      printf("parent\n");
   } else {
      printf("child\n");
   }
   printf("common\n");
}
```

The parent and child processes start off with the same memory, but as they start writing to their own memory, they will diverge. In the tutorial question below, we'd end up with the following process tree (imagine the spaces in the strings are actually new lines);

However, note that because this creates new processes that run in parallel, the actual order of execution would be non-deterministic, and therefore the outputs can change the order in which they are printed.

UNIX Processes (execve)

While fork creates a copy of the parent process, we often want the child process to do something different; int execve(const char *path, char *const argv[], char *const envp[]).

• path full path name of the program to run

• arguments passed to main

• environment variables such as \$PATH and \$HOME

Running this changes the process image, and runs the new process. To start a new process, you could fork the current process, and if it is the child, then run execve to change the image. This has many useful wrappers, and man execve can be used as a reference.

UNIX Processes (waitpid)

The example below is an application, a simple command interpreter, for the two functions previously discussed, as well as a use of int waitpid(int pid, int* stat, int options);

```
while (1) {
   read_command(command, parameters);
   if (fork() != 0) {
        // parent code here
        waitpid(-1, &status, 0);
   } else {
        // child code
        execve(command, parameters, 0);
   }
}
```

This suspends the execution of the calling process until the process with PID pid terminates, or a signal is received. If pid is set to the following values, it can wait for more than one child;

- -1 wait for any child
- 0 any child in the same process group as the caller
- -gid wait for any child with the process group gid

This will return the pid of the terminated process, -1 if it is an error, or 0 if the call is not blocking and no children are terminated.

UNIX Processes (Termination)

A process can terminate from itself by executing void exit(int status), which is also called implicitly once the program completes execution, and obviously does not return in the calling process (instead returns an exit status to the parent process). It can also be terminated by another process via void kill(int pid, int sig), which sends the signal sig to the process associated with pid.

Design Philosophy

The UNIX design philosophy is to be simplistic. Having both fork and execve allows us to use the small building blocks, which have limited behaviour, to perform more complex tasks. This contrasts with Windows' CreateProcess() which combines both of them, however, it's much more complex and takes 10 parameters.

Process Communication

• signals (UNIX)

Signals are an Inter-Process Communication mechanism, and they work similar to the delivery of hardware interrupts. If a process runs on behalf of root, the superuser, it has the permission to send signals to any process. The kernel can also send signals to any process. Some of the cases for signals being generated are as follows;

signal	meaning
SIGINT	interrupt from keyboard
SIGABRT	abort signal from abort
SIGFPE	floating point exception
SIGSEGV	invalid memory reference
SIGPIPE	broken pipe: writing to a pipe with no readers
SIGALRM	timer signal from alarm
SIGTERM	termination signal

The default action for most signals is to terminate the process, however the receiving process may choose to do the following (SIGKILL and SIGSTOP cannot be ignored / handled);

```
- ignore it
```

- handle it manually with a signal handler;

```
signal(SIGINT, my_handler);

void my_handler(int sig) {
 printf("ignoring SIGINT");
}
```

• pipes

This can be considered as a one-way communication channel between two processes. This essentially opens a byte stream from process A to process B, allowing A to send data to process B. This is commonly used in the command line, for example cat file.txt | grep foobar (the output of cat is now the input for grep). There are two types; unnamed (default) and named (can be referred to).

This is opened with the int pipe(int fd[2]) system call, which returns two file descriptors, the read end being in fd[0], and the write end being in fd[1]. If the receiver is reading from an empty pipe, it blocks until data is written, and if the sender is writing to a full pipe, it blocks until data is read. The parent typically makes the system call, and then forks the process, passing

the file descriptors to the child. The sender should close the read end, and the receiver should close the write end.

A persistent pipe can outlive the process that created it - it is stored on the file system, and has different semantics since it is flushed when read from.

- 1. When two processes communicate through a pipe, the kernel allocated a buffer (say 64KB). What happens when the process at the write-end of the pipe attempts to send additional bytes on a full pipe?
 - It cannot write to the buffer, therefore it will block (and the scheduler will choose another process to run) until the pipe is read from (and therefore freed up space in the buffer).
- 2. What happens when the process at the write-end of the pipe attempts to send additional bytes but the other process already closed the file descriptor associated with the pipe?
 - The writing process will have an error returned to it.
- 3. The process at the write-end of the pipe wants to transmit a linked list data structure (with one integer field and a "next" pointer) over a pipe? How can it do this?

The data must be serialised (as if it were going through a network). Since all processes have their own address spaces, the pointer would be meaningless.

- shared memory
- semaphores

Threads

Threads are also an abstraction for execution, but unlike processes, they are execution streams that share the same address space. When multithreading is used, each process can contain one or more threads. A thread lives within a process.

per process

- address space
- global variables
- open files
- child processes
- signals

per thread

- program counter (PC)
- registers
- stack

Threads allow for programs to execute in parallel, but more importantly they can block independently, therefore blocking in one part of the program (waiting for I/O, etc) does not affect the rest of it. This is useful, over having many processes, as processes have too much overhead, it is difficult to communicate between address spaces, and anything that blocks may switch out the entire application.

However, there can be issues with multiple threads. Since we are working with the same address space, we need to handle synchronisation, and prevent threads from interfering with each other accidentally (such as stack corruption).

Typically, when a fork is performed from a thread, only a single thread is created - however this can lead to issues if the parent is holding locks, the thread now also holds them. Generally, we want to avoid calling fork in a thread. While signalling and threading are compatible, there are many corner cases which can complicate the implementation.

PThreads

Posix Threads are defined by IEEE standard 1003.1c, and is implemented by most UNIX systems.

```
#include <pthread.h>
#include <sys/types.h>

pthread_t // type representing a thread
pthread_attr_t // type representing the attributes of a thread
```

Creating a thread is done with int pthread_create(pthread_t *thread, const pthread_attr_t *attr, void *(*start_routine)(void*), void *arg). It stores the newly created thread in *thread, and returns 0 if it was created successfully, or an error code otherwise (possibly due to lack of memory, due to the need for a stack). A function pointer is also required, as the thread will run the specified function with the arguments provided. The arguments are as follows;

• attr specifies attributes (NULL for default) such as minimum stack size, behaviour on process termination, etc.

- start_routine C function the thread will start executing
- arg argument to be passed into start_routine (can be NULL if none) if we want to pass in more arguments, pass in a struct, since it is in the same address space

A thread can be terminated with pthread_exit(void *value_ptr), which terminates the thread, and makes the value_ptr available to any successful join (this is fine as threads reside in the same address space).

It's also important to note that a thread is automatically allocated for the main entry point (starting main()). If the main thread terminates without calling pthread_exit(), the entire process is terminated, however if it does call it, the remaining threads continue until termination (or exit() is called).

Yielding a thread with int pthread_yield(void) would be done for the same reasons as the system call nice() is done for processes (lowering priority in the scheduler). It releases the CPU to let another thread run, and will always return 0 (success) on Linux.

In order to join threads, int pthread_join(pthread_t thread, void **value_ptr) can be used. This blocks the caller until thread terminates, and the value can be accessed.

All of the content mentioned before assumes a kernel-level thread, such that all of the scheduling is managed by the kernel. However, a process can manage its own user-level threads. Threads in user-level tend to be more lightweight, as there is very low overhead of context switching, and synchronisation is fast. However, because it not visible to the kernel, it may preempt all the threads controlled by a process, instead of just a single one - if one of the threads perform a blocking system call, none of the other threads can run.

Tutorial Question

In this question, you are to compare reading a file using a single-threaded file server and a multithreaded server, running on a single-CPU machine. It takes 15ms to get a request for work, dispatch it, and do the rest of the necessary processing assuming that the data needed are in the block cache. A disk operation is needed $\frac{1}{3}$ of the time, requiring an additional 75ms, during which time the thread sleeps. Assume that thread switching time is negligible. How many requests per second can the server handle if it is single threaded.