# CO212 - Networks and Communications

# **14th January 2020**

Week 1, Lecture 1

## **Evolution of the Internet**

Literally only writing this part so I have something for the first lecture.

- (1969 October) first message sent on ARPANET; "login", crashed after "l" and "o" were sent
- (1971) universities in West and East coast of USA connected
- (1980) London connected

# 14th January 2020

Week 2, Lecture 1

## World Wide Web (WWW)

This is an example of an **application** on the internet, based on HTTP (HyperText Transfer Protocol). A web browser (the client) sends a request to the web server over a pipe, which can be any form of connection between the two devices (can also be the same device), which in turn sends back a response.



#### Layers

#### • application layer

Any software written for the internet is on the application layer.

#### • transport layer

In the **transport layer**, packets leave your (client) machine to the server, and the server sends back packets to your client. This layer divides a (big) message into smaller chunks, and sends them to the other side (re-ordered) to be presented to the recipient.

#### network layer

The **route** / **path** (sequences of switches a packet goes through) each packet takes can be different from the others, and is often the most optimal route available. This is done on the **network layer**, which routers are a part of.



### • data link layer

Our devices are linked to the network on the **data link layer**, via network interface controllers (NICs). Examples of this include Ethernet, fiber optic network cards, as well as wireless devices such as WiFi access points, and USB dongles for 4G. A communication link is any connection between packet switches and / or end systems.

## • physical layer

Finally, on the **physical layer**, there are various forms of communication media, including fiber-optic cables, twisted-pair copper wire, coaxial cables, and wireless local-area links (802.11, Bluetooth, etc).

# 16th January 2020

# Week 2, Lecture 2

# Circuit Switching

Old phones used circuit switching, which creates a connection between the two points, which is used for the entire communication. This isn't used for the internet as the failure of one node in the circuit would lead the entire communication dropping - whereas a different route would be calculated in packet switching.

Compared to packet switching, it has an expensive setup phase, but will need very little processing once the connection is established. However, it is inefficient for sharing resources - if a node is used as part of a circuit, it cannot be used by another connection for a different circuit. The resources are blocked once a connection is established (hence it is an inefficient way to use the network). On the other hand, packet switching has no setup cost, but has a processing cost, as well as space overhead, for every packet. It has a processing cost for forwarding the packets, as well as space overhead as there must be redundant data for each packet, such that it is self contained. It is specifically designed to share links, hence it allows for a better utilisation of network resources.

#### **Protocols**

A protocol is a set of rules (an agreement between communicating parties on how communication is to proceed), run by end systems as well as packet switches. It must be unambiguous, complete (includes actions and / or responses for all possible situations), and also define all necessary message formats. The phases are as follows;

handshake

establishes identities and / or context

conversation

free-form exchange

closing

terminating the conversation

The internet protocol stack is based on the 5 layers briefly covered in the previous lecture. Some examples of design issues that can be encountered are as follows;

addressing

how to denote the intended recipient

• error control

how to detect (and possibly fix) transmission errors, e.g. checksums

• flow control

ensure data travels through communication media without issues

- multiplexing / demultiplexing conversion of data into binary, and parallel communications
- routing

which route is chosen

Most network layers are either connection-oriented, where a connection is first established, data is exchanged, and the connection is finally released, or connectionless, where data is marked with its destination.

The TCP/IP (4 layer) stack consists of application, transport, internet, and network access (which combines data link and physical). On the other hand, the OSI (7 layer) model consists of the application layer, presentation, session, transport, network, data link, and physical.

application
presentation
session
transport
network
data link
physical

application
transport
network / internet
data link
physical



A **service** is a set of primitives that a layer provides to the layer above it, whereas a **protocol** is a set of rules that prescribe the layout and meaning of packets. In a protocol stack, layer k puts its entire packet as data into a layer k-1 packet, the latter may add a header and / or a trailer. This may have to be split across several lower level packets (**fragmentation**). An example of protocol layering is as follows;



Note that the connection between the two machines can have multiple nodes in between, that can read up to a different physical layer. For example, if there was a link-layer switch after the source machine, it can read up to the link layer (layer 2), remove and add headers / trailers, and then send it on to the next device. The next device may be a router for example, which can read up to the network layer (layer 3), and do the same.

The data from the layer above is known as the SDU (service data unit), and the SDU combined with a header, added by the current layer, is known as the PDU (protocol data unit).

# 16th January 2020

Week 2, Lecture 3

#### **Protocol Layers**

The types of protocols on each layer are as follows;

## application layer

Protocols on the application layer defines functionality and message formats. Some examples are as follows:

- traditional name services (DNS), sending email (SMTP), file transfer (FTP), web (HTTP(S))
- modern

includes middleware protocols to support distributed systems with special protocols to handle replication, fault tolerance, caching, etc.

- special application-level protocols for e-commerce, banking etc. - high-level BitTorrent, old-Skype (awful API)
- peer-to-peer

## • transport layer

These protocols generally offer connection-oriented (TCP) as well as connectionless (UDP) services, which have varying degrees of reliability. These often provide a network interface to application via sockets. It's also important to note there is a difference between reliability and security; the former guarantees that the data is sent, whereas the latter ensures that it is encrypted in some form. This layer also provides flow control; mechanisms to ensure fast senders don't overwhelm slow receivers.

## network layer

In this layer, the protocols generally describe how routing is performed, such as determining which computers / routers are in the network, the best route between two points, how to handle faults (such as a device going down), as well as handling congestion (when a router is overloaded and packets are dropped).

# • data link layer

In this layer, we need to detect bit transmission errors. This can be done by adding redundancy bits in frames to detect errors - for example adding a parity bit to every 7 bits, where a 1 indicates an odd number of 1s, and a 0 indicates an even number of 1s, or adding a checksum (cyclic redundancy check) which should match the bits before it.

It also specifies how many computers can share a common channel, with the medium access control sub-layer (MAC). A well known protocol is the Ethernet protocol.

#### physical layer

This describes the transmission of raw bits, in terms of the physical mechanical and electrical issues. For example, when two computers are connected with a wire, -3V may indicate to a binary 1, and +4V may correspond to a binary 0. It may also specify the number of times the voltage can be changed per second.

For example if the voltage can be changed 20,000 times per second, it indicates that the maximum transfer rate is 20,000 bits per second, which is 20 Kbps (20 kilobits per second).

#### Units

• 1 Byte = 8 bits note that a byte has an uppercase B, whereas a bit has lowercase b

• 1000 Bytes = 1 KB(Kilobyte)

• 1024 Bytes = 1 KiB(Kibibyte)

Typically we use powers of 10 for networks, but as long as we are consistent in what we use it is fine.

# Quantifying Data Transfer

#### • bandwidth

the amount of information that can get into the connection in a time unit

## • throughput

the amount of information that **actually** get into the connection in a time unit - at steady-state, we assume zero accumulation of traffic therefore the input and output throughputs are equal

## latency

the time it takes for one bit to go through the connection

Note that for the following formula, we use these values;

 $\bullet$  to the time the first packet leaves the source

•  $t_1$  the time the first packet reaches the destination

 $\bullet$   $t_2$  the time all the packets reach the destination

 $\bullet$  L the size of the packet in bits

• latency (propagation delay)  $d = t_1 - t_0 \text{ (generally } \frac{\text{distance}}{\text{wave propagation speed}})$ 

note that this is half the RTT (round-trip time)

• throughput (link bandwidth) 
$$R = \frac{L}{t_2 - t_1} \text{ (generally } \frac{\text{transferred bits}}{\text{duration}})$$

• packetization (transmission delay / store-and-forward delay)

time it takes for the entire packet to be received after the first bit is received

• transfer time (propagation delay + transmission delay)  $\Delta = d + \frac{L}{R}$ 

However, it's important to note that the connections are (almost) never direct, and therefore will have additional delays at each router. Note that our bandwidth is also bottlenecked by the lowest bandwidth.



$$d_{\text{end-end}} = \begin{cases} d_1 + \frac{L}{R_1} + d_x + d_2 & R_1 < R_2 \\ d_1 + d_x + \frac{L}{R_2} + d_2 & R_1 \ge R_2 \end{cases}$$
$$= d_1 + d_x + d_2 + \frac{L}{\min(R_1, R_2)}$$

The router delay,  $d_x$  has two components; the processing delay  $d_{\text{proc}}$  which is the processing time (checking for bit errors and determining the output link), as well as  $d_q$ , which is the queueing delay the time waiting at the output link for transmission, which depends on how congested the router is. We can quantify the **traffic intensity** as follows;

R = link bandwidth

L = packet length (bits)

a = average packet arrival rate

 $\frac{La}{R}$  = traffic intensity

$\frac{La}{R} \approx 0$	small average queueing delay
$\frac{La}{R} \to 1$	large average queueing delay
$\frac{La}{R} > 1$	more working arriving than can be serviced, infinite delay

# 21st January 2020

Week 3, Lecture 1

#### Clients and Servers

We can distinguish between the two roles in a pair of communicating processes, in a connection-oriented model;

• client initiates communication

• server waits to be contacted

On the other hand, some applications have processes that act as both the client and the server, which is referred to P2P (or peer-to-peer) architecture.

## **End System Applications**

Internet applications are processes on the end systems. They must have a way of addressing each other, either via the internet (such as chat servers), or they can directly communicate (such as FTP) - but this depends on the protocol in use. Note that a single end system (or host) can run multiple programs, which run multiple processes, all of which connect through a network API provided by the operating system. Each process is addressed within its host by a **port number**. When an application wants to communicate with another application, the OS opens a socket, which allows data to be transferred between the two machines.

client application

server application (on host H)

- 1. create a socket C by connecting to server application (connecting to host H on port P)
- 2. read and write data to socket C
- 3. disconnect and destroy C

- 1. create a socket S by accepting connection on part P (port is often called a server socket)
- 2. read and write data to socket S
- 3. disconnect and destroy S

The server application can open more sockets to server multiple clients at a time. A DDoS (distributed denial of service) attack works by opening many sockets, preventing the server from serving legitimate requests.

## The World Wide Web

Invented in 1989 (formally defined in 1991) by Sir Tim Berners-Lee. Based on the idea of hypertext and hyperlinks (based on a proposal by William Tunnicliffe in late 1960s). Commonly used terminology is as follows;

• document a webpage is called a document

• object any called within a document (images, stylesheets, etc.)

• Uniform Resource Locator (URL) specifies the address of an object

• browser also called user agent - client used to access documents

• web server application that makes documents and objects available through HTTP

#### Protocol

In general, the request and reply would include the following;

request

- protocol version
- URL specification
- connection attributes
- content / feature negotiation

- protocol version
- reply status / value
- connection attributes
- object attributes
- content specification
- content

A protocol should always include a version number, as it allows the protocol design to change. HTTP/2 will replace HTTP/1.x in the next few years (hopefully), as the former is able to fully multiplex a connection since all content is binary, and can use a single TCP connection for parallelism.

reply

The URL contains the host name, which determines where the requests goes, by mapping to a network address. The request consists of a request line, such as GET /path/to/index.html HTTP/1.1, zero or more header lines, an empty line, followed by the object body (which can be empty). The request line contains a method, such as;

• GET retrieve the object identified by the URL

• POST allows for submission of data to the server

• HEAD similar to GET but only receives headers

• PUT requests the enclosed object to be stored under the given URL

• DELETE deletes the given object

• OPTIONS requests the available communication options for the given object

The status code in a server response is generally as follows;

• 1xx informational

• 2xx successful

• 3xx redirection (e.g. object has temporarily or permanently moved)

• 4xx client error (e.g. malformed request, unauthorised, object not found, method not allowed)

• 5xx server error (e.g. internal server error, service overloaded)

# **23rd January 2020**

# Week 3, Lecture 2

#### How HTTP uses TCP

HTTP uses TCP as it is essentially a file transfer protocol, which needs to be connection-oriented. The first version of HTTP uses a TCP connection for each object, which was an inefficient use of both the network and the operating system. HTTP/1.1 introduced persistent connection, which allows for an existing connection to be used to issue multiple requests (either sending a request, waiting for a response, sending the next request and so on, or through pipelining) - which will eventually close with a timeout. Pipelining allows the client to send all its requests without waiting for a response, and the server delivers them in response.

#### Web Caching

A proxy is a server which acts as an intermediate between the client and the destination server. This can be used for caching by storing a copy of the content, which reduces load on the origin server, and also allows for lower latency. Data isn't cached for an extended period of time as it can lead to stale data (where old content is served to a user, even after the content is changed on the origin server). Proxies can also protect the clients by providing anonymity, as well blocking malicious content through the use of a single firewall on the proxy. However, this also acts as a single point of failure - if the proxy fails then the clients may not be able to connect.

A HEAD request could be used to see if an object has been updated, which is less expensive than retrieving the entire object with a GET request. The request can also include Cache-Control: no-cache, which indicates it does not want cached objects, thus requiring proxies to go to the origin server, or Cache-Control: max-age=20, which only gets a cached object if the cache is less than 20 seconds old.

On the other hand, the reply can also include Cache-Control: no-cache, which informs the proxy not to cache the object, or Cache-Control: maxage=100; must-revalidate, which specifies to the proxy that it must revalidate the object after 100 seconds.

#### Sessions

Note that HTTP is a **stateless** protocol, which means that responses have no memory of past requests. However, HTTP allows higher-level applications to maintain **stateful** sessions, via the use of cookies. The **Set-Cookie** header is sent from a server, informing the client to store the cookie as a session identifier for that site. On the other hand, the client sends a **Cookie** header, which tells the server which session the request belongs to. This can be useful for storing identifying a user on a page (allowing for personalised pages). However, this can be also be used to track users for profiling and targeted advertising - leading to privacy issues.

## Dynamic Web Pages

Servers often generate pages on-the-fly, instead of only serving statically stored pages. CGI (common gateway interface) allows you to identify a program and its parameters in a URL, which then starts a process to execute the program and return any results as a regular web page. On the other hand, servelets in Java maintain state (whereas CGI is stateless), and the webserver contains an instance of the JVM.

Another approach is for the web page to incorporate interpretable code, which is executed when the page is being processed on the client-side (via JavaScript). It's important to distinguish this from server-side processing in something such as PHP, which the user should not see.

#### IP and Hosts

Each end system is identified and addressed by its IP address, which is 32 bits in IPv4, or 128 bits in IPv6. This is easy to process by a computer, as it can easily work in powers of two, but not practical for people to use.

Host names are used to create human-readable "aliases" for IP addresses. Originally, before 1983, all mappings were in the hosts file, since there weren't many different hosts. However, as more hosts became present, DNS (Domain Name System) was developed, which provides a distributed lookup facility.

There are 13 root DNS servers, which know where the top-level servers are located. The top-level domain servers are each associated with a top-level domain. However, knowing where to connect to requires a large amount of communication between servers. This can therefore be a bottleneck for applications, and also be a critical point of failure. To circumvent this, we can also cache DNS lookups.

This improves performance as we do not have to do as much communication, and it also reduces the overall load on the DNS infrastructure.

However, this can be an issue if enough DNS servers advertise an incorrect lookup, causing subsequent requests to point to an incorrect IP (DNS cache poisoning).

DNS query types are as follows;

- A maps a host name to its address, **name** is a host name, and **value** is its IP address
- NS

a query for a name server, **name** is a domain name, and **value** is the authoritative name server for that domain

• CNAME

a query for a canonical name, name is a host name alias, value is the primary host name

MX

a query for the mail exchange server **name** is a host or domain name, and **value** is the name of the mail server handling incoming mail

The DNS protocol is connectionless, and runs on UDP port 53. UDP (best effort) is used since it only involves two network packets (request and response), setting up and closing a TCP (reliable) connection every time would be wasteful. If it fails, it can just try again.

Round Robin DNS is a load balancing technique, as it responds to DNS requests with a list of IP addresses instead of a single IP address. The IP at the top of list is returned a set number of times before it is moved to the bottom of the list (the IP that was previously second in the list is now at the top). If load balancing is used, the TTL should be small, as we want this to constantly change depending on server load.

# **23rd January 2020**

Week 3, Lecture 3

### Content Distribution Networks (CDNs)

We have the following options when we want to provide a streaming service from millions of videos to many simultaneous users;

- 1. single, large "mega-server"
  - single point of failure, and point of network congestion
  - long path to distant clients (slow)
  - multiple copies of video sent over outgoing link

This solution does not scale to a large amount of users.

- 2. store multiple copies of videos at multiple geographically distributed sites
  - enter deep push CDN servers into many access networks (close to users) used by Akamai (216000+ servers, 120+ countries, 1500+ networks)
  - **bring home** smaller number of large clusters in PoPs near (not within) access networks used by Limelight (80+ PoPs Points of Presence)

A CDN DNS can select a good CDN node by picking the CDN node closest to the client, or a CDN node with the shortest delay to the client. However, it's important to note that the CDN doesn't know the IP address of the client, only the address of the local DNS which may not be fully accurate. An alternative is to let the client decide by giving a list of CDN servers. The client can then select the "best" based on the lowest RTT.

#### Electronic Mail

While email was able to achieve asynchronous communication, one-to-many communication, as well as multimedia content it had a number of limitations. Privacy and security was an issue, as there was initially no authentication - hence messages could be modified or forged, and messages could be read by others. Additionally, it was unreliable as there were no delivery guarantees, and had no reliable acknowledgement system.



The user agent is the client the user uses to read, compose, reply, send and forward messages. The mail server can do the following;

- accept messages for remote delivery (delivers message to remote destination server with transport protocol)
- accept messages for local delivery (saves messages in local persistent mailbox)
- allows user agents to access local mailboxes (to allow for retrieval and / or deletion of messages)

## Simple Mail Transfer Protocol

It's important to note that the 'S' in SMTP does not stand for secure (no authentication). This is a connection-oriented protocol (TCP), on port 25. As it is a very simple protocol, it can be left unsecured - this is often targeted by spammers and phishers who use unsecured mail servers to send mail without using their own resources.

The general format of using SMTP is headers, followed by an empty line, and then content. A single dot is used to end the email, and QUIT is used to exit. SMTP is completely oblivious to the contents of a message, other than the **received** header, which is added by each receiving SMTP server. This can be used to trace the origins of an email.

The initial message format had many limitations - it only supported 7-bit text content, and was essentially only usable for the English language. The MIME (multipurpose internet mail extensions) format defined useful extensions on top of SMTP, which includes the following types;

• text/plain

normal ASCII message

• text/html

HTML-formatted message

• image/jpeg

contains only an image file

• multipart/mixed

consists of multiple parts

## Post Office Protocol (POP3) and IMAP

The user's mailbox is often stored on a different machine than the user agent, but we need remote access to incoming (and outgoing) messages. However, POP3 is insecure (at least on port 110), due to the transmission of credentials in plain text. It also implicitly assumes the retrieved mail is deleted at the server, which isn't useful if people wanted to access mail from different clients.

The internet message access protocol (IMAP) solves this, by storing messages on a server, and requiring the client to be online to read mail.

#### Dark Web

TOR (The Onion Router) hides the user behind a series of machines (proxies), and also allows for access to .onion sites (as well as regular ones). This can be used for privacy purposes, as well as for circumventing censorship. The exit nodes of TOR can be owned by law enforcement agencies, allowing for a user to be compromised if they were to subpoena all intermediate proxies.

Not that this shouldn't be confused with the **deep web**, which is typically just not indexed on the surface web.

# **27th January 2020**

Week 4, Lecture 1

# Transport Layer

The transport layer provides both reliable connection-oriented services (TCP - transmission control protocol), as well as unreliable connection-less services (UDP - user datagram protocol). This provides for logical communication between application processes, and only runs on end hosts (not routers / switches). TCP data are called segments, whereas UDP data are called datagrams.

We also assume that the underlying layer is working, with every host having a unique IP address, and that IP is a "best-effort" delivery service. This means that it has no guarantees on the integrity of data (or packet) transmission, nor does it guarantee the order of delivery of packets or segments.

## **Data Encapsulation**

For each layer, we have the following terminology - we can't refer to everything as packets;

• application layer data

• transport layer TCP segments or UDP datagrams

(TCP only) segmentation can be done when the segments are too large - if the UDP datagrams are too large, it cannot be sent

• network / internet layer IP datagrams (or packets) similarly, fragmentation can be done when the packets are too large

• data link layer frames

• physical layer bits

#### Ports

Note that it's possible for a client (one IP) to communicate with the same host (one IP) via multiple applications, such as HTTP and SMTP. Each application on ta host is identified with a unique port number - they can be thought of as cross-platform process identifiers. A socket consists of two pairs of ip\_address + port\_number + TCP/UDP; such as

146.179.40.24:80 TCP ⇔ 192.168.1.1:7155 TCP

The first 1024 ports (0 - 1023) are reserved, and cannot be used to form a connection as a client (unless it is done as a superuser).

#### Transmission Control Protocol

TCP is the Internet's primary transport protocol. It is a connection-oriented service, and endpoints initially perform a handshake to establish a connection. This is a full-duplex service, thus both endpoints can send a receive at the same time. Some definitions for TCP are as follows;

• TCP segment

"envelope" for TCP data

# • maximum segment size (MSS)

maximum amount of application data transmitted in a single segment (does not include headers) - typically related to MTU to avoid network-level fragmentation

• maximum transmission unit (MTU) largest link-layer frame available to the sender host path MTU discovery (PMTUD) is used to determine the largest link-layer frame that can be sent on all links from the sender to the receiver

The TCP header consists of the following fields;

• source and destination ports

16-bit each (identifies applications)

• sequence number

32-bit (used to implement reliable data transfer)

These numbers are not associated with the segments, but instead are associated with the bytes in the data stream. It indicates the sequence number (the place) of the first byte carried by the TCP segment. When the connection is initialised, a random ISN (initial sequence number) is decided upon to avoid accidentally receiving leftover segments.

• acknowledgement number

32-bit (used to implement reliable data transfer)

Represents the first number not yet seen by the receiver (one higher than the sequence number of the last bit received). These can be cumulative, and typically TCP implementations acknowledge every other packet;

A 	[seq#=1200,], size(data) = 1000	В
	[seq#=2200,], size(data) = 500	
	[seq#=,ack#=2700]	
Ì	i i	

Note that because a TCP connection consists of a full-duplex link, there are two streams, hence two different sequence numbers (see the example below, of an "echo" application). Acknowledgements are "piggybacked" on data segments.

A	
[seq#=100,data="C"]	
[ack#=101,seq#=200,data="C"]	
<del>\</del>	
[seq#=101,ack#=201,data="i"]	
<u> </u>	
[ack#=201,seq#=102,data="i"]	
[40111 201,5041 102,4404 1]	

• receive window

16-bit (size of window on receiver end)

• header length / offset

4-bit (size of TCP header in 32-bit words)

• optional fields

variable length (may be used to negotiate protocol parameters)

• URG flag

1-bit (informs receiver some data is marked as urgent)

• ACK flag 1-bit (value contained in the acknowledge number is a valid acknowledgement)

See acknowledgement number above, and the three-way handshake section.

• PSH flag 1-bit (solicit receiver to pass data to application immediately)

• RST flag 1-bit (used during connection setup and shutdown)

• SYN flag 1-bit (used during connection setup and shutdown)

See the three-way handshake section below.

• FIN flag 1-bit (used during connection shutdown)

A client sends a TCP segment with FIN set, and the server responds with ACK, and then the server sends a FIN TCP segment, client then responds with ACK. Closing a connection is simpler than initialising one.

• checksum

16-bit (used to detect transmission errors)

## Three-Way Handshake

The three steps are as follows;

- 1. client sends a TCP segment with SYN set, and an initial sequence number
- 2. server responds with another TCP segment with SYN set, as well as ACK, the first unseen client sequence number, and the ISN for the server
- 3. **client** reserved with a TCP segment with ACK set, the first unseen server sequence number, and the client's new sequence number



#### User Datagram Protocol

UDP only provides the two most basic functions of a transport protocol, which are application identification (multiplexing and demultiplexing), and an integrity check via a CRC-type checksum. There is no flow control, no error control, nor any retransmissions. The datagrams cannot be larger than 65K, there is no segmentation, and the router will just drop it. The 65K consists of 20B IP header, 8B UDP header, 65507B of data, coming to a total of 65535 bytes. In practice, only 500 to 1000 bytes are used (the smaller the datagram, the more likely it will arrive intact).

Instead of just using IP, it adds port numbers on top of it, allowing us to differentiate between applications. This is a connection-less protocol, therefore there is no need to connect (just send the data) but each datagram packet must carry the full address and port of the recipient. The UDP header consists of the following fields;

• source and destination ports

16-bit each

• length of data

16-bit

• checksum 16-bit

Any application where we care more about speed, we can use UDP, since it is generally faster (due to the lack of connection establishment), and also has a smaller packet overhead.

## Berkeley Socket Interface

The **Berkeley** socket interface is as follows;

• SOCKET create a new communication endpoint

• BIND attach a local address to a socket

the client and server each bind a transport-level address and a name to the locally created socket

• LISTEN announce willingness to accept N connections server starts listening on this socket, thus telling the kernel it will wait for connections from clients

• ACCEPT block until a remote client wishes to establish a connection this blocks the current thread, thus it is a synchronous operation from here the server can accept or select connections from clients

• CONNECT attempt to establish a connection a client connects to the socket, it needs to provide the full transport-level address to locate the socket

• SEND send data over a connection

• RECEIVE receive data over a connection now the client and server communicate through these operations on their respective sockets

• CLOSE release the connection end the communication, must be closed otherwise connections may be continued, and may

end the communication, must be closed otherwise connections may be continued, and may run out of ports



Note that the part in violet would not be present for UDP.

# 30th January 2020

# Week 4, Lecture 2

## TCP vs UDP

The scenario is as follows; movie player app is being built that allows (paying) users to stream public domain movies. Since the users are paying, we should be using TCP, as it guarantees quality of service, whereas UDP does not. The difference in performance (TCP being slower than UDP) can be circumvented by pre-buffering (sending some data in advance for the client to store locally). This however doesn't work for live events - we can either switch to UDP, or introduce a delay between the feed and the live event.

## **QUIC**

QUIC (Quick UDP Internet Connections) is a new layer 4 protocol, implemented by a Google engineer in 2012. Originally, it was designed for general purpose, but now it is being used for HTTP (layer 5). This is still a draft, but is actively being used by some web servers.

#### Finite-State Machines

A finite-state machine (FSM) is a mathematical abstraction, where states are represented as nodes, and transitions are directed edges between states, labelled with events. They are also known as finite-state automaton (FSA), deterministic finite-state automaton (DFA), and non-deterministic finite-state automaton (NFA) - multiple edges with the same label from one node. This can be used to specify protocols, where the states represent the state of a protocol, and transitions are characterised by an event / action label (event typically consists of an input message or timeout, whereas an action typically consists of an output message).

$$\frac{\text{input / timeout (event)}}{\text{output (action)}}$$

Examples of this are in the slides, for the TCP state machines for both the client and server.

#### Reliable Data Transfer

TCP adds a reliable channel on top of an unreliable channel (IP) which is "best effort" delivery. The service provided by the transport layer sits on top of the service provided by the network layer.



Another issue is transmitting data through a noisy channel. There is a chance no packets will be lost, but a a bit may be modified during the transmission (flipped). The stages of dealing with this are as follows;

## • error detection

receiver must know when a received packet is corrupted

Some strategies for detecting errors are as follows;

- sending redundant information
  - sending information twice, report an error if two different messages received inefficient
- error-detection codes

parity bit, adding a single bit at the end that is the XOR of all other bits in the message, if the recomputed XOR (by receiver) is different, then an error occurred

• receiver feedback receiver must be able to alert sender that a corrupted packet was received

ACKs and NACKs are also protected with an error-detection code, with corrupted ACKs being treated as NACKs. This may possibly generate duplicate segments, however sequence numbers allow the receiver to ignore these data segments.

• retransmission

the sender must retransmit corrupted packets

Note that in the diagram below, [data]\* indicates a packet containing data and an error-detection code, and A represents the acknowledgement state.



This is a synchronous (or stop-and-wait) for each segment, as the sender must receive a positive acknowledgement before it can take more data from the application layer. However, this can have issues when the ACK/NACK packets have issues. A way around this is for the sender to add a sequence number to each packet, thus allowing the receiver to determine whether a packet is a retransmission. If the sender does not hear an acknowledgement, due to some failure, it assumes a NACK, and retransmits. However, if the receiver did actually send an acknowledgement, it would ignore the packet, since it knows it is a retransmission. It then resends the ACK, and doesn't process the retransmitted.

Since this is a stop-and-wait protocol for each segment, only one bit is needed for the sequence number - as all we need to do is distinguish between the next segment and the retransmission of the current segment.

However, now that we have sequence numbers, we don't need both ACK and NACK, since we can convey the same semantics by sending an ACK for the last good packet it received.





# **Acknowledgement Generation**

The following are cases of segment arrival, and how the protocol handles them;

• arrival of in-order segment with expected sequence number (all data up to expected sequence number already acknowledged)

delayed ACK, wait up to  $500 \mathrm{ms}$  for another in-order segment, if it doesn't arrive, send ACK for just this segment

• arrival of in-order segment with expected sequence number (one other in-order segment awaiting ACK, from above case)

immediately send cumulative ACK for both segments

- arrival of out of order segment with higher-than-expected sequence number (gap detected) immediately send duplicate ACK the sender will know to fill in the gap, as it would've already seen this acknowledgement
- arrival of segment that fills a gap in the received data immediately send ACK if segment starts at lower end of gap

Additionally, it's important to note that lost packets can easily be treated as corrupted packets. Since I don't really want to draw the FSM again, add a  $start\_timer()$  after every  $u\_send(...)$ , and an additional transition loop to  $A_0$  and  $A_1$ , which sends the same data, but the input is timeout.

There's also a small section after this on the alternating bit protocol, which isn't used in practice.

# 30th January 2020

# Week 4, Lecture 3

#### Congestion Detection

If the queue of one or more routers between the sender and receiver overflow, we call it **congestion** - this has the visible effect of segments being dropped. The server can assume the network experiences congestion when it detects a segment loss; either on a timeout, hence no ACK, or multiple acknowledgements, which is equivalent to NACK.

TCP we've described so far is referred to as TCP Reno. Another popular implementation is TCP Vegas, which aims to detect congestion before losses occur. It does this by predicting imminent packet loss via observing the RTT - the longer it is, the greater the congestion in the routers. However, flows

with small RTTs are advantaged, compared to the ones with large RTTs, as their window can grow faster. TCP CUBIC circumvents this by making the window increase as a function of time rather than RTT.

## Congestion Window and Congestion Control

The congestion window, W, is maintained by the sender, and limits the amount of bytes that the sender pushes into the network before it blocks to wait for acknowledgements.

LastByteSent - LastByteAcked  $\leq W = \min(\text{CongestionWindow}, \text{ReceiverWindow})$ 

This gives a resulting maximum output of roughly

$$\lambda = \frac{W}{\text{RTT}}$$

The phases are as follows;

#### • slow start

The initial value of W is the maximum segment size (MSS), which is quite low for modern (high-speed) networks. To result in a good throughput, TCP increases the sending rate exponentially for its first phase. It increases W by 1 MSS on every (positive) segment acknowledgement (doubles each time - the first ACK increases it by 1 MSS, the second ACK will be after sending 2 segments, hence it increases by a further s2 MSS, and so on), until it reaches some slow start threshold (ssthresh), or until congestion occurs. If W is greater than (ssthresh), then use congestion avoidance (if they are equal, either could be used).

## • congestion avoidance

TCP then increases W linearly in this phase.

$$W = W + \underbrace{\mathrm{MSS} \cdot \frac{\mathrm{MSS}}{W}}_{\text{increment}}$$

This happens until congestion is detected.

#### • Additive-Increase / Multiplicative-Decrease (AIMD)

- at every good acknowledgement, increase W in accordance with congestion avoidance  $(\frac{\text{MSS}^2}{W})$
- at every packet loss event, TCP halves the congestion window

There are two possibilities for packet loss. TCP provides reliable data transfer by using a timer to detect lost segments. If there is a timeout, without an ACK, it means that there is likely a lost packet, hence a retransmission is required. This timeout interval, T, must be larger than the RTT to avoid unnecessary retransmissions, however it shouldn't be too far from RTT, as we want to detect and retransmit lost segments as quickly as possible. TCP sets its timeouts as follows, where (1) is the estimated RTT, and (2) is the variability estimate;

$$T = \underbrace{\overline{\text{RTT}}}_{(1)} + 4 \cdot \underbrace{\overline{\text{DevRTT}}}_{(2)}$$

The timeout is controlled by continuously estimating the current RTT.

The agreement is that 3 duplicate ACKs (hence 4 identical ACKs overall), are interpreted as a NACK in **fast retransmit**. While both timeouts and NACKs signal a loss, they say different things about the status of the network, hence TCP should react differently. A timeout indicates congestion, whereas the duplicate ACKs suggests the network is able to still able to deliver segments along that path.

In the formulae below, assume the current window size is  $W = \overline{W}$ ;

\* timeout

In the event of a timeout, set W = MSS, and run slow start until W reaches  $\frac{\overline{W}}{2}$  (which is the new ssthresh), and then proceed with congestion avoidance.

\* NACK

Similarly set sethersh to  $\frac{\overline{W}}{2}$ , but set  $W = \frac{\overline{W}}{2}$ . We then continue to run congestion avoidance, which increases W linearly - **fast recovery**.

## Selective Repeat

The sender only transmits packets it suspects were lost or corrupted. However, if we were to use a TCP flavour that uses this, we'd need powerful routers in the path, as it requires storage and processing.

- sender maintains a vector of acknowledgement flags
- receiver maintains a vector of acknowledged flags maintains a buffer of out-of-order packets
- sender maintains a timer for each pending packet
- sender resends a packet when its timer experiences
- sender slides the window when the lowest pending sequence number is acknowledged



#### Flow Control vs Congestion Control

The former aims to not overflow the receiver, whereas the latter aims not to overflow the network. An example of flow control is as follows;



The receiver sends the maximum number of bytes that may be sent (ReceiverWindow) along with the acknowledgement - a size of 0 is legal, and it means no more messages can be sent, except a 1-byte segment to ping receivers.

#### Wireless TCP

TCP assumes that IP is running across wires. Therefore, when packets are lost, it assumes that this is due to congestion and slows down, whereas in wireless environments, packets are usually lost to channel reliability issues (where TCP should actually try harder).

One solution it to split TCP connections to distinguish between wired and wireless IP. Another solution would be to allow the base station to do some retransmission, without informing the source (if it still fails, the source is then informed).

## Network Usage

We can quantify network usage with the utilisation factor;

how much we actually used the network how much we could have used it

For example, if we were to rent a 24Mbps line, and download at 2MBps, we are at around 67% utilisation (note the conversion from bits to bytes). This may be due to congestion control and / or flow control, as it may not be possible for all nodes in the route to support the amount of traffic you wish to send.

If we have all the data, we can use the following formula for utilisation;

$$U = \frac{\frac{L}{R}}{RTT + \frac{L}{R}}$$

For example, if we have a RTT of 30ms, a channel with transmission rate R=1Gbps, and a packet size L=1000bits, we have a utilisation of  $U\approx 0.027\%$ .

# 4th February 2020

Week 5, Lecture 1

H/P/V/A/C

#### • hackers

Originally meant highly competent computer engineers who explore different ways of using / combining things. Can be divided into the following;

- white hat a researcher who informs the company of problems before they go public
- grey hat an analyst who does not inform anyone unless they get paid
- black hat a malicious individual who abuses the findings to cause harm

#### phreakers

Phone hackers - not as prevalent anymore, due to the telephone network being almost fully digital. Playing the right frequencies allowed for access to administrative interface for a phone network.

## • virii (creators)

Create viruses, for curiosity or money. Popular viruses include ransomware, spyware, and Trojans (remotely controlled botnet, and profit from renting). A rootkit is injected into the root account, running as the superuser, thus having more control.

• anarchists "hacktivists"

#### crackers

Originally meant wannabe hackers (script kiddies), who use the tools of others to infiltrate systems.

#### Methods and Tools

Some commonly used methods are as follows;

• credential reuse / stuffing leaked email:password combinations tested on other services

• network monitor / packet sniffing reading messages not intended for your NIC

• code / SQL injection running your own code in someone else's system

• session / cookie hijacking use another session without credentials

• wardriving searching and using unsecured WiFi spots

• dumpster diving / trashing physically checking trash for information

• clickjacking forcing users to click on hidden links

• bat and switch legitimate-looking ads leading to malicious destinations

• spoofing IP (layer 3), MAC (layer 2), DNS poisoning

Some commonly used tools are as follows;

• rootkit runs as an administrator (can reinstall itself)

• keyloggers allows attackers to record all keypresses

• trojans allows attackers to remote control an entire system (similar to *TeamViewer* or VNC)

• TAILS

The Amnesic Incognito Live System - forgets on reboot

• Kali Linux large collection of security and pentesting tools

• Metasploit identifies systems and their vulnerabilities (similar to nmap)

#### Laws and Standards

Basically just a long list of laws (and their years), and organisations.

• Computer Misuse Act (1990) most intrusions fall under this

• Copyright, Designs, and Patents Act (1988) piracy

• Criminal Justice Act (2003)

• Data Protection Act (2018)

• Defamation Act (2013) cyber-bullying

• Disability Discrimination Act (2005)

• Freedom of Information Act (2000) can be used against companies

• Obscene Publications Act (1964)

• Protection of Children Act (1978)

1999 version still being amended

• Regulation of Investigatory Powers Act (2000)

Note that an intruder is trialled in both the country they reside in, as well as the laws of the country where the involved hosts are physically located.

• IANA (Internet Assigned Numbers Authority) sets these standards, and assigns port numbers

• ICANN (Internet Corporation for Assigned Numbers and Names) names for corporations

• IETF (Internet Engineering Task Force) attempt to set standards straight

• ISOC (Internet Society) push governments to update laws

• EFF (Electronic Frontier Foundation) push rights (free speech and equality) online

• W3C (World Wide Web Consortium)

• ISO (International Organisation for Standardisation)

## Examples

Some examples include Heartbleed, KRACK, and some other legal / ethical grey areas. GDPR forces companies to inform their users of hacks within 72 hours.

## **Network Security Issues**

We want control access over a channel between a user and a resource. We need a way to ensure only specific users can access a resource (access control), as well as a way to authenticate the user (and resource). Additionally, confidentiality also has to be ensured to limit access to information owned by users, as well as integrity (actions of a user should not be able to affect the overall integrity of a resource). Users also cannot deny communication took place (non-repudiation) - blockchain is an example. To achieve this we need;

- access control
- security policy
- secure channel (users and data are authenticated, information exchanged is confidential)
- monitoring / logging / auditing

#### Access Control



Assuming a secure channel, the guard controls which principals can access the resource, where principals are allowed to be located (access within networks), and what requests (actions) principals are allowed to make.

This is done via the use of a **firewall**, which controls access to the network by providing a security gateway between the internal and external networks.

• application-level gateway runs on the host, and only protects that host (such as iptables)

This is in a logical connection, allowing it to monitor traffic. This means that it can block / filter / report based on application level message content (as well as scan for data leaks, viruses, etc). Data can also be rewritten, therefore we do not want this to be compromised. If the data is encrypted, it may ask for the ability to read it, thus decrypting it, and then re-encrypting it for the client.

proxy server

runs on network, and can protect entire LAN

Proxies can filter incoming / outgoing traffic in different modes;

- **normal** client is aware (and needs to be set up)

- transparent client is unaware (local router takes care of everything)

- reverse runs on receiving side, impersonates servers (CDN load balancing)

SOCKS proxies can be used for any protocol, whereas HTTP is for web.

- circuit-level gateway takes over host's communication as a non-caching proxy (such as Tor)
- stateless packet filtering checks source / destination IP addresses and ports
- stateful packet filtering checks contents of current and previous packets

It can also perform user authentication. Connections can be dropped based on destination, incorrect packets, time, or volume. This is done with inspection to the layer 4 ports, layer 3 IP addresses, and the layer 2 MAC addresses.

The **Bastion** host is the host that all public connections arrive to. It should expect to be attacked, and perform auditing / logging on a secure OS.

The is set by using **access control lists**, which contain packet filtering rules. The firewall scans through the list of rules, until it finds one that matches, and performs the actions. The rules contain a number to uniquely identify them, a direction (incoming or outgoing), an action (block or allow), as well as two IP and port pairs for the inside and outside. Usually, the last rule is to block everything else.

## Other Systems

- IDS (Intrusion Detection Systems) detects intrusions (such as identifying a DDoS attack) doesn't stop the intrusion, only informs the system
- IPS (Intrusion Prevention System) actively prevents intrusions (such as blocking SYN floods) either includes an IDS, or works with an IDS
- NGFW (Next Generation Firewall) a (stateful) firewall with an IPS/IDS system
- UTM (Unified Thread Management) similar to NGFW but more capabilities (e.g. antivirus)

## DMZ (Demilitarised Zone)

This is the part of the network accessible to external hosts. All sensitive servers should lie behind the DMZ. The router uses NAT (Network Address Translation) to get external messages to the correct internal host - if we want to expose an internal host without putting it in the DMZ, port forwarding can be used.

Port forwarding lets the router know that packets for certain ports should be directly forwarded to an internal host's port. For example, if we tell the router to forward any packet at port 12345, it should be forwarded to the NAT-based LAN IP of an internal host at port 80, accessing http://publicip:12345/is actually accessing http://internalhost:80/ indirectly, since the internal host does not have a public IP.

#### Getting Around Firewalls

Methods of getting around a firewall include ssh tunnelling, which uses another server to act as a proxy between services; VNC can also be used in a similar way. Another method is to spoof the software MAC address - if a firewall was to allow a certain address through. Similarly spoofing an IP could be attempted, but a stateful firewall will most likely catch this.

## Security Policy and Logging

Each company or organisation needs to define its Network Security Policy, which includes (but is not limited to);

- intranet / internet access rights
- allowed use of software (whether the user should be allowed to install software) / hardware (whether the user should be allowed to use their own hardware)
- risk assessments
- training

Systems are likely already keeping logs, and these can be used to identify system or network issues, as well as being used evidence of criminal activities (if the log files haven't been deleted). Anything useful identified by an audit should be permanently stored.

# Cryptography

Cryptography is the process of writing something in code (encode or encrypt), with a specific algorithm, whilst retaining the ability to retrieve it afterwards (decode or decrypt). The latter is only possible in the case of encryption (see **hashing** later on). We assume that the physical channel is open to attack from the enemy, who can read and alter any bit pattern.

# Encryption



Only certain users should have K (the encryption key), and  $K^{-1}$  (the decryption key). If someone were to intercept  $M_c$ , without  $K^{-1}$ , the attacker can only find M by enumerating all possible  $K^{-1}$  via a brute-force attack. Another property is that it should be difficult to obtain the values of K and  $K^{-1}$  with just M and  $M_c$ .

- secret key (symmetric) encryption has  $K = K^{-1}$ , hence the same key is used to encrypt and decrypt the file, thus the key must be very carefully distributed otherwise all files can be decrypted
- public key (asymmetric / public-private key pair) encryption has  $K \neq K^{-1}$

 $K_t$  is the private-key of host  $H_t$ , and is only stored / used by that host. On the other hand,  $K_t^{-1}$  is the public-key of the same host, and is freely distributed. Therefore anything encrypted with  $K_t^{-1}$  can only be decrypted by the host  $H_t$ . This also means anyone can decrypt something encrypted by  $H_t$  with  $K_t$  - if it is successful, it authenticates the message as coming from  $H_t$ .

In this example, let  $H_t$  have its own private key  $K_t$ , as well as  $H_r$ 's public key  $K_r^{-1}$  (and vice versa for  $H_r$ ).  $H_t$  first signs the message with its own private key,  $E(K_t, M)$ . It then encrypts the message with the destination's public key,  $E(K_r^{-1}, E(K_t, M))$  - ensuring only  $H_r$  can read the message. Now, **only**  $H_r$  can obtain the signed message as follows;

$$D(K_r, E(K_r^{-1}, E(K_t, M))) = E(K_t, M)$$

Additionally, we can validate that the sender was actually  $H_t$  with  $H_t$ 's public key  $K_t^{-1}$ ;

$$D(K_t^{-1}, E(K_t, M)) = M$$

We can compare the two approaches as follows;

public key (asymmetric)

secret key (symmetric)

- 1. owner of private-key does not need to disclose its value to communicate
- 2. more secure
- 3. slow encryption / decryption
- 4. example: RSA

- 1. owner of private-key needs to disclose its value in order to communicate
- 2. less secure
- 3. faster encryption / decryption
- 4. example: AES

## Diffie-Hellman Key Exchange

An approach for this, to establish a new key on the spot, is the *Diffie-Hellman key exchange*, which can then be used for encryption by symmetric algorithms. This can potentially be defeated by powerful systems, but is still used by TLS (formally SSL). The (simplified) algorithm is as follows;

- 1. Bob and Alice agree on a public value g (generator), and a large prime number p
- 2. Bob chooses a secret value b, and Alice chooses a secret value a (these are not shared) both values must be lower than p
- 3. The secret values are used to calculate their public values (which are then exchanged);
  - bob:  $x = g^b \mod p$ • alice:  $y = g^a \mod p$
- 4. They use each other's public value to calculate the shared secret key which can be used to communicate securely;
  - bob:  $y^b \mod p = (g^a \mod p)^b \mod p \equiv g^{ab} \mod p$ • alice:  $x^a \mod p = (g^b \mod p)^a \mod p \equiv g^{ab} \mod p$
- 5. Eve, the eavesdropper, cannot guess / derive the shared secret key, even if they have access to g, p, x, y since they don't know either of the secret values.

An example of this is as follows;

$$a=4$$
 $b=5$ 
 $g=6$ 
 $p=p$ 
(Bob)  $x=(g^b \mod p)$ 
 $=6^5 \mod 97$ 
 $=7776 \mod 97$ 
 $=16$ 
(Alice)  $y=(g^a \mod p)$ 
 $=6^4 \mod 97$ 
 $=1296 \mod 97$ 
 $=35$ 
(Bob)  $y^b \mod p=35^5 \mod 97$ 
 $=52521875 \mod 97$ 
 $=61$ 
(Alice)  $x^a \mod p=16^4 \mod 97$ 
 $=65536 \mod 97$ 
 $=61$ 

## Key Server (Kerberos)

Another approach is to have a trusted key server, which the host already knows how to communicate with safely.

Kerberos (Needham and Schroeder) is a user authentication system which knows your password. It also knows the password of the user / resource you want to communicate with. It has a KDC (key distribution centre) that can provide tickets, allowing you to communicate with the desired user / resource, which expire after a predefined amount of time.

#### Hashing

When a message is hashed, the original message cannot be retrieved - it one way. A hash is a fixed size alphanumeric string, calculated based on a specific input - the hash function should always produce the same hash value with the same input. Since it should not be possible to derive the input from the hash value, this can be used for safely storing passwords.

# 11th February 2020

# Week 6, Lecture 1

The scenario is as follows; an IoT research and design institute will receive government funds for a new device used by the police.

- web servers running Apache 2.4.27 with OpenSSL 1.0.1 on Red Hat Enterprise Linux 7.3
- many desktop computers available, running Windows Vista
   they are slow, so many staff members bring their own MacBooks to work
- reception desk on ground floor, with server room at back of floor secured by RFID card reader
- research team on first floor
- design team on second floor
- HR team shares third floor with CEO and CTO
- lower ground level used as storage for technical equipment and parking space
- all desktops have wired Ethernet

CEO and CTO have company laptops, wireless AP added on top floor for LAN and Internet connection

- employees are planned to be provided with iPads, so they can use iCloud to work from anywhere
- installing more access points throughout building

Some identified security vulnerabilities are as follows;

- server room easily accessible (move to basement)
- use biometric scanner instead of RFID
- LAN and Internet connected means local network could be exposed
- wireless network can be accessed without being in the building (packet sniffing)
- sensitive data should not be stored on an external service (iCloud)
- OpenSSL 1.0.1 is vulnerable to Heartbleed
- Apache 2.4.27 (Optionsbleed) and RHEL 7.3 (Local Privilege Escalation Bug) are all broken (CVE can be easily searched)
- Windows Vista
- no building security overnight?
- employees should not be using personal devices
- third-party repairs for MacBooks may expose data
- visitor parking area also has technology
- insecure connections if working from home (VPN should be used)
- employees could be blackmailed or phished (social engineering)
- "evil twin" for wireless AP
- flood risk for ground floor server room

# 13th February 2020

# Week 6, Lecture 2

This lecture is the Wireshark practical (enable Promiscuous Mode and Monitor Mode). Promiscuous mode works for both wired and wireless connections, and tells the NIC to not drop any packets (for a wireless network; it only focuses on the connected network). Monitor mode only works on wireless networks, which tells the NIC to start listening in on all networks - any WiFi network with a password will have encrypted data. Most NICs do not support this, or will need different drivers.

With Wireshark, we can add display filters to the captured packets to select the ones we are interested in, such as;

- http.request.method == GET
- http contains "password"
- ip.src == 192.168.9.220

# 13th February 2020

# Week 6, Lecture 3

This continues on from the last lecture, with the Wireshark practical. Change the root password for a Raspberry Pi - and ensure new users haven't been created (or keys added).

"skrrrrr" - root

# 18th February 2020

# Week 7, Lecture 1

## Introduction to the Network Layer

This is also referred to as the Internet Layer, and contains the Internet Protocol (IP). At this layer, data travel in IP datagrams (or packets), and data are fragmented into packets, with a layer 3 header added in front of each.

A router (layer 3) typically has a line in port, which is connected to the ISP via Ethernet, a phone cable, or co-axial. There may also additional Ethernet ports to connect devices multiple devices to the local network, via the use of a switch (layer 2) within the router. A router is a fundamental component of the network layer (they are the nodes in the graph), and have a finite set of input / output connections. It has interfaces (or physical ports - not the same as layer 4 ports), which are individual network interface controllers, and therefore a router can have multiple IP addresses.

# Routing

The network layer provides facilities to get data from a source to a destination, and may require making many **hops** at at intermediate routers along the way (frames in the data link layer are moved only within the same network) - this is routing. To do this, it must know the topology of the network to choose appropriate paths. Load balancing may be used to prevent congestion. This layer also has to deal with network heterogeneity, as there may be very old routers still in the network.

#### **Datagram Networks and Forwarding**

IP is connectionless (each message is routed through the system independent of others, there is also no connection setup or tear-down phase) and packet-switched (each datagram is forwarded from one router to the next based on forwarding decisions). This is a best-effort service, with no guarantees on delivery, maximum latency, bandwidth, in-order delivery nor congestion indication.

There are potentially multiple (possibly asymmetric paths) for the same source / destination. In forwarding, we have the destination of the datagram as the input, and an output port as the output. A simple design for this is a forwarding table.

Routers must cooperate to find the best routes between all pairs of nodes, and build a sink tree (or approximation) for each node. The sink tree of each node does not contain loops, and only contains the optimal routes towards that specific host.

Some strategies for routing are as follows;

## • shortest path routing

Shortest Path Routing (SPR) uses Dijkstra's Algorithm (see CO150), where the labels on arcs represent cost. At each step, we select newly reachable node with the lowest cost, and then add that edge to the tree built so far.

## • flood routing

In flood routing, an incoming packet is forwarded across every outgoing link (except the original source). We have to avoid too many packets in the network;

- hop counter discard a packet after it was forwarded across N routers
- forward only once avoid cycles, requires storing sequence numbers per source address
- flood selectively only forward in a direction that makes sense

Flooding always chooses the shortest path because all paths are explored in parallel. This only makes sense to do when **robustness** is needed, such as in the discovery of unknown destinations.

#### • distance vector routing


The previous protocols are static, meaning they do not take the current network load into account. DVR, or *Bellman-Ford* is a dynamic protocol that does the following;

- 1. consider costs that direct neighbours are advertising to get packet to destination
- 2. select neighbour who's advertised cost, added with own cost to get to that neighbour, is lowest
- 3. advertise the new cost to neighbours


The main idea is expressed by the Bellman-Ford equation;

$$D'_{u}[v] = \min_{x \in \text{neighbours}(u)} (c(u, x) + D_{x}[v])$$

We want to find the cost of the least cost path from u to v. This is the minimum sum of the cost between u and x, and the least cost path between x and v, where x is each direct neighbour of u. At the start, if we don't know anything, we can start with flood routing to discover neighbours.



An example of this is as follows;




(a)	a	b	c	d
$D_a$	0	2	$\infty$	4
$D_b$	$\infty$	$\infty$	$\infty$	$\infty$
$D_d$	$\infty$	$\infty$	$\infty$	$\infty$
(b)	a	b	c	d
$D_b$	2	0	1	$\infty$
$D_a$	$\infty$	$\infty$	$\infty$	$\infty$
$D_c$	$\infty$	$\infty$	$\infty$	$\infty$
(c)	a	b	c	d
$D_c$	$\infty$	1	0	9
$D_b$	$\infty$	$\infty$	$\infty$	$\infty$
$D_d$	$\infty$	$\infty$	$\infty$	$\infty$
(d)	a	b	c	d
$D_d$	4	$\infty$	9	0
$D_a$	$\infty$	$\infty$	$\infty$	$\infty$
$D_c$	$\infty$	$\infty$	$\infty$	$\infty$

(a)	a	b	c	d
$D_a$	0	2	3	4
$D_b$	2	0	1	$\infty$
$D_d$	4	$\infty$	9	0
(b)	a	b	c	d
$D_b$	2	0	1	6
$D_a$	0	2	$\infty$	4
$D_c$	$\infty$	1	0	9
(c)	a	b	c	d
$D_c$	3	1	0	9
$D_b$	2	0	1	$\infty$
$D_d$	4	$\infty$	9	0
(d)	a	b	c	d
$D_d$	4	6	9	0
$D_a$	0	2	$\infty$	4
$D_c$	$\infty$	1	0	9

(a)	a	b	c	d
$D_a$	0	2	3	4
$D_b$	2	0	1	6
$D_d$	4	9	9	0
(b)	a	b	c	d
$D_b$	2	0	1	6
$D_a$	0	2	3	4
$D_c$	3	1	0	9
(c)	a	b	c	d
$(c)$ $D_c$	$\frac{a}{3}$	b 1	0	$\frac{d}{7}$
_ ` ′				
$D_c$	3	1	0	7
$D_c$ $D_b$	3 2	1 0	0	7 6
$ \begin{array}{c} D_c \\ D_b \\ D_d \end{array} $	3 2 4	1 0 6	0 1 9	7 6 0
$ \begin{array}{c} D_c \\ D_b \\ D_d \\ (d) \end{array} $	3 2 4 a	1 0 6 b	0 1 9	7 6 0 d
$ \begin{array}{c} D_c \\ D_b \\ D_d \\ (d) \\ D_d \end{array} $	3 2 4 a 4	1 0 6 <i>b</i>	0 1 9 c	7 6 0 d

However, there is a problem with DVR - good news propagates quickly, but bad news propagates slowly. Consider the following graph, and assume all costs are 1 (hence we can just look at the number of hops);



Consider the table below, where we have the distance from a;

b	c	d	e	comment
$\infty$	$\infty$	$\infty$	$\infty$	initial state
а	com	es or	nline	after being down
1	$\infty$	$\infty$	$\infty$	after 1 exchange
1	2	$\infty$	$\infty$	after 2 exchanges
1	2	3	$\infty$	after 3 exchanges
1	2	3	4	after 4 exchanges
	C	$a  \operatorname{sud}$	ldenl	y goes down
3	2	3	4	after 5 exchanges
3	4	3	4	after 6 exchanges
5	4	5	4	after 7 exchanges
5	6	5	6	after 8 exchanges
7	6	7	6	after 9 exchanges
7	8	7	8	after 10 exchanges
				:
$\infty$	$\infty$	$\infty$	$\infty$	

When a suddenly goes down, they keep increasing their route up to infinity (count-to-infinity problem) We can set infinity to be one more than the longest acceptable path.

#### • link state routing

This was published in 1979, aiming to replace DVR. The goal is to broadcast information about the network topology to all routers, and each router calculates the sink tree to other routers. Each router does the following;

- 1. discover direct neighbours and gets their network addresses
  - routers know their local network interfaces, and therefore sends a HELLO packet through each interface the routers on the other end responds with its address
- 2. calculates cost for sending packet to each neighbour
  - an ECHO packet is sent through each interface and the RTT is measured (this gives a reasonable estimate of actual delay)
- 3. constructs LSA (link state advertisement) packet with all information done with flooding to send LSA to all other routers, once a router has LSAs from every
  - router, it has complete knowledge of the network
- 4. sends that packet to all routers (as well as collecting that packet from all routers) not limited to just neighbours
- 5. runs Dijkstra's algorithm locally to find shortest paths

This means that each router stores information about its neighbours, the entire network, and the generated routing table.

Both DVR and LSR are used, in order to support routers both old (DVR) and new (LSR) routers.

	distance vector routing	link state routing
network knowledge	local	global
computation	global	local
synchronisation	gradual	"instant" (after SPR calculation)

These protocols are used internally, and therefore a specific one can be chosen for a local network.

## **Hierarchical Routing**

All of the previously discussed routing algorithms require each router to know about the others - this cannot scale, as it becomes too demanding in terms of memory and processing power. A solution to this is to introduce regions, and have separate algorithms for intra-region (within the region) and inter-region (between regions) routing. Two or three levels is generally sufficient. We no longer take an optimal route - we just know where to forward packets.

#### **Broadcast Routing**

If we want to send a message to (almost) every host on a network, we can take the following approaches;

• message each host individually

inefficient

• flood routing

accepted, if we can limit the flood

- multi-destination routing via a list sent with the packet
  - router checks destination and splits list when forwarding to different interfaces the message must contain all destinations.
- build sink tree at source and use that for multicast route
  - must be spanning tree, and routers need to agree on trees

We can construct this spanning tree with reverse-path forwarding (RPF) broadcast. Every router forwards / broadcasts a packet to every adjacent router, except where it came from. A router only accepts a broadcast packet p originating at A if p arrives on a link that is on a direct (unicast) path between themselves and A.

#### **Multicast Routing**

We want to send a message to only a subset of nodes, and we need to know when a host enters or leaves a multicast group. The solution to this is to construct a spanning tree at each router, and use a group ID to prune paths that do not contain members of group.

The main issue with this is scalability - as we need to maintain a spanning tree per source. Another approach is to use core-based trees, and have a single spanning tree per group, with the root (core) near the middle of the group. For a multicast message to be sent, the host sends it to the core which then performs multicast along the tree.

# 20th February 2020

## Internetworking

Internetworking is the process of linking different types of networks together. All of these different networks have different protocol stacks, and need to somehow communicate with each other. Instead of forcing all networks to run the same stack, we can construct gateways (routers) that interconnect different types of networks. Different types of networks include, but are not limited to;

• PAN (Personal Area Network) such as phone connected to PC via Bluetooth (1 user)

• LAN (Local Area Network) such as laptop connected to desktop via WiFi AP

• MAN (Metropolitan Area Network) such as displaying bus times without internet (city)

• WAN (Wide Area Network) such as the Internet

Additionally, we have the following terminology for devices;

• repeaters / hubs physical layer boosts signals by repeating everything received at one port to every other port

• switches and bridges data link layer creates interconnections by storing a table, and deciding where to forward based on MAC addresses

• multi-protocol routers / gateways network layer forwards (and possibly splits up) packets - makes decisions based on IP addresses (note that Transport Layer Gateways and Application Layer Gateways also exist)

#### The Internet

The internet is a collection of autonomous systems (ASes) connected by backbones.

An application offers a data stream to the transport layer, using either connection-oriented or connection-less services. The data stream on the transport layer is converted into an IP datagram for the network layer. These are routed through the internet, and routers pass datagrams to the underlying data link layer (LANs and WANs). After this, data is in the physical layer, transmitted through cables.

At the Internet Network Layer, the following needs to be provided;

• IP (Internet Protocol)
this includes datagram format, fragmentation, addressing, and packet handling

• ICMP (Internet Control Message Protocol)
this provides error handling, and signalling (such as ping)

• DHCP (Dynamic Host Configuration Protocol)
this provides address configuration

## **Fragmentation**

Similar to how TCP includes the sequence number in the header, the layer 3 (IP) header includes the fragment offset from the start of the IP datagram. Fragmentation occurs when the router encounters the case where the size of the input datagram exceeds the MTU (maximum transmission unit) of the output link.

Only the destination reassembles fragmented datagrams, as this pushes complexity out of network. Along the path, the datagram may have to be fragmented further. The fragmentation scheme must ensure the destination host can figure out if and when all fragments were received, as well as recognising two fragments of the same datagram.

Assume an initial (non-fragmented) datagram of size X. The sender assigns a 16-bit identifier to the datagram, and sets the fragment offset (offset in units of 8 bytes) to 0, which indicates this packet contains data starting at position 0 of the original datagram. Note that the fragment offset field is 13 bits, hence there can be  $2^{13} = 8192$  (0 to 8191) units of 8B in one fragment. Note that all fragments should be multiples of 8B, except the last one.

However, the total length field is 16 bits, therefore it can only support a maximum size of 65535B. The IP header itself is 20B, meaning that there are 65515B available, which means that there are 8189 possible units of 8B, and an additional unit of 3B. If the more fragments flag is set to 1, more fragments are expected to follow.

An example of this is as follows - assuming an MTU of 512B, and a total packet size of 1020B;

identifier	fragment offset	more fragments	length	header length	total length
789	0	1	488	20	508
789	61	1	488	20	508
789	122	0	24	20	44

#### IPv4 Addressing

In IPv4, the addresses are in the format XXX.XXX.XXX, where XXX is from 0 to 255 - they are 32-bit, and thus there are 4 billion possible IP addresses. Each address is associated with an interface, not host, and therefore a host with multiple interfaces may have more than one IP.

The key idea is to assign addresses with the same prefix to interfaces belonging to the same organisation. Originally, this was done with classful addressing, however this is no longer used as it became apparent that it would quickly run out, due to companies buying more addresses than needed. Note in the table below, the leftmost bit is bit 0.

class	prefix	network bits	max networks	host bits	max hosts	range of host addresses
Α	0	1-7	126	8-31	16,777,214	1.0.0.0 to
А	U	1-1	120	0-31	10,777,214	127.255.255.255.255
В	10	2-15	16,382	16-31 65,536		128.0.0.0 to
Б	10	2-15	10,362	16-31 65,53	05,550	191.255.255.255.255
$\overline{C}$	110	3-23	2,097,150	24-31	254	192.0.0.0 to
C	110	3-23	2,097,130	7 24-31 254	233.255.255.255.255	
	1110		multipagt ad	ldrogg		224.0.0.0 to
D	D 1110 multicast address			239.255.255.255.255		
	E 4444					240.0.0.0 to
	1111		reserved for future use			255.255.255.255.255

Nowadays, IP addresses are managed by ICANN to avoid conflicts. It delegates parts of address space to regional authorities, which give out IP addresses to ISPs and companies.

#### **Subnet Masking**

Hosts on the same network must share the same network address. The solution to this was to use a single network address for the entire organisation, and divide internally into subnet addresses and host IDs. This divides the address into the class, network, subnet, and host, thus introducing a three-level routing hierarchy;

- 1. external routers only consider the network address, and forward the packet to one of the routers of the organisation
- 2. subnet routers apply the subnet mask, and check if the destination is on their subnet, or if they should forward it to another subnet router
- 3. after host is found, router knows which interface to use to forward packet

All interfaces in the same subnet share the same address prefix. If we were to get rid of the classes entirely; we will have a notation called classless inter-domain routing (CIDR), which has the format address/prefix-length. For example, 123.1.1.0/24 means that all addresses share the same leftmost 24 bits with 123.1.1.0. This scheme is not limited to entire bytes.

For example; if we were to be asked for the range of addresses in 128.138.207.160/27;

_	subnet		
10000000	10001010	11001111	101 00000
10000000	10001010	11001111	10100000
10000000	10001010	11001111	10100001
10000000	10001010	11001111	10100010
10000000	10001010	11001111	10100011
:			
10000000	10001010	11001111	10111110
10000000	10001010	11001111	10111111

We would have a range of 128.138.207.160 - 128.138.207.191.

The mask notation is address/mask, and a prefix of length p corresponds to the following mask;

$$M = \overbrace{11 \cdots 1}^{p \text{ times}} \underbrace{00 \cdots 0}_{32-p \text{ times}}$$

Therefore we have the following conversions (example);

```
128.207.160/27 = 128.207.160/255.255.255.224

127.0.0.1/8 = 127.0.0.1/255.0.0.0

92.168.0.3/24 = 92.168.0.3/255.255.255.0

195.176.181.11/32 = 195.176.181.11/255.255.255.255
```

When we (bitwise) AND the address with the mask, we obtain the network address.

#### **Longest-Prefix Matching**

Routers attempt to match the maximum possible prefix in order to select the correct network. They (bitwise) AND the IP address with its subnet mask to obtain the network address. If they know where this is (based on the router's forwarding table), it will forward it out of the correct port. Otherwise, it depends on the algorithm (or a default port where packets for unknown networks go to).

#### ICMP and NAT

ICMP encapsulates control messages in IP packets, and each type is further specified by a code. This may be blocked on some routers, as it can be abused, thus a UDP implementation of ping can be used instead.

Network Address Translation (NAT) partially solves address shortage by assigning each company a single IP. This also allows for home connection to be shared among multiple devices. Within a company each device gets a unique local IP used for routing internal traffic, when a packet exits the local network, address translation takes place. The following ranges are declared as private to be used in local networks;

```
10.0.0.0-10.255.255.255/8 16,777,216 addresses
172.16.0.0-172.31.255.255/12 1,048,576 addresses
192.168.0.0-192.168.255.255/16 65,536 addresses
```

NAT hides the local addresses in the intranet from the public addresses in the internet. Other special addresses include the following;

- 0.0.0.0/0 default route, used for packet forwarding when no other applicable IP matches
- 0.0.0.0/8 this host on the network (not sent)
- 127.0.0.0/8 loopback (this host, again) but can be sent (localhost = 127.0.0.1)
- 169.254.0.0/16 link local (something went wrong trying to acquire an IP address)

The use of NAT allows one IP to be rented, and then many internal IPs can then be allocated.

For example, if a connection is set up from 10.0.0.1 (local address), on port X, the router uses its public source address 138.76.29.7 on port Y, and also registers a mapping  $X \leftrightarrow Y$ . A reply sent to the router on port Y is then sent to 10.0.0.1 on port X.

Similarly, to allow for incoming connections, port forwarding can be done. This is a static mapping on the router, such as telling it to redirect all traffic on port 80 to 10.0.0.2 on port 8080.

While NAT has widespread use, it has a number of problems, and criticism;

- violates architectural IP modal, which states an IP address should **uniquely** identify a single machine worldwide
- changes Internet from connectionless to connection-oriented network (NAT gateway maintains mapping for each connection)
- violates rule of protocol layering by making assumptions about higher layers
- cannot easily support new transport protocols
- P2P protocols may require full connectivity users behind NAT cannot be contacted directly by peers

IPv6 deals with all of this, by having many more addresses.

#### **Dynamic Host Configuration Protocol**

A host needs to determine its own IP address, and this can be done via DHCP (RFC 2131 and 2132);

- 1. each newly-booted machine broadcasts a DHCPDISCOVER packet when it connects
- 2. DHCP server (may be the router) replies with the assigned IP address

may maintain static mappings, or assign different addresses each time the host connects

To prevent a host from keeping an address for ever, periodic refreshing is required (leasing). This is used for a router to receive an IP from the ISP.