Using ld

The GNU linker

ld version 2 January 1994

Steve Chamberlain Cygnus Support

Cygnus Support steve@cygnus.com, doc@cygnus.com Using LD, the GNU linker Edited by Jeffrey Osier (jeffrey@cygnus.com)

Copyright © 1991, 92, 93, 94, 95, 96, 97, 1998 Free Software Foundation, Inc.

Permission is granted to make and distribute verbatim copies of this manual provided the copyright notice and this permission notice are preserved on all copies.

Permission is granted to copy and distribute modified versions of this manual under the conditions for verbatim copying, provided also that the entire resulting derived work is distributed under the terms of a permission notice identical to this one.

Permission is granted to copy and distribute translations of this manual into another language, under the above conditions for modified versions.

Table of Contents

1	Ovei	rview		
2	Invocation 3			
	2.1	Command Line Options		
	2.2	Environment Variables		
3	Com	nmand Language 19		
	3.1	Linker Scripts		
	3.2	Expressions		
		3.2.1 Integers		
		3.2.2 Symbol Names		
		3.2.3 The Location Counter		
		3.2.4 Operators		
		3.2.5 Evaluation		
		3.2.6 Assignment: Defining Symbols		
		3.2.7 Arithmetic Functions		
		3.2.8 Semicolons		
	3.3	Memory Layout		
	3.4	Specifying Output Sections		
		3.4.1 Section Definitions		
		3.4.2 Section Placement		
		3.4.3 Section Data Expressions 30		
		3.4.4 Optional Section Attributes		
		3.4.5 Overlays 34		
	3.5	ELF Program Headers		
	3.6	The Entry Point		
	3.7	Version Script		
	3.8	Option Commands		
4	Mac	hine Dependent Features 45		
	4.1	ld and the H8/300 45		
	4.2	1d and the Intel 960 family		
5	BFD	0		
	5.1	How it works: an outline of BFD		
	_	5.1.1 Information Loss		
		5.1.2 The BFD canonical object-file format		
6	Rep	orting Bugs 51		
	6.1	Have you found a bug?		
	_	How to report bugs 51		

ii	Using LD, the GNU linker
Appendix A MRI	Compatible Script Files 55
Index	57

1 Overview

1d combines a number of object and archive files, relocates their data and ties up symbol references. Usually the last step in compiling a program is to run 1d.

1d accepts Linker Command Language files written in a superset of AT&T's Link Editor Command Language syntax, to provide explicit and total control over the linking process.

This version of 1d uses the general purpose BFD libraries to operate on object files. This allows 1d to read, combine, and write object files in many different formats—for example, COFF or a.out. Different formats may be linked together to produce any available kind of object file. See Chapter 5 [BFD], page 47, for more information.

Aside from its flexibility, the GNU linker is more helpful than other linkers in providing diagnostic information. Many linkers abandon execution immediately upon encountering an error; whenever possible, 1d continues executing, allowing you to identify other errors (or, in some cases, to get an output file in spite of the error).

2 Invocation

The GNU linker 1d is meant to cover a broad range of situations, and to be as compatible as possible with other linkers. As a result, you have many choices to control its behavior.

2.1 Command Line Options

The linker supports a plethora of command-line options, but in actual practice few of them are used in any particular context. For instance, a frequent use of 1d is to link standard Unix object files on a standard, supported Unix system. On such a system, to link a file hello.o:

```
ld -o output /lib/crt0.o hello.o -lc
```

This tells 1d to produce a file called *output* as the result of linking the file /lib/crt0.o with hello.o and the library libc.a, which will come from the standard search directories. (See the discussion of the '-1' option below.)

The command-line options to 1d may be specified in any order, and may be repeated at will. Repeating most options with a different argument will either have no further effect, or override prior occurrences (those further to the left on the command line) of that option. Options which may be meaningfully specified more than once are noted in the descriptions below.

Non-option arguments are objects files which are to be linked together. They may follow, precede, or be mixed in with command-line options, except that an object file argument may not be placed between an option and its argument.

Usually the linker is invoked with at least one object file, but you can specify other forms of binary input files using '-1', '-R', and the script command language. If no binary input files at all are specified, the linker does not produce any output, and issues the message 'No input files'.

If the linker can not recognize the format of an object file, it will assume that it is a linker script. A script specified in this way augments the main linker script used for the link (either the default linker script or the one specified by using '-T'). This feature permits the linker to link against a file which appears to be an object or an archive, but actually merely defines some symbol values, or uses INPUT or GROUP to load other objects. Note that specifying a script in this way should only be used to augment the main linker script; if you want to use some command that logically can only appear once, such as the SECTIONS or MEMORY command, you must replace the default linker script using the '-T' option. See Chapter 3 [Commands], page 19.

For options whose names are a single letter, option arguments must either follow the option letter without intervening whitespace, or be given as separate arguments immediately following the option that requires them.

For options whose names are multiple letters, either one dash or two can precede the option name; for example, '--oformat' and '--oformat' are equivalent. Arguments to multiple-letter options must either be separated from the option name by an equals sign, or be given as separate arguments immediately following the option that requires them. For example, '--oformat srec' and '--oformat=srec' are equivalent. Unique abbreviations of the names of multiple-letter options are accepted.

-akevword

This option is supported for HP/UX compatibility. The *keyword* argument must be one of the strings 'archive', 'shared', or 'default'. '-aarchive' is functionally equivalent to '-Bstatic', and the other two keywords are functionally equivalent to '-Bdynamic'. This option may be used any number of times.

-Aarchitecture

--architecture=architecture

In the current release of ld, this option is useful only for the Intel 960 family of architectures. In that ld configuration, the architecture argument identifies the particular architecture in the 960 family, enabling some safeguards and modifying the archive-library search path. See Section 4.2 [ld and the Intel 960 family], page 45, for details.

Future releases of 1d may support similar functionality for other architecture families.

-b input-format

--format=input-format

1d may be configured to support more than one kind of object file. If your 1d is configured this way, you can use the '-b' option to specify the binary format for input object files that follow this option on the command line. Even when 1d is configured to support alternative object formats, you don't usually need to specify this, as 1d should be configured to expect as a default input format the most usual format on each machine. input-format is a text string, the name of a particular format supported by the BFD libraries. (You can list the available binary formats with 'objdump -i'.) See Chapter 5 [BFD], page 47.

You may want to use this option if you are linking files with an unusual binary format. You can also use '-b' to switch formats explicitly (when linking object files of different formats), by including '-b input-format' before each group of object files in a particular format.

The default format is taken from the environment variable GNUTARGET. See Section 2.2 [Environment], page 17. You can also define the input format from a script, using the command TARGET; see Section 3.8 [Option Commands], page 40.

-c MRI-commandfile

--mri-script=MRI-commandfile

For compatibility with linkers produced by MRI, 1d accepts script files written in an alternate, restricted command language, described in Appendix A [MRI Compatible Script Files], page 55. Introduce MRI script files with the option '-c'; use the '-T' option to run linker scripts written in the general-purpose 1d scripting language. If MRI-cmdfile does not exist, 1d looks for it in the directories specified by any '-L' options.

-d

-dc -dp

These three options are equivalent; multiple forms are supported for compatibility with other linkers. They assign space to common symbols even if a relocatable output file is specified (with '-r'). The script command FORCE_COMMON_ALLOCATION has the same effect. See Section 3.8 [Option Commands], page 40.

-e entry

--entry=entry

Use entry as the explicit symbol for beginning execution of your program, rather than the default entry point. See Section 3.6 [Entry Point], page 37, for a discussion of defaults and other ways of specifying the entry point.

 $-\mathbf{E}$

--export-dynamic

When creating a dynamically linked executable, add all symbols to the dynamic symbol table. The dynamic symbol table is the set of symbols which are visible from dynamic objects at run time.

If you do not use this option, the dynamic symbol table will normally contain only those symbols which are referenced by some dynamic object mentioned in the link.

If you use **dlopen** to load a dynamic object which needs to refer back to the symbols defined by the program, rather than some other dynamic object, then you will probably need to use this option when linking the program itself.

-f

--auxiliary name

When creating an ELF shared object, set the internal DT_AUXILIARY field to the specified name. This tells the dynamic linker that the symbol table of the shared object should be used as an auxiliary filter on the symbol table of the shared object name.

If you later link a program against this filter object, then, when you run the program, the dynamic linker will see the DT_AUXILIARY field. If the dynamic linker resolves any symbols from the filter object, it will first check whether there is a definition in the shared object name. If there is one, it will be used instead of the definition in the filter object. The shared object name need not exist. Thus the shared object name may be used to provide an alternative implementation of certain functions, perhaps for debugging or for machine specific performance.

This option may be specified more than once. The DT_AUXILIARY entries will be created in the order in which they appear on the command line.

-F name

--filter name

When creating an ELF shared object, set the internal DT_FILTER field to the specified name. This tells the dynamic linker that the symbol table of the shared object which is being created should be used as a filter on the symbol table of the shared object name.

If you later link a program against this filter object, then, when you run the program, the dynamic linker will see the DT_FILTER field. The dynamic linker will resolve symbols according to the symbol table of the filter object as usual, but it will actually link to the definitions found in the shared object name. Thus the filter object can be used to select a subset of the symbols provided by the object name.

Some older linkers used the -F option throughout a compilation toolchain for specifying object-file format for both input and output object files. The GNU linker uses other mechanisms for this purpose: the -b, --format, --oformat options, the TARGET command in linker scripts, and the GNUTARGET environment variable. The GNU linker will ignore the -F option when not creating an ELF shared object.

--force-exe-suffix

Make sure that an output file has a .exe suffix.

If a successfully built fully linked output file does not have a .exe or .dll suffix, this option forces the linker to copy the output file to one of the same name with a .exe suffix. This option is useful when using unmodified Unix makefiles on a Microsoft Windows host, since some versions of Windows won't run an image unless it ends in a .exe suffix.

-g Ignored. Provided for compatibility with other tools.

-G value

--gpsize=value

Set the maximum size of objects to be optimized using the GP register to size. This is only meaningful for object file formats such as MIPS ECOFF which supports putting large and small objects into different sections. This is ignored for other object file formats.

-hname

$-\mathtt{soname} = name$

When creating an ELF shared object, set the internal DT_SONAME field to the specified name. When an executable is linked with a shared object which has a DT_SONAME field, then when the executable is run the dynamic linker will attempt to load the shared object specified by the DT_SONAME field rather than the using the file name given to the linker.

-i Perform an incremental link (same as option '-r').

-larchive

--library=archive

Add archive file archive to the list of files to link. This option may be used any number of times. 1d will search its path-list for occurrences of libarchive.a for every archive specified.

On systems which support shared libraries, 1d may also search for libraries with extensions other than .a. Specifically, on ELF and SunOS systems, 1d will search a directory for a library with an extension of .so before searching

for one with an extension of .a. By convention, a .so extension indicates a shared library.

The linker will search an archive only once, at the location where it is specified on the command line. If the archive defines a symbol which was undefined in some object which appeared before the archive on the command line, the linker will include the appropriate file(s) from the archive. However, an undefined symbol in an object appearing later on the command line will not cause the linker to search the archive again.

See the - (option for a way to force the linker to search archives multiple times. You may list the same archive multiple times on the command line.

This type of archive searching is standard for Unix linkers. However, if you are using 1d on AIX, note that it is different from the behaviour of the AIX linker.

-Lsearchdir

--library-path=searchdir

Add path searchdir to the list of paths that 1d will search for archive libraries and 1d control scripts. You may use this option any number of times. The directories are searched in the order in which they are specified on the command line. Directories specified on the command line are searched before the default directories. All -L options apply to all -l options, regardless of the order in which the options appear.

The default set of paths searched (without being specified with '-L') depends on which emulation mode 1d is using, and in some cases also on how it was configured. See Section 2.2 [Environment], page 17.

The paths can also be specified in a link script with the SEARCH_DIR command. Directories specified this way are searched at the point in which the linker script appears in the command line.

-memulation

Emulate the *emulation* linker. You can list the available emulations with the '--verbose' or '-V' options.

If the '-m' option is not used, the emulation is taken from the LDEMULATION environment variable, if that is defined.

Otherwise, the default emulation depends upon how the linker was configured.

_ M

--print-map

Print a link map to the standard output. A link map provides information about the link, including the following:

- Where object files and symbols are mapped into memory.
- How common symbols are allocated.
- All archive members included in the link, with a mention of the symbol which caused the archive member to be brought in.

-n

--nmagic Set the text segment to be read only, and mark the output as NMAGIC if possible.

-N

--omagic Set the text and data sections to be readable and writable. Also, do not pagealign the data segment. If the output format supports Unix style magic numbers, mark the output as OMAGIC.

-o output

--output=output

Use *output* as the name for the program produced by 1d; if this option is not specified, the name 'a.out' is used by default. The script command OUTPUT can also specify the output file name.

-r

--relocateable

Generate relocatable output—i.e., generate an output file that can in turn serve as input to ld. This is often called partial linking. As a side effect, in environments that support standard Unix magic numbers, this option also sets the output file's magic number to OMAGIC. If this option is not specified, an absolute file is produced. When linking C++ programs, this option will not resolve references to constructors; to do that, use '-Ur'.

This option does the same thing as '-i'.

-R filename

--just-symbols=filename

Read symbol names and their addresses from *filename*, but do not relocate it or include it in the output. This allows your output file to refer symbolically to absolute locations of memory defined in other programs. You may use this option more than once.

For compatibility with other ELF linkers, if the -R option is followed by a directory name, rather than a file name, it is treated as the -rpath option.

-s

--strip-all

Omit all symbol information from the output file.

-S

--strip-debug

Omit debugger symbol information (but not all symbols) from the output file.

- +

--trace Print the names of the input files as 1d processes them.

-T commandfile

--script=commandfile

Read link commands from the file *commandfile*. These commands replace ld's default link script (rather than adding to it), so *commandfile* must specify everything necessary to describe the target format. You must use this option if you want to use a command which can only appear once in a linker script, such as the SECTIONS or MEMORY command. See Chapter 3 [Commands], page 19. If *commandfile* does not exist, ld looks for it in the directories specified by any preceding '-L' options. Multiple '-T' options accumulate.

-u symbol

--undefined=symbol

Force symbol to be entered in the output file as an undefined symbol. Doing this may, for example, trigger linking of additional modules from standard libraries. '-u' may be repeated with different option arguments to enter additional undefined symbols.

-v

--version

-V Display the version number for ld. The -V option also lists the supported emulations.

-x

--discard-all

Delete all local symbols.

-X

--discard-locals

Delete all temporary local symbols. For most targets, this is all local symbols whose names begin with 'L'.

-y symbol

--trace-symbol=symbol

Print the name of each linked file in which symbol appears. This option may be given any number of times. On many systems it is necessary to prepend an underscore.

This option is useful when you have an undefined symbol in your link but don't know where the reference is coming from.

-Y path Add path to the default library search path. This option exists for Solaris compatibility.

-z keyword

This option is ignored for Solaris compatibility.

-(archives -)

--start-group archives --end-group

The archives should be a list of archive files. They may be either explicit file names, or '-1' options.

The specified archives are searched repeatedly until no new undefined references are created. Normally, an archive is searched only once in the order that it is specified on the command line. If a symbol in that archive is needed to resolve an undefined symbol referred to by an object in an archive that appears later on the command line, the linker would not be able to resolve that reference. By grouping the archives, they all be searched repeatedly until all possible references are resolved.

Using this option has a significant performance cost. It is best to use it only when there are unavoidable circular references between two or more archives.

-assert keyword

This option is ignored for SunOS compatibility.

-Bdynamic

-dy

-call_shared

Link against dynamic libraries. This is only meaningful on platforms for which shared libraries are supported. This option is normally the default on such platforms. The different variants of this option are for compatibility with various systems. You may use this option multiple times on the command line: it affects library searching for -1 options which follow it.

-Bstatic

-dn

-non_shared

-static

Do not link against shared libraries. This is only meaningful on platforms for which shared libraries are supported. The different variants of this option are for compatibility with various systems. You may use this option multiple times on the command line: it affects library searching for -1 options which follow it.

-Bsymbolic

When creating a shared library, bind references to global symbols to the definition within the shared library, if any. Normally, it is possible for a program linked against a shared library to override the definition within the shared library. This option is only meaningful on ELF platforms which support shared libraries.

--cref

Output a cross reference table. If a linker map file is being generated, the cross reference table is printed to the map file. Otherwise, it is printed on the standard output.

The format of the table is intentionally simple, so that it may be easily processed by a script if necessary. The symbols are printed out, sorted by name. For each symbol, a list of file names is given. If the symbol is defined, the first file listed is the location of the definition. The remaining files contain references to the symbol.

--defsym symbol=expression

Create a global symbol in the output file, containing the absolute address given by expression. You may use this option as many times as necessary to define multiple symbols in the command line. A limited form of arithmetic is supported for the expression in this context: you may give a hexadecimal constant or the name of an existing symbol, or use + and - to add or subtract hexadecimal constants or symbols. If you need more elaborate expressions, consider using the linker command language from a script (see Section 3.2.6 [Assignment: Symbol Definitions], page 22). Note: there should be no white space between symbol, the equals sign ("\(\existsim \)"), and expression.

--dynamic-linker file

Set the name of the dynamic linker. This is only meaningful when generating dynamically linked ELF executables. The default dynamic linker is normally correct; don't use this unless you know what you are doing.

-EB Link big-endian objects. This affects the default output format.

-EL Link little-endian objects. This affects the default output format.

--embedded-relocs

This option is only meaningful when linking MIPS embedded PIC code, generated by the -membedded-pic option to the GNU compiler and assembler. It causes the linker to create a table which may be used at runtime to relocate any data which was statically initialized to pointer values. See the code in testsuite/ld-empic for details.

--help Print a summary of the command-line options on the standard output and exit.

-Map mapfile

Print a link map to the file mapfile. See the description of the '-M' option, above.

--no-keep-memory

1d normally optimizes for speed over memory usage by caching the symbol tables of input files in memory. This option tells 1d to instead optimize for memory usage, by rereading the symbol tables as necessary. This may be required if 1d runs out of memory space while linking a large executable.

--no-warn-mismatch

Normally 1d will give an error if you try to link together input files that are mismatched for some reason, perhaps because they have been compiled for different processors or for different endiannesses. This option tells 1d that it should silently permit such possible errors. This option should only be used with care, in cases when you have taken some special action that ensures that the linker errors are inappropriate.

--no-whole-archive

Turn off the effect of the --whole-archive option for subsequent archive files.

--noinhibit-exec

Retain the executable output file whenever it is still usable. Normally, the linker will not produce an output file if it encounters errors during the link process; it exits without writing an output file when it issues any error whatsoever.

--oformat output-format

1d may be configured to support more than one kind of object file. If your 1d is configured this way, you can use the '--oformat' option to specify the binary format for the output object file. Even when 1d is configured to support alternative object formats, you don't usually need to specify this, as 1d should be configured to produce as a default output format the most usual format on each machine. output-format is a text string, the name of a particular format supported by the BFD libraries. (You can list the available binary formats with 'objdump -i'.) The script command OUTPUT_FORMAT can also specify the output format, but this option overrides it. See Chapter 5 [BFD], page 47.

-qmagic This option is ignored for Linux compatibility.

-Qy This option is ignored for SVR4 compatibility.

--relax An option with machine dependent effects. This option is only supported on a few targets. See Section 4.1 [ld and the H8/300], page 45. See Section 4.2 [ld and the Intel 960 family], page 45.

On some platforms, the '--relax' option performs global optimizations that become possible when the linker resolves addressing in the program, such as relaxing address modes and synthesizing new instructions in the output object file

On platforms where this is not supported, '--relax' is accepted, but ignored.

--retain-symbols-file filename

Retain only the symbols listed in the file filename, discarding all others. filename is simply a flat file, with one symbol name per line. This option is especially useful in environments (such as VxWorks) where a large global symbol table is accumulated gradually, to conserve run-time memory.

`--retain-symbols-file' does not discard undefined symbols, or symbols needed for relocations.

You may only specify '--retain-symbols-file' once in the command line. It overrides '-s' and '-S'.

-rpath dir

Add a directory to the runtime library search path. This is used when linking an ELF executable with shared objects. All -rpath arguments are concatenated and passed to the runtime linker, which uses them to locate shared objects at runtime. The -rpath option is also used when locating shared objects which are needed by shared objects explicitly included in the link; see the description of the -rpath-link option. If -rpath is not used when linking an ELF executable, the contents of the environment variable LD_RUN_PATH will be used if it is defined.

The -rpath option may also be used on SunOS. By default, on SunOS, the linker will form a runtime search patch out of all the -L options it is given. If a -rpath option is used, the runtime search path will be formed exclusively using the -rpath options, ignoring the -L options. This can be useful when using gcc, which adds many -L options which may be on NFS mounted filesystems. For compatibility with other ELF linkers, if the -R option is followed by a directory name, rather than a file name, it is treated as the -rpath option.

-rpath-link DIR

When using ELF or SunOS, one shared library may require another. This happens when an ld-shared link includes a shared library as one of the input files.

When the linker encounters such a dependency when doing a non-shared, non-relocateable link, it will automatically try to locate the required shared library and include it in the link, if it is not included explicitly. In such a case, the -rpath-link option specifies the first set of directories to search. The -rpath-link option may specify a sequence of directory names either by specifying a list of names separated by colons, or by appearing multiple times.

The linker uses the following search paths to locate required shared libraries.

- 1. Any directories specified by -rpath-link options.
- 2. Any directories specified by -rpath options. The difference between rpath and -rpath-link is that directories specified by -rpath options are included in the executable and used at runtime, whereas the -rpath-link option is only effective at link time.
- 3. On an ELF system, if the -rpath and rpath-link options were not used, search the contents of the environment variable LD_RUN_PATH.
- 4. On SunOS, if the -rpath option was not used, search any directories specified using -L options.
- 5. For a native linker, the contents of the environment variable LD_LIBRARY_PATH.
- 6. The default directories, normally '/lib' and '/usr/lib'.

If the required shared library is not found, the linker will issue a warning and continue with the link.

-shared

-Bshareable

Create a shared library. This is currently only supported on ELF, XCOFF and SunOS platforms. On SunOS, the linker will automatically create a shared library if the -e option is not used and there are undefined symbols in the link.

--sort-common

This option tells 1d to sort the common symbols by size when it places them in the appropriate output sections. First come all the one byte symbols, then all the two bytes, then all the four bytes, and then everything else. This is to prevent gaps between symbols due to alignment constraints.

--split-by-file

Similar to --split-by-reloc but creates a new output section for each input file.

--split-by-reloc count

Trys to creates extra sections in the output file so that no single output section in the file contains more than *count* relocations. This is useful when generating huge relocatable for downloading into certain real time kernels with the COFF object file format; since COFF cannot represent more than 65535 relocations in a single section. Note that this will fail to work with object file formats which do not support arbitrary sections. The linker will not split up individual input sections for redistribution, so if a single input section contains more than *count* relocations one output section will contain that many relocations.

--stats Compute and display statistics about the operation of the linker, such as execution time and memory usage.

--traditional-format

For some targets, the output of ld is different in some ways from the output of some existing linker. This switch requests ld to use the traditional format instead.

For example, on SunOS, 1d combines duplicate entries in the symbol string table. This can reduce the size of an output file with full debugging information by over 30 percent. Unfortunately, the SunOS dbx program can not read the resulting program (gdb has no trouble). The '--traditional-format' switch tells 1d to not combine duplicate entries.

- -Tbss org
- -Tdata org
- -Ttext org

Use org as the starting address for—respectively—the bss, data, or the text segment of the output file. org must be a single hexadecimal integer; for compatibility with other linkers, you may omit the leading 'Ox' usually associated with hexadecimal values.

-Ur For anything other than C++ programs, this option is equivalent to '-r': it generates relocatable output—i.e., an output file that can in turn serve as input to 1d. When linking C++ programs, '-Ur' does resolve references to constructors, unlike '-r'. It does not work to use '-Ur' on files that were themselves linked with '-Ur'; once the constructor table has been built, it cannot be added to. Use '-Ur' only for the last partial link, and '-r' for the others.

--verbose

Display the version number for 1d and list the linker emulations supported. Display which input files can and cannot be opened. Display the linker script if using a default builtin script.

--version-script=version-scriptfile

Specify the name of a version script to the linker. This is typically used when creating shared libraries to specify additional information about the version heirarchy for the library being created. This option is only meaningful on ELF platforms which support shared libraries. See Section 3.7 [Version Script], page 38.

--warn-common

Warn when a common symbol is combined with another common symbol or with a symbol definition. Unix linkers allow this somewhat sloppy practice, but linkers on some other operating systems do not. This option allows you to find potential problems from combining global symbols. Unfortunately, some C libraries use this practice, so you may get some warnings about symbols in the libraries as well as in your programs.

There are three kinds of global symbols, illustrated here by C examples:

'int i = 1;'

A definition, which goes in the initialized data section of the output file.

'extern int i;'

An undefined reference, which does not allocate space. There must be either a definition or a common symbol for the variable somewhere. 'int i;' A common symbol. If there are only (one or more) common symbols for a variable, it goes in the uninitialized data area of the output file. The linker merges multiple common symbols for the same variable into a single symbol. If they are of different sizes, it picks the largest size. The linker turns a common symbol into a declaration, if there is a definition of the same variable.

The '--warn-common' option can produce five kinds of warnings. Each warning consists of a pair of lines: the first describes the symbol just encountered, and the second describes the previous symbol encountered with the same name. One or both of the two symbols will be a common symbol.

1. Turning a common symbol into a reference, because there is already a definition for the symbol.

```
file(section): warning: common of 'symbol'
  overridden by definition
file(section): warning: defined here
```

2. Turning a common symbol into a reference, because a later definition for the symbol is encountered. This is the same as the previous case, except that the symbols are encountered in a different order.

```
file(section): warning: definition of 'symbol'
   overriding common
file(section): warning: common is here
```

3. Merging a common symbol with a previous same-sized common symbol.

```
file(section): warning: multiple common
   of 'symbol'
file(section): warning: previous common is here
```

4. Merging a common symbol with a previous larger common symbol.

```
file(section): warning: common of 'symbol'
   overridden by larger common
file(section): warning: larger common is here
```

5. Merging a common symbol with a previous smaller common symbol. This is the same as the previous case, except that the symbols are encountered in a different order.

```
file(section): warning: common of 'symbol'
   overriding smaller common
file(section): warning: smaller common is here
```

--warn-constructors

Warn if any global constructors are used. This is only useful for a few object file formats. For formats like COFF or ELF, the linker can not detect the use of global constructors.

--warn-multiple-gp

Warn if multiple global pointer values are required in the output file. This is only meaningful for certain processors, such as the Alpha. Specifically, some processors put large-valued constants in a special section. A special register

(the global pointer) points into the middle of this section, so that constants can be loaded efficiently via a base-register relative addressing mode. Since the offset in base-register relative mode is fixed and relatively small (e.g., 16 bits), this limits the maximum size of the constant pool. Thus, in large programs, it is often necessary to use multiple global pointer values in order to be able to address all possible constants. This option causes a warning to be issued whenever this case occurs.

--warn-once

Only warn once for each undefined symbol, rather than once per module which refers to it.

--warn-section-align

Warn if the address of an output section is changed because of alignment. Typically, the alignment will be set by an input section. The address will only be changed if it not explicitly specified; that is, if the SECTIONS command does not specify a start address for the section (see Section 3.4 [SECTIONS], page 26).

--whole-archive

For each archive mentioned on the command line after the --whole-archive option, include every object file in the archive in the link, rather than searching the archive for the required object files. This is normally used to turn an archive file into a shared library, forcing every object to be included in the resulting shared library. This option may be used more than once.

$--wrap \ symbol$

Use a wrapper function for symbol. Any undefined reference to symbol will be resolved to __wrap_symbol. Any undefined reference to __real_symbol will be resolved to symbol.

This can be used to provide a wrapper for a system function. The wrapper function should be called <u>__wrap_symbol</u>. If it wishes to call the system function, it should call <u>__real_symbol</u>.

Here is a trivial example:

```
void *
__wrap_malloc (int c)
{
   printf ("malloc called with %ld\n", c);
   return __real_malloc (c);
}
```

If you link other code with this file using --wrap malloc, then all calls to malloc will call the function __wrap_malloc instead. The call to __real_malloc in __wrap_malloc will call the real malloc function.

You may wish to provide a __real_malloc function as well, so that links without the --wrap option will succeed. If you do this, you should not put the definition of __real_malloc in the same file as __wrap_malloc; if you do, the assembler may resolve the call before the linker has a chance to wrap it to malloc.

2.2 Environment Variables

You can change the behavior of ld with the environment variables GNUTARGET and LDEMULATION.

GNUTARGET determines the input-file object format if you don't use '-b' (or its synonym '--format'). Its value should be one of the BFD names for an input format (see Chapter 5 [BFD], page 47). If there is no GNUTARGET in the environment, 1d uses the natural format of the target. If GNUTARGET is set to default then BFD attempts to discover the input format by examining binary input files; this method often succeeds, but there are potential ambiguities, since there is no method of ensuring that the magic number used to specify object-file formats is unique. However, the configuration procedure for BFD on each system places the conventional format for that system first in the search-list, so ambiguities are resolved in favor of convention.

LDEMULATION determines the default emulation if you don't use the '-m' option. The emulation can affect various aspects of linker behaviour, particularly the default linker script. You can list the available emulations with the '--verbose' or '-V' options. If the '-m' option is not used, and the LDEMULATION environment variable is not defined, the default emulation depends upon how the linker was configured.

3 Command Language

The command language provides explicit control over the link process, allowing complete specification of the mapping between the linker's input files and its output. It controls:

- input files
- file formats
- output file layout
- addresses of sections
- placement of common blocks

You may supply a command file (also known as a linker script) to the linker either explicitly through the '-T' option, or implicitly as an ordinary file. Normally you should use the '-T' option. An implicit linker script should only be used when you want to augment, rather than replace, the default linker script; typically an implicit linker script would consist only of INPUT or GROUP commands.

If the linker opens a file which it cannot recognize as a supported object or archive format, nor as a linker script, it reports an error.

3.1 Linker Scripts

The 1d command language is a collection of statements; some are simple keywords setting a particular option, some are used to select and group input files or name output files; and two statement types have a fundamental and pervasive impact on the linking process.

The most fundamental command of the 1d command language is the SECTIONS command (see Section 3.4 [SECTIONS], page 26). Every meaningful command script must have a SECTIONS command: it specifies a "picture" of the output file's layout, in varying degrees of detail. No other command is required in all cases.

The MEMORY command complements SECTIONS by describing the available memory in the target architecture. This command is optional; if you don't use a MEMORY command, 1d assumes sufficient memory is available in a contiguous block for all output. See Section 3.3 [MEMORY], page 25.

You may include comments in linker scripts just as in C: delimited by '/*' and '*/'. As in C, comments are syntactically equivalent to whitespace.

3.2 Expressions

Many useful commands involve arithmetic expressions. The syntax for expressions in the command language is identical to that of C expressions, with the following features:

- All expressions evaluated as integers and are of "long" or "unsigned long" type.
- All constants are integers.
- All of the C arithmetic operators are provided.
- You may reference, define, and create global variables.
- You may call special purpose built-in functions.

3.2.1 Integers

An octal integer is '0' followed by zero or more of the octal digits ('01234567').

```
_as_octal = 0157255;
```

A decimal integer starts with a non-zero digit followed by zero or more digits ('0123456789').

```
_{as\_decimal} = 57005;
```

A hexadecimal integer is '0x' or '0X' followed by one or more hexadecimal digits chosen from '0123456789abcdefABCDEF'.

```
_as_hex = Oxdead;
```

To write a negative integer, use the prefix operator '-' (see Section 3.2.4 [Operators], page 21).

```
_{as_neg} = -57005;
```

Additionally the suffixes K and M may be used to scale a constant by 1024 or 1024² respectively. For example, the following all refer to the same quantity:

```
_fourk_1 = 4K;
_fourk_2 = 4096;
_fourk_3 = 0x1000;
```

3.2.2 Symbol Names

Unless quoted, symbol names start with a letter, underscore, or point and may include any letters, underscores, digits, points, and hyphens. Unquoted symbol names must not conflict with any keywords. You can specify a symbol which contains odd characters or has the same name as a keyword, by surrounding the symbol name in double quotes:

```
"SECTION" = 9;
"with a space" = "also with a space" + 10;
```

Since symbols can contain many non-alphabetic characters, it is safest to delimit symbols with spaces. For example, 'A-B' is one symbol, whereas 'A-B' is an expression involving subtraction.

3.2.3 The Location Counter

The special linker variable dot '.' always contains the current output location counter. Since the . always refers to a location in an output section, it must always appear in an expression within a SECTIONS command. The . symbol may appear anywhere that an ordinary symbol is allowed in an expression, but its assignments have a side effect. Assigning a value to the . symbol will cause the location counter to be moved. This may be used to create holes in the output section. The location counter may never be moved backwards.

```
. += 1000;
file3(.text)
} = 0x1234;
}
```

In the previous example, file1 is located at the beginning of the output section, then there is a 1000 byte gap. Then file2 appears, also with a 1000 byte gap following before file3 is loaded. The notation '= 0x1234' specifies what data to write in the gaps (see Section 3.4.4 [Section Options], page 32).

3.2.4 Operators

The linker recognizes the standard C set of arithmetic operators, with the standard bindings and precedence levels:

Precedence	Associativity	Operators
highest		
1	left	- ~ ! †
2	left	* / %
3	left	+ -
4	left	>> <<
5	left	== != > < <= >=
6	left	&
7	left	I
8	left	&&
9	left	H
10	right	? :
11	right	&= += -= *= /= ‡
lowest		

- † Prefix operators.
- ‡ See Section 3.2.6 [Assignment], page 22.

3.2.5 Evaluation

The linker uses "lazy evaluation" for expressions; it only calculates an expression when absolutely necessary. The linker needs the value of the start address, and the lengths of memory regions, in order to do any linking at all; these values are computed as soon as possible when the linker reads in the command file. However, other values (such as symbol values) are not known or needed until after storage allocation. Such values are evaluated later, when other information (such as the sizes of output sections) is available for use in the symbol assignment expression.

3.2.6 Assignment: Defining Symbols

You may create global symbols, and assign values (addresses) to global symbols, using any of the C assignment operators:

```
symbol = expression;
symbol &= expression;
symbol += expression;
symbol -= expression;
symbol *= expression;
symbol /= expression;
```

Two things distinguish assignment from other operators in 1d expressions.

- Assignment may only be used at the root of an expression; 'a=b+3;' is allowed, but 'a+b=3;' is an error.
- You must place a trailing semicolon ("O") at the end of an assignment statement.

Assignment statements may appear:

- as commands in their own right in an ld script; or
- as independent statements within a SECTIONS command; or
- as part of the contents of a section definition in a SECTIONS command.

The first two cases are equivalent in effect—both define a symbol with an absolute address. The last case defines a symbol whose address is relative to a particular section (see Section 3.4 [SECTIONS], page 26).

When a linker expression is evaluated and assigned to a variable, it is given either an absolute or a relocatable type. An absolute expression type is one in which the symbol contains the value that it will have in the output file; a relocatable expression type is one in which the value is expressed as a fixed offset from the base of a section.

The type of the expression is controlled by its position in the script file. A symbol assigned within a section definition is created relative to the base of the section; a symbol assigned in any other place is created as an absolute symbol. Since a symbol created within a section definition is relative to the base of the section, it will remain relocatable if relocatable output is requested. A symbol may be created with an absolute value even when assigned to within a section definition by using the absolute assignment function ABSOLUTE. For example, to create an absolute symbol whose address is the last byte of an output section named .data:

The linker tries to put off the evaluation of an assignment until all the terms in the source expression are known (see Section 3.2.5 [Evaluation], page 21). For instance, the sizes of sections cannot be known until after allocation, so assignments dependent upon these are not performed until after allocation. Some expressions, such as those depending upon the

location counter dot, '.' must be evaluated during allocation. If the result of an expression is required, but the value is not available, then an error results. For example, a script like the following

```
SECTIONS { ...
  text 9+this_isnt_constant :
     { ...
  }
... }
```

will cause the error message "Non constant expression for initial address".

In some cases, it is desirable for a linker script to define a symbol only if it is referenced, and only if it is not defined by any object included in the link. For example, traditional linkers defined the symbol 'etext'. However, ANSI C requires that the user be able to use 'etext' as a function name without encountering an error. The PROVIDE keyword may be used to define a symbol, such as 'etext', only if it is referenced but not defined. The syntax is PROVIDE(symbol = expression).

3.2.7 Arithmetic Functions

The command language includes a number of built-in functions for use in link script expressions.

ABSOLUTE(exp)

Return the absolute (non-relocatable, as opposed to non-negative) value of the expression exp. Primarily useful to assign an absolute value to a symbol within a section definition, where symbol values are normally section-relative.

ADDR (section)

Return the absolute address of the named section. Your script must previously have defined the location of that section. In the following example, symbol_1 and symbol_2 are assigned identical values:

```
SECTIONS{ ...
    .output1 :
        {
        start_of_output_1 = ABSOLUTE(.);
        ...
      }
    .output :
        {
        symbol_1 = ADDR(.output1);
        symbol_2 = start_of_output_1;
        }
    ... }
```

LOADADDR(section)

Return the absolute load address of the named section. This is normally the same as ADDR, but it may be different if the AT keyword is used in the section definition (see Section 3.4.4 [Section Options], page 32).

ALIGN(exp)

Return the result of the current location counter (.) aligned to the next exp boundary. exp must be an expression whose value is a power of two. This is equivalent to

```
(. + exp - 1) & "(exp - 1)
```

ALIGN doesn't change the value of the location counter—it just does arithmetic on it. As an example, to align the output .data section to the next 0x2000 byte boundary after the preceding section and to set a variable within the section to the next 0x8000 boundary after the input sections:

```
SECTIONS{ ...
  .data ALIGN(0x2000): {
   *(.data)
   variable = ALIGN(0x8000);
}
}
```

The first use of ALIGN in this example specifies the location of a section because it is used as the optional *start* attribute of a section definition (see Section 3.4.4 [Section Options], page 32). The second use simply defines the value of a variable.

The built-in NEXT is closely related to ALIGN.

DEFINED (symbol)

Return 1 if symbol is in the linker global symbol table and is defined, otherwise return 0. You can use this function to provide default values for symbols. For example, the following command-file fragment shows how to set a global symbol begin to the first location in the .text section—but if a symbol called begin already existed, its value is preserved:

```
SECTIONS{ ...
   .text : {
    begin = DEFINED(begin) ? begin : . ;
    ...
}
... }
```

NEXT(exp)

Return the next unallocated address that is a multiple of exp. This function is closely related to ALIGN(exp); unless you use the MEMORY command to define discontinuous memory for the output file, the two functions are equivalent.

SIZEOF(section)

Return the size in bytes of the named section, if that section has been allocated. In the following example, symbol_1 and symbol_2 are assigned identical values:

```
SECTIONS{ ...
    .output {
        .start = . ;
        ...
        .end = . ;
    }
    symbol_1 = .end - .start ;
    symbol_2 = SIZEOF(.output);
    ... }
```

SIZEOF_HEADERS sizeof_headers

Return the size in bytes of the output file's headers. You can use this number as the start address of the first section, if you choose, to facilitate paging.

MAX(exp1, exp2)

Returns the maximum of exp1 and exp2.

MIN(exp1, exp2)

Returns the minimum of exp1 and exp2.

3.2.8 Semicolons

Semicolons ("(;)") are required in the following places. In all other places they can appear for aesthetic reasons but are otherwise ignored.

Assignment

Semicolons must appear at the end of assignment expressions. See Section 3.2.6 [Assignment], page 22

PHDRS Semicolons must appear at the end of a PHDRS statement. See Section 3.5 [PHDRS], page 35

3.3 Memory Layout

The linker's default configuration permits allocation of all available memory. You can override this configuration by using the MEMORY command. The MEMORY command describes the location and size of blocks of memory in the target. By using it carefully, you can describe which memory regions may be used by the linker, and which memory regions it must avoid. The linker does not shuffle sections to fit into the available regions, but does move the requested sections into the correct regions and issue errors when the regions become too full.

A command file may contain at most one use of the MEMORY command; however, you can define as many blocks of memory within it as you wish. The syntax is:

```
MEMORY
{
    name (attr) : ORIGIN = origin, LENGTH = len
    ...
}
```

name

is a name used internally by the linker to refer to the region. Any symbol name may be used. The region names are stored in a separate name space, and will not conflict with symbols, file names or section names. Use distinct names to specify multiple regions.

is an optional list of attributes that specify whether to use a particular memory to place sections that are not listed in the linker script. Valid attribute lists must be made up of the characters "ALIRWX" that match section attributes. If you omit the attribute list, you may omit the parentheses around it as well. The attributes currently supported are:

'Letter'	Section Attribute
'R'	Read-only sections.
`W'	Read/write sections.
'х'	Sections containing executable code.
'Α'	Allocated sections.
ï,	Initialized sections.
L'	Same as I.
· i ,	Invert the sense of any of the following attributes.

origin is the start address of the region in physical memory. It is an expression that must evaluate to a constant before memory allocation is performed. The keyword ORIGIN may be abbreviated to org or o (but not, for example, 'ORG').

len is the size in bytes of the region (an expression). The keyword LENGTH may be abbreviated to len or 1.

For example, to specify that memory has two regions available for allocation—one starting at 0 for 256 kilobytes, and the other starting at 0x40000000 for four megabytes. The rom memory region will get all sections without an explicit memory register that are either read-only or contain code, while the ram memory region will get the sections.

```
MEMORY
{
  rom (rx) : ORIGIN = 0, LENGTH = 256K
  ram (!rx) : org = 0x40000000, 1 = 4M
  }
```

Once you have defined a region of memory named mem, you can direct specific output sections there by using a command ending in '>mem' within the SECTIONS command (see Section 3.4.4 [Section Options], page 32). If the combined output sections directed to a region are too big for the region, the linker will issue an error message.

3.4 Specifying Output Sections

The SECTIONS command controls exactly where input sections are placed into output sections, their order in the output file, and to which output sections they are allocated.

You may use at most one SECTIONS command in a script file, but you can have as many statements within it as you wish. Statements within the SECTIONS command can do one of three things:

- define the entry point;
- assign a value to a symbol;
- describe the placement of a named output section, and which input sections go into it.

You can also use the first two operations—defining the entry point and defining symbols—outside the SECTIONS command: see Section 3.6 [Entry Point], page 37, and Section 3.2.6 [Assignment], page 22. They are permitted here as well for your convenience in reading the script, so that symbols and the entry point can be defined at meaningful points in your output-file layout.

If you do not use a SECTIONS command, the linker places each input section into an identically named output section in the order that the sections are first encountered in the input files. If all input sections are present in the first file, for example, the order of sections in the output file will match the order in the first input file.

3.4.1 Section Definitions

The most frequently used statement in the SECTIONS command is the section definition, which specifies the properties of an output section: its location, alignment, contents, fill pattern, and target memory region. Most of these specifications are optional; the simplest form of a section definition is

```
sections { ...
  secname : {
    contents
  }
... }
```

secname is the name of the output section, and contents a specification of what goes there—for example, a list of input files or sections of input files (see Section 3.4.2 [Section Placement], page 28). The whitespace around secname is required, so that the section name is unambiguous. The other whitespace shown is optional. You do need the colon ':' and the braces '{}', however.

secname must meet the constraints of your output format. In formats which only support a limited number of sections, such as a.out, the name must be one of the names supported by the format (a.out, for example, allows only .text, .data or .bss). If the output format supports any number of sections, but with numbers and not names (as is the case for Oasys), the name should be supplied as a quoted numeric string. A section name may consist of any sequence of characters, but any name which does not conform to the standard 1d symbol name syntax must be quoted. See Section 3.2.2 [Symbol Names], page 20.

The special secname '/DISCARD/' may be used to discard input sections. Any sections which are assigned to an output section named '/DISCARD/' are not included in the final link output.

The linker will not create output sections which do not have any contents. This is for convenience when referring to input sections that may or may not exist. For example,

```
.foo { *(.foo) }
```

will only create a '.foo' section in the output file if there is a '.foo' section in at least one input file.

3.4.2 Section Placement

In a section definition, you can specify the contents of an output section by listing particular input files, by listing particular input-file sections, or by a combination of the two. You can also place arbitrary data in the section, and define symbols relative to the beginning of the section.

The *contents* of a section definition may include any of the following kinds of statement. You can include as many of these as you like in a single section definition, separated from one another by whitespace.

filename

You may simply name a particular input file to be placed in the current output section; all sections from that file are placed in the current section definition. If the file name has already been mentioned in another section definition, with an explicit section name list, then only those sections which have not yet been allocated are used.

To specify a list of particular files by name:

```
.data : { afile.o bfile.o cfile.o }
```

The example also illustrates that multiple statements can be included in the contents of a section definition, since each file name is a separate statement.

```
filename( section )
filename( section , section, ...)
filename( section section ...)
```

You can name one or more sections from your input files, for insertion in the current output section. If you wish to specify a list of input-file sections inside the parentheses, separate the section names with whitespace.

- * (section)
- * (section, section, ...)
- * (section section ...)

Instead of explicitly naming particular input files in a link control script, you can refer to all files from the ld command line: use '*' instead of a particular file name before the parenthesized input-file section list.

If you have already explicitly included some files by name, '*' refers to all remaining files—those whose places in the output file have not yet been defined.

For example, to copy sections 1 through 4 from an Oasys file into the .text section of an a.out file, and sections 13 and 14 into the .data section:

```
SECTIONS {
    .text :{
       *("1" "2" "3" "4")
    }
    .data :{
       *("13" "14")
    }
}
```

'[section ...]' used to be accepted as an alternate way to specify named sections from all unallocated input files. Because some operating systems (VMS) allow brackets in file names, that notation is no longer supported.

```
filename( COMMON )
*( COMMON )
```

Specify where in your output file to place uninitialized data with this notation. *(COMMON) by itself refers to all uninitialized data from all input files (so far as it is not yet allocated); filename(COMMON) refers to uninitialized data from a particular file. Both are special cases of the general mechanisms for specifying where to place input-file sections: 1d permits you to refer to uninitialized data as if it were in an input-file section named COMMON, regardless of the input file's format.

In any place where you may use a specific file or section name, you may also use a wildcard pattern. The linker handles wildcards much as the Unix shell does. A '*' character matches any number of characters. A '?' character matches any single character. The sequence '[chars]' will match a single instance of any of the chars; the '-' character may be used to specify a range of characters, as in '[a-z]' to match any lower case letter. A '\' character may be used to quote the following character.

When a file name is matched with a wildcard, the wildcard characters will not match a '/' character (used to separate directory names on Unix). A pattern consisting of a single '*' character is an exception; it will always match any file name. In a section name, the wildcard characters will match a '/' character.

Wildcards only match files which are explicitly specified on the command line. The linker does not search directories to expand wildcards. However, if you specify a simple file name—a name with no wildcard characters—in a linker script, and the file name is not also specified on the command line, the linker will attempt to open the file as though it appeared on the command line.

In the following example, the command script arranges the output file into three consecutive sections, named .text, .data, and .bss, taking the input for each from the correspondingly named sections of all the input files:

```
SECTIONS {
   .text : { *(.text) }
   .data : { *(.data) }
   .bss : { *(.bss) *(COMMON) }
}
```

The following example reads all of the sections from file all.o and places them at the start of output section outputs which starts at location 0x10000. All of section .input1 from file foo.o follows immediately, in the same output section. All of section .input2 from foo.o goes into output section outputb, followed by section .input1 from foo1.o. All of the remaining .input1 and .input2 sections from any files are written to output section outputc.

```
SECTIONS {
   outputa 0x10000 :
     {
      all.o
      foo.o (.input1)
   }
   outputb :
      {
      foo.o (.input2)
      foo1.o (.input1)
      }
   outputc :
      {
      *(.input1)
      *(.input2)
      }
}
```

This example shows how wildcard patterns might be used to partition files. All .text sections are placed in .text, and all .bss sections are placed in .bss. For all files beginning with an upper case character, the .data section is placed into .DATA; for all other files, the .data section is placed into .data.

```
SECTIONS {
  .text : { *(.text) }
  .DATA : { [A-Z]*(.data) }
  .data : { *(.data) }
  .bss : { *(.bss) }
}
```

3.4.3 Section Data Expressions

The foregoing statements arrange, in your output file, data originating from your input files. You can also place data directly in an output section from the link command script. Most of these additional statements involve expressions (see Section 3.2 [Expressions], page 19). Although these statements are shown separately here for ease of presentation, no such segregation is needed within a section definition in the SECTIONS command; you can intermix them freely with any of the statements we've just described.

CREATE_OBJECT_SYMBOLS

Create a symbol for each input file in the current section, set to the address of the first byte of data written from that input file. For instance, with a.out files it is conventional to have a symbol for each input file. You can accomplish this by defining the output .text section as follows:

```
SECTIONS {
   .text 0x2020 :
        {
      CREATE_OBJECT_SYMBOLS
     *(.text)
      _etext = ALIGN(0x2000);
    }
   ...
}
```

If sample.ld is a file containing this script, and a.o, b.o, c.o, and d.o are four input files with contents like the following—

```
/* a.c */
afunction() { }
int adata=1;
int abss;
```

'ld -M -T sample.ld a.o b.o c.o d.o' would create a map like this, containing symbols matching the object file names:

```
OOOOOOOO A __DYNAMIC
00004020 B _abss
00004000 D _adata
00002020 T _afunction
00004024 B _bbss
00004008 D _bdata
00002038 T _bfunction
00004028 B _cbss
00004010 D _cdata
00002050 T _cfunction
0000402c B _dbss
00004018 D _ddata
00002068 T _dfunction
00004020 D _edata
00004030 B _end
00004000 T _etext
00002020 t a.o
00002038 t b.o
00002050 t c.o
00002068 t d.o
```

```
symbol = expression ;
symbol f = expression ;
```

symbol is any symbol name (see Section 3.2.2 [Symbols], page 20). "f=" refers to any of the operators &= += -= *= /= which combine arithmetic and assignment.

When you assign a value to a symbol within a particular section definition, the value is relative to the beginning of the section (see Section 3.2.6 [Assignment], page 22). If you write

```
SECTIONS {
   abs = 14 ;
   ...
   .data : { ... rel = 14 ; ... }
   abs2 = 14 + ADDR(.data);
   ...
}
```

abs and rel do not have the same value; rel has the same value as abs2.

```
BYTE (expression)
SHORT (expression)
LONG (expression)
QUAD (expression)
SQUAD (expression)
```

By including one of these four statements in a section definition, you can explicitly place one, two, four, eight unsigned, or eight signed bytes (respectively) at the current address of that section. When using a 64 bit host or target, QUAD and SQUAD are the same. When both host and target are 32 bits, QUAD uses an unsigned 32 bit value, and SQUAD sign extends the value. Both will use the correct endianness when writing out the value.

Multiple-byte quantities are represented in whatever byte order is appropriate for the output file format (see Chapter 5 [BFD], page 47).

FILL (expression)

Specify the "fill pattern" for the current section. Any otherwise unspecified regions of memory within the section (for example, regions you skip over by assigning a new value to the location counter '.') are filled with the two least significant bytes from the expression argument. A FILL statement covers memory locations after the point it occurs in the section definition; by including more than one FILL statement, you can have different fill patterns in different parts of an output section.

3.4.4 Optional Section Attributes

Here is the full syntax of a section definition, including all the optional portions:

secname and contents are required. See Section 3.4.1 [Section Definition], page 27, and Section 3.4.2 [Section Placement], page 28, for details on contents. The remaining elements—start, BLOCK(align), (NOLOAD), AT (ldadr), >region, :phdr, and =fill—are all optional.

Start You can force the output section to be loaded at a specified address by specifying start immediately following the section name. start can be represented

as any expression. The following example generates section output at location 0x40000000:

```
SECTIONS {
    ...
    output 0x40000000: {
        ...
    }
    ...
}
```

BLOCK(align)

You can include BLOCK() specification to advance the location counter. prior to the beginning of the section, so that the section will begin at the specified alignment. align is an expression.

(NOLOAD) The '(NOLOAD)' directive will mark a section to not be loaded at run time. The linker will process the section normally, but will mark it so that a program loader will not load it into memory. For example, in the script sample below, the ROM section is addressed at memory location 'O' and does not need to be loaded when the program is run. The contents of the ROM section will appear in the linker output file as usual.

```
SECTIONS {
  ROM O (NOLOAD) : { ... }
  ...
}
```

AT (ldadr)

The expression *ldadr* that follows the AT keyword specifies the load address of the section. The default (if you do not use the AT keyword) is to make the load address the same as the relocation address. This feature is designed to make it easy to build a ROM image. For example, this SECTIONS definition creates two output sections: one called '.text', which starts at Ox1000, and one called '.mdata', which is loaded at the end of the '.text' section even though its relocation address is Ox2000. The symbol _data is defined with the value Ox2000:

```
SECTIONS
{
   .text 0x1000 : { *(.text) _etext = . ; }
   .mdata 0x2000 :
    AT ( ADDR(.text) + SIZEOF ( .text ) )
    { _data = . ; *(.data); _edata = . ; }
   .bss 0x3000 :
    { _bstart = . ; *(.bss) *(COMMON) ; _bend = . ;}
}
```

The run-time initialization code (for C programs, usually crt0) for use with a ROM generated this way has to include something like the following, to copy the initialized data from the ROM image to its runtime address:

```
char *src = _etext;
char *dst = _data;

/* ROM has data at end of text; copy it. */
while (dst < _edata) {
   *dst++ = *src++;
}

/* Zero bss */
for (dst = _bstart; dst< _bend; dst++)
   *dst = 0;</pre>
```

>region Assign this section to a previously defined region of memory. See Section 3.3 [MEMORY], page 25.

: phdr Assign this section to a segment described by a program header. See Section 3.5 [PHDRS], page 35. If a section is assigned to one or more segments, then all subsequent allocated sections will be assigned to those segments as well, unless they use an explicitly : phdr modifier. To prevent a section from being assigned to a segment when it would normally default to one, use : NONE.

=fill Including =fill in a section definition specifies the initial fill value for that section. You may use any expression to specify fill. Any unallocated holes in the current output section when written to the output file will be filled with the two least significant bytes of the value, repeated as necessary. You can also change the fill value with a FILL statement in the contents of a section definition.

3.4.5 Overlays

The OVERLAY command provides an easy way to describe sections which are to be loaded as part of a single memory image but are to be run at the same memory address. At run time, some sort of overlay manager will copy the overlaid sections in and out of the runtime memory address as required, perhaps by simply manipulating addressing bits. This approach can be useful, for example, when a certain region of memory is faster than another.

The OVERLAY command is used within a SECTIONS command. It appears as follows:

```
OVERLAY start : [ NOCROSSREFS ] AT ( ldaddr )
{
   secname1 { contents } :phdr =fill
   secname2 { contents } :phdr =fill
   ...
} >region :phdr =fill
```

Everything is optional except OVERLAY (a keyword), and each section must have a name (secname1 and secname2 above). The section definitions within the OVERLAY construct are identical to those within the general SECTIONS contruct (see Section 3.4 [SECTIONS], page 26), except that no addresses and no memory regions may be defined for sections within an OVERLAY.

The sections are all defined with the same starting address. The load addresses of the sections are arranged such that they are consecutive in memory starting at the load address

used for the OVERLAY as a whole (as with normal section definitions, the load address is optional, and defaults to the start address; the start address is also optional, and defaults to .).

If the NOCROSSREFS keyword is used, and there any references among the sections, the linker will report an error. Since the sections all run at the same address, it normally does not make sense for one section to refer directly to another. See Section 3.8 [Option Commands], page 40.

For each section within the OVERLAY, the linker automatically defines two symbols. The symbol __load_start_secname is defined as the starting load address of the section. The symbol __load_stop_secname is defined as the final load address of the section. Any characters within secname which are not legal within C identifiers are removed. C (or assembler) code may use these symbols to move the overlaid sections around as necessary.

At the end of the overlay, the value of . is set to the start address of the overlay plus the size of the largest section.

Here is an example. Remember that this would appear inside a SECTIONS construct.

```
OVERLAY 0x1000 : AT (0x4000)
{
    .text0 { o1/*.o(.text) }
    .text1 { o2/*.o(.text) }
}
```

This will define both .text0 and .text1 to start at address 0x1000. .text0 will be loaded at address 0x4000, and .text1 will be loaded immediately after .text0. The following symbols will be defined: __load_start_text0, __load_stop_text0, __load_start_text1, __load_stop_text1.

C code to copy overlay .text1 into the overlay area might look like the following.

Note that the OVERLAY command is just syntactic sugar, since everything it does can be done using the more basic commands. The above example could have been written identically as follows.

```
.text0 Ox1000 : AT (Ox4000) { o1/*.o(.text) }
__load_start_text0 = LOADADDR (.text0);
__load_stop_text0 = LOADADDR (.text0) + SIZEOF (.text0);
.text1 Ox1000 : AT (Ox4000 + SIZEOF (.text0)) { o2/*.o(.text) }
__load_start_text1 = LOADADDR (.text1);
__load_stop_text1 = LOADADDR (.text1) + SIZEOF (.text1);
. = Ox1000 + MAX (SIZEOF (.text0), SIZEOF (.text1));
```

3.5 ELF Program Headers

The ELF object file format uses program headers, which are read by the system loader and describe how the program should be loaded into memory. These program headers must be set correctly in order to run the program on a native ELF system. The linker will create reasonable program headers by default. However, in some cases, it is desirable to specify

the program headers more precisely; the PHDRS command may be used for this purpose. When the PHDRS command is used, the linker will not generate any program headers itself.

The PHDRS command is only meaningful when generating an ELF output file. It is ignored in other cases. This manual does not describe the details of how the system loader interprets program headers; for more information, see the ELF ABI. The program headers of an ELF file may be displayed using the '-p' option of the objdump command.

This is the syntax of the PHDRS command. The words PHDRS, FILEHDR, AT, and FLAGS are keywords.

```
PHDRS {
    name type [FILEHDR] [PHDRS] [AT (address)]
        [FLAGS (flags)];
}
```

The name is used only for reference in the SECTIONS command of the linker script. It does not get put into the output file.

Certain program header types describe segments of memory which are loaded from the file by the system loader. In the linker script, the contents of these segments are specified by directing allocated output sections to be placed in the segment. To do this, the command describing the output section in the SECTIONS command should use ':name', where name is the name of the program header as it appears in the PHDRS command. See Section 3.4.4 [Section Options], page 32.

It is normal for certain sections to appear in more than one segment. This merely implies that one segment of memory contains another. This is specified by repeating ':name', using it once for each program header in which the section is to appear.

If a section is placed in one or more segments using ':name', then all subsequent allocated sections which do not specify ':name' are placed in the same segments. This is for convenience, since generally a whole set of contiguous sections will be placed in a single segment. To prevent a section from being assigned to a segment when it would normally default to one, use :NONE.

The FILEHDR and PHDRS keywords which may appear after the program header type also indicate contents of the segment of memory. The FILEHDR keyword means that the segment should include the ELF file header. The PHDRS keyword means that the segment should include the ELF program headers themselves.

The type may be one of the following. The numbers indicate the value of the keyword.

PT_NULL (0)

Indicates an unused program header.

PT_LOAD (1)

Indicates that this program header describes a segment to be loaded from the file.

PT_DYNAMIC (2)

Indicates a segment where dynamic linking information can be found.

PT_INTERP (3)

Indicates a segment where the name of the program interpreter may be found.

```
PT_NOTE (4)
Indicates a segment holding note information.

PT_SHLIB (5)
A reserved program header type, defined but not specified by the ELF ABI.

PT_PHDR (6)
Indicates a segment where the program headers may be found.
```

expression An expression giving the numeric type of the program header. This may be used for types not defined above.

It is possible to specify that a segment should be loaded at a particular address in memory. This is done using an AT expression. This is identical to the AT command used in the SECTIONS command (see Section 3.4.4 [Section Options], page 32). Using the AT command for a program header overrides any information in the SECTIONS command.

Normally the segment flags are set based on the sections. The FLAGS keyword may be used to explicitly specify the segment flags. The value of flags must be an integer. It is used to set the p_flags field of the program header.

Here is an example of the use of PHDRS. This shows a typical set of program headers used on a native ELF system.

```
PHDRS
  headers PT_PHDR PHDRS;
  interp PT_INTERP ;
  text PT_LOAD FILEHDR PHDRS ;
  data PT_LOAD ;
  dynamic PT_DYNAMIC ;
}
SECTIONS
  . = SIZEOF_HEADERS;
  .interp : { *(.interp) } :text :interp
  .text : { *(.text) } :text
  .rodata : { *(.rodata) } /* defaults to :text */
  . = . + 0x1000; /* move to a new page in memory */
  .data : { *(.data) } :data
  .dynamic : { *(.dynamic) } :data :dynamic
}
```

3.6 The Entry Point

The linker command language includes a command specifically for defining the first executable instruction in an output file (its entry point). Its argument is a symbol name:

```
ENTRY (symbol)
```

Like symbol assignments, the ENTRY command may be placed either as an independent command in the command file, or among the section definitions within the SECTIONS command—whatever makes the most sense for your layout.

ENTRY is only one of several ways of choosing the entry point. You may indicate it in any of the following ways (shown in descending order of priority: methods higher in the list override methods lower down).

- the '-e' entry command-line option;
- the ENTRY(symbol) command in a linker control script;
- the value of the symbol start, if present;
- the address of the first byte of the .text section, if present;
- The address 0.

For example, you can use these rules to generate an entry point with an assignment statement: if no symbol start is defined within your input files, you can simply define it, assigning it an appropriate value—

```
start = 0x2020;
```

The example shows an absolute address, but you can use any expression. For example, if your input object files use some other symbol-name convention for the entry point, you can just assign the value of whatever symbol contains the start address to start:

```
start = other_symbol ;
```

3.7 Version Script

The linker command script includes a command specifically for specifying a version script, and is only meaningful for ELF platforms that support shared libraries. A version script can be build directly into the linker script that you are using, or you can supply the version script as just another input file to the linker at the time that you link. The command script syntax is:

```
VERSION { version script contents }
```

The version script can also be specified to the linker by means of the '--version-script' linker command line option. Version scripts are only meaningful when creating shared libraries.

The format of the version script itself is identical to that used by Sun's linker in Solaris 2.5. Versioning is done by defining a tree of version nodes with the names and interdependencies specified in the version script. The version script can specify which symbols are bound to which version nodes, and it can reduce a specified set of symbols to local scope so that they are not globally visible outside of the shared library.

The easiest way to demonstrate the version script language is with a few examples.

```
VERS_1.1 {
  global:
  foo1;
  local:
  old*;
  original*;
```

```
new*;
};

VERS_1.2 {
  foo2;
} VERS_1.1;

VERS_2.0 {
  bar1; bar2;
} VERS_1.2;
```

In this example, three version nodes are defined. 'VERS_1.1' is the first version node defined, and has no other dependencies. The symbol 'foo1' is bound to this version node, and a number of symbols that have appeared within various object files are reduced in scope to local so that they are not visible outside of the shared library.

Next, the node 'VERS_1.2' is defined. It depends upon 'VERS_1.1'. The symbol 'foo2' is bound to this version node.

Finally, the node 'VERS_2.0' is defined. It depends upon 'VERS_1.2'. The symbols 'bar1' and 'bar2' are bound to this version node.

Symbols defined in the library which aren't specifically bound to a version node are effectively bound to an unspecified base version of the library. It is possible to bind all otherwise unspecified symbols to a given version node using 'global: *' somewhere in the version script.

Lexically the names of the version nodes have no specific meaning other than what they might suggest to the person reading them. The '2.0' version could just as well have appeared in between '1.1' and '1.2'. However, this would be a confusing way to write a version script.

When you link an application against a shared library that has versioned symbols, the application itself knows which version of each symbol it requires, and it also knows which version nodes it needs from each shared library it is linked against. Thus at runtime, the dynamic loader can make a quick check to make sure that the libraries you have linked against do in fact supply all of the version nodes that the application will need to resolve all of the dynamic symbols. In this way it is possible for the dynamic linker to know with certainty that all external symbols that it needs will be resolvable without having to search for each symbol reference.

The symbol versioning is in effect a much more sophisticated way of doing minor version checking that SunOS does. The fundamental problem that is being addressed here is that typically references to external functions are bound on an as-needed basis, and are not all bound when the application starts up. If a shared library is out of date, a required interface may be missing; when the application tries to use that interface, it may suddenly and unexpectedly fail. With symbol versioning, the user will get a warning when they start their program if the libraries being used with the application are too old.

There are several GNU extensions to Sun's versioning approach. The first of these is the ability to bind a symbol to a version node in the source file where the symbol is defined instead of in the versioning script. This was done mainly to reduce the burden on the library maintainer. This can be done by putting something like:

```
__asm__(".symver original_foo,foo@VERS_1.1");
```

in the C source file. This renamed the function 'original_foo' to be an alias for 'foo' bound to the version node 'VERS_1.1'. The 'local:' directive can be used to prevent the symbol 'original_foo' from being exported.

The second GNU extension is to allow multiple versions of the same function to appear in a given shared library. In this way an incompatible change to an interface can take place without increasing the major version number of the shared library, while still allowing applications linked against the old interface to continue to function.

This can only be accomplished by using multiple '.symver' directives in the assembler. An example of this would be:

```
__asm__(".symver original_foo,foo@");
__asm__(".symver old_foo,foo@VERS_1.1");
__asm__(".symver old_foo1,foo@VERS_1.2");
__asm__(".symver new_foo,foo@@VERS_2.0");
```

In this example, 'foo@' represents the symbol 'foo' bound to the unspecified base version of the symbol. The source file that contains this example would define 4 C functions: 'original_foo', 'old_foo', 'old_foo1', and 'new_foo'.

When you have multiple definitions of a given symbol, there needs to be some way to specify a default version to which external references to this symbol will be bound. This can be accomplished with the 'foo@@VERS_2.0' type of '.symver' directive. Only one version of a symbol can be declared 'default' in this manner - otherwise you would effectively have multiple definitions of the same symbol.

If you wish to bind a reference to a specific version of the symbol within the shared library, you can use the aliases of convenience (i.e. 'old_foo'), or you can use the '.symver' directive to specifically bind to an external version of the function in question.

3.8 Option Commands

The command language includes a number of other commands that you can use for specialized purposes. They are similar in purpose to command-line options.

CONSTRUCTORS

When linking using the a.out object file format, the linker uses an unusual set construct to support C++ global constructors and destructors. When linking object file formats which do not support arbitrary sections, such as ECOFF and XCOFF, the linker will automatically recognize C++ global constructors and destructors by name. For these object file formats, the CONSTRUCTORS command tells the linker where this information should be placed. The CONSTRUCTORS command is ignored for other object file formats.

The symbol __CTOR_LIST__ marks the start of the global constructors, and the symbol __DTOR_LIST marks the end. The first word in the list is the number of entries, followed by the address of each constructor or destructor, followed by a zero word. The compiler must arrange to actually run the code. For these object file formats GNU C++ calls constructors from a subroutine __main; a call to __main is automatically inserted into the startup code for main. GNU C++ runs destructors either by using atexit, or directly from the function exit.

For object file formats such as COFF or ELF which support multiple sections, GNU C++ will normally arrange to put the addresses of global constructors and destructors into the .ctors and .dtors sections. Placing the following sequence into your linker script will build the sort of table which the GNU C++ runtime code expects to see.

```
__CTOR_LIST__ = .;

LONG((__CTOR_END__ - __CTOR_LIST__) / 4 - 2)

*(.ctors)

LONG(0)

__CTOR_END__ = .;

__DTOR_LIST__ = .;

LONG((__DTOR_END__ - __DTOR_LIST__) / 4 - 2)

*(.dtors)

LONG(0)

__DTOR_END__ = .;
```

Normally the compiler and linker will handle these issues automatically, and you will not need to concern yourself with them. However, you may need to consider this if you are using C++ and writing your own linker scripts.

FLOAT

NOFLOAT

These keywords were used in some older linkers to request a particular math subroutine library. 1d doesn't use the keywords, assuming instead that any necessary subroutines are in libraries specified using the general mechanisms for linking to archives; but to permit the use of scripts that were written for the older linkers, the keywords FLOAT and NOFLOAT are accepted and ignored.

FORCE_COMMON_ALLOCATION

This command has the same effect as the '-d' command-line option: to make ld assign space to common symbols even if a relocatable output file is specified ('-r').

INCLUDE filename

Include the linker script filename at this point. The file will be searched for in the current directory, and in any directory specified with the -L option. You can nest calls to INCLUDE up to 10 levels deep.

```
INPUT ( file, file, ...)
INPUT ( file file ...)
```

Use this command to include binary input files in the link, without including them in a particular section definition. Specify the full name for each file, including '.a' if required.

1d searches for each file through the archive-library search path, just as for files you specify on the command line. See the description of '-L' in Section 2.1 [Command Line Options], page 3.

If you use '-lfile', ld will transform the name to libfile.a as with the command line argument '-l'.

```
GROUP ( file, file, ...)
GROUP ( file file ...)
```

This command is like INPUT, except that the named files should all be archives, and they are searched repeatedly until no new undefined references are created. See the description of '-(' in Section 2.1 [Command Line Options], page 3.

OUTPUT (filename)

Use this command to name the link output file *filename*. The effect of OUTPUT(*filename*) is identical to the effect of '-o *filename*', which overrides it. You can use this command to supply a default output-file name other than a.out.

OUTPUT_ARCH (bfdname)

Specify a particular output machine architecture, with one of the names used by the BFD back-end routines (see Chapter 5 [BFD], page 47). This command is often unnecessary; the architecture is most often set implicitly by either the system BFD configuration or as a side effect of the OUTPUT_FORMAT command.

OUTPUT_FORMAT (bfdname)

When 1d is configured to support multiple object code formats, you can use this command to specify a particular output format. bfdname is one of the names used by the BFD back-end routines (see Chapter 5 [BFD], page 47). The effect is identical to the effect of the '--oformat' command-line option. This selection affects only the output file; the related command TARGET affects primarily input files.

SEARCH_DIR (path)

Add path to the list of paths where ld looks for archive libraries. SEARCH_DIR(path) has the same effect as '-Lpath' on the command line.

STARTUP (filename)

Ensure that filename is the first input file used in the link process.

TARGET (format)

When ld is configured to support multiple object code formats, you can use this command to change the input-file object code format (like the command-line option '-b' or its synonym '--format'). The argument format is one of the strings used by BFD to name binary formats. If TARGET is specified but OUTPUT_FORMAT is not, the last TARGET argument is also used as the default format for the ld output file. See Chapter 5 [BFD], page 47.

If you don't use the TARGET command, 1d uses the value of the environment variable GNUTARGET, if available, to select the output file format. If that variable is also absent, 1d uses the default format configured for your machine in the BFD libraries.

NOCROSSREFS (section section ...)

This command may be used to tell 1d to issue an error about any references among certain sections.

In certain types of programs, particularly on embedded systems, when one section is loaded into memory, another section will not be. Any direct references

between the two sections would be errors. For example, it would be an error if code in one section called a function defined in the other section.

The NOCROSSREFS command takes a list of section names. If 1d detects any cross references between the sections, it reports an error and returns a non-zero exit status. The NOCROSSREFS command uses output section names, defined in the SECTIONS command. It does not use the names of input sections.

4 Machine Dependent Features

1d has additional features on some platforms; the following sections describe them. Machines where 1d has no additional functionality are not listed.

4.1 1d and the H8/300

For the H8/300, ld can perform these global optimizations when you specify the '--relax' command-line option.

relaxing address modes

1d finds all jsr and jmp instructions whose targets are within eight bits, and turns them into eight-bit program-counter relative bsr and bra instructions, respectively.

synthesizing instructions

1d finds all mov.b instructions which use the sixteen-bit absolute address form, but refer to the top page of memory, and changes them to use the eight-bit address form. (That is: the linker turns 'mov.b @aa:16' into 'mov.b @aa:8' whenever the address aa is in the top page of memory).

4.2 1d and the Intel 960 family

You can use the '-Aarchitecture' command line option to specify one of the two-letter names identifying members of the 960 family; the option specifies the desired output target, and warns of any incompatible instructions in the input files. It also modifies the linker's search strategy for archive libraries, to support the use of libraries specific to each particular architecture, by including in the search loop names suffixed with the string identifying the architecture.

For example, if your 1d command line included '-ACA' as well as '-ltry', the linker would look (in its built-in search paths, and in any paths you specify with '-L') for a library with the names

```
try
libtry.a
tryca
libtryca.a
```

The first two possibilities would be considered in any event; the last two are due to the use of '-ACA'.

You can meaningfully use '-A' more than once on a command line, since the 960 architecture family allows combination of target architectures; each use will add another pair of name variants to search for when '-1' specifies a library.

ld supports the '--relax' option for the i960 family. If you specify '--relax', ld finds all balx and calx instructions whose targets are within 24 bits, and turns them into 24-bit program-counter relative bal and cal instructions, respectively. ld also turns cal instructions into bal instructions when it determines that the target subroutine is a leaf routine (that is, the target subroutine does not itself call any subroutines).

Chapter 5: BFD

5 BFD

The linker accesses object and archive files using the BFD libraries. These libraries allow the linker to use the same routines to operate on object files whatever the object file format. A different object file format can be supported simply by creating a new BFD back end and adding it to the library. To conserve runtime memory, however, the linker and associated tools are usually configured to support only a subset of the object file formats available. You can use objdump -i (see section "objdump" in The GNU Binary Utilities) to list all the formats available for your configuration.

As with most implementations, BFD is a compromise between several conflicting requirements. The major factor influencing BFD design was efficiency: any time used converting between formats is time which would not have been spent had BFD not been involved. This is partly offset by abstraction payback; since BFD simplifies applications and back ends, more time and care may be spent optimizing algorithms for a greater speed.

One minor artifact of the BFD solution which you should bear in mind is the potential for information loss. There are two places where useful information can be lost using the BFD mechanism: during conversion and during output. See Section 5.1.1 [BFD information loss], page 47.

5.1 How it works: an outline of BFD

When an object file is opened, BFD subroutines automatically determine the format of the input object file. They then build a descriptor in memory with pointers to routines that will be used to access elements of the object file's data structures.

As different information from the the object files is required, BFD reads from different sections of the file and processes them. For example, a very common operation for the linker is processing symbol tables. Each BFD back end provides a routine for converting between the object file's representation of symbols and an internal canonical format. When the linker asks for the symbol table of an object file, it calls through a memory pointer to the routine from the relevant BFD back end which reads and converts the table into a canonical form. The linker then operates upon the canonical form. When the link is finished and the linker writes the output file's symbol table, another BFD back end routine is called to take the newly created symbol table and convert it into the chosen output format.

5.1.1 Information Loss

Information can be lost during output. The output formats supported by BFD do not provide identical facilities, and information which can be described in one form has nowhere to go in another format. One example of this is alignment information in b.out. There is nowhere in an a.out format file to store alignment information on the contained data, so when a file is linked from b.out and an a.out image is produced, alignment information will not propagate to the output file. (The linker will still use the alignment information internally, so the link is performed correctly).

Another example is COFF section names. COFF files may contain an unlimited number of sections, each one with a textual section name. If the target of the link is a format which

does not have many sections (e.g., a.out) or has sections without names (e.g., the Oasys format), the link cannot be done simply. You can circumvent this problem by describing the desired input-to-output section mapping with the linker command language.

Information can be lost during canonicalization. The BFD internal canonical form of the external formats is not exhaustive; there are structures in input formats for which there is no direct representation internally. This means that the BFD back ends cannot maintain all possible data richness through the transformation between external to internal and back to external formats.

This limitation is only a problem when an application reads one format and writes another. Each BFD back end is responsible for maintaining as much data as possible, and the internal BFD canonical form has structures which are opaque to the BFD core, and exported only to the back ends. When a file is read in one format, the canonical form is generated for BFD and the application. At the same time, the back end saves away any information which may otherwise be lost. If the data is then written back in the same format, the back end routine will be able to use the canonical form provided by the BFD core as well as the information it prepared earlier. Since there is a great deal of commonality between back ends, there is no information lost when linking or copying big endian COFF to little endian COFF, or a.out to b.out. When a mixture of formats is linked, the information is only lost from the files whose format differs from the destination.

5.1.2 The BFD canonical object-file format

The greatest potential for loss of information occurs when there is the least overlap between the information provided by the source format, that stored by the canonical format, and that needed by the destination format. A brief description of the canonical form may help you understand which kinds of data you can count on preserving across conversions.

files

Information stored on a per-file basis includes target machine architecture, particular implementation format type, a demand pageable bit, and a write protected bit. Information like Unix magic numbers is not stored here—only the magic numbers' meaning, so a ZMAGIC file would have both the demand pageable bit and the write protected text bit set. The byte order of the target is stored on a per-file basis, so that big- and little-endian object files may be used with one another.

sections

Each section in the input file contains the name of the section, the section's original address in the object file, size and alignment information, various flags, and pointers into other BFD data structures.

symbols

Each symbol contains a pointer to the information for the object file which originally defined it, its name, its value, and various flag bits. When a BFD back end reads in a symbol table, it relocates all symbols to make them relative to the base of the section where they were defined. Doing this ensures that each symbol points to its containing section. Each symbol also has a varying amount of hidden private data for the BFD back end. Since the symbol points to the original file, the private data format for that symbol is accessible. 1d can operate on a collection of symbols of wildly different formats without problems.

Normal global and simple local symbols are maintained on output, so an output file (no matter its format) will retain symbols pointing to functions and to global, static, and common variables. Some symbol information is not worth retaining; in a.out, type information is stored in the symbol table as long symbol names. This information would be useless to most COFF debuggers; the linker has command line switches to allow users to throw it away.

There is one word of type information within the symbol, so if the format supports symbol type information within symbols (for example, COFF, IEEE, Oasys) and the type is simple enough to fit within one word (nearly everything but aggregates), the information will be preserved.

relocation level

Each canonical BFD relocation record contains a pointer to the symbol to relocate to, the offset of the data to relocate, the section the data is in, and a pointer to a relocation type descriptor. Relocation is performed by passing messages through the relocation type descriptor and the symbol pointer. Therefore, relocations can be performed on output data using a relocation method that is only available in one of the input formats. For instance, Oasys provides a byte relocation format. A relocation record requesting this relocation type would point indirectly to a routine to perform this, so the relocation may be performed on a byte being written to a 68k COFF file, even though 68k COFF has no such relocation type.

line numbers

Object formats can contain, for debugging purposes, some form of mapping between symbols, source line numbers, and addresses in the output file. These addresses have to be relocated along with the symbol information. Each symbol with an associated list of line number records points to the first record of the list. The head of a line number list consists of a pointer to the symbol, which allows finding out the address of the function whose line number is being described. The rest of the list is made up of pairs: offsets into the section and line numbers. Any format which can simply derive this information can pass it successfully between formats (COFF, IEEE and Oasys).

6 Reporting Bugs

Your bug reports play an essential role in making 1d reliable.

Reporting a bug may help you by bringing a solution to your problem, or it may not. But in any case the principal function of a bug report is to help the entire community by making the next version of 1d work better. Bug reports are your contribution to the maintenance of 1d.

In order for a bug report to serve its purpose, you must include the information that enables us to fix the bug.

6.1 Have you found a bug?

If you are not sure whether you have found a bug, here are some guidelines:

- If the linker gets a fatal signal, for any input whatever, that is a ld bug. Reliable linkers never crash.
- If ld produces an error message for valid input, that is a bug.
- If 1d does not produce an error message for invalid input, that may be a bug. In the general case, the linker can not verify that object files are correct.
- If you are an experienced user of linkers, your suggestions for improvement of 1d are welcome in any case.

6.2 How to report bugs

A number of companies and individuals offer support for GNU products. If you obtained 1d from a support organization, we recommend you contact that organization first.

You can find contact information for many support companies and individuals in the file 'etc/SERVICE' in the GNU Emacs distribution.

In any event, we also recommend that you send bug reports for ld to 'bug-gnu-utils@gnu.org'. The fundamental principle of reporting bugs usefully is this: report all the facts. If you are not sure whether to state a fact or leave it out, state it!

Often people omit facts because they think they know what causes the problem and assume that some details do not matter. Thus, you might assume that the name of a symbol you use in an example does not matter. Well, probably it does not, but one cannot be sure. Perhaps the bug is a stray memory reference which happens to fetch from the location where that name is stored in memory; perhaps, if the name were different, the contents of that location would fool the linker into doing the right thing despite the bug. Play it safe and give a specific, complete example. That is the easiest thing for you to do, and the most helpful.

Keep in mind that the purpose of a bug report is to enable us to fix the bug if it is new to us. Therefore, always write your bug reports on the assumption that the bug has not been reported previously.

Sometimes people give a few sketchy facts and ask, "Does this ring a bell?" Those bug reports are useless, and we urge everyone to refuse to respond to them except to chide the sender to report bugs properly.

To enable us to fix the bug, you should include all these things:

- The version of ld. ld announces it if you start it with the '--version' argument. Without this, we will not know whether there is any point in looking for the bug in the current version of ld.
- Any patches you may have applied to the ld source, including any patches made to the BFD library.
- The type of machine you are using, and the operating system name and version number.
- What compiler (and its version) was used to compile 1d—e.g. "gcc-2.7".
- The command arguments you gave the linker to link your example and observe the bug. To guarantee you will not omit something important, list them all. A copy of the Makefile (or the output from make) is sufficient.
 - If we were to try to guess the arguments, we would probably guess wrong and then we might not encounter the bug.
- A complete input file, or set of input files, that will reproduce the bug. It is generally most helpful to send the actual object files, unencoded if necessary to get them through the mail system. Making them available for anonymous FTP is not as good, but may be the only reasonable choice for large object files.
 - If the source files were assembled using gas or compiled using gcc, then it may be OK to send the source files rather than the object files. In this case, be sure to say exactly what version of gas or gcc was used to produce the object files. Also say how gas or gcc were configured.
- A description of what behavior you observe that you believe is incorrect. For example, "It gets a fatal signal."
 - Of course, if the bug is that ld gets a fatal signal, then we will certainly notice it. But if the bug is incorrect output, we might not notice unless it is glaringly wrong. You might as well not give us a chance to make a mistake.
 - Even if the problem you experience is a fatal signal, you should still say so explicitly. Suppose something strange is going on, such as, your copy of 1d is out of synch, or you have encountered a bug in the C library on your system. (This has happened!) Your copy might crash and ours would not. If you told us to expect a crash, then when ours fails to crash, we would know that the bug was not happening for us. If you had not told us to expect a crash, then we would not be able to draw any conclusion from our observations.
- If you wish to suggest changes to the ld source, send us context diffs, as generated by diff with the '-u', '-c', or '-p' option. Always send diffs from the old file to the new file. If you even discuss something in the ld source, refer to it by context, not by line number.

The line numbers in our development sources will not match those in your sources. Your line numbers would convey no useful information to us.

Here are some things that are not necessary:

• A description of the envelope of the bug.

Often people who encounter a bug spend a lot of time investigating which changes to the input file will make the bug go away and which changes will not affect it.

This is often time consuming and not very useful, because the way we will find the bug is by running a single example under the debugger with breakpoints, not by pure deduction from a series of examples. We recommend that you save your time for something else.

Of course, if you can find a simpler example to report *instead* of the original one, that is a convenience for us. Errors in the output will be easier to spot, running under the debugger will take less time, and so on.

However, simplification is not vital; if you do not want to do this, report the bug anyway and send us the entire test case you used.

• A patch for the bug.

A patch for the bug does help us if it is a good one. But do not omit the necessary information, such as the test case, on the assumption that a patch is all we need. We might see problems with your patch and decide to fix the problem another way, or we might not understand it at all.

Sometimes with a program as complicated as 1d it is very hard to construct an example that will make the program follow a certain path through the code. If you do not send us the example, we will not be able to construct one, so we will not be able to verify that the bug is fixed.

And if we cannot understand what bug you are trying to fix, or why your patch should be an improvement, we will not install it. A test case will help us to understand.

• A guess about what the bug is or what it depends on.

Such guesses are usually wrong. Even we cannot guess right about such things without first using the debugger to find the facts.

Appendix A MRI Compatible Script Files

To aid users making the transition to GNU 1d from the MRI linker, 1d can use MRI compatible linker scripts as an alternative to the more general-purpose linker scripting language described in Chapter 3 [Command Language], page 19. MRI compatible linker scripts have a much simpler command set than the scripting language otherwise used with 1d. GNU 1d supports the most commonly used MRI linker commands; these commands are described here

In general, MRI scripts aren't of much use with the a.out object file format, since it only has three sections and MRI scripts lack some features to make use of them.

You can specify a file containing an MRI-compatible script using the '-c' command-line option.

Each command in an MRI-compatible script occupies its own line; each command line starts with the keyword that identifies the command (though blank lines are also allowed for punctuation). If a line of an MRI-compatible script begins with an unrecognized keyword, 1d issues a warning message, but continues processing the script.

Lines beginning with '*' are comments.

You can write these commands using all upper-case letters, or all lower case; for example, 'chip' is the same as 'CHIP'. The following list shows only the upper-case form of each command.

ABSOLUTE secname

ABSOLUTE secname, secname, ... secname

Normally, 1d includes in the output file all sections from all the input files. However, in an MRI-compatible script, you can use the ABSOLUTE command to restrict the sections that will be present in your output program. If the ABSOLUTE command is used at all in a script, then only the sections named explicitly in ABSOLUTE commands will appear in the linker output. You can still use other input sections (whatever you select on the command line, or using LOAD) to resolve addresses in the output file.

ALIAS out-secname, in-secname

Use this command to place the data from input section *in-secname* in a section called *out-secname* in the linker output file.

in-secname may be an integer.

ALIGN secname = expression

Align the section called secname to expression. The expression should be a power of two.

BASE expression

Use the value of expression as the lowest address (other than absolute addresses) in the output file.

CHIP expression

CHIP expression, expression

This command does nothing; it is accepted only for compatibility.

END This command does nothing whatever; it's only accepted for compatibility.

FORMAT output-format

Similar to the OUTPUT_FORMAT command in the more general linker language, but restricted to one of these output formats:

- 1. S-records, if output-format is 'S'
- 2. IEEE, if output-format is 'IEEE'
- 3. COFF (the 'coff-m68k' variant in BFD), if output-format is 'COFF'

LIST anything...

Print (to the standard output file) a link map, as produced by the ld command-line option '-M'.

The keyword LIST may be followed by anything on the same line, with no change in its effect.

LOAD filename

LOAD filename, filename, ... filename

Include one or more object file *filename* in the link; this has the same effect as specifying *filename* directly on the 1d command line.

NAME output-name

output-name is the name for the program produced by 1d; the MRI-compatible command NAME is equivalent to the command-line option '-o' or the general script language command OUTPUT.

ORDER secname, secname, ... secname

ORDER secname secname secname

Normally, 1d orders the sections in its output file in the order in which they first appear in the input files. In an MRI-compatible script, you can override this ordering with the ORDER command. The sections you list with ORDER will appear first in your output file, in the order specified.

PUBLIC name=expression

PUBLIC name, expression

PUBLIC name expression

Supply a value (expression) for external symbol name used in the linker input files.

SECT secname, expression

SECT secname=expression

SECT secname expression

You can use any of these three forms of the SECT command to specify the start address (expression) for section secname. If you have more than one SECT statement for the same secname, only the first sets the start address.

Index 57

\mathbf{Index}

*	undefined=symbol	8
*(COMMON)29	verbose	14
*(section)	version	
	version-script=version-scriptfile	14
_	warn-comon	14
_	warn-constructors	15
-(warn-multiple-gp	15
architecture= <i>arch</i>	warn-once	16
auxiliary 5	warn-section-align	1€
cref 10	whole-archive	1€
defsym symbol=exp 10	wrap	1€
discard-all	-Aarch	4
discard-locals	-akeyword	4
dynamic-linker file 10	-assert keyword	9
embedded-relocs	-b format	4
entry=entry 5	-Bdynamic	
export-dynamic 5	-Bshareable	13
filter 5	-Bstatic	10
force-exe-suffix	-Bsymbolic	10
format=format 4	-c MRI-cmdfile	4
gpsize 6	-call_shared	
help 11	-d	4
just-symbols=file	-dc	4
library-path=dir 7	-dn	10
library=archive	-dp	4
mri-script=MRI-cmdfile	- dy	
nmagic 7	-E	5
no-keep-memory	-e entry	5
no-warn-mismatch	-EB	10
no-whole-archive	-EL	10
noinhibit-exec	-f	5
oformat	-F	5
omagic 7	-g	E
output= <i>output</i> 8	-G	€
print-map 7	-hname	<i>E</i>
relax	-i	<i>E</i>
relax on i960	-larchive	E
relocateable 8	-Ldir	7
script=script 8	-M	7
sort-common	-m emulation	7
split-by-file	-Map	11
split-by-reloc	-n	
stats	-N	7
strip-all 8	-non_shared	
strip-debug 8	-o output	
trace	-qmagic	
$\verb trace-symbol = symbol$	-Qy	
traditional-format	••	

-r 8	\mathbf{A}	
-R file 8	ABSOLUTE (MRI)	55
-rpath	absolute and relocatable symbols	22
-rpath-link 12	ABSOLUTE (exp)	23
-s 8	ADDR (section)	23
-S 8	ALIAS (MRI)	55
-shared	ALIGN (MRI)	55
-soname=name 6	ALIGN(exp)	23
-static	aligning sections	33
-t 8	allocating memory	25
-T script 8	architectures	. 4
-Tbss org	archive files, from cmd line	. 6
-Tdata org 14	arithmetic	19
-Ttext org 14	arithmetic operators	21
-u symbol	assignment in scripts	22
-Ur	assignment, in section defn	31
-ψ9	AT (ldadr)	33
-V9		
-x9	В	
-X	back end	47
-Y path 9	BASE (MRI)	
-у symbol 9	BFD canonical format	
-z keyword	BFD requirements	
	big-endian objects	
•	binary input files	
20	binary input format	
	BLOCK (align)	
•	bug criteria	
•	bug reports	
: phdr	bugs in 1d	
	BYTE (expression)	
;	2112 (e.i.p.1 easieil)	
;	\mathbf{C}	
	-	
_	C++ constructors, arranging in link	
	CHIP (MRI)	
=fill	combining symbols, warnings on	
_	command files	
	command line	
[section], not supported	commands, fundamental	
,	comments	
11	common allocation	
	commons in output	
"	compatibility, MRI	
	constructors	
>	CONSTRUCTORS	
>region	constructors, arranging in link	
	contents of a section	
0	crash of linker	
	CREATE_DBJECT_SYMBOLS	
0x	cross reference table	10

Index 59

cross references	\mathbf{G}
current output location) GNU linker
	GNUTARGET 17, 42
D	GROUP (files)
D	grouping input files
dbx	
decimal integers	
default emulation	$^{\prime}$ \mathbf{H}
default input format	⁷ H8/300 support
DEFINED (symbol)	header size
deleting local symbols	help
direct output	hexadecimal integers
discontinuous memory 25	holes
dot	
dynamic linker, from command line 10)
dynamic symbol table 5	\mathbf{I}
	i960 support
\mathbf{E}	INCLUDE filename
	including a linker script
ELF program headers	including an entire archive
emulation	in anomental link
emulation, default	INPIIT (files)
END (MRI)	input file format 49
endianness	input filoname eymbole
entry point, defaults	input files displaying
entry point, from command line	input files section defn
ENTRY (symbol)	input format
error on valid input	input sections to output section
expression evaluation order	integer notation
expression syntax	integer suffixes
expression, absolute	internal object file format
expressions in a section	invalid input51
F	K
fatal signal	_
filename	
filename (section)	,
files and sections, section defn	
files, including in output sections	
fill pattern, entire section	
FILL (expression)	
-	9 / 1
first input file	
FLOAT 41 FORCE_COMMON_ALLOCATION 41	
FORMAT (MRI)	*
format, output file	-
functions in expression language	
fundamental script commands	little-endian objects

LOAD (MRI) 56	OUTPUT (filename)
load address, specifying	output file after errors
LOADADDR(section)	output file layout
loading, preventing	OUTPUT_ARCH (bfdname)
local symbols, deleting	OUTPUT_FORMAT (bfdname)
location counter	OVERLAY
LONG (expression)	overlays
T. /I	P
\mathbf{M}	
M and K integer suffixes	partial link 8
machine architecture, output	path for libraries
machine dependencies	PHDRS 35
MAX	precedence in expressions
MEMORY 25	prevent unnecessary loading
memory region attributes	program headers
memory regions and sections	program headers and sections
memory usage	provide
MIN	PUBLIC (MRI)
MIPS embedded PIC code	100010 (191101)
MRI compatibility	Q
with companionity	•
N ⊺	QUAD (expression) 32
N	quoted symbol names
NAME (MRI) 56	D
names	\mathbf{R}
naming memory regions	read-only text 7
naming output sections	read/write from cmd line 7
naming the output file 8, 42	regions of memory
negative integers	relaxing addressing modes
NEXT(exp)24	relaxing on H8/300 45
NMAGIC 7	relaxing on i960 45
NOCROSSREFS (sections)	relocatable and absolute symbols
NOFLOAT 41	relocatable output
NOLOAD 33	reporting bugs in 1d
Non constant expression	requirements for BFD
non constant expression	retaining specified symbols
0	
	rounding up location counter
o =	runtime library name
objdump -i	runtime library search path
object file management	\mathbf{S}
object files 3	э
object formats available	scaled integers
object size6	script files
octal integers	search directory, from cmd line
OMAGIC 7	search path, libraries
opening object files	SEARCH_DIR (path)
Operators for arithmetic	SECT (MRI) 56
options	section address
ORDER (MRI) 56	section alignment
org =	section alignment, warnings on
ORIGIN =	section definition

Index 61

section defn, full syntax	symbols, from command line	10
section fill pattern 34	symbols, relocatable and absolute	22
section load address	symbols, retaining selectively	12
section size	synthesizing linker	1:
section start	synthesizing on H8/300	45
section, assigning to memory region 34		
section, assigning to program header 34	${f T}$	
SECTIONS	TARGET (format)	49
segment origins, cmd line	traditional format	
semicolon	ti aditional format	T
shared libraries	ŢIJ	
SHORT (expression)	•	
SIZEOF (section)	unallocated address, next	
sizeof_headers	undefined symbol	
SIZEOF_HEADERS	undefined symbols, warnings on	
specify load address	uninitialized data	
SQUAD (expression) 32	unspecified memory	
standard Unix system	usage	11
start address, section	\mathbf{V}	
start of execution	V	
STARTUP (filename)	variables, defining	
strip all symbols	verbose	1
strip debugger symbols 8	version	
stripping all but some symbols	VERSION {script text}	38
suffixes for integers	version script	
symbol = expression ;	version script, symbol versions	14
symbol defaults	versions of symbols	38
symbol definition, scripts		
symbol f = expression;	${f W}$	
symbol names	warnings, on combining symbols	14
symbol tracing9	warnings, on section alignment	16
symbol versions	warnings, on undefined symbols	16
symbol-only input	what is this?	-

The body of this manual is set in cmr10 at 10.95pt, with headings in cmb10 at 10.95pt and examples in cmtt10 at 10.95pt. cmti10 at 10.95pt and cmsl10 at 10.95pt are used for emphasis.