Introduction to Computer Organization

DIS 1A - WEEK 2

Today's Schedule

- x86 Organization
- x86 Assembly
- Lecture material review
- Lab 1 overview

The basic abstraction of memory that is taught in CS 31 and CS 32 is that data is stored in memory.

• For example, if you have a 32-bit addressable space, then the addresses that are in memory range from 0x00000000 to 0xFFFFFFF(2³¹-1).

It's not like you'll ever see a variable that you can't dereference in
C. Therefore variables must always be stored in memory, right?

• The variables will be stored in memory, which is a physical construct (RAM).

 However, RAM is too slow to keep up with the demands of a processor.

 Accessing RAM takes approximately 200 times the amount of time as it takes to execute a standard instruction.

• Since nearly everything involves doing some operation on a variable, we need some way of accessing memory at a speed that is comparable to the speed that it takes to execute the average instruction.

• We need caches, we need virtual memory, but for now, we'll focus on "registers".

- Registers are extremely small physical containers that each store a number of bits.
- A 64-bit addressable machine will have registers that are 64-bits.
- In such a case, each register holds 8 bytes (which is tiny), but the access time is extremely quick.
- When a program needs to work on a piece of data, it will bring it into a register first.

x86 Organization: Registers

- x86-64 contains 16 general purpose registers.
- They are identified by a short name such as (%rax, %rsi, %r8, etc.)
- In the interest of being able to access each register at a finer grain, there are multiple ways of accessing the data within each register.
- Ex. %rax refers to the full 64-bits stored in the register while %eax refers to the lower 32-bits.

x86 Organization: Registers

- h: upper 8-bits of lower 16-bits
- l: lower 8-bits
- _x :lower 16-bits.
- e_x : lower 32-bits (e stands for 'extended').
- r x : full 64-bit register

x86 Organization: Registers

 Registers are very simple containers that store a bit configuration and nothing more.

• If you know that a 64-bit signed long is stored in a register, there is nothing about this register that indicates that the original intention was for this value to be signed.

• The compiler will simply compile machine code that treats the bit vector in the register as if it were a signed value.

x86 Assembly

 AT&T's (also GNU/GAS) x86 notation (thenotation that we will use):

```
[op] [src] [dst]
```

• "Fun" fact: Intel's x86 notation:

```
[op] [dst] [src]
```

x86 Assembly

[operation] [source] [destination]

ex.

- movq %rax 4(%rbx)
- addq %rbx %rcx

x86 Assembly: Ops

The mov_ family: move data from the source to the destination. The suffix determines how much data to move.

- movb : move a byte
- movw : move a word (16 bits)
- movq : move a quad word (64 bits)
- movq %rax, %rbx
- movq %rax, (%rbx)

x86 Assembly: Ops

A comment regarding "word" size.

- A "word" is just a label of convenience that is used refer to contiguous bytes of memory of a common size.
- On a 32-bit machine, a word is 4 bytes. On a 64-bit machine, a word is 8 bytes.
- But back when registers were only 16-bits and x86 was being developed, "words" were 16-bits.

x86 Assembly: Addressing Modes

- Consider:
- movq %rax, (%rbx) <--- ?</pre>
- The parentheses indicate a memory operation.
- That is, the source and destination operands are able to refer to values that are located in memory, rather than just registers.
- The parentheses () means:
- Treat the bit vector within as a memory address.
- Go follow that address into memory and get the value at that address.

x86 Assembly: Addressing Modes

- Say %rax = 0xFEEDABBA and %rbx = 0x80.
- movq %rax, %rbx
- Result: %rax = 0xFEEDABBA, %rbx = 0xFEEDABBA
- movq %rax, (%rbx)
- Result: the value that is located in memory address 0x80 is set as 0xFEEDABBA.
- In a more C-like form, this is essentially:
- -MEM[0x80] = 0xFEEDABBA; or
- -*(0x80) = 0xFEEDABBA;

x86 Assembly: Addressing Modes

• The '\$' symbol prefix indicates an "immediate" which is constant number value.

• If %rax = 0xb1ab

- movl \$0xdea1, %rax
- Result: %rax = 0xdea1

x86 Assembly: Basic Instructions

Other instructions:

- add_ src, dst # dst = dst + src
- sub_ src, dst # dst = dst src
- neg_ dst #dst = -dst
- not dst #dst = ~dst
- sar imm, dst # dst = dst >> imm (shift arithmetic right)
- Etc...

x86 Assembly: Advanced Addressing Modes

- IMM(R1, R2, S): Scaled and displaced array access.
- Intended usage:
- R1 : Base array address
- R2 : Index into array
- S : Size of array data type in bytes
- IMM : Displacement
- movq A(B, C, D), %rax
- -%rax = *(A + B + C*D)

x86 Assembly: Advanced Addressing Modes

- D(R1): Base + displacement addressing
- If %rax = 0x10.
- movq 8(%rax), %rbx

Result: %rbx gets the value at memory address 0x10 + 8 = 0x18,
not the number 0x18

• %rbx = *(%rax + 8).

x86 Assembly: Advanced Addressing Modes

- (,R2,S) : Scaled indexing, s must be 1, 2, 4, or 8.
- If %rax = 0x01 and S = 2.
- movl (, %rax, 2), %rcx
- Result: The value at memory address 0x01 * 2 is saved to %rcx.
- IMM(R1, R2, S): Scaled and displaced array access.
- If %rax = 0x400, %rbx = 2, S = 2, and D = 20.
- movl 0x20(%rax, %rbx, 2), %rcx
- Result: The value at memory address 0x400 + 0x2*2 + 0x20 is placed in %rcx.

- It is possible to move from a smaller container to a larger container.
- Assume that %dh = 0xCD, %eax = 0x98765432
- movb %dh, %eax
- What's the result?

- It is possible to move from a smaller container to a larger container.
- Assume that %dh = 0xCD, %eax = 0x98765432
- movb %dh, %eax
- What's the result? It's not allowed (suffix mismatch).

The destination has a 32-bit length while the movb expects only to move a byte.

- movb %dh, %al
- Result: %eax = 0x987654CD

- movsXY: move and sign extend from size X to size Y.
- Ex: movsbl: move a byte from the source and sign extend it to a long (4 bytes)

- movzXY: move and zero extend from size X to size Y.
- Ex: movzbw : move a byte from the source and zero extend it to a word (2 bytes

- %dh = 0xCD, %eax = 0x98765432
- movsbl %dh, %eax
- Result: %eax = 0xFFFFFCD
- movzbl %dh, %eax
- Result: %eax = 0x000000CD
- movzbw %dh, %eax?
- Result: Not allowed. Sign extending to w (16-bits) but to %eax (32-bit container).

- As a final note about mov, the size of the prefix must match the operands. You cannot have:
- movl %ax, (%esp) // Can't move a 32-bit quantity from a 16-bit register
- movl %eax, %dx // Can't move a 32-bit quantity into a 16-bit register.

Additionally memory references match all sizes:

- movb %al, (%rbx)
- movw %ax, (%rbx)
- movq %rax, (%rbx)
- All allowed. The data will be moved to memory starting at that address based on the data type size

x86 Assembly nuances

- Certain operations are expected to work with data types that are larger than a single register can contain.
- Consider the x86-64 case. We have 64-bit registers, but in order to store a 128-bit value, we can use two registers.
- Ex: %rdx contains the upper 64-bits of the value, %rax contains the lower 64-bits of the value.
- Value = %rdx : %rax, the colon means concatenation.

x86 Assembly nuances

- imulq S:
- The register %rdx contains the upper half of R[%rax] * S.
- The register %rax contains the lower half of R[%rax] * S.
- idivq S
- %rax contains the quotient of R[%rdx]:R[%rax]/S
- %rdx contains the remainder of R[%rdx]:R[%rax]/S
- Note: none of these instructions technically specified %rax or %rdx. mulq and divq are single operand. By convention %rax and %rdx are the registers that are used in this case.


x86 Assembly: Some Context

 Hopefully at this point, the basics of assembly are clear. That is, if you see a snippet of assembly, you should be able to describe the operations that are happening.

Now, let's establish some context as to how a program is run.

Namely, memory

- What we know:
- Data is stored in memory (and in registers when we need to operate on them)
- int i = 100;
- If you do &i, you may get something like 0x7FFF4980, which is it's address in memory.
- This treats memory as if it were a single construct when in fact, it can be subdivided further.



- The main reason I brought this up:
- The program code is stored in memory. So how does the processor keep track of where it is executing?
- Naturally, with a pointer that points to the instructions location in memory.

• This pointer is stored in register %eip (in 32-bit) or %rip (in 64-bit).

• "ip" stands for instruction pointer.

• This register simply contains the address of the instruction that is to be executed (note: not the instruction itself).