powerd++ 0.4.2

Generated by Doxygen 1.8.15

1 Main Page	1
1.1 Using powerd++	2
1.1.1 Packages	2
1.1.2 Running powerd++	2
1.1.3 Manuals	2
1.1.4 Tuning	3
1.1.5 -requesting-features Reporting Issues / Requesting Features	3
1.2 Building/Installing	
1.2.1 Building	
1.2.2 Installing	4
1.2.3 Documentation	
1.3 Development	
1.3.1 Design	
1.3.2 License	5
2 LICENSE	6
3 Manual loadplay(1)	6
4 Manual loadrec(1)	9
5 Manual powerd++(8)	11
6 Module Index	16
6.1 Modules	16
7 Namespace Index	16
7.1 Namespace List	16
8 Hierarchical Index	17
8.1 Class Hierarchy	17
9 Class Index	20
9.1 Class List	20
10 File Index	22
10.1 File List	22
11 Module Documentation	23
11.1 Standard I/O File Access	23
11.1.1 Detailed Description	23
12 Namespace Documentation	23
12.1 anonymous_namespace{clas.cpp} Namespace Reference	23
12.1.1 Detailed Description	24
12.1.2 Enumeration Type Documentation	24
12.1.3 Function Documentation	25

12.1.4 Variable Documentation	25
12.2 anonymous_namespace{libloadplay.cpp} Namespace Reference	25
12.2.1 Detailed Description	27
12.2.2 Class Documentation	27
12.2.3 Typedef Documentation	28
12.2.4 Function Documentation	29
12.2.5 Variable Documentation	32
12.3 anonymous_namespace{loadplay.cpp} Namespace Reference	33
12.3.1 Detailed Description	33
12.3.2 Enumeration Type Documentation	33
12.3.3 Function Documentation	34
12.3.4 Variable Documentation	35
12.4 anonymous_namespace{loadrec.cpp} Namespace Reference	35
12.4.1 Detailed Description	36
12.4.2 Typedef Documentation	36
12.4.3 Enumeration Type Documentation	37
12.4.4 Function Documentation	37
12.4.5 Variable Documentation	38
12.5 anonymous_namespace{powerd++.cpp} Namespace Reference	39
12.5.1 Detailed Description	40
12.5.2 Class Documentation	40
12.5.3 Enumeration Type Documentation	43
12.5.4 Function Documentation	44
12.5.5 Variable Documentation	47
12.6 clas Namespace Reference	48
12.6.1 Detailed Description	48
12.6.2 Function Documentation	49
12.7 constants Namespace Reference	52
12.7.1 Detailed Description	52
12.7.2 Variable Documentation	52
12.8 errors Namespace Reference	53
12.8.1 Detailed Description	53
12.8.2 Class Documentation	54
12.8.3 Enumeration Type Documentation	54
12.8.4 Function Documentation	55
12.8.5 Variable Documentation	55
12.9 nih Namespace Reference	56
12.9.1 Detailed Description	56
12.9.2 Class Documentation	56
12.9.3 Function Documentation	57
12.10 sys Namespace Reference	58
12.10.1 Detailed Description	58

12.11 sys::ctl Namespace Reference	58
12.11.1 Detailed Description	59
12.11.2 Class Documentation	60
12.11.3 Typedef Documentation	60
12.11.4 Function Documentation	60
12.12 sys::env Namespace Reference	63
12.12.1 Detailed Description	63
12.12.2 Class Documentation	63
12.12.3 Variable Documentation	63
12.13 sys::io Namespace Reference	64
12.13.1 Detailed Description	65
12.13.2 Class Documentation	65
12.13.3 Typedef Documentation	67
12.13.4 Enumeration Type Documentation	67
12.13.5 Variable Documentation	68
12.14 sys::pid Namespace Reference	69
12.14.1 Detailed Description	69
12.14.2 Class Documentation	69
12.15 sys::sig Namespace Reference	69
12.15.1 Detailed Description	70
12.15.2 Class Documentation	
12.16 timing Namespace Reference	
12.16.1 Detailed Description	70
12.17 types Namespace Reference	70
12.17.1 Detailed Description	
12.17.2 Typedef Documentation	
12.18 utility Namespace Reference	
12.18.1 Detailed Description	72
12.18.2 Function Documentation	72
12.19 utility::literals Namespace Reference	
12.19.1 Detailed Description	
12.19.2 Function Documentation	
12.20 version Namespace Reference	74
12.20.1 Detailed Description	
12.20.2 Enumeration Type Documentation	
12.21 version::literals Namespace Reference	75
12.21.1 Detailed Description	
12.21.2 Function Documentation	76
13 Class Documentation	76
$13.1\ an onymous\_name space \{libload play.cpp\} :: Callback < Function Args > Class\ Template\ Reference and the control of t$	e 76
13.1.1 Detailed Description	77
13.1.2 Constructor & Destructor Documentation	77

13.1.3 Member Function Documentation	/8
13.2 sys::io::contains < set < Set >, Value > Struct Template Reference	78
13.2.1 Detailed Description	79
13.3 sys::io::query::contains_ftor Struct Reference	79
13.3.1 Detailed Description	80
13.3.2 Member Function Documentation	80
13.4 timing::Cycle Class Reference	8
13.4.1 Detailed Description	82
13.4.2 Member Function Documentation	82
13.5 anonymous_namespace{libloadplay.cpp}::Emulator Class Reference	83
13.5.1 Detailed Description	84
13.5.2 Class Documentation	84
13.5.3 Constructor & Destructor Documentation	85
13.5.4 Member Function Documentation	85
13.5.5 Member Data Documentation	86
13.6 sys::io::enable_if< bool, T > Struct Template Reference	86
13.6.1 Detailed Description	86
13.7 sys::io::enable_if< false, T $>$ Struct Template Reference	87
13.7.1 Detailed Description	87
13.8 nih::enum_has_members < OptionT, class > Struct Template Reference	87
13.8.1 Detailed Description	88
13.9 sys::io::file< link, Features > Class Template Reference	89
13.9.1 Detailed Description	9(
13.9.2 Constructor & Destructor Documentation	90
13.9.3 Member Function Documentation	92
13.10 sys::io::file< own, Features > Class Template Reference	93
13.10.1 Detailed Description	94
13.10.2 Constructor & Destructor Documentation	95
13.10.3 Member Function Documentation	96
13.11 sys::io::file_feature < FileT, > Class Template Reference	98
13.11.1 Detailed Description	98
13.11.2 Constructor & Destructor Documentation	99
13.11.3 Member Function Documentation	99
13.12 sys::io::file_feature< FileT, read, Tail > Class Template Reference	100
13.12.1 Detailed Description	102
13.12.2 Member Function Documentation	102
13.13 sys::io::file_feature< FileT, seek, Tail > Class Template Reference	105
13.13.1 Detailed Description	106
13.13.2 Member Function Documentation	106
13.14 sys::io::file_feature< FileT, write, Tail > Class Template Reference	108
13.14.1 Detailed Description	109
13.14.2 Member Function Documentation	11(

$13.15 \ utility :: Formatter < Buf Size > Class \ Template \ Reference \\ \ \dots \dots$
13.15.1 Detailed Description
13.15.2 Member Function Documentation
13.16 anonymous_namespace{libloadplay.cpp}::Report::Frame Class Reference
13.16.1 Detailed Description
13.16.2 Constructor & Destructor Documentation
13.16.3 Member Function Documentation
13.17 anonymous_namespace{powerd++.cpp}::FreqGuard Class Reference
13.17.1 Detailed Description
$13.18\ anonymous\_namespace \{libload play.cpp\} :: Hold < T > Class\ Template\ Reference \ \dots \ \dots \ 118 \}$
13.18.1 Detailed Description
13.18.2 Constructor & Destructor Documentation
13.18.3 Member Data Documentation
13.19 sys::io::is_superset_of< LSetT, set< RSet $>>$ Struct Template Reference
13.19.1 Detailed Description
13.20 anonymous_namespace{libloadplay.cpp}::Main Class Reference
13.20.1 Detailed Description
13.20.2 Constructor & Destructor Documentation
13.21 utility:: $Max < T > Class$ Template Reference
13.21.1 Detailed Description
13.21.2 Constructor & Destructor Documentation
13.21.3 Member Function Documentation
13.22 anonymous_namespace{libloadplay.cpp}::mib_t Struct Reference
13.22.1 Detailed Description
13.22.2 Constructor & Destructor Documentation
13.22.3 Member Function Documentation
13.23 utility:: $Min < T > Class$ Template Reference
13.23.1 Detailed Description
13.23.2 Constructor & Destructor Documentation
13.23.3 Member Function Documentation
13.24 sys::ctl::Once $<$ T, SysctlT $>$ Class Template Reference
13.24.1 Detailed Description
13.24.2 Constructor & Destructor Documentation
13.24.3 Member Function Documentation
13.25 nih::Options < Option T, Def Count > Class Template Reference
13.25.1 Detailed Description
13.25.2 Constructor & Destructor Documentation
13.25.3 Member Function Documentation
13.25.4 Member Data Documentation
13.26 sys::pid::Pidfile Class Reference
13.26.1 Detailed Description
13.26.2 Constructor & Destructor Documentation

1	3.26.3 Member Function Documentation	140
1	3.26.4 Member Data Documentation	140
13.27 a	nonymous_namespace{libloadplay.cpp}::Report Class Reference	141
1	3.27.1 Detailed Description	142
1	3.27.2 Constructor & Destructor Documentation	142
1	3.27.3 Member Function Documentation	142
13.28 s	ys::sc_error< Domain > Struct Template Reference	143
1	3.28.1 Detailed Description	143
1	3.28.2 Member Function Documentation	143
13.29 s	ys::sig::Signal Class Reference	144
1	3.29.1 Detailed Description	144
1	3.29.2 Constructor & Destructor Documentation	144
13.30 u	tility::Sum $<$ T $>$ Class Template Reference	145
1	3.30.1 Detailed Description	146
1	3.30.2 Constructor & Destructor Documentation	146
1	3.30.3 Member Function Documentation	146
13.31 s	ys::ctl::Sync< T, SysctlT > Class Template Reference	147
1	3.31.1 Detailed Description	147
1	3.31.2 Constructor & Destructor Documentation	148
1	3.31.3 Member Function Documentation	148
13.32 s	ys::ctl::Sysctl< MibDepth > Class Template Reference	149
1	3.32.1 Detailed Description	150
1	3.32.2 Constructor & Destructor Documentation	150
1	3.32.3 Member Function Documentation	151
13.33 s	ys::ctl::Sysctl< 0 > Class Template Reference	153
1	3.33.1 Detailed Description	154
	3.33.2 Constructor & Destructor Documentation	
1	3.33.3 Member Function Documentation	155
13.34 a	nonymous_namespace{libloadplay.cpp}::Sysctls Class Reference	157
1	3.34.1 Detailed Description	158
1	3.34.2 Member Function Documentation	158
1	3.34.3 Member Data Documentation	160
13.35 a	nonymous_namespace{libloadplay.cpp}::SysctlValue Class Reference	161
1	3.35.1 Detailed Description	162
1	3.35.2 Constructor & Destructor Documentation	162
1	3.35.3 Member Function Documentation	163
1	3.35.4 Member Data Documentation	168
13.36 s	ys::env::Var Class Reference	169
	3.36.1 Detailed Description	
1	3.36.2 Constructor & Destructor Documentation	170
1	3.36.3 Member Function Documentation	170
13 37 c	vsenvVars Struct Reference	172

13.37.1 Detailed Description	172
13.37.2 Member Function Documentation	172
14 File Documentation 1	73
14.1 src/clas.hpp File Reference	173
14.1.1 Detailed Description	175
14.2 src/constants.hpp File Reference	175
14.2.1 Detailed Description	177
14.3 src/Cycle.hpp File Reference	177
14.3.1 Detailed Description	178
14.4 src/errors.hpp File Reference	178
14.4.1 Detailed Description	179
14.4.2 Class Documentation	179
14.5 src/libloadplay.cpp File Reference	180
14.5.1 Detailed Description	182
14.5.2 Class Documentation	183
14.5.3 Function Documentation	185
14.6 src/loadplay.cpp File Reference	189
14.6.1 Detailed Description	190
14.6.2 Function Documentation	190
14.7 src/loadrec.cpp File Reference	190
14.7.1 Detailed Description	192
14.7.2 Function Documentation	192
14.8 src/Options.hpp File Reference	194
14.8.1 Detailed Description	195
14.8.2 Class Documentation	197
14.9 src/powerd++.cpp File Reference	197
14.9.1 Detailed Description	199
14.9.2 Class Documentation	200
14.9.3 Function Documentation	203
14.10 src/sys/env.hpp File Reference	204
14.10.1 Detailed Description	205
14.10.2 Class Documentation	205
14.11 src/sys/error.hpp File Reference	205
14.11.1 Detailed Description	206
14.12 src/sys/io.hpp File Reference	206
14.12.1 Detailed Description	208
14.12.2 Class Documentation	208
14.13 src/sys/pidfile.hpp File Reference	210
14.13.1 Detailed Description	211
14.13.2 Class Documentation	211
14.14 src/sys/signal.hpp File Reference	212
14.14.1 Detailed Description	213

1 Main Page

Index		221
	14.18.1 Detailed Description	219
14.18	src/version.hpp File Reference	218
	14.17.1 Detailed Description	218
14.17	src/utility.hpp File Reference	216
	14.16.1 Detailed Description	216
14.16	src/types.hpp File Reference	215
	14.15.2 Class Documentation	215
	14.15.1 Detailed Description	<b>21</b> 5
14.15	src/sys/sysctl.hpp File Reference	<b>21</b> 3
	14.14.2 Class Documentation	<b>21</b> 3

# 1 Main Page



The powerd++ daemon is a drop-in replacement for FreeBSD's native powerd. Its purpose is to reduce the energy consumption of CPUs for the following benefits:

- · Avoid unnecessary fan noise from portable devices
- Improve the battery runtime of portable devices
- Improve hardware lifetime by reducing thermal stress
- · Energy conservation

## Contents

- 1. Using powerd++
  - (a) Packages
  - (b) Running powerd++
  - (c) Manuals
  - (d) Tuning
  - (e) Reporting Issues / Requesting Features
- 2. Building/Installing
  - (a) Building
  - (b) Installing
  - (c) Documentation
- 3. Development
  - (a) Design
  - (b) License

## 1.1 Using powerd++

Powerd++ offers the following features:

- · Load target based clock frequency control
- · Tunable sampling with moving average filter
- · Load recording and replay tooling for benchmarking, tuning and reporting issues
- Command line compatibility with powerd(8)
- · Temperature based throttling
- · Expressive command line arguments with units, ranges and argument chaining
- · Helpful error messages
- · Comprehensive manual pages

## 1.1.1 Packages

The FreeBSD port is sysutils/powerdxx, the package name powerdxx.

## 1.1.2 Running powerd++

It is not intended to run powerd++ simultaneously with powerd. To prevent this powerd++ uses the same default pidfile as powerd:

```
# service powerdxx onestart
Starting powerdxx.
powerd++: (ECONFLICT) a power daemon is already running under PID: 59866
/usr/local/etc/rc.d/powerdxx: WARNING: failed to start powerdxx
```

So if powerd is already setup, it first needs to be disabled:

```
# service powerd stop
Stopping powerd.
Waiting for PIDS: 50127.
# service powerd disable
powerd disabled in /etc/rc.conf
```

### Afterwards powerd++ can be enabled:

```
# service powerdxx enable
powerdxx enabled in /etc/rc.conf
# service powerdxx start
Starting powerdxx.
```

## 1.1.3 Manuals

Comprehensive manual pages exist for powerd++ and its accompanying tools loadrec and loadplay:

The current version of the manual pages may be read directly from the repository: > man man/\*

The manual pages as of the last release can also be read online.

### 1.1.4 Tuning

Three parameters affect the responsiveness of powerd++:

- The load target (refer to -a, -b and -n)
- The polling interval (refer to -p)
- The sample count (refer to -s)

The key to tuning powerd++ is the -f flag, which keeps powerd++ in foreground and causes it to report its activity. This allows directly observing the effects of a parameter set.

Observing the defaults in action may be a good start:

```
# powerd++
power: online, load:
                       693 MHz,
                                 42 C, cpu.O.freq: 2401 MHz, wanted: 1848 MHz
power:
        online, load:
                       475 MHz,
                                 43 C, cpu.O.freq: 1800 MHz, wanted: 1266 MHz
        online, load:
                       271 MHz,
                                 43 C, cpu.O.freq: 1300 MHz, wanted:
power:
        online, load:
                        64 MHz,
                                 43 C, cpu.O.freq:
                                                    768 MHz, wanted:
power:
power:
        online, load:
                        55 MHz.
                                 42 C, cpu.O.freq:
                                                    768 MHz, wanted:
                                                                       146 MHz
                        57 MHz,
                                                                       152 MHz
                                 42 C, cpu.O.freq:
                                                    768 MHz, wanted:
power:
        online, load:
                        60 MHz,
        online, load:
                                 44 C, cpu.O.freq:
                                                    768 MHz, wanted:
                                                                       160 MHz
power:
       online, load:
                        67 MHz,
                                42 C, cpu.O.freq:
                                                    768 MHz, wanted:
power:
```

Note, the immediate high load is due to the load buffer being filled under the assumption that the past load fits the current clock frequency when powerd++ starts.

1.1.5 -requesting-features Reporting Issues / Requesting Features

Please report issues and feature requests on GitHub or to kamikaze@bsdforen.de.

If powerd++ behaves in some unexpected or undesired manner, please mention all the command line flags (e.g. from /etc/rc.conf powerdxx\_flags) and provide a load recording:
> loadrec -o myissue.load

The default recording duration is 30 s. Do not omit the -o parameter, printing the output on the terminal may create significant load and impact the recorded load significantly.

Before submitting the report, try to reproduce the behaviour using the recorded load:

```
> loadplay -i myissue.load -o /dev/null powerd++ -f
      online, load: 224 MHz, cpu.0.freq:
                                            768 MHz. wanted:
       online, load: 155 MHz, cpu.O.freq:
                                            768 MHz, wanted:
power:
       online, load:
                       85 MHz, cpu.O.freq:
                                            768 MHz, wanted:
                                                              226 MHz
power:
       online, load:
                       29 MHz, cpu.O.freq:
                                            768 MHz, wanted:
                                                               77 MHz
                                            768 MHz, wanted:
power: online, load:
                       23 MHz, cpu.O.freq:
                                                               61 MHz
```

## 1.2 Building/Installing

The Makefile offers a set of targets, it is written for FreeBSD's make(1):

Target	Description
all	Build everything
debug	Build with CXXFLAGS=-00 -g -DEBUG
paranoid	Turn on undefined behaviour canaries
install	Install tools and manuals
deinstall	Deinstall tools and manuals
clean	Clear build directory obj/
doc	Build HTML documentation
gh-pages	Build and publish HTML and PDF documentation

Generated by Doxygen

### 1.2.1 Building

The all target is the default target that is called implicitly if make is run without arguments:

```
c++ -02 -pipe -march=haswell -std=c++17 -Wall -Werror -pedantic -c src/powerd++.cpp -o powerd++.o
c++ -02 -pipe -march=haswell -std=c++17 -Wall -Werror -pedantic -c src/clas.cpp -o clas.o
c++ -02 -pipe -march=haswell -std=c++17 -Wall -Werror -pedantic powerd++.o clas.o -lutil -o powerd++
c++ -02 -pipe -march=haswell -std=c++17 -Wall -Werror -pedantic -c src/loadrec.cpp -o loadrec.o
c++ -02 -pipe -march=haswell -std=c++17 -Wall -Werror -pedantic loadrec.o clas.o -o loadrec
c++ -02 -pipe -march=haswell -std=c++17 -Wall -Werror -pedantic loadplay.o clas.o -o loadplay.o
c++ -02 -pipe -march=haswell -std=c++17 -Wall -Werror -pedantic loadplay.o clas.o -o loadplay
c+- -02 -pipe -march=haswell -std=c++17 -Wall -Werror -pedantic loadplay.o -std=c++17 -Wall -Werror -pedantic loadplay.o -lpthread -shared -o libloadplay.so
```

The debug and paranoid flags perform the same build as the all target, but with different/additional CXXF← LAGS. The debug and paranoid targets can be combined.

### 1.2.2 Installing

The installer installs the tools and manual pages according to a recipe in pkg/files. The following variables can be passed to make install or make deinstall to affect the install destination:

Variable	Default
DESTDIR	
PREFIX	/usr/local
DOCSDIR	\${PREFIX}/share/doc/powerdxx

DESTDIR can be used to install powerd++ into a chroot or jail, e.g. to put it into the staging area when building a package using the FreeBSD ports. Unlike PREFIX and DOCSDIR it does not affect the installed files themselves.

### 1.2.3 Documentation

Building the documentation requires doxygen 1.8.15 or later, building the PDF version of the documentation requires xelatex as provided by the tex-xetex package.

The doc target populates doc/html and doc/latex, to create the PDF documentation doc/latex/refman. ← pdf must be built.

The gh-pages target builds the HTML and PDF documentation and drops it into the gh-pages submodule for publishing on github.io.

## 1.3 Development

The following table provides an overview of repository contents:

File/Folder	Contents
doc/	Output directory for doxygen documentation
doxy/	Doxygen configuration and filter scripts
gh-pages/	Submodule for publishing the documentation
man/	Manual pages written using mdoc(7) markup
obj/	Build output

1.3 Development 5

File/Folder	Contents
pkg/	Installer scripts and instructions
src/	C++ source files
src/sys/	C++ wrappers for common C interfaces
powerd++.rc	Init script / service description
LICENSE.md	ISC license
Makefile	Build instructions
README.md	Project overview

## 1.3.1 Design

The life cycle of the powerd++ process goes through three stages:

- 1. Command line argument parsing
- 2. Initialisation and optionally printing the detected/configured parameters
- 3. Clock frequency control

The first stage is designed to maximise usability by providing both, the compact short option syntax (e. $\leftarrow$  g. -vfbhadp) as well as the more self-descriptive long option syntax (e.g. --verbose --foreground --batt hiadaptive).

The second stage is designed to trigger all known error conditions in order to fail before calling daemon(3) at the start of the third stage. Both the first and second stage are meant to provide specific, helpful error messages.

The third stage tracks the CPU load and performs clock frequency control. It is designed to provide its functionality with as little runtime as possible. This is achieved by:

- · Using integer arithmetic only
- · Minimising branching

The latter is achieved by using function templates to roll out possible runtime state combinations as multiple functions. A single, central switch/case selects the correct function each cycle. This basically rolls out multiple code paths through a single function into multiple functions with a single code path.

The trade-off made is for runtime over code size. With every bit of state rolled out like this the number of functions that need to be generated doubles, thus this approach is limited to the few bits of state that control the most expensive functionality, e.g. the foreground mode.

### 1.3.2 License

This project is published under the ISC license.

## 2 LICENSE

Copyright © 2016 - 2019 Dominic Fandrey kami@freebsd.org

Permission to use, copy, modify, and distribute this software for any purpose with or without fee is hereby granted, provided that the above copyright notice and this permission notice appear in all copies.

THE SOFTWARE IS PROVIDED "AS IS" AND THE AUTHOR DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY SPECIAL, DIRECT, INDIRECT, OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

# 3 Manual loadplay(1)

```
loadplay(1)
                        FreeBSD General Commands Manual
                                                                     loadplay(1)
NAME
     loadplay - CPU load player
SYNOPSIS
     loadplay -h
     loadplay [-i file] [-o file] \underline{\text{command}} [...]
DESCRIPTION
     The loadplay command replays a load recording created with loadrec(1).
     The command can either be powerd(8) or powerd++(8), compatibility with
     other tools has not been tested.
   OPTIONS
     The following options are supported:
     -h, --help
             Show usage and exit.
     -i, --input file
             Read load recording from file instead of stdin.
     -o, --output file
             Output statistics to file instead of stdout.
USAGE NOTES
     The loadplay command injects libloadplay.so into command. This library
     simulates the load from the input and outputs load statistics.
   OUTPUT
     The first line of output contains column headings, columns are separated
     by a single space.
```

The Following columns are present, columns containing %d occur for each core simulated:

#### time[s]

The simulation progress in 0.001 second resolution.

### cpu.%d.rec.freq[MHz]

The recorded clock frequency, sampled at the end of the frame.

### cpu.%d.rec.load[MHz]

The recorded load in 0.1 MHz resolution.

#### cpu.%d.run.freq[MHz]

The simulated clock frequency set by the host process, sampled at the end of the frame.

### cpu.%d.run.load[MHz]

The simulated load in 0.1 MHz resolution.

### SAMPLING

There is one sample for each recorded line. The duration of each frame depends on the recording, which defaults to 25 ms. At this sample rate loads are dominated by noise, so a gliding average should be applied to any load columns for further use, such as plotting.

### IMPLEMENTATION NOTES

The injected <u>libloadplay.so</u> works by intercepting system function calls and substituting the host environment with the recording. To achieve this the following function calls are intercepted:

- sysctl(3), sysctlnametomib(3), sysctlbyname(3)
- daemon(3)
- geteuid(2)
- pidfile\_open(3), pidfile\_write, pidfile\_close(3), pidfile\_remove(3), pidfile\_fileno(3)

## INITIALISATION

The sysctl family of functions is backed by a table that is initialised from the header of the load recording. If the heading is incomplete the setup routines print a message on  $\underline{\text{stderr}}$ . All the following intercepted function calls will return failure, ensuring that the host process is unable to operate and terminates.

Like powerd++(8) and loadrec(1) loadplay is core agnostic. Meaning that any core may have a .freq and .freq\_levels sysctl handle. Due to this flexibility load recordings may in part or wholly be fabricated to test artificial loads or systems and features that do not yet exist. E.g. it is possible to offer a .freq handle for each core or fabricate new .freq\_levels.

#### SIMULATION

If setup succeeds a simulation thread is started that reads the remaining input lines, simulates the load and updates the kern.cp\_times entry in the thread safe sysctl table. For each frame a line of output with load statistics is produced.

Interaction with the host process happens solely through the sysctl table. The simulation reads the recorded loads and the current core frequencies to update kern.cp\_times. The host process reads this data and adjusts the clock frequencies, which in turn affects the next frame.

#### FINALISATION

After reading the last line of input the simulation thread sends a SIGINT to the process to cause it to terminate.

### ENVIRONMENT

#### LOADPLAY\_IN

If set the file named is used for input instead of  $\underline{\text{stdin}}$ . This only affects the input of loadplay, the host process is not affected.

### LOADPLAY\_OUT

If set the file named is used for output instead of <u>stdout</u>. This only affects the output of loadplay, the host process is not affected.

#### LD\_PRELOAD

Used to inject libloadplay.so into the host process.

### FILES

### /usr/local/lib/libloadplay.so

A library injected into  $\underline{\text{command}}$  via the LD\_PRELOAD environment variable.

### **EXAMPLES**

Play a load recording with loadplay:

Capture load and loadplay output simultaneously into two different files:

> loadplay -i loads/freq\_tracking.load -o load.csv powerd++ -f > load.out

0.275 1700 0.0 1700 0.0 1700 0.0 1700 0.0 1700 0.0 1700 0.0 1700 0.0 1700 0.0

4 Manual loadrec(1)

Capture and display loadplay output:

```
> loadplay -i loads/freq_tracking.load -o load.csv powerd++ -f $|$ tee load.out
         power: online, load: 527 MHz, cpu0.freq: 1700 MHz, wanted: 1405 MHz
        power: online, load: 459 MHz, cpu0.freq: 1400 MHz, wanted: 1224 MHz
        power: online, load: 502 MHz, cpu0.freq: 1200 MHz, wanted: 1338 MHz
        power: online, load: 548 MHz, cpu0.freq: 1300 MHz, wanted: 1461 MHz
        power: online, load: 704 MHz, cpu0.freq: 1500 MHz, wanted: 1877 MHz
        power: online, load: 750 MHz, cpu0.freq: 1900 MHz, wanted: 2000 MHz
        power: online, load: 805 MHz, cpu0.freq: 2000 MHz, wanted: 2146 MHz
        power: online, load: 772 MHz, cpu0.freq: 2200 MHz, wanted: 2058 MHz
        power: online, load: 574 MHz, cpu0.freq: 2000 MHz, wanted: 1530 MHz
        power: online, load: 515 MHz, cpu0.freq: 1500 MHz, wanted: 1373 MHz
SEE ALSO
     loadrec(1), powerd(8), powerd++(8), rtld(1), signal(3), tee(1)
AUTHORS
     Implementation and manual by Dominic Fandrey <kami@freebsd.org>
FreeBSD 12.0-STABLE
                              20 February, 2019
                                                 FreeBSD 12.0-STABLE
    Manual loadrec(1)
loadrec(1)
                       FreeBSD General Commands Manual
                                                                   loadrec(1)
NAME
     loadrec - CPU load recorder
SYNOPSIS
     loadrec [-v] [-d ival] [-p ival] [-o file]
DESCRIPTION
     The loadrec command performs a recording of the current load. The purpose
     is to reproduce this load to test different powerd(8) and powerd++(8)
     configurations under identical load conditions using loadplay(1).
   ARGUMENTS
     The following argument types can be given:
     ival
             A time interval can be given in seconds or milliseconds.
                  s. ms
             An interval without a unit is treated as milliseconds.
     file
             A file name.
```

The following options are supported:

OPTIONS

```
-h, --help
             Show usage and exit.
     -v, --verbose
             Be verbose and produce initial diagnostics on stderr.
     -d, --duration ival
             The duration of the recording session, defaults to 30 seconds.
     -p, --poll ival
             The polling interval to take load samples at, defaults to 25
     -o, --output file
             The output file to write the load to.
USAGE NOTES
    To create reproducible results set a fixed CPU frequency below the
    threshold at which the turbo mode is activated. E.g. an Intel(R) Core(TM)
     i7-4500U CPU supports the following frequency settings:
         > sysctl dev.cpu.O.freq_levels
     dev.cpu.0.freq_levels: 2401/15000 2400/15000 2300/14088 2200/13340 2000/11888 1900/11184 1800/10495 1700/968
     Supposedly the first mode, which is off by 1 MHz, invokes the turbo mode.
    However all modes down to 1800 MHz actually invoke the turbo mode for
    this model. The only way to determine this is by benchmarking the
    steppings to find out that there is a huge performance step between 1700
    and 1800 MHz and that all the modes above 1700 MHz show the exact same
    performance (given similar thermal conditions).
    So in order to produce a usable measurement for this CPU the clock needs
    to be set to 1700 MHz or lower (higher is better to be able to record a
    wider range of loads):
         # service powerd++ stop
         Stopping powerdxx.
         Waiting for PIDS: 63574.
         # powerd++ -M1700
    Run loadrec for a brief time to test it:
         > loadrec -d.25s
         usr.app.powerdxx.loadrec.features=1
         hw.machine=amd64
         hw.model=Intel(R) Core(TM) i7-4500U CPU @ 1.80GHz
         hw.ncpu=4
         hw.acpi.acline=1
         dev.cpu.0.freq=768
      dev.cpu.0.freq_levels=2401/15000 2400/15000 2300/14088 2200/13340 2000/11888 1900/11184 1800/10495 1700/9680
      0 768 768 768 768 728001 0 278439 54957 10215972 753315 0 245117 7838 10270972 767662 0 241991 37110 10230545 77
         25 768 768 768 768 0 0 0 0 3 2 0 0 0 1 0 0 0 3 0 0 0 0 4
         25 768 768 768 768 0 0 0 0 3 1 0 0 0 2 0 0 0 0 3 1 0 0 0 2
         25 768 768 768 768 0 0 1 0 2 1 0 2 0 0 0 0 0 3 0 0 1 0 2
         25 768 768 768 768 3 0 0 0 1 1 0 2 0 1 1 0 3 0 0 2 0 2 0 0
         25 768 768 768 768 0 0 0 0 3 0 0 1 0 2 0 0 0 0 3 3 0 0 0 0
         25 768 768 768 768 0 0 0 0 3 0 0 0 3 0 0 0 0 3 2 0 1 0 0
         25 768 768 768 768 0 0 0 0 3 0 0 0 3 0 0 0 0 3 2 0 1 0 0
         25 768 768 768 768 2 0 0 0 1 1 0 1 0 1 0 0 2 0 1 2 0 1 0 0
         25 768 768 768 768 0 0 0 0 4 1 0 2 0 1 0 0 0 0 4 0 0 1 0 2
         25 768 768 768 768 0 0 0 0 3 2 0 1 0 0 0 0 0 3 0 0 0 0 4
```

Printing the load creates significant load itself, so for the actual measurement the output should be written to a file. Create your workload and start your measurement:

> loadrec -o video-session.load

On the example setup loadrec produces a load of 0.001 (i.e. 0.1%), so its effect on the measurement is negligible.

#### SEE ALSO

```
cpufreq(4), loadplay(1), powerd(8), powerd++(8), sysctl(8)
```

#### AUTHORS

Implementation and manual by Dominic Fandrey <kami@freebsd.org>

FreeBSD 12.0-STABLE

4 February, 2019

FreeBSD 12.0-STABLE

## 5 Manual powerd++(8)

```
powerd++(8) FreeBSD System Manager's Manual powerd++(8)
```

#### NAME

powerd++ - CPU clock speed daemon

## SYNOPSIS

## DESCRIPTION

The powerd++ daemon monitors the system load and adjusts the CPU clock speed accordingly. It is a drop-in replacement for powerd(8) and supports two modes of operation, a load feedback control loop or fixed frequency operation.

## ARGUMENTS

The following argument types can be given:

```
mode
    The mode is either a load target or a fixed freq. The powerd(8)
    modes are interpreted as follows:
    maximum, max
        Use the highest clock frequency.
minimum, min
        Use the lowest clock frequency.
adaptive, adp
        A target load of 0.5 (50%).
hiadaptive, hadp
        A target load of 0.375 (37.5%).
```

If a scalar number is given, it is interpreted as a load.

-m, --min freq

-M, --max freq

load A load is either a fraction in the range [0.0, 1.0] or a percentage in the range [0%, 100%]. A clock frequency consists of a number and a frequency unit. freq Hz, KHz, MHz, GHz, THz The unit is not case sensitive, if omitted MHz are assumed for compatibility with powerd(8). temp A temperature consisting of a number and a temperature unit. Supported units are: C, K, F, R These units stand for deg. Celsius, Kelvin, deg. Fahrenheit and deg. Rankine. A value without a unit is treated as deg. Celsius. ival A time interval can be given in seconds or milliseconds. An interval without a unit is treated as milliseconds. cntA positive integer. file A file name. OPTIONS The following options are supported: -h, --help Show usage and exit -v, --verbose Be verbose and produce initial diagnostics on stderr. -f, --foreground Stay in foreground, produce an event log on stdout. -a, --ac mode Mode to use while the AC power line is connected (default hadp). -b, --batt mode Mode to use while battery powered (default adp). -n, --unknown mode Mode to use while the power line state is unknown (default hadp).

The lowest CPU clock frequency to use (default OHz).

The highest CPU clock frequency to use (default 1THz).

Generated by Doxygen

### --min-ac freq

The lowest CPU clock frequency to use on AC power.

## --max-ac freq

The highest CPU clock frequency to use on AC power.

## --min-batt freq

The lowest CPU clock frequency to use on battery power.

#### --max-batt freq

The highest CPU clock frequency to use on battery power.

## -F, --freq-range freq:freq

A pair of frequency values representing the minimum and maximum  $\ensuremath{\mathtt{CPU}}$  clock frequency.

### -A, --freq-range-ac freq:freq

A pair of frequency values representing the minimum and maximum CPU clock frequency on AC power.

## -B, --freq-range-batt freq:freq

A pair of frequency values representing the minimum and maximum  $\ensuremath{\mathtt{CPU}}$  clock frequency on battery power.

## -H, --hitemp-range $\underline{\text{temp:temp}}$

Set the high to critical temperature range, enables temperature based throttling.

### -p, --poll ival

The polling interval that is used to take load samples and update the CPU clock (default 0.5s).

## -s, --samples cnt

The number of load samples to use to calculate the current load. The default is 4.

## -P, --pid file

Use an alternative pidfile, the default is <a href="//var/run/powerd.pid">var/run/powerd.pid</a>. The default ensures that powerd(8) and powerd++ are not run simultaneously.

### -i, -r load

Legacy arguments from powerd(8) not applicable to powerd++ and thus ignored.

### SERVICE

The powerd++ daemon can be run as an rc(8) service. Add the following line to rc.conf(5):

powerdxx\_enable="YES"

Command line arguments can be set via powerdxx\_flags.

### TOOLS

The loadrec(1) and loadplay(1) tools offer the possibility to record system loads and replay them.

#### IMPLEMENTATION NOTES

This section describes the operation of powerd++.

Both powerd(8) and powerd++ have in common, that they work by polling kern.cp\_times via sysctl(3), which is an array of the accumulated loads of every core. By subtracting the last cp\_times sample the loads over the polling interval can be determined. This information is used to set a new CPU clock frequency by updating dev.cpu.0.freq.

#### Initialisation

After parsing command line arguments powerd++ assigns a clock frequency controller to every core. I.e. cores are grouped by a common dev.cpu.%d.freq handle that controls the clock for all of them. Due to limitations of cpufreq(4) dev.cpu.0.freq is the controlling handle for all cores, even across multiple CPUs. However powerd++ is not built with that assumption and per CPU, core or thread controls will work as soon as the hardware and kernel support them.

In the next initialisation stage the available frequencies for every core group are determined to set appropriate lower and upper boundaries. This is a purely cosmetic measure and used to avoid unnecessary frequency updates. The controlling algorithm does not require this information, so failure to do so will only be reported (non-fatally) in verbose mode.

Unless the -H option is given, the initialisation checks for a critical temperature source. If one is found temperature throttling is implicitly turned on, causing throttling to start 10 deg. Celsius below the critical temperature.

So far the sysctl(3) dev.cpu.%d.coretemp.tjmax is the only supported critical temperature source.

### Detaching From the Terminal

After the initialisation phase powerd++ prepares to detach from the terminal. The first step is to acquire a lock on the pidfile. Afterwards all the frequencies are read and written as a last opportunity to fail. After detaching from the terminal the pidfile is written and the daemon goes into frequency controlling operation until killed by a signal.

## Load Control Loop

The original powerd(8) uses a hysteresis to control the CPU frequency. I.e. it determines the load over all cores since taking the last sample (the summary load during the last polling interval) and uses a lower and an upper load boundary to decide whether it should update the frequency or not.

powerd++ has some core differences. It can take more than two samples (four by default), this makes it more robust against small spikes in load, while retaining much of its ability to quickly react to sudden surges in load. Changing the number of samples does not change the runtime cost of running powerd++.

Instead of taking the sum of all loads, the highest load within the core group is used to decide the next frequency target. Like with powerd(8) this means, that high load on a single core will cause an increase in the clock frequency. Unlike powerd(8) it also means that moderate load over all cores allows a decrease of the clock frequency.

The powerd++ daemon steers the clock frequency to match a load target, e.g. if there was a 25% load at 2 GHz and the load target was 50%, the frequency would be set to 1 GHz.

### Temperature Based Throttling

If temperature based throttling is active and the temperature is above the high temperature boundary (the critical temperature minus 10 deg. Celsius by default), the core clock is limited to a value below the permitted maximum. The limit depends on the remaining distance to the critical temperature.

Thermal throttling ignores user-defined frequency limits, i.e. when using -F, -B, -A or -m to prevent the clock from going unreasonably low, sufficient thermal load may cause powerd++ to select a clock frequency below the user provided minimum.

### Termination and Signals

The signals HUP and TERM cause an orderly shutdown of powerd++. An orderly shutdown means the pidfile is removed and the clock frequencies are restored to their original values.

## FILES

```
/var/run/powerd.pid
```

Common pidfile with powerd(8).

### /usr/local/etc/rc.d/powerdxx

Service file, enable in rc.conf(5).

### **EXAMPLES**

```
Run in foreground, minimum clock frequency 800 MHz: powerd++ -fm800
```

```
Report configuration before detaching into the background: powerd++ -\mathtt{v}
```

```
Target 75% load on battery power and run at 2.4 GHz on AC power: powerd++ -b .75 -a 2.4ghz
```

```
Target 25% load on AC power: powerd++ -a 25%
```

```
Use the same load sampling powerd(8) does: powerd++ -s1 -p.25s
```

Limit CPU clock frequencies to a range from 800 MHz to 1.8 GHz: powerd++ -F800:1.8ghz

IAGNOSTICS  The powerd++ daemon exits 0 on receiving an INT or TERM signal, and an error occurs.	>0 if
OMPATIBILITY  So far powerd++ requires ACPI to detect the current power line state	
<pre>EE ALSO      cpufreq(4), powerd(8), loadrec(1), loadplay(1)</pre>	
JTHORS Implementation and manual by Dominic Fandrey < <a href="mailto:kami@freebsd.org">kami@freebsd.org</a>	
reeBSD 12.0-STABLE 9 May, 2017 FreeBSD 12.0-S	TABLE
Module Index	
.1 Modules	
ere is a list of all modules:  Standard I/O File Access	22
Standard I/O File Access	23
Namespace Index	
.1 Namespace List	
ere is a list of all documented namespaces with brief descriptions:	
anonymous_namespace{clas.cpp} File local scope	23
anonymous_namespace{libloadplay.cpp} File local scope	25
anonymous_namespace{loadplay.cpp} File local scope	33
anonymous_namespace{loadrec.cpp} File local scope	35
anonymous_namespace{powerd++.cpp} File local scope	39
clas A collection of functions to process command line arguments	48
constants A collection of constants	52

8 Hierarchical Index 17

	Common error handling types and functions	53
	nih Not invented here namespace, for code that substitutes already commonly available functionality	56
	sys Wrappers around native system interfaces	58
	sys::ctl This namespace contains safer c++ wrappers for the sysctl() interface	58
	sys::env Provides wrappers around the getenv() family of functions	63
	sys::io This namespace contains c++ wrappers for <cstdio> functionality</cstdio>	64
	sys::pid This namespace contains safer c++ wrappers for the pidfile_*() interface	69
	sys::sig This namespace provides c++ wrappers for signal(3)	69
	timing Namespace for time management related functionality	70
	types A collection of type aliases	70
	utility A collection of generally useful functions	71
	utility::literals Contains literal operators	74
	version Version information constants and types	74
	version::literals Literals to set flag bits	75
8	Hierarchical Index	
8.1	Class Hierarchy	
Th	is inheritance list is sorted roughly, but not completely, alphabetically:	
	anonymous_namespace{powerd++.cpp}::Global::ACSet	39
	$an onymous\_names pace \{libload play.cpp\} :: Callback < Function Args >$	<b>7</b> 6
	$anonymous\_namespace\{libloadplay.cpp\}::Callback<\ anonymous\_namespace\{libloadplay. \leftarrow cpp\}::SysctlValue\ \&>$	<b>7</b> 6
	sys::io::contains < SetT, Value >	64

8

8.

sys::io::query::contains_ftor	79
$an onymous\_name space \{libload play.cpp\} :: Emulator :: Core$	83
anonymous_namespace{powerd++.cpp}::Core	39
$an on ymous\_names pace \{libload play.cpp\} :: Core Frame Report$	25
anonymous_namespace{powerd++.cpp}::CoreGroup	39
anonymous_namespace{libloadplay.cpp}::CoreReport	<b>2</b> 5
timing::Cycle	81
anonymous_namespace{libloadplay.cpp}::Emulator	83
sys::io::enable_if< bool, T >	86
sys::io::enable_if< false, T >	87
sys::io::enable_if<((Set==Value)  )>	86
sys::io::contains< set< Set >, Value >	78
sys::io::enable_if<(contains_v< LSetT, RSet > &&)>	86
sys::io::is_superset_of< LSetT, set< RSet > >	120
sys::env::error	63
sys::pid::error	69
sys::sig::error	69
sys::ctl::error	58
errors::Exception	53
sys::io::file< Ownership, Features >	64
sys::io::file< io::link >	64
sys::io::file< io::own >	64
sys::io::file_feature < FileT, >	98
${\sf sys::io::file\_feature} < {\sf file} < {\sf link}, {\sf Features} \ldots >, {\sf Features} \ldots >$	98
sys::io::file < link, Features >	89
${\sf sys::io::file\_feature} < {\sf file} < {\sf own, Features} \dots >, {\sf Features} \dots >$	98
sys::io::file< own, Features >	93
sys::io::file_feature< FileT, Tail >	98
sys::io::file_feature< FileT, read, Tail >	100
sys::io::file_feature< FileT, seek, Tail >	105
sys::io::file_feature< FileT, write, Tail >	108
utility::Formatter< BufSize >	114

anonymous_namespace{libloadplay.cpp}::Report::Frame	115
anonymous_namespace{powerd++.cpp}::FreqGuard	117
anonymous_namespace{powerd++.cpp}::Global	39
$an onymous\_names pace \{libload play.cpp\} :: Hold < T >$	118
sys::io::is_superset_of < LSetT, RSetT >	64
anonymous_namespace{libloadplay.cpp}::Main	121
utility::Max< T >	122
utility::Max< decikelvin_t >	122
utility::Max< mhz_t >	122
anonymous_namespace{libloadplay.cpp}::mib_t	124
utility::Min <t></t>	127
utility::Min< decikelvin_t >	127
utility::Min< mhz_t >	127
sys::ctl::Once< T, SysctlT >	129
sys::ctl::Once< coreid_t, 2 >	129
${\tt nih::Options} {<}  {\tt OptionT}, {\tt DefCount} {>}$	131
nih::Parameter < OptionT >	56
sys::pid::Pidfile	139
sys::io::query	64
anonymous_namespace{libloadplay.cpp}::Report	141
sys::sc_error< Domain >	143
sys::io::set < Set >	64
sys::sig::Signal	144
utility::Sum< T >	145
utility::Sum< uint64_t >	145
sys::ctl::Sync< T, SysctlT >	147
sys::ctl::Sync< decikelvin_t >	147
sys::ctl::Sync< mhz_t >	147
sys::ctl::Sysctl< MibDepth >	149
sys::ctl::Sysctl< 0 >	153
anonymous namespace{libloadplay.cpp}::Sysctls	157

anonymous_namespace{libloadplay.cpp}::SysctlValue true_type	161
nih::enum_has_members< OptionT, class >	87
sys::env::Var	169
sys::env::Vars	172
9 Class Index	
o Class Macx	
9.1 Class List	
Here are the classes, structs, unions and interfaces with brief descriptions:	
anonymous_namespace{libloadplay.cpp}::Callback< FunctionArgs > Implements a recursion safe std::function wrapper	76
sys::io::contains< set< Set >, Value > Specialise io::contains to unpack io::set	78
sys::io::query::contains_ftor  Test a string whether it contains a set of characters	79
timing::Cycle Implements an interruptible cyclic sleeping functor	81
anonymous_namespace{libloadplay.cpp}::Emulator Instances of this class represent an emulator session	83
sys::io::enable_if< bool, T > Similar to std::enable_if, but it also has the value of the expression	86
sys::io::enable_if< false, T > Specialise enable_if for a false expression	87
nih::enum_has_members < OptionT, class > Tests whether the given enum provides all the required definitions	87
sys::io::file< link, Features > Specialise for FILE object linking file instances	89
sys::io::file< own, Features > Specialise for FILE object owning file instances	93
sys::io::file_feature < FileT, > Implements the base functionality of all file access types	98
sys::io::file_feature< FileT, read, Tail > Implement read support for file types	100
sys::io::file_feature< FileT, seek, Tail > Implement seek support for file types	105
sys::io::file_feature< FileT, write, Tail > Implement write support for file types	108

9.1 Class List 21

utility::Formatter < BufSize > A formatting wrapper around string literals	114
anonymous_namespace{libloadplay.cpp}::Report::Frame Represents a frame of the report	115
anonymous_namespace{powerd++.cpp}::FreqGuard A core frequency guard	117
anonymous_namespace{libloadplay.cpp}::Hold< T > Sets a referenced variable to a given value and restores it when going out of context	118
sys::io::is_superset_of < LSetT, set < RSet > > Specialise is_superset_of to unpack the right hand io::set	120
anonymous_namespace{libloadplay.cpp}::Main Singleton class representing the main execution environment	121
utility::Max< T > A simple value container that provides the maximum of assigned values	122
anonymous_namespace{libloadplay.cpp}::mib_t Represents MIB, but wraps it to provide the necessary operators to use it as an std::map key	124
utility::Min< T > A simple value container that provides the minimum of assigned values	127
sys::ctl::Once< T, SysctlT > A read once representation of a Sysctl	129
nih::Options < OptionT, DefCount > An instance of this class offers operators to retrieve command line options and arguments	131
sys::pid::Pidfile A wrapper around the pidfile_* family of commands implementing the RAII pattern	139
anonymous_namespace{libloadplay.cpp}::Report Provides a mechanism to provide frame wise per core load information	141
sys::sc_error< Domain > Can be thrown by syscall function wrappers if the function returned with an error	143
sys::sig::Signal Sets up a given signal handler and restores the old handler when going out of scope	144
utility::Sum< T > A simple value container only allowing += and copy assignment	145
sys::ctl::Sync< T, SysctlT > This is a wrapper around Sysctl that allows semantically transparent use of a sysctl	147
sys::ctl::Sysctl < MibDepth > Represents a sysctl MIB address	149
sys::ctl::Sysctl < 0 > This is a specialisation of Sysctl for sysctls using symbolic names	153
anonymous_namespace{libloadplay.cpp}::Sysctls Singleton class representing the sysctl table for this library	157

anonymous_namespace{libloadplay.cpp}::SysctlValue Instances of this class represents a specific sysctl value	161
sys::env::Var  A reference type refering to an environment variable	169
sys::env::Vars  A singleton class providing access to environment variables	172
10 File Index	
10.1 File List	
Here is a list of all documented files with brief descriptions:	
src/clas.hpp Implements functions to process command line arguments	173
src/constants.hpp Defines a collection of constants	175
src/Cycle.hpp Implements timing::Cycle, a cyclic sleep functor	177
src/errors.hpp Common error handling code	178
src/libloadplay.cpp Implements a library intended to be injected into a clock frequency deamon via LD RELOAD	_P⊷ 180
src/loadplay.cpp Implements the loadplay a bootstrapping tool for libloadplay	189
src/loadrec.cpp Implements a load recorder, useful for simulating loads to test CPU clock daemons settings	and 190
<pre>src/Options.hpp     This file provides nih::Options&lt;&gt;&gt;, a substitute for getopt(3)</pre>	194
src/powerd++.cpp Implements powerd++ a drop in replacement for FreeBSD's powerd	197
src/types.hpp A collection of type aliases	215
src/utility.hpp Implements generally useful functions	216
src/version.hpp  Defines types and constants used for version management	218
src/sys/env.hpp Implements zero-cost abstractions for the getenv(3) facilities	204
src/sys/error.hpp Provides system call error handling	205

src/sys/io.hpp Implements c++ wrappers for <cstdio> I/O functionality</cstdio>	206
src/sys/pidfile.hpp	
Implements safer c++ wrappers for the pidfile_*() interface	210
src/sys/signal.hpp	
Implements a c++ wrapper for the signal(3) call	212
src/sys/sysctl.hpp	
Implements safer c++ wrappers for the sysctl() interface	<b>21</b> 3

## 11 Module Documentation

### 11.1 Standard I/O File Access

A set of file instances providing access to stderr, stdout and stdin.

### Variables

• file < link, write > sys::io::ferr {stderr}

File access instances for stderr.

• file< link, write > sys::io::fout {stdout}

File access instances for stdout.

• file< link, read > sys::io::fin {stdin}

File access instances for stdin.

## 11.1.1 Detailed Description

A set of file instances providing access to stderr, stdout and stdin.

In theory these should be functions returning a reference to a local static file object, to avoid global object initialisation order issues.

This would be annoying to access, though. In practice it works the way it is and it would be hard to notice if it did not.

# 12 Namespace Documentation

## 12.1 anonymous\_namespace{clas.cpp} Namespace Reference

File local scope.

### Enumerations

```
    enum Unit : size_t {
        Unit::SCALAR, Unit::PERCENT, Unit::SECOND, Unit::MILLISECOND,
        Unit::HZ, Unit::KHZ, Unit::MHZ, Unit::GHZ,
        Unit::THZ, Unit::CELSIUS, Unit::KELVIN, Unit::FAHRENHEIT,
        Unit::RANKINE, Unit::UNKNOWN }
```

Command line argument units.

### **Functions**

• Unit unit (std::string const &str)

Determine the unit of a string encoded value.

### Variables

• char const \*const UnitStr []

The unit strings on the command line, for the respective Unit instances.

## 12.1.1 Detailed Description

File local scope.

## 12.1.2 Enumeration Type Documentation

## 12.1.2.1 Unit

```
\verb"enum anonymous_namespace{clas.cpp}:: Unit : size_t [strong]"
```

Command line argument units.

These units are supported for command line arguments, for SCALAR arguments the behaviour of powerd is to be imitated.

### Enumerator

SCALAR	Values without a unit.
PERCENT	%
SECOND	S
MILLISECOND	ms
HZ	hz
KHZ	khz
MHZ	mhz
GHZ	ghz
THZ	thz
CELSIUS	C.
KELVIN	K.
FAHRENHEIT	F.
RANKINE	R.
UNKNOWN	Unknown unit.

### 12.1.3 Function Documentation

```
12.1.3.1 unit()
Unit anonymous_namespace{clas.cpp}::unit (
```

Determine the unit of a string encoded value.

std::string const & str )

**Parameters** 

```
str The string to determine the unit of
```

Returns

A unit

12.1.4 Variable Documentation

```
12.1.4.1 UnitStr
```

```
char const* const anonymous_namespace{clas.cpp}::UnitStr[]
```

```
Initial value:
```

```
{
    "", "%", "s", "ms", "hz", "khz", "mhz", "ghz", "thz", "C", "K", "F", "R"
}
```

The unit strings on the command line, for the respective Unit instances.

12.2 anonymous\_namespace{libloadplay.cpp} Namespace Reference

File local scope.

Classes

• class Callback

Implements a recursion safe std::function wrapper.

struct CoreFrameReport

The report frame information for a single CPU pipeline. More...

struct CoreReport

The reported state of a single CPU pipeline. More...

class Emulator

Instances of this class represent an emulator session.

class Hold

Sets a referenced variable to a given value and restores it when going out of context.

• class Main

Singleton class representing the main execution environment.

struct mib\_t

Represents MIB, but wraps it to provide the necessary operators to use it as an std::map key.

· class Report

Provides a mechanism to provide frame wise per core load information.

class Sysctls

Singleton class representing the sysctl table for this library.

• class SysctlValue

Instances of this class represents a specific sysctl value.

### **Typedefs**

```
    template<auto Ownership>
        using ofile = io::file< Ownership, io::write >
            Output file type alias.
    template<auto Ownership>
        using ifile = io::file< Ownership, io::read >
            Input file type alias.
```

## **Functions**

```
    template<size_t Size>
        int strcmp (char const *const s1, char const (&s2)[Size])
        Safe wrapper around strncmp, which automatically determines the buffer size of s2.
    std::regex operator""_r (char const *const str, size_t const len)
        User defined literal for regular expressions.
```

```
    template<typename... ArgTs>
        constexpr void dprintf (ArgTs &&... args)
        Calls io::ferr.printf(...) if built with -DEBUG.
```

template<> std::string SysctlValue::get< std::string > () const

Returns a copy of the value string.

• template<typename... MsgTs>

```
ofile< io::link > debug (MsgTs &&... msg)
```

Print a debugging message if built with -DEBUG.

template<typename... MsgTs>
 ofile< io::link > warn (MsgTs &&... msg)
 Print a warning.

template<typename... MsgTs>
 ofile< io::link > fail (MsgTs &&... msg)

This prints an error message and sets sys\_results to make the hijacked process fail.

 $\bullet \ \, ofile < io::link > operator << (ofile < io::link > fout, CoreFrameReport \ const \ \&frame) \\$ 

Print recorded and running clock frequency and load for a frame.

### Variables

constexpr flag\_t const FEATURES

The set of supported features.

• int sys\_results = 0

The success return value of intercepted functions.

- class anonymous\_namespace{libloadplay.cpp}::Sysctls sysctls
   Sole instance of Sysctls.
- class anonymous\_namespace{libloadplay.cpp}::Main main Sole instance of Main.
- bool sysctl\_fallback = false

Set to activate fallback to the original sysctl functions.

### 12.2.1 Detailed Description


File local scope.

### 12.2.2 Class Documentation

## 12.2.2.1 struct anonymous\_namespace{libloadplay.cpp}::CoreFrameReport

The report frame information for a single CPU pipeline.

Collaboration diagram for anonymous\_namespace{libloadplay.cpp}::CoreFrameReport:




## Class Members

CoreReport	rec	The recorded core state.
CoreReport	run	The running core state.

## 12.2.2.2 struct anonymous\_namespace{libloadplay.cpp}::CoreReport

The reported state of a single CPU pipeline.

Collaboration diagram for anonymous\_namespace{libloadplay.cpp}::CoreReport:



## Class Members

mhz_t	freq	The core clock frequency in [MHz].
double	load	The core load as a fraction.

## 12.2.3 Typedef Documentation

## 12.2.3.1 ifile

template<auto Ownership>
using anonymous\_namespace{libloadplay.cpp}::ifile = typedef io::file<Ownership, io::read>

Input file type alias.

**Template Parameters** 

Ownership	The io::ownership type of the file

12.2.3.2 ofile

```
template<auto Ownership>
using anonymous_namespace{libloadplay.cpp}::ofile = typedef io::file<Ownership, io::write>
```

Output file type alias.

**Template Parameters** 

```
Ownership The io::ownership type of the file
```

12.2.4 Function Documentation

```
12.2.4.1 debug()
```

```
\label{lem:continuous_names} $$ \end{template} < io::link> anonymous_namespace{libloadplay.cpp}::debug ($$ MsgTs &\&... $msg$ ) [inline]
```

Print a debugging message if built with -DEBUG.

**Template Parameters** 

Msg⇔	The message argument types
Ts	

Parameters

```
msg The debugging message
```

Returns

An output file handle for extending the message

```
12.2.4.2 dprintf()
template<typename ... ArgTs>
```

Calls io::ferr.printf(...) if built with -DEBUG.

#### **Template Parameters**

Arg⇔	The argument types to forward
Ts	

#### Parameters

```
args | Arguments are forwarded to fprintf()
```

```
12.2.4.3 fail()
```

This prints an error message and sets sys\_results to make the hijacked process fail.

#### **Template Parameters**

Msg⇔	The message argument types
Ts	

#### Parameters

msg	The error message
-----	-------------------

#### Returns

An output file handle for extending the message

User defined literal for regular expressions.

#### Parameters

```
str,len The literal string and its length
```

#### Returns

A regular expression

Print recorded and running clock frequency and load for a frame.

The clock frequency is printed at 1 MHz resolution, the load at 0.1 MHz.

#### **Parameters**

fout	The stream to print to
frame	The frame information to print

#### Returns

A reference to the out stream

Safe wrapper around strncmp, which automatically determines the buffer size of s2.

**Template Parameters** 

Size	The size of the buffer s2

#### **Parameters**

```
s1,s2 The strings to compare
```

#### Return values

0	Strings are equal
!0	Strings are not equal

#### 12.2.4.7 SysctlValue::get < std::string >()

```
template<>
std::string anonymous_namespace{libloadplay.cpp}::SysctlValue::get< std::string > ( ) const
```

Returns a copy of the value string.

Returns

The value

Print a warning.

**Template Parameters** 

```
Msg← The message argument types
Ts
```

Parameters

```
msg The warning message
```

Returns

An output file handle for extending the message

12.2.5 Variable Documentation

```
12.2.5.1 FEATURES
```

```
\verb|constexpr| flag_t| const| anonymous_namespace{libloadplay.cpp}:: FEATURES| | constexpr| flag_t| const| constexpr| flag_t| const| co
```

```
Initial value:
{
    1_FREQ_TRACKING
}
```

The set of supported features.

This value is used to ensure correct input data interpretation.

```
12.2.5.2 main
```

 ${\tt class\ anonymous\_namespace\{libloadplay.cpp\}::} {\tt Main\ anonymous\_namespace\{liblo$ 

Sole instance of Main.

```
12.2.5.3 sysctls
{\tt class\ anonymous\_namespace\{libloadplay.cpp\}}:: {\tt Sysctls\ anonymous\_namespace}: {\tt sysctls\ anonymous\_namespace}: {\tt sysctls\ anonymous\_namespace}: {\tt sysctls\ anonymou
Sole instance of Sysctls.
                        anonymous_namespace{loadplay.cpp} Namespace Reference
File local scope.
 Enumerations
             • enum OE {
                   OE::USAGE, OE::FILE_IN, OE::FILE_OUT, OE::CMD,
                   OE::OPT NOOPT = CMD, OE::OPT UNKNOWN, OE::OPT DASH, OE::OPT LDASH,
                   OE::OPT_DONE }
                             An enum for command line parsing.
 Functions

    char const * filename (char const *const path)

                              Performs very rudimentary file name argument checks.

    void execute (char const *const file, char *const argv[])

                             Executes the given command, substituting this process.
 Variables
             • char const *const USAGE = "[-h] [-i file] [-o file] command [...]"
                              The short usage string.

    Parameter < OE > const PARAMETERS []

                              Definitions of command line parameters.
 12.3.1 Detailed Description
File local scope.
 12.3.2 Enumeration Type Documentation
 12.3.2.1 OE
enum anonymous_namespace{loadplay.cpp}::OE [strong]
An enum for command line parsing.
```

#### Enumerator

USAGE	Print help.
FILE_IN	Set input file instead of stdin.
FILE_OUT	Set output file instead of stdout.
CMD	The command to execute.
OPT_NOOPT	Obligatory.
OPT_UNKNOWN	Obligatory.
OPT_DASH	Obligatory.
OPT_LDASH	Obligatory.
OPT_DONE	Obligatory.

#### 12.3.3 Function Documentation

Executes the given command, substituting this process.

This function is a wrapper around execvp(3) and does not return.

#### Parameters

file	The command to execute, looked up in PATH if no path is provided
argv	The command line arguments of the command

#### Exceptions

```
errors::Exception{Exit::EEXEC}
```

```
12.3.3.2 filename()
```

Performs very rudimentary file name argument checks.

- · Fail on empty path
- Return nullptr on '-'

**Parameters** 

```
path The file path to check
```

Returns

The given path or nullptr if the given path is '-'

12.3.4 Variable Documentation

#### 12.3.4.1 PARAMETERS

```
Parameter<OE> const anonymous_namespace{loadplay.cpp}::PARAMETERS[]
```

```
Initial value:
{
    {0E::USAGE, 'h', "help", "", "Show usage and exit"},
    {0E::FILE_IN, 'i', "input", "file", "Input file (load recording)"},
    {0E::FILE_OUT, 'o', "output", "file", "Output file (replay stats)"},
    {0E::CMD, 0, "", "command,[...]", "The command to execute"},
```

Definitions of command line parameters.

12.4 anonymous\_namespace{loadrec.cpp} Namespace Reference

File local scope.

Typedefs

template<auto Ownership>
 using ofile = io::file< Ownership, io::write >
 Output file type alias.

#### Enumerations

```
    enum OE {
        OE::USAGE, OE::IVAL_DURATION, OE::IVAL_POLL, OE::FILE_OUTPUT,
        OE::FILE_PID, OE::FLAG_VERBOSE, OE::OPT_UNKNOWN, OE::OPT_NOOPT,
        OE::OPT_DASH, OE::OPT_LDASH, OE::OPT_DONE }
```

An enum for command line parsing.

#### **Functions**

```
• template<typename... MsgTs>
      void verbose (MsgTs &&... msg)
          Outputs the given printf style message on stderr if g.verbose is set.
    • void init ()
         Set up output to the given file.

    void read_args (int const argc, char const *const argv[])

          Parse command line arguments.
    void print_sysctls ()
          Print the sysctls.
    • void run ()
          Report the load frames.
Variables

    constexpr flag_t const FEATURES

          The set of supported features.
      struct {
      bool verbose {false}
           Verbosity flag.
      ms duration {30000}
           Recording duration in ms.
      ms interval {25}
           Recording sample interval in ms.
       ofile< io::link > fout = io::fout
           The output stream either io::fout (stdout) or a file.
       char const * outfilename {nullptr}
           The user provided output file name.
       sys::ctl::SysctlOnce< coreid_t, 2 > const ncpu {1U, {CTL_HW, HW_NCPU}}
           The number of CPU cores/threads.
      } g
          The global state.
    • char const *const USAGE = "[-hv] [-d ival] [-p ival] [-o file]"
          The short usage string.

    Parameter < OE > const PARAMETERS []

          Definitions of command line parameters.
12.4.1 Detailed Description
File local scope.
12.4.2 Typedef Documentation
12.4.2.1 ofile
template<auto Ownership>
using anonymous_namespace{loadrec.cpp}::ofile = typedef io::file<Ownership, io::write>
Output file type alias.
```

#### **Template Parameters**

Ownership   The io::ownership type of the file
--

#### 12.4.3 Enumeration Type Documentation

#### 12.4.3.1 OE

```
enum anonymous_namespace{loadrec.cpp}::OE [strong]
```

An enum for command line parsing.

#### Enumerator

USAGE	Print help.
IVAL_DURATION	Set the duration of the recording.
IVAL_POLL	Set polling interval.
FILE_OUTPUT	Set output file.
FILE_PID	Set PID file.
FLAG_VERBOSE	Verbose output on stderr.
OPT_UNKNOWN	Obligatory.
OPT_NOOPT	Obligatory.
OPT_DASH	Obligatory.
OPT_LDASH	Obligatory.
OPT_DONE	Obligatory.

#### 12.4.4 Function Documentation

```
12.4.4.1 read_args()
```

Parse command line arguments.

#### Parameters

|--|

```
12.4.4.2 run()
```

```
void anonymous_namespace{loadrec.cpp}::run ( )
```

Report the load frames.

This prints the time in ms since the last frame and the cp\_times growth as a space separated list.

Outputs the given printf style message on stderr if g.verbose is set.

**Template Parameters** 

```
Msg← The message argument types
```

#### **Parameters**

```
msg The message to output
```

#### 12.4.5 Variable Documentation

#### 12.4.5.1 FEATURES

 $\verb|constexpr| flag_t| const| anonymous_namespace \{ \verb|loadrec.cpp| \} :: FEATURES| \\$ 

### Initial value: { 1\_FREQ\_TRACKING }

The set of supported features.

This value is stored in load recordings to allow loadplay to correctly interpret the data.

#### 12.4.5.2 PARAMETERS

```
Parameter<0E> const anonymous_namespace{loadrec.cpp}::PARAMETERS[]
```

#### Initial value:

Definitions of command line parameters.

12.5 anonymous\_namespace{powerd++.cpp} Namespace Reference

File local scope.

#### Classes

• struct Core

Contains the management information for a single CPU core. More...

struct CoreGroup

Contains the management information for a group of cores with a common clock frequency. More...

class FreqGuard

A core frequency guard.

struct Global

A collection of all the gloabl, mutable states. More...

#### **Enumerations**

enum AcLineState: unsigned int { AcLineState::BATTERY, AcLineState::ONLINE, AcLineState::UNKNOWN, AcLineState::LENGTH }

The available AC line states.

```
enum OE {
```

```
OE::USAGE, OE::MODE_AC, OE::MODE_BATT, OE::FREQ_MIN,
OE::FREQ_MAX, OE::FREQ_MIN_AC, OE::FREQ_MAX_AC, OE::FREQ_MIN_BATT,
OE::FREQ_MAX_BATT, OE::FREQ_RANGE, OE::FREQ_RANGE_AC, OE::FREQ_RANGE_BATT,
OE::HITEMP_RANGE, OE::MODE_UNKNOWN, OE::IVAL_POLL, OE::FILE_PID,
OE::FLAG_VERBOSE, OE::FLAG_FOREGROUND, OE::CNT_SAMPLES, OE::IGNORE,
OE::OPT_UNKNOWN, OE::OPT_NOOPT, OE::OPT_DASH, OE::OPT_LDASH,
OE::OPT_DONE }
```

An enum for command line parsing.

#### Functions

```
    template<typename... MsgTs>
void verbose (MsgTs &&... msg)
```

Outputs the given printf style message on stderr if g.verbose is set.

void sysctl\_fail (sys::sc\_error< sys::ctl::error > const err)

Treat sysctl errors.

void init ()

Perform initial tasks.

 template < bool Load = 1, bool Temperature = 0> void update loads ()

Updates the cp\_times ring buffer and computes the load average for each core.

template<>

```
void update_loads < 0, 0 > ()
```

Do nada if neither load nor temperature are to be updated.

 template<bool Foreground, bool Temperature, bool Fixed> void update\_freq (Global::ACSet const &acstate)

Update the CPU clocks depending on the AC line state and targets.

void update\_freq ()

Dispatch update\_freq<>().

void init\_loads ()

Fill the loads buffers with n samples.

• void set\_mode (AcLineState const line, char const \*const str)

Sets a load target or fixed frequency for the given AC line state.

void read\_args (int const argc, char const \*const argv[])

Parse command line arguments.

void show\_settings ()

Prints the configuration on stderr in verbose mode.

• void signal\_recv (int signal)

Sets g.signal, terminating the main loop.

• void run\_daemon ()

Daemonise and run the main loop.

#### **Variables**

struct anonymous\_namespace{powerd++.cpp}::Global g

The gobal state.

char const \*const USAGE = "[-hvf] [-abn mode] [-mM freq] [-FAB freq:freq] [-H temp:temp] [-p ival] [-s cnt] [-P file]"

The short usage string.

• Parameter < OE > const PARAMETERS []

Definitions of command line parameters.

#### 12.5.1 Detailed Description


File local scope.

#### 12.5.2 Class Documentation

#### 12.5.2.1 struct anonymous\_namespace{powerd++.cpp}::Core

Contains the management information for a single CPU core.

 $Collaboration\ diagram\ for\ an onymous\_namespace \{powerd++.cpp\} :: Core:$ 




#### Class Members

cptime_t	all	Count of all ticks.
cptime_t const *	cp_time	A pointer to the kern.cp_times section for this core.
CoreGroup *	group	The core that controls the frequency for this core.
cptime_t	idle	The idle ticks count.
SysctlSync< decikelvin_t >	temp	The dev.cpu. d.temperature sysctl, if present.

#### 12.5.2.2 struct anonymous\_namespace{powerd++.cpp}::CoreGroup

Contains the management information for a group of cores with a common clock frequency.

 $Collaboration\ diagram\ for\ an onymous\_namespace \{powerd++.cpp\} :: CoreGroup:$ 



#### Class Members

coreid_t	corei	The number of the core owning dev.cpu. d.freq.
SysctlSync< mhz_t >	freq	The sysctl dev.cpu. d.freq.
Max< mhz_t >	load	The maximum load reported by all cores in the group. This is updated by update_loads().
unique_ptr< mhz_t[]>	loads	A ring buffer of maximum load samples for this core group. Each maximum load sample is weighted with the core frequency at which it was taken.  This is updated by update_loads().
mhz_t	loadsum	The maximum load sum of all controlled cores. This is updated by update_loads().
Min< mhz_t >	max	The maximum group clock rate. The least of all core maxima in the group.
Max< mhz_t >	min	The minimum group clock rate. The greatest of all core minima in the group.
mhz_t	sample_freq	The dev.cpu. d.freq value for the current load sample. This is updated by update_loads().

#### Class Members


Max< decikelvin_t >	temp	The maximum temperature measurement taken in the group.
Min< decikelvin_t >	temp_crit	Critical core temperature in dK.
Min< decikelvin_t >	temp_high	High core temperature in dK.

#### 12.5.2.3 struct anonymous\_namespace{powerd++.cpp}::Global

A collection of all the gloabl, mutable states.

This is mostly for semantic clarity.

Collaboration diagram for anonymous\_namespace{powerd++.cpp}::Global:



#### Class Members

Sysctl	acline_ctl	The hw.acpi.acline ctl.
struct anonymous_namespace{powerd++	ADP[3]	
struct anonymous_namespace{powerd++	battery[3]	
unique_ptr< Core[]>	cores	This buffer is to be allocated with ncpu instances of the Core struct to store the management information of every core.
unique_ptr< cptime_t[][CPUSTATES]>	cp_times	The kern.cp_times buffer for all cores.
Sysctl	cp_times_ctl	The kern.cp_times sysctl.
bool	foreground	Foreground mode.
struct anonymous_namespace{powerd++	FREQ_DEFAULT_MAX[3]	
struct anonymous_namespace{powerd++	FREQ_DEFAULT_MIN[3]	
struct anonymous_namespace{powerd++	FREQ_UNSET[3]	

#### Class Members

unique_ptr< CoreGroup[]>	groups	This buffer is to be allocated with the number of core groups. A core group is created by init() for each core that has a dev.cpu.d.freq handle.
struct anonymous_namespace{powerd++	HADP[3]	
ms	interval	The polling interval.
SysctlOnce< coreid_t, 2 > const	псри	The number of CPU cores or threads.
coreid_t	ngroups	The number of frequency controlling core groups.
struct anonymous_namespace{powerd++	online[3]	
char const *	pidfilename	Name of an alternative pidfile. If not given pidfile_open() uses a default name.
size_t	sample	The current sample.
size_t	samples	The number of load samples to take.
volatile sig_atomic_t	signal	The last signal received, used for terminating.
decikelvin_t	temp_crit	User set critical core temperature in dK.
decikelvin_t	temp_high	User set high core temperature in dK.
bool	temp_throttling	Temperature throttling mode.
struct anonymous_namespace{powerd++	unknown[3]	The power states.
bool	verbose	Verbose mode.

#### 12.5.3 Enumeration Type Documentation

#### 12.5.3.1 AcLineState

 $\verb"enum anonymous_namespace{powerd++.cpp}{::} \verb"AcLineState": unsigned int [strong]"$ 

The available AC line states.

#### Enumerator

BATTERY	Battery is power source.
ONLINE	External power source.
UNKNOWN	Unknown power source.
LENGTH	Enum length.

#### 12.5.3.2 OE

enum anonymous\_namespace{powerd++.cpp}::OE [strong]

An enum for command line parsing.

#### Enumerator

USAGE	Print help.
MODE_AC	Set AC power mode.
MODE_BATT	Set battery power mode.
FREQ_MIN	Set minimum clock frequency.
FREQ_MAX	Set maximum clock frequency.
FREQ_MIN_AC	Set minimum clock frequency on AC power.
FREQ_MAX_AC	Set maximum clock frequency on AC power.
FREQ_MIN_BATT	Set minimum clock frequency on battery power.
FREQ_MAX_BATT	Set maximum clock frequency on battery power.
FREQ_RANGE	Set clock frequency range.
FREQ_RANGE_AC	Set clock frequency range on AC power.
FREQ_RANGE_BATT	Set clock frequency range on battery power.
HITEMP_RANGE	Set a high temperature range.
MODE_UNKNOWN	Set unknown power source mode.
IVAL_POLL	Set polling interval.
FILE_PID	Set pidfile.
FLAG_VERBOSE	Activate verbose output on stderr.
	Stay in foreground, log events to stdout.
FLAG_FOREGROUND	
CNT_SAMPLES	Set number of load samples.
IGNORE	Legacy settings.
OPT_UNKNOWN	Obligatory.
OPT_NOOPT	Obligatory.
OPT_DASH	Obligatory.
OPT_LDASH	Obligatory.
OPT_DONE	Obligatory.

#### 12.5.4 Function Documentation

#### 12.5.4.1 init()

 ${\tt void anonymous\_namespace\{powerd++.cpp\}::init ()}$ 

Perform initial tasks.

- Get number of CPU cores/threads
- Determine the clock controlling core for each core
- Set the MIBs of hw.acpi.acline and kern.cp\_times

```
12.5.4.2 init_loads()
void anonymous_namespace{powerd++.cpp}::init_loads ( )
```

Fill the loads buffers with n samples.

The samples are filled with the target load, this creates a bias to stay at the initial frequency until sufficient real measurements come in to flush these initial samples out.

Parse command line arguments.

#### **Parameters**

urgc,argv The command line argu	uments
---------------------------------	--------

Sets a load target or fixed frequency for the given AC line state.

The string must be in the following format:

Scalar values are treated as loads.

The predefined values have the following meaning:

Symbol	Meaning
minimum	The minimum clock rate (default 0 MHz)
min	
maximum	The maximum clock rate (default 1000000 MHz)
max	
adaptive	A target load of 50%
adp	
hiadptive	A target load of 37.5%
hadp	

#### Parameters

line	The power line state to set the mode for
str	A mode string

Sets g.signal, terminating the main loop.

#### Parameters

Treat sysctl errors.

Fails appropriately for the given error.

#### Parameters

```
err The errno value after calling sysctl
```

```
12.5.4.7 update_freq()
```

Update the CPU clocks depending on the AC line state and targets.

#### **Template Parameters**

Foreground	Set for foreground operation (reporting on std::cout)
Temperature	Set for temperature based throttling
Fixed	Set for fixed frequency mode

#### **Parameters**

```
12.5.4.8 update_loads()
```

```
template<bool Load = 1, bool Temperature = 0>
void anonymous_namespace{powerd++.cpp}::update_loads ( )
```

Updates the cp\_times ring buffer and computes the load average for each core.

#### **Template Parameters**

Load	Determines whether CoreGroup::loadsum is updated
Temperature	Determines whether CoreGroup::temp is updated

#### 12.5.4.9 verbose()

Outputs the given printf style message on stderr if g.verbose is set.

#### **Template Parameters**

Msg⇔	The message argument types
Ts	

#### **Parameters**

msg	The message to output
-----	-----------------------

#### 12.5.5 Variable Documentation

```
12.5.5.1 g
```

The gobal state.

#### 12.5.5.2 PARAMETERS

```
Parameter<OE> const anonymous_namespace{powerd++.cpp}::PARAMETERS[]
```

```
Initial value:
    {OE::USAGE,
                              'h', "help",
                                                                        "Show usage and exit"},
    {OE::FLAG_VERBOSE,
                             'v', "verbose",
                                                                        "Be verbose"},
    {OE::FLAG_FOREGROUND, 'f', "foreground",
                                                                        "Stay in foreground"},
                             'a', "ac",
'b', "batt",
'n', "unknown",
    {OE::MODE_AC,
                                                         "mode",
                                                                        "Mode while on AC power"},
                                                         "mode",
    {OE::MODE BATT
                                                                        "Mode while on battery power"},
                                                         "mode",
                                                                        "Mode while power source is unknown"},
"Minimum CPU frequency"},
    {OE::MODE UNKNOWN.
                             'm', "min",
                                                         "freq",
    {OE::FREQ MIN.
    {OE::FREQ_MAX,
                                                         "freq",
                                                                        "Maximum CPU frequency"},
                             'M', "max",
    {OE::FREQ_MIN_AC,
                                                        "freq",
                                                                        "Minimum CPU frequency on AC power"},
    {OE::FREQ_MAX_AC,
                              0 , "max-ac",
                                                         "freq",
                                                                        "Maximum CPU frequency on AC power"},
                             0 , "min-batt",
0 , "max-batt",
'F', "freq-range",
                                                         "freq",
    {OE::FREQ_MIN_BATT,
                                                                        "Minimum CPU frequency on battery power"},
                                                         "freq"
    {OE::FREQ MAX BATT.
                                                                        "Maximum CPU frequency on battery power"},
                                                         "freq:freq",
    {OE::FREQ RANGE,
                                                                       "CPU frequency range (min:max)"},
    {OE::FREQ_RANGE_AC, 'A', "freq-range-ac", "freq:freq", {OE::FREQ_RANGE_BATT, 'B', "freq-range-batt", "freq:freq",
                                                                        "CPU frequency range on AC power"},
                                                                        "CPU frequency range on battery power"}
    {OE::HITEMP_RANGE,
                             'H', "hitemp-range",
                                                         "temp:temp",
                                                                        "High temperature range (high:critical)"},
    {OE::IVAL_POLL,
                              'p', "poll",
                                                        "ival",
                                                                        "The polling interval"},
    {OE::CNT_SAMPLES,
                                   "samples",
                                                        "cnt",
"file",
                                                                        "The number of samples to use"},
    {OE::FILE PID,
                                   "pid",
                                                                        "Alternative PID file"},
    {OE::IGNORE,
                                                         "load",
                                                                        "Ignored"},
    {OE::IGNORE,
                                                         "load",
                                                                        "Ignored"}
```

Definitions of command line parameters.

#### 12.6 clas Namespace Reference

A collection of functions to process command line arguments.

#### Functions

types::cptime\_t load (char const \*const str)

Convert string to load in the range [0, 1024].

types::mhz\_t freq (char const \*const str)

Convert string to frequency in MHz.

types::ms ival (char const \*const str)

Convert string to time interval in milliseconds.

size\_t samples (char const \*const str)

A string encoded number of samples.

• types::decikelvin\_t temperature (char const \*const str)

Convert string to temperature in dK.

• int celsius (types::decikelvin\_t const val)

Converts dK into <sup>°</sup>C for display purposes.

• template<typename T >

```
std::pair < T, T > range (T(&func)(char const *const), char const *const str)
```

Takes a string encoded range of values and returns them.

#### 12.6.1 Detailed Description

A collection of functions to process command line arguments.

#### 12.6.2 Function Documentation

Converts dK into °C for display purposes.

**Parameters** 

```
val A temperature in dK
```

Returns

The temperature in  ${}^{\circ}\!C$ 

Convert string to frequency in MHz.

The given string must have the following format:

```
freq = <float>, [ "hz" | "khz" | "mhz" | "ghz" | "thz" ];
```

For compatibility with powerd MHz are assumed, if no unit string is given.

The resulting frequency must be in the range [0Hz, 1THz].

**Parameters** 

```
str A string encoded frequency
```

Returns

The frequency given by str

Convert string to time interval in milliseconds.

The given string must have the following format:

```
ival = <float>, [ "s" | "ms" ];
```

For compatibility with powerd scalar values are assumed to represent milliseconds.

#### Parameters

```
str | A string encoded time interval
```

#### Returns

The interval in milliseconds

Convert string to load in the range [0, 1024].

The given string must have the following format:

```
load = <float>, [ "%" ];
```

The input value must be in the range [0.0, 1.0] or [0%, 100%].

#### Parameters

```
str A string encoded load
```

#### Return values

[0,1024]	The load given by str
>	1024 The given string is not a load

Takes a string encoded range of values and returns them.

A range has the format from:to.

**Template Parameters** 

```
T The return type of the conversion function
```

#### **Parameters**

func		The function that converts the values from the string
	str	The string containing the range

#### Returns

A pair with the from and to values

A string encoded number of samples.

The string is expected to contain a scalar integer.

#### Parameters

```
str The string containing the number of samples
```

#### Returns

The number of samples

```
12.6.2.7 temperature()
```

Convert string to temperature in dK.

The given string must have the following format:

```
temperature = <float>, [ "C" | "K" | "F" | "R" ];
```

In absence of a unit  ${}^{\circ}\!C$  is assumed.

#### **Parameters**

str | A string encoded temperature

#### Returns

The temperature given by str

#### 12.7 constants Namespace Reference

A collection of constants.

#### Variables

• char const \*const CP\_TIMES = "kern.cp\_times"

The MIB name for per-CPU time statistics.

• char const \*const ACLINE = "hw.acpi.acline"

The MIB name for the AC line state.

• char const \*const FREQ = "dev.cpu.%d.freq"

The MIB name for CPU frequencies.

char const \*const FREQ\_LEVELS = "dev.cpu.%d.freq\_levels"

The MIB name for CPU frequency levels.

• char const \*const TEMPERATURE = "dev.cpu.%d.temperature"

The MIB name for CPU temperatures.

char const \*const TJMAX\_SOURCES []

An array of maximum temperature sources.

types::mhz\_t const FREQ\_DEFAULT\_MAX {1000000}

Default maximum clock frequency value.

• types::mhz\_t const FREQ\_DEFAULT\_MIN {0}

Default minimum clock frequency value.

types::mhz t const FREQ UNSET {1000001}

Clock frequency representing an uninitialised value.

char const \*const POWERD\_PIDFILE = "/var/run/powerd.pid"

The default pidfile name of powerd.

• types::cptime\_t const ADP {512}

The load target for adaptive mode, equals 50% load.

types::cptime\_t const HADP {384}

The load target for hiadaptive mode, equals 37.5% load.

types::decikelvin\_t const HITEMP\_OFFSET {100}

The default temperautre offset between high and critical temperature.

#### 12.7.1 Detailed Description

A collection of constants.

#### 12.7.2 Variable Documentation

## 12.7.2.1 TJMAX\_SOURCES char const\* const constants::TJMAX\_SOURCES[] Initial value:

An array of maximum temperature sources.

"dev.cpu.%d.coretemp.tjmax"

12.8 errors Namespace Reference

Common error handling types and functions.

#### Classes

• struct Exception

Exceptions bundle an exit code, errno value and message. More...

#### Enumerations

```
• enum Exit: int {
    Exit::OK, Exit::ECLARG, Exit::EOUTOFRANGE, Exit::ELOAD,
    Exit::EFREQ, Exit::EMODE, Exit::EIVAL, Exit::ESAMPLES,
    Exit::ESYSCTL, Exit::ENOFREQ, Exit::ECONFLICT, Exit::EPID,
    Exit::EFORBIDDEN, Exit::EDAEMON, Exit::EWOPEN, Exit::ESIGNAL,
    Exit::ERANGEFMT, Exit::ETEMPERATURE, Exit::EEXCEPT, Exit::EFILE,
    Exit::EEXEC, Exit::LENGTH }
    Exit codes.
```

#### **Functions**

• void fail (Exit const exitcode, int const err, std::string const &msg)

Throws an Exception instance with the given message.

#### Variables

• const char \*const ExitStr []

Printable strings for exit codes.

#### 12.8.1 Detailed Description


Common error handling types and functions.

#### 12.8.2 Class Documentation

#### 12.8.2.1 struct errors::Exception

Exceptions bundle an exit code, errno value and message.

 $Collaboration\ diagram\ for\ errors :: Exception:$ 



#### Class Members

int	err	The errno value at the time of creation.
Exit	exitcode	The code to exit with.
string	msg	An error message.

#### 12.8.3 Enumeration Type Documentation

#### 12.8.3.1 Exit

enum errors::Exit : int [strong]

Exit codes.

#### Enumerator

OK	Regular termination.
ECLARG	Unexpected command line argument.
EOUTOFRANGE	A user provided value is out of range.
ELOAD	The provided value is not a valid load.

#### Enumerator

EFREQ	The provided value is not a valid frequency.
EMODE	The provided value is not a valid mode.
EIVAL	The provided value is not a valid interval.
ESAMPLES	The provided value is not a valid sample count.
ESYSCTL	A sysctl operation failed.
ENOFREQ	System does not support changing core frequencies.
ECONFLICT	Another frequency daemon instance is running.
EPID	A pidfile could not be created.
EFORBIDDEN	Insufficient privileges to change sysctl.
EDAEMON	Unable to detach from terminal.
EWOPEN	Could not open file for writing.
ESIGNAL	Failed to install signal handler.
ERANGEFMT	A user provided range is missing the separator.
ETEMPERATURE	The provided value is not a valid temperature.
EEXCEPT	Untreated exception.
EFILE	Not a valid file name.
EEXEC	Command execution failed.
LENGTH	Enum length.

#### 12.8.4 Function Documentation

Throws an Exception instance with the given message.

#### Parameters

	exitcode	The exit code to return on termination
err T		The errno value at the time the exception was created
	msg	The message to show

#### 12.8.5 Variable Documentation

# 12.8.5.1 ExitStr const char\* const errors::ExitStr[] Initial value: { "OK", "ECLARG", "EOUTOFRANGE", "ELOAD", "EFREQ", "EMODE", "EIVAL", "ESAMPLES", "ESYSCTL", "ENOFREQ", "ECONFLICT", "EPID", "EFORBIDDEN", "EDAEMON", "EWOPEN", "ESIGNAL", "ERANGEFMT", "ETEMPERATURE", "EEXCEPT", "EFILE", "EEXEC"

Printable strings for exit codes.

#### 12.9 nih Namespace Reference

Not invented here namespace, for code that substitutes already commonly available functionality.

#### Classes

· struct enum has members

Tests whether the given enum provides all the required definitions.

class Options

An instance of this class offers operators to retrieve command line options and arguments.

struct Parameter

Container for an option definition. More...

#### **Functions**

```
    template<class OptionT >
        size_t argCount (Parameter< OptionT > const &def)
```

Retrieves the count of arguments in an option definition.

template<class OptionT, size\_t DefCount>
 constexpr Options
 OptionT, DefCount > make\_Options (int const argc, char const \*const \*const argv, char const \*const usage, Parameter
 OptionT > const (&defs)[DefCount])

Wrapper around the Options<> constructor, that uses function template matching to deduce template arguments.

#### 12.9.1 Detailed Description

Not invented here namespace, for code that substitutes already commonly available functionality.

12.9.2 Class Documentation

12.9.2.1 struct nih::Parameter

```
template < class OptionT >
struct nih::Parameter < OptionT >
```

Container for an option definition.

Aliases can be defined by creating definitions with the same option member.

The lparam, args and usage members have to be 0 terminated, using string literals is safe.

#### **Template Parameters**

OptionT	An enum or enum class representing the available options
---------	--

#### Class Members

char const *	args	A comma separated list of arguments. Set to nullptr or "" if no argument is available.
char const *	lparam	The long version of this parameter. Set to nullptr or "" if no long parameter is available.
OptionT	option	The enum value to return for this option.
char	sparam	The short version of this parameter. Set to 0 if no short parameter is available.
char const *	usage	A usage string.

#### 12.9.3 Function Documentation

Retrieves the count of arguments in an option definition.

**Template Parameters** 

OptionT An enum or enum class representing the available optio	ns
--	----

#### Parameters

```
def The parameter definition
```

#### Returns

The number of arguments specified in the given definition

Wrapper around the Options<> constructor, that uses function template matching to deduce template arguments.

#### **Template Parameters**

OptionT	An enum for all the available options
DefCount	The number of option definitions

#### **Parameters**

argc,argv	The command line arguments
usage	A usage string that is used in the header of the usage output
defs An array of parameter definitions	

#### 12.10 sys Namespace Reference

Wrappers around native system interfaces.

#### Namespaces

ctl

This namespace contains safer c++ wrappers for the sysctl() interface.

env

 $Provides\ wrappers\ around\ the\ getenv()\ family\ of\ functions.$ 

io

This namespace contains c++ wrappers for < cstdio> functionality.

pid

This namespace contains safer c++ wrappers for the pidfile\_\*() interface.

• sig

This namespace provides c++ wrappers for signal(3).

#### Classes

struct sc\_error

Can be thrown by syscall function wrappers if the function returned with an error.

#### 12.10.1 Detailed Description

Wrappers around native system interfaces.

#### 12.11 sys::ctl Namespace Reference

This namespace contains safer c++ wrappers for the sysctl() interface.

#### Classes

· struct error

The domain error type. More...

· class Once

A read once representation of a Sysctl.

class Sync

This is a wrapper around Sysctl that allows semantically transparent use of a sysctl.

class Sysctl

Represents a sysctl MIB address.

class Sysctl< 0 >

This is a specialisation of Sysctl for sysctls using symbolic names.

#### **Typedefs**

typedef int mib\_t

Management Information Base identifier type (see sysctl(3)).

```
    template<typename T, size_t MibDepth = 0>
    using SysctlSync = Sync< T, Sysctl< MibDepth >>
```

A convenience alias around Sync.

template<typename T, size\_t MibDepth>
 using SysctlOnce = Once< T, Sysctl< MibDepth >>

A convenience alias around Once.

#### **Functions**

• void sysctl\_raw (mib\_t const \*name, u\_int const namelen, void \*const oldp, size\_t \*const oldlenp, void const \*const newp, size\_t const newlen)

A wrapper around the sysctl() function.

```
    template<size_t MibDepth>
    void sysctl_get (mib_t const (&mib)[MibDepth], void *const oldp, size_t &oldlen)
```

Returns a sysctl() value to a buffer.

template<size\_t MibDepth>
 void sysctl\_set (mib\_t const (&mib)[MibDepth], void const \*const newp, size\_t const newlen)

Sets a sysctl() value.

• template<typename... Args>

```
constexpr Sysctl < sizeof...(Args) > make_Sysctl (Args const ... args)
```

Create a Sysctl instances.

• template<typename T , class SysctlT >

constexpr Once < T, SysctIT > make\_Once (T const &value, SysctIT const &sysctI) noexcept

This creates a Once instance.

#### 12.11.1 Detailed Description

This namespace contains safer c++ wrappers for the sysctl() interface.

The template class Sysctl represents a sysctl address and offers handles to retrieve or set the stored value.

The template class Sync represents a sysctl value that is read and written synchronously.

The template class Once represents a read once value.

```
12.11.2 Class Documentation
```

12.11.2.1 struct sys::ctl::error

The domain error type.

#### 12.11.3 Typedef Documentation

#### 12.11.3.1 SysctlOnce

```
template<typename T , size_t MibDepth>
using sys::ctl::SysctlOnce = typedef Once<T, Sysctl<MibDepth> >
```

#### A convenience alias around Once.

```
// Once<coreid_t, Sysctl<2>> ncpu{0, {CTL_HW, HW_NCPU}};
SysctlOnce<coreid_t, 2> ncpu{1, {CTL_HW, HW_NCPU}};
```

#### **Template Parameters**

Т	The type to represent the sysctl as
MibDepth	The maximum allowed MIB depth

#### 12.11.3.2 SysctlSync

#### **Template Parameters**

```
T The type to represent the sysctl as

MibDepth The MIB depth, provide only for compile time initialisation
```

#### 12.11.4 Function Documentation

```
12.11.4.1 make_Once()
```

```
template<typename T , class SysctlT >
constexpr Once<T, SysctlT> sys::ctl::make_Once (
```

```
T const & value,  \\  \text{SysctlT const & } sysctl \text{ }) \quad [\text{noexcept}]
```

This creates a Once instance.

This is intended for cases when a Once instance is created as a temporary to retrieve a value, using it's fallback to a default mechanism.

**Template Parameters** 

Т	The value type
SysctlT	The Sysctl type

#### **Parameters**

value	The default value to fall back to	
sysctl	The sysctl to try and read from	

Create a Sysctl instances.

This is only compatible with creating sysctls from predefined MIBs.

**Template Parameters** 

Args	List of argument types, should all be pid_t
------	---

#### Parameters

#### Returns

A Sysctl instance with the depth matching the number of arguments

Returns a sysctl() value to a buffer.

#### **Template Parameters**

of the MIB buffer	MibDepth The
-------------------	--------------

#### **Parameters**

mib	The MIB buffer	
oldp,oldlen	A pointers to the return buffer and a reference to its length	

#### Exceptions

ys::sc_error <error></error>	Throws if sysctl() fails for any reason
------------------------------	---

A wrapper around the sysctl() function.

All it does is throw an exception if sysctl() fails.

#### Parameters

name,namelen	The MIB buffer and its length
oldp,oldlenp	Pointers to the return buffer and its length
newp,newlen	A pointer to the buffer with the new value and the buffer length

#### Exceptions

```
sys::sc_error<error> Throws if sysctl() fails for any reason
```

Sets a sysctl() value.

#### **Template Parameters**

#### **Parameters**

mib	The MIB buffer
newp,newlen	A pointer to the buffer with the new value and the buffer length

#### Exceptions

sys::sc_error <error></error>	Throws if sysctl() fails for any reason
-------------------------------	---

#### 12.12 sys::env Namespace Reference

Provides wrappers around the getenv() family of functions.

#### Classes

struct error

The domain error type. More...

class Var

A reference type refering to an environment variable.

struct Vars

A singleton class providing access to environment variables.

#### Variables

• struct sys::env::Vars vars

Singleton providing access to environment variables.

#### 12.12.1 Detailed Description

Provides wrappers around the getenv() family of functions.

12.12.2 Class Documentation

12.12.2.1 struct sys::env::error

The domain error type.

12.12.3 Variable Documentation

```
12.12.3.1 vars
struct sys::env::Vars sys::env::vars
Singleton providing access to environment variables.
         sys::io Namespace Reference
12.13
This namespace contains c++ wrappers for <cstdio> functionality.
Classes

    struct contains

           Check whether a set type contains a value. More...
     struct contains< set< Set ... >, Value >
           Specialise io::contains to unpack io::set.
     • struct enable_if
           Similar to std::enable_if, but it also has the value of the expression.

    struct enable_if< false, T >

           Specialise enable_if for a false expression.

    class file

           Produces file access types around the C file handling facilities. More...

    class file < link, Features ... >

           Specialise for FILE object linking file instances.

 class file < own, Features ... >

           Specialise for FILE object owning file instances.

    class file_feature

           Implements the base functionality of all file access types.
     • class file_feature< FileT, read, Tail ... >
           Implement read support for file types.

    class file_feature
    FileT, seek, Tail ... >

           Implement seek support for file types.

    class file_feature
    FileT, write, Tail ... >

           Implement write support for file types.
     • struct is_superset_of
           Check whether the left hand set is a superest of the right hand set. More...

    struct is_superset_of< LSetT, set< RSet ... >>

           Specialise is_superset_of to unpack the right hand io::set.

    struct query

           Ask questions about the contents of a string. More...

    struct set

           Pack a set of integral values in a type. More...
Typedefs
     • template < class SetT, auto Value >
       using contains_t = typename contains< SetT, Value >::type
           Check whether a set type contains a value.

    template < class LSetT , class RSetT >

       using \ is\_superset\_of\_t = typename \ is\_superset\_of < LSetT, RSetT > ::type
```

Check whether the left hand set is a superest of the right hand set.

#### Enumerations

• enum feature { feature::read, feature::write, feature::seek }

Feature flags for file type composition.

enum ownership { ownership::own, ownership::link }

Ownership relation to the underlying FILE object.

#### Variables

• template<class SetT, auto Value>
constexpr auto const contains\_v = contains<SetT, Value>::value

Check whether a set type contains a value.

template < class LSetT, class RSetT >
 constexpr auto const is\_superset\_of\_v = is\_superset\_of < LSetT, RSetT > ::value
 Check whether the left hand set is a superest of the right hand set.

• file< link, write > ferr {stderr}

File access instances for stderr.

file< link, write > fout {stdout}

File access instances for stdout.

file< link, read > fin {stdin}

File access instances for stdin.

### 12.13.1 Detailed Description

This namespace contains c++ wrappers for <cstdio> functionality.

12.13.2 Class Documentation

12.13.2.1 struct sys::io::contains

template < class SetT, auto Value > struct sys::io::contains < SetT, Value >

Check whether a set type contains a value.

**Template Parameters** 

SetT	A set of integral values packed in io::set
Value	The value to look up

12.13.2.2 class sys::io::file

template<ownership Ownership, feature ... Features> class sys::io::file< Ownership, Features>

Produces file access types around the C file handling facilities.

# **Template Parameters**

Ownership	Determine the ownership relationship to the underlying FILE object
Features	A list of features the file type supports

# See also

ownership feature file<own, Features ...> file<link, Features ...> file\_feature

12.13.2.3 struct sys::io::is\_superset\_of

template<class LSetT, class RSetT> struct sys::io::is\_superset\_of< LSetT, RSetT >

Check whether the left hand set is a superest of the right hand set.


# **Template Parameters**

LSetT,RSetT | Two io::set instances

# 12.13.2.4 struct sys::io::query

Ask questions about the contents of a string.

Collaboration diagram for sys::io::query:



# Class Members

struct contains_ftor	contains	Query the string for characters.

12.13.2.5 struct sys::io::set

```
template<auto ... Set> struct sys::io::set< Set >
```

Pack a set of integral values in a type.

**Template Parameters** 

```
Set A set of integral values
```

12.13.3 Typedef Documentation

```
12.13.3.1 contains_t
```

```
template<class SetT , auto Value>
using sys::io::contains_t = typedef typename contains<SetT, Value>::type
```

Check whether a set type contains a value.

**Template Parameters** 

SetT	A set of integral values packed in io::set
Value	The value to look up

```
12.13.3.2 is_superset_of_t
```

```
template<class LSetT , class RSetT >
using sys::io::is_superset_of_t = typedef typename is_superset_of<LSetT, RSetT>::type
```

Check whether the left hand set is a superest of the right hand set.

**Template Parameters** 

```
LSetT,RSetT | Two io::set instances
```

12.13.4 Enumeration Type Documentation

```
12.13.4.1 feature
```

```
enum sys::io::feature [strong]
```

Feature flags for file type composition.

See also

file\_feature

# Enumerator

read	The file type supports read operations.
	See also
	file_feature <filet, read,="" tail=""></filet,>
write	The file type supports write operations.
	See also
	file_feature <filet, tail="" write,=""></filet,>
seek	The file type supports seek operations.
	See also
	file_feature <filet, seek,="" tail=""></filet,>

# 12.13.4.2 ownership

```
enum sys::io::ownership [strong]
```

Ownership relation to the underlying FILE object.

# Enumerator

own	The file instance owns the FILE object.
	See also
	file <own, features=""></own,>
link	The file instance refers to a FILE object managed somewhere else.
	See also
	file <link, features=""></link,>

## 12.13.5 Variable Documentation

```
12.13.5.1 contains_v

template<class SetT , auto Value>
constexpr auto const sys::io::contains_v = contains<SetT, Value>::value
```

Check whether a set type contains a value.

## **Template Parameters**

SetT	A set of integral values packed in io::set
Value	The value to look up

```
12.13.5.2 is_superset_of_v
```

```
template<class LSetT , class RSetT >
constexpr auto const sys::io::is_superset_of_v = is_superset_of<LSetT, RSetT>::value
```

Check whether the left hand set is a superest of the right hand set.

**Template Parameters** 

# 12.14 sys::pid Namespace Reference

This namespace contains safer c++ wrappers for the pidfile\_\*() interface.

## Classes

struct error

The domain error type. More...

· class Pidfile

A wrapper around the pidfile\_\* family of commands implementing the RAII pattern.

# 12.14.1 Detailed Description

This namespace contains safer c++ wrappers for the pidfile\_\*() interface.

The class Pidfile implements the RAII pattern for holding a pidfile.

12.14.2 Class Documentation

12.14.2.1 struct sys::pid::error

The domain error type.

# 12.15 sys::sig Namespace Reference

This namespace provides c++ wrappers for signal(3).

## Classes

• struct error

The domain error type. More...

class Signal

Sets up a given signal handler and restores the old handler when going out of scope.

# Typedefs

using sig\_t = void(\*)(int)
 Convenience type for signal handlers.

## 12.15.1 Detailed Description

This namespace provides c++ wrappers for signal(3).

12.15.2 Class Documentation

12.15.2.1 struct sys::sig::error

The domain error type.

# 12.16 timing Namespace Reference

Namespace for time management related functionality.

# Classes

• class Cycle

Implements an interruptible cyclic sleeping functor.

# 12.16.1 Detailed Description

Namespace for time management related functionality.

# 12.17 types Namespace Reference

A collection of type aliases.

### **Typedefs**

typedef std::chrono::milliseconds ms
 Millisecond type for polling intervals.

• typedef int coreid\_t

Type for CPU core indexing.

typedef unsigned long cptime\_t

Type for load counting.

typedef unsigned int mhz\_t

Type for CPU frequencies in MHz.

• typedef int decikelvin\_t

Type for temperatures in dK.

### 12.17.1 Detailed Description

A collection of type aliases.

## 12.17.2 Typedef Documentation

```
12.17.2.1 cptime_t
```

typedef unsigned long types::cptime\_t

Type for load counting.

According to src/sys/kern/kern\_clock.c the type is long (an array of loads long [CPUSTATES] is defined). But in order to have defined wrapping characteristics unsigned long will be used here.

# 12.18 utility Namespace Reference

A collection of generally useful functions.

## Namespaces

literals

Contains literal operators.

#### Classes

class Formatter

A formatting wrapper around string literals.

class Max

A simple value container that provides the maximum of assigned values.

class Min

A simple value container that provides the minimum of assigned values.

class Sum

A simple value container only allowing += and copy assignment.

### **Functions**

```
    template<typename T, size_t Count>
        constexpr size_t count of (T(&)[Count])
```

Like sizeof(), but it returns the number of elements an array consists of instead of the number of bytes.

```
template<typename... Args>
void sprintf (Args...)
```

This is a safeguard against accidentally using sprintf().

template<size\_t Size, typename... Args>
 int sprintf\_safe (char(&dst)[Size], char const \*const format, Args const ... args)

A wrapper around snprintf() that automatically pulls in the destination buffer size.

template<class ET, typename VT = typename std::underlying\_type<ET>::type>
constexpr VT to\_value (ET const op)

Casts an enum to its underlying value.

### 12.18.1 Detailed Description

A collection of generally useful functions.

12.18.2 Function Documentation

Like sizeof(), but it returns the number of elements an array consists of instead of the number of bytes.

**Template Parameters** 

```
T,Count The type and number of array elements
```

#### Returns

The number of array entries

This is a safeguard against accidentally using sprintf().

Using it triggers a static\_assert(), preventing compilation.

## **Template Parameters**

Args   Catch all argu	ıments
-----------------------	--------

```
12.18.2.3 sprintf_safe()
```

A wrapper around snprintf() that automatically pulls in the destination buffer size.

# **Template Parameters**

Size	The destination buffer size
Args	The types of the arguments

#### Parameters

dst	A reference to the destination buffer
format	A printf style formatting string
args	The printf arguments

## Returns

The number of characters in the resulting string, regardless of the available space

```
12.18.2.4 to_value()
```

Casts an enum to its underlying value.

# **Template Parameters**

ET,VT	The enum and value type

### Parameters

ор	The operand to convert
----	------------------------

Returns

The integer representation of the operand

12.19 utility::literals Namespace Reference

Contains literal operators.

**Functions** 

• constexpr Formatter < 16384 > operator""\_fmt (char const \*const fmt, size\_t const)

Literal to convert a string literal to a Formatter instance.

12.19.1 Detailed Description

Contains literal operators.

12.19.2 Function Documentation

Literal to convert a string literal to a Formatter instance.

**Parameters** 

fmt A printf style format string

Returns

A Formatter instance

12.20 version Namespace Reference

Version information constants and types.

Namespaces

literals

Literals to set flag bits.

## **Typedefs**

typedef uint64\_t flag\_t
 The data type to use for feature flags.

### Enumerations

enum LoadrecBits { LoadrecBits::FREQ\_TRACKING }
 Feature flags for load recordings.

### Variables

char const \*const LOADREC\_FEATURES = "usr.app.powerdxx.loadrec.features"
 The pseudo MIB name for the load recording feature flags.

### 12.20.1 Detailed Description

Version information constants and types.

12.20.2 Enumeration Type Documentation

### 12.20.2.1 LoadrecBits

enum version::LoadrecBits [strong]

Feature flags for load recordings.

### Enumerator

	Record clock frequencies per frame.
FREQ_TRACKING	

# 12.21 version::literals Namespace Reference

Literals to set flag bits.

## **Functions**

constexpr flag\_t operator""\_FREQ\_TRACKING (unsigned long long int value)
 Set the FREQ\_TRACKING bit.

# 12.21.1 Detailed Description

Literals to set flag bits.

#### 12.21.2 Function Documentation

Set the FREQ\_TRACKING bit.

#### **Parameters**

value	The bit value
-------	---------------

### Returns

The flag at the correct bit position

# 13 Class Documentation

13.1 anonymous\_namespace{libloadplay.cpp}::Callback< FunctionArgs > Class Template Reference

Implements a recursion safe std::function wrapper.

# **Public Types**

typedef std::function< void(FunctionArgs...)> function\_t
 The callback function type.

## **Public Member Functions**

• Callback ()

Default constructor, creates a non-callable handle.

Callback (function\_t const &callback)

Construct from function.

Callback (function\_t &&callback)

Construct from temporary function.

void operator() (FunctionArgs... args)

Forward call to callback functions.

# Private Attributes

function\_t callback

Storage for the callback function.

• bool called {false}

Set if this handle is currently in use.

### 13.1.1 Detailed Description

```
template<typename... FunctionArgs>
class anonymous_namespace{libloadplay.cpp}::Callback< FunctionArgs >
```

Implements a recursion safe std::function wrapper.

The purpose is to prevent recursive calls of a callback function handle, in cases when a callback function performs actions that cause a successive call of the callback function.

To avoid having to return a value when a successive function call occurs only functions returning void are valid callback functions.

This is not thread safe.

**Template Parameters** 

Function←	The argument types of the callback function
Args	

#### 13.1.2 Constructor & Destructor Documentation

```
13.1.2.1 Callback() [1/2]
```

Construct from function.

**Parameters** 

```
callback | The callback function
```

# 13.1.2.2 Callback() [2/2]

Construct from temporary function.

Parameters

```
callback The callback function
```

## 13.1.3 Member Function Documentation

Forward call to callback functions.

### Parameters

a	rgs	The arguments to the callback function
---	-----	--

# Exceptions

dler was default constructed or constructed from a nullptr	std::bad_function_call   In case this handler wa
--	--

The documentation for this class was generated from the following file:


• src/libloadplay.cpp

# 13.2 sys::io::contains< set< Set ... >, Value > Struct Template Reference


Specialise io::contains to unpack io::set.

```
\verb|#include| < \verb|io.hpp|>
```

 $Inheritance\ diagram\ for\ sys::io::contains < set < Set\ ...\ >,\ Value >:$ 



Collaboration diagram for sys::io::contains< set< Set ... >, Value >:



Additional Inherited Members

## 13.2.1 Detailed Description

```
template<auto ... Set, auto Value> struct sys::io::contains< set< Set ... >, Value >
```

Specialise io::contains to unpack io::set.

**Template Parameters** 

Set	The set of integral values to search
Value	The value to find in Set

The documentation for this struct was generated from the following file:

• src/sys/io.hpp

# 13.3 sys::io::query::contains\_ftor Struct Reference

Test a string whether it contains a set of characters.

```
#include <io.hpp>
```

**Public Member Functions** 

- constexpr bool operator() (char const ch) const Check for a single character.
- template<typename ... CharTs>
   constexpr bool any (CharTs const ... chars) const
   Check for a set of characters if at least one is part of the string.
- template<typename ... CharTs>
   constexpr bool all (CharTs const ... chars) const
   Check for a set of characters if all of them are part of the string.

**Public Attributes** 

• char const \*const str

The string to ask about.

## 13.3.1 Detailed Description

Test a string whether it contains a set of characters.

13.3.2 Member Function Documentation

Check for a set of characters if all of them are part of the string.

**Template Parameters** 

Char⇔	The character types
Ts	

# Parameters

```
chars The set of characters
```

Returns

Whether all of the given characters are in the string

Check for a set of characters if at least one is part of the string.

Template Parameters

Char⇔	The character types
Ts	

## **Parameters**

chars	The set of characters

### Returns

Whether at least one of the given characters is in the string

Check for a single character.

#### **Parameters**

```
ch The character to check for
```

#### Returns

Whether the given character is part of the string

The documentation for this struct was generated from the following file:

• src/sys/io.hpp

# 13.4 timing::Cycle Class Reference

Implements an interruptible cyclic sleeping functor.

```
#include <Cycle.hpp>
```

**Public Member Functions** 

• bool operator() () const

Completes an interrupted sleep cycle.

template<class... DurTraits>
bool operator() (std::chrono::duration< DurTraits... > const &cycleTime)

Sleep for the time required to complete the given cycle time.

### Private Types

- using clock = std::chrono::steady\_clock
   Use steady\_clock, avoid time jumps.
- using us = std::chrono::microseconds
   Shorthand for microseconds.

#### Private Attributes

std::chrono::time\_point < clock > clk = clock::now()
 The current time clock.

## 13.4.1 Detailed Description

Implements an interruptible cyclic sleeping functor.

Cyclic sleeping means that instead of having a fixed sleeping time, each sleep is timed to meet a fixed wakeup time. I.e. the waking rhythm does not drift with changing system loads.

The canonical way to do this in C++ is like this:

```
#include <chrono>
#include <thread>
int main() {
    std::chrono::milliseconds const ival{500};
    auto time = std::chrono::steady_clock::now();
    while (...something...) {
        std::this_thread::sleep_until(time += ival);
        ...do stuff...
    }
    return 0;
}
```

The issue is that you might want to install a signal handler to guarantee stack unwinding and sleep\_until() will resume its wait after the signal handler completes.

The Cycle class offers you an interruptible sleep:

```
#include "Cycle.hpp"
#include <csignal>
...signal handlers...
int main() {
   std::chrono::milliseconds const ival{500};
   ...setup some signal handlers...
   timing::Cycle sleep;
   while (...something... && sleep(ival)) {
        ...do stuff...
   }
   return 0;
}
```

In the example the while loop is terminated if the sleep() is interrupted by a signal. Optionally the sleep cycle can be resumed:

```
timing::Cycle sleep;
while (...something...) {
   if (!sleep(ival)) {
        ...interrupted...
        while (!sleep());
   }
   ...do stuff...
}
```

Note there was a design decision between providing a cycle time to the constructor or providing it every cycle. The latter was chosen so the cycle time can be adjusted.

### 13.4.2 Member Function Documentation

```
13.4.2.1 operator()() [1/2]
bool timing::Cycle::operator() ( ) const [inline]
```

Completes an interrupted sleep cycle.

l.e. if the last sleep cycle was 500 ms and the sleep was interrupted 300 ms into the cycle, this would sleep for the remaining 200 ms unless interrupted.

### Return values

true	Sleep completed uninterrupted
false	Sleep was interrupted

## 13.4.2.2 operator()() [2/2]

Sleep for the time required to complete the given cycle time.

l.e. if the time since the last sleep cycle was 12 ms and the given cycleTime was 500 ms, the actual sleeping time would be 488 ms.

### **Template Parameters**

Dur⊷	The traits of the duration type
Traits	

#### Parameters

cycle↔	The duration of the cycle to complete
Time	

### Return values

	true	Command completed uninterrupted
Ī	false	Command was interrupted

The documentation for this class was generated from the following file:

• src/Cycle.hpp

# 13.5 anonymous\_namespace{libloadplay.cpp}::Emulator Class Reference

Instances of this class represent an emulator session.

 $Collaboration\ diagram\ for\ an onymous\_name space \{libload play.cpp\} :: Emulator:$ 



#### Classes

struct Core

Per core information. More...

#### **Public Member Functions**

• Emulator (ifile< io::link > fin, ofile< io::link > fout, bool const &die)

The constructor initialises all the members necessary for emulation.

void operator() ()

Performs load emulation and prints statistics on io::fout.

#### **Private Attributes**

• ifile < io::link > fin

The input data source.

ofile< io::link > fout

The output data sink.

• bool const & die

A reference to a bool that tells the emulator to die.

size\_t const size = sysctls[CP\_TIMES].size()

The size of the kern.cp\_times buffer.

• int const ncpu = this->size / sizeof(cptime\_t[CPUSTATES])

The number of CPUs in kern.cp\_times, may be greater than the hw.ncpu value (e.g.

std::unique\_ptr< Core[]> cores {new Core[this->ncpu]{}}

Simulation state information for each core.

• SysctlValue & cp\_times = sysctls[CP\_TIMES]

The kern.cp\_times sysctl handler.

std::unique\_ptr< cptime\_t[]> sum {new cptime\_t[CPUSTATES \* ncpu]{}}

The current kern.cp\_times values.

## 13.5.1 Detailed Description

Instances of this class represent an emulator session.

This should be run in its own thread and expects the sysctl table to be complete.

### 13.5.2 Class Documentation

13.5.2.1 struct anonymous\_namespace{libloadplay.cpp}::Emulator::Core

Per core information.

Collaboration diagram for anonymous\_namespace{libloadplay.cpp}::Emulator::Core:



## Class Members

cptime_t	carryLoadCycles	The load cycles carried over to the next frame in [kcycles]. This is determined at the beginning of frame and used to calculated the simulation load at the beginning of the next frame.
SysctlValue *	freqCtl	The sysctl handler. The constructor ensures this points to a valid handler.
mhz_t	recFreq	The recorded clock frequency. If FREQ_TRACKING is enabled this is updated at during the preliminary stage and used at the beginning of frame stage.
mhz_t	runFreq	The clock frequency the simulation is running at. Updated at the end of frame and used in the next frame.
cptime_t	runLoadCycles	The load cycles simulated for this frame in [kcycles]. This is determined at the beginning of frame and used to calculate the reported load at the end of frame.

### 13.5.3 Constructor & Destructor Documentation

## 13.5.3.1 Emulator()

The constructor initialises all the members necessary for emulation.

It also prints the column headers on stdout.

# Exceptions

std::out_of_range	In case one of the required sysctls is missing
-------------------	--

### Parameters

fin,fout	The character input and output streams	
die	If the referenced bool is true, emulation is terminated prematurely	

## 13.5.4 Member Function Documentation

# 13.5.4.1 operator()()

```
void anonymous_namespace{libloadplay.cpp}::Emulator::operator() ( ) [inline]
```

Performs load emulation and prints statistics on io::fout.

Reads fin to pull in load changes and updates the kern.cp\_times sysctl to represent the current state.

When it runs out of load changes it terminates emulation and sends a SIGINT to the process.

13.5.5 Member Data Documentation

```
13.5.5.1 ncpu
```

```
int const anonymous_namespace{libloadplay.cpp}::Emulator::ncpu = this->size / sizeof(cptime_t[CPUSTATES])
[private]
```

The number of CPUs in kern.cp\_times, may be greater than the hw.ncpu value (e.g.

if hyperthreading was turned off).

The documentation for this class was generated from the following file:

• src/libloadplay.cpp

```
13.6 sys::io::enable_if< bool, T > Struct Template Reference
```

Similar to std::enable\_if, but it also has the value of the expression.

```
#include <io.hpp>
```

**Public Types** 

using type = T
 Provide the requested type.

Static Public Attributes

• static constexpr bool const value {true}

The given expression is true.

## 13.6.1 Detailed Description

```
template < bool, class T = void>
struct sys::io::enable_if < bool, T >
```

Similar to std::enable\_if, but it also has the value of the expression.

**Template Parameters** 

```
The return type if the expression is true
```

The documentation for this struct was generated from the following file:

• src/sys/io.hpp

```
13.7 sys::io::enable_if< false, T > Struct Template Reference
```

Specialise enable\_if for a false expression.

```
#include <io.hpp>
```

Static Public Attributes

static constexpr bool const value {false}
 The given expression is false.

# 13.7.1 Detailed Description

```
template < class T >
struct sys::io::enable_if < false, T >
```

Specialise enable\_if for a false expression.

**Template Parameters** 

```
T | The return type if the expression was true
```

The documentation for this struct was generated from the following file:


• src/sys/io.hpp

13.8 nih::enum\_has\_members< OptionT, class > Struct Template Reference


Tests whether the given enum provides all the required definitions.

```
\verb|#include| < Options.hpp>
```

Inheritance diagram for nih::enum\_has\_members< OptionT, class >:



 $Collaboration\ diagram\ for\ nih::enum\_has\_members < OptionT,\ class >:$ 



# 13.8.1 Detailed Description

template<class OptionT, class = void>
struct nih::enum\_has\_members< OptionT, class >

Tests whether the given enum provides all the required definitions.

The Options<> template expects the provided enum to provide the following members:

Member	Description
OPT_UNKNOWN	An undefined option (long or short) was encountered
OPT_NOOPT	The encountered command line argument is not an option
OPT_DASH	A single dash "-" was encountered
OPT_LDASH	Double dashes "" were encountered
OPT_DONE	All command line arguments have been processed

**Template Parameters** 

Option T An enum or enum class representing the available options

The documentation for this struct was generated from the following file:


• src/Options.hpp

13.9 sys::io::file < link, Features ... > Class Template Reference


Specialise for FILE object linking file instances.

#include <io.hpp>

Inheritance diagram for sys::io::file < link, Features ... >:



Collaboration diagram for sys::io::file < link, Features ... >:



**Public Member Functions** 

• file (FILE \*const handle)

Use the given FILE object.

template<ownership Ownership, feature ... Superset, class = is\_superset\_of\_t<set<Superset ...>, set<Features ...>>>
file (file< Ownership, Superset ... > const &copy)

Copy construct from another file type instance.

template<feature ... Superset, class = is\_superset\_of\_t<set<Superset ...>, set<Features ...>>>
file (file< own, Superset ... > &&)=delete

Must not move construct from files with ownership of their handle.

• template<ownership Ownership, feature ... Superset, class = is\_superset\_of\_t<set<Superset ...>, set<Features ...>>> file & operator= (file< Ownership, Superset ... > const &copy)

Copy assign from another file type instance.

template<feature ... Superset, class = is\_superset\_of\_t<set<Superset ...>, set<Features ...>>>
file & operator= (file< own, Superset ... > &&)=delete

Must not move assign from files with ownership of their handle.

• FILE \* get () const

Provide the internal FILE object pointer.

Additional Inherited Members

13.9.1 Detailed Description

```
template<feature ... Features> class sys::io::file< link, Features ... >
```

Specialise for FILE object linking file instances.

Lack of ownership implies some semantics:

- Cannot be used to open files
- Can be copy constructed/assigned from other owning and non-owning file instances
- Cannot be move constructed/assigned from owning file instances
- Cannot close()

**Template Parameters** 

```
Features | The set of file access features to support
```

13.9.2 Constructor & Destructor Documentation

Use the given FILE object.

This can be used to refer to FILE objects managed by legacy C code.

### **Parameters**

```
handle A pointer to a FILE object
```

```
13.9.2.2 file() [2/3]

template<feature ... Features>
template<ownership Ownership, feature ... Superset, class = is_superset_of_t<set<Superset ...>, set<\leftarrow
Features ...>>>
```

Copy construct from another file type instance.

 $sys::io::file<\ link,\ Features\ \dots\ >::file$  (

The origin file type instance must support all features supported by this file type.

file< Ownership, Superset ... > const & copy ) [inline]

### **Template Parameters**

Ownership	The ownership status of the other file type
Superset	The feature set of another file type
Cond	Whether Superset is an actual superset of Features

### Parameters

```
copy The Ivalue file to acquire the FILE object from
```

```
13.9.2.3 file() [3/3]
```

Must not move construct from files with ownership of their handle.

# Template Parameters

Superset	The feature set of another FILE object owning file type
0 4 9 0.001	The reating set of another tribe object of thing the type

### 13.9.3 Member Function Documentation

```
13.9.3.1 get()

template<feature ... Features>

FILE* sys::io::file< link, Features ... >::get ( ) const [inline]
```

Provide the internal FILE object pointer.

Can be used to pass the file to legacy C interfaces.

## Returns

A pointer to the managed FILE object

Copy assign from another file type instance.

The origin file type instance must support all features supported by this file type.

### **Template Parameters**

Ownership	The ownership status of the other file type
Superset	The feature set of another file type
Cond	Whether Superset is an actual superset of Features

## Parameters

```
copy The Ivalue file to acquire the FILE object from
```

## Returns

A self reference

```
13.9.3.3 operator=() [2/2]

template<feature ... Features>
template<feature ... Superset, class = is_superset_of_t<set<Superset ...>, set<Features ...>>>
```

Must not move assign from files with ownership of their handle.

**Template Parameters** 

Superset The feature set of another FILE object owning file type

Returns

A self reference

The documentation for this class was generated from the following file:


• src/sys/io.hpp

13.10 sys::io::file < own, Features ... > Class Template Reference


Specialise for FILE object owning file instances.

```
#include <io.hpp>
```

Inheritance diagram for sys::io::file < own, Features ... >:



Collaboration diagram for sys::io::file < own, Features ... >:



### **Public Member Functions**

• file (file const &)=delete

Must not copy construct for risk of multiple close() on the same file.

• file (file &&move)

Move construct from a temporary.

file (FILE \*const handle)

Take ownership of the given FILE object.

• template<feature ... Superset, class = is\_superset\_of\_t<set<Superset ...>, set<Features ...>>> file (file< own, Superset ... > &&move)

Move construct from another owning file type instance.

• file (char const \*const filename, char const \*const mode)

Open a file by name.

• ~file ()

Free all resources.

template<feature ... Superset, class = is\_superset\_of\_t<set<Superset ...>, set<Features ...>>>
file & operator= (file< own, Superset ... > &&move)

Move assign from another owning file type instance.

• FILE \* get () const

Provide the internal FILE object pointer.

FILE \* release ()

Surrender ownership of the internal FILE object pointer.

• file & close ()

Close the file.

## Additional Inherited Members

# 13.10.1 Detailed Description

```
template<feature ... Features> class sys::io::file< own, Features ... >
```

Specialise for FILE object owning file instances.

Ownership implies some semantics:

- Offers a constructor that opens a file
- · Cannot be copy constructed/assigned
- Can be move constructed/assigned from other owning file instances
- Can close()
- Implicit close() when going out of scope

# **Template Parameters**

Features The set of file access features to support

13.10.2 Constructor & Destructor Documentation

```
13.10.2.1 file() [1/4]

template<feature ... Features>
sys::io::file< own, Features ... >::file (
file< own, Features ... > && move ) [inline]
```

Move construct from a temporary.

**Parameters** 

*move* The rvalue file to acquire the FILE object from

Take ownership of the given FILE object.

This can be used to take ownership of FILE objects provided by a legacy C interface.

### Parameters

handle A pointer to a FILE object

```
13.10.2.3 file() [3/4] template<feature ... Features>
```

Move construct from another owning file type instance.

The origin file type instance must support all features supported by this file type.

**Template Parameters** 

3	Superset	The feature set of the original FILE object owner	
---	----------	---	--

#### **Parameters**

	move	The rvalue file to acquire the FILE object from	
--	------	---	--

Open a file by name.

Failure to open a file occurs silently, but can be detected by boolean checking the file instance.

The arguments of this constructor are forwarded to fopen(), provided the mode argument does not contradict the feature set of this file type.

It is recommended to always add the 'b' (binary) character to the mode string, because text mode behaves quirkily.

The feature::seek feature is not supported with 'a' (append), it is available with 'a+', but it behaves quirkily. Which means two different files of the same type may have different seek behaviour, depending on how the file was opened. Refer to the fopen() spec for the unsettling details.

See also

fopen()

### **Parameters**

filename	The name of the file	
mode	The file access mode, must not contradict the feature set of this file type	

### 13.10.3 Member Function Documentation

```
13.10.3.1 close()

template<feature ... Features>
file& sys::io::file< own, Features ... >::close ( ) [inline]

Close the file.
```

Returns

A self reference

```
13.10.3.2 get()

template<feature ... Features>

FILE* sys::io::file< own, Features ... >::get ( ) const [inline]
```

Provide the internal FILE object pointer.

Can be used to pass the file to legacy C interfaces.

Returns

A pointer to the managed FILE object

Move assign from another owning file type instance.

The origin file type instance must support all features supported by this file type.

**Template Parameters** 

Superset The feature set of the original FILE object owner

Parameters

move The rvalue file to acquire the FILE object from

Returns

A self reference

```
13.10.3.4 release()

template<feature ... Features>
FILE* sys::io::file< own, Features ... >::release ( ) [inline]
```

Surrender ownership of the internal FILE object pointer.

Can be used to pass the file to legacy C interfaces.

Returns

A pointer to the managed FILE object

The documentation for this class was generated from the following file:

• src/sys/io.hpp

# 13.11 sys::io::file\_feature< FileT,... > Class Template Reference

Implements the base functionality of all file access types.

```
#include <io.hpp>
```

**Public Member Functions** 

• operator bool () const

Cast to boolean.

• bool eof () const

Return whether the file instance is in EOF state.

• bool error () const

Return whether the file instance is in an error state.

**Protected Member Functions** 

operator FileT & ()

Implicit cast up to inheriting file access type.

• file\_feature (FILE \*const handle)

Construct from a FILE object pointer.

# Protected Attributes

• FILE \* handle

A pointer to the underlying FILE object.

# 13.11.1 Detailed Description

```
template<class FileT, feature ...> class sys::io::file_feature< FileT,...>
```

Implements the base functionality of all file access types.

**Template Parameters** 

FileT The file access type inheriting the feature

See also

```
file_feature<FileT, read, Tail ...>
file_feature<FileT, write, Tail ...>
file_feature<FileT, seek, Tail ...>
```

13.11.2 Constructor & Destructor Documentation

Construct from a FILE object pointer.

**Parameters** 

handle A pointer to the object keeping file descriptor state

13.11.3 Member Function Documentation

```
13.11.3.1 eof()

template<class FileT, feature ... >
bool sys::io::file_feature< FileT,... >::eof ( ) const [inline]
```

Return whether the file instance is in EOF state.

See also

feof()

Returns

Whether the file instance points to a FILE object and is in EOF state

```
13.11.3.2 error()
template<class FileT, feature ... >
bool sys::io::file_feature< FileT,... >::error ( ) const [inline]
Return whether the file instance is in an error state.
See also
     ferror()
Returns
     Whether the file instance points to a FILE object and is in an error state
13.11.3.3 operator bool()
template<class FileT, feature \dots >
sys::io::file_feature< FileT,... >::operator bool ( ) const [inline], [explicit]
Cast to boolean.
See also
     feof()
     ferror()
Return values
```

true	The file instance point to a FILE object, which is not in EOF or error state
false	The file instance does not point to a FILE object, or the FILE object is in EOF or error state

The documentation for this class was generated from the following file:


• src/sys/io.hpp

13.12 sys::io::file\_feature< FileT, read, Tail ... > Class Template Reference


Implement read support for file types.

#include <io.hpp>

Inheritance diagram for sys::io::file\_feature< FileT, read, Tail ... >:



Collaboration diagram for sys::io::file\_feature< FileT, read, Tail ... >:



**Public Member Functions** 

• int getc ()

Read a single character from the file.

template<typename T > std::size\_t read (T &dst)

Read the given object from the file.

• template<typename T , auto Count> std::size\_t read (T(&dst)[Count], std::size\_t const count)

Read the requested number of objects from the file.

template<auto CountFmt, typename ... RefTs>
int scanf (char const (&fmt)[CountFmt], RefTs &... refs)
Read formatted input.

template<auto Count> bool gets (char(&dst)[Count])

Read a line from the file.

Additional Inherited Members

## 13.12.1 Detailed Description

```
template<class FileT, feature ... Tail> class sys::io::file_feature< FileT, read, Tail ... >
```

Implement read support for file types.

**Template Parameters** 

FileT	The file access type inheriting the feature
Tail	The remaining features

#### 13.12.2 Member Function Documentation

```
13.12.2.1 getc()
```

```
template<class FileT , feature ... Tail>
int sys::io::file_feature< FileT, read, Tail ... >::getc ( ) [inline]
```

Read a single character from the file.

See also

fgetc()

Returns

The character or EOF

```
13.12.2.2 gets()
template<class FileT , feature ... Tail>
```

Read a line from the file.

Reads the file up to and including the first newline or terminating zero, as long as it fits into the destination buffer. Always zero terminated.

See also

fgets()

Count   The maximum number of characters to read	Count	The maximum number of characters to read
--	-------	--

#### **Parameters**

```
dst A reference to the destination buffer
```

## Return values

true	Characters have been read
false	Characters could not be read

Read the given object from the file.

See also

fread()

**Template Parameters** 

```
T The object type, should be a POD type
```

# Parameters

```
dst A reference to the object to overwrite
```

Returns

The number of characters read

Read the requested number of objects from the file.

See also

fread()

## **Template Parameters**

Т	The object type, should be a POD type
Count	The number of objects in the destination buffer

## **Parameters**

dst	A reference to an array of objects
count	The number of objects to read

## Returns

The number of characters read

Read formatted input.

See also

fscanf()

# **Template Parameters**

CountFmt	The number of characters in the format string
RefTs	The argument types to read

### Parameters

fmt	The input format
refs	A set of references to write to

## Returns

The number of inputs successfully parsed

### Return values

E⊷	No inputs could be parsed due to end of file
OF	

The documentation for this class was generated from the following file:


• src/sys/io.hpp

13.13 sys::io::file\_feature< FileT, seek, Tail ... > Class Template Reference


Implement seek support for file types.

#include <io.hpp>

Inheritance diagram for sys::io::file\_feature< FileT, seek, Tail ... >:



Collaboration diagram for sys::io::file\_feature< FileT, seek, Tail ... >:



**Public Member Functions** 

```
- FileT & seek (long int const offset, int const origin)
```

Seek file position.

• FileT & rewind ()

Reset file position to the beginning of the file.

• long int tell ()

Retrieve the current file position.

Additional Inherited Members

```
13.13.1 Detailed Description
```

```
template<class FileT, feature ... Tail> class sys::io::file_feature< FileT, seek, Tail ... >
```

Implement seek support for file types.

**Template Parameters** 

FileT	The file access type inheriting the feature
Tail	The remaining features

## 13.13.2 Member Function Documentation

```
13.13.2.1 rewind()
```

```
template<class FileT , feature ... Tail>
FileT& sys::io::file_feature< FileT, seek, Tail ... >::rewind ( ) [inline]
```

Reset file position to the beginning of the file.

See also

frewind()

Returns

A self reference

### **Parameters**

offset	The origin relative file position for binary files or an absolute position returned by tell() for text files
origin	One of SEEK_SET, SEEK_CUR, SEEK_END

### Returns

A self reference

```
13.13.2.3 tell()

template < class FileT , feature ... Tail>
long int sys::io::file_feature < FileT, seek, Tail ... >::tell ( ) [inline]

Retrieve the current file position.

See also
    ftell()
```

Returns

The current file offset

The documentation for this class was generated from the following file:


• src/sys/io.hpp

13.14 sys::io::file\_feature < FileT, write, Tail ... > Class Template Reference


Implement write support for file types.

```
\verb|#include| < \verb|io.hpp|>
```

Inheritance diagram for sys::io::file\_feature< FileT, write, Tail ... >:



Collaboration diagram for sys::io::file\_feature< FileT, write, Tail ... >:



#### **Public Member Functions**

```
    template<auto CountFmt, typename ... ArgTs>
        FileT & printf (char const (&fmt)[CountFmt], ArgTs const &... args)
```

Output with printf style formatting.

• template<auto CountFmt>

FileT & printf (char const (&fmt)[CountFmt])

Output a printf style formatted string.

• template<auto Count>

FileT & print (char const (&msg)[Count])

Print an unformatted string, excluding the last character.

• FileT & putc (int const character)

Write a single character to the string.

• template<typename T >

FileT & write (T const &src)

Write an object to file.

• template<typename T , auto Count>

FileT & write (T const (&src)[Count], std::size\_t const count)

Write an objects to file.

• FileT & flush ()

Flush file buffers.

Additional Inherited Members

### 13.14.1 Detailed Description

```
template<class FileT, feature ... Tail> class sys::io::file_feature< FileT, write, Tail ... >
```

Implement write support for file types.

FileT	The file access type inheriting the feature
Tail	The remaining features

## 13.14.2 Member Function Documentation

```
13.14.2.1 flush()

template < class FileT , feature ... Tail>
FileT& sys::io::file_feature < FileT, write, Tail ... >::flush ( ) [inline]

Flush file buffers.

See also
    fflush()
Returns
```

A self reference

Print an unformatted string, excluding the last character.

This method is built around the assumption that the argument is a string literal and the last character is a terminating zero.

See also

fwrite()

**Template Parameters** 

Count The number of characters in the string

### **Parameters**

### Returns

A self reference

Output with printf style formatting.

See also

fprintf()

## **Template Parameters**

CountFmt	The number of characters in the formatting string
ArgTs	The argument types of the data to print

### Parameters

fmt	The format string
args	The set of data to print

## Returns

A self reference

Output a printf style formatted string.

This overload exists as a workaround for a bug in clang++-8's -Wformat-security that does not recognise the format as a literal string if no arguments follow.

```
See also
```

fprintf()

**Template Parameters** 

CountFmt

The number of characters in the formatting string

**Parameters** 

```
fmt | The format string
```

Returns

A self reference

```
13.14.2.5 putc()
```

Write a single character to the string.

See also

fputc()

Parameters

```
character | The character to write
```

Returns

A self reference

```
13.14.2.6 write() [1/2]
```

Write an object to file.

See also

fwrite()

T The object type, should be a POD type

### Parameters

```
src The object to write out to the file
```

## Returns

A self reference

```
13.14.2.7 write() [2/2]
```

Write an objects to file.

See also

fwrite()

## **Template Parameters**

T	The object type, should be a POD type
Count	The number of objects in the source buffer

## **Parameters**

src	The object to write out to the file
count	The number of objects to write

# Returns

A self reference

The documentation for this class was generated from the following file:

src/sys/io.hpp

# 13.15 utility::Formatter < BufSize > Class Template Reference

A formatting wrapper around string literals.

```
#include <utility.hpp>
```

**Public Member Functions** 

- constexpr Formatter (char const \*const fmt)
   Construct from string literal.
- template<typename... ArgTs>

```
std::string operator() (ArgTs const &... args) const
```

Returns a formatted string.

### **Private Attributes**

char const \*const fmt
 Pointer to the string literal.

## 13.15.1 Detailed Description

```
template<size_t BufSize> class utility::Formatter< BufSize >
```

A formatting wrapper around string literals.

Overloads operator (), which treats the string as a printf formatting string, the arguments represent the data to format.

```
In combination with the literal _fmt, it can be used like this: std::cout << "^-15.15s \%018p\n''_fmt("Address:", this);
```

**Template Parameters** 

```
Buf ← The buffer size for formatting, resulting strings cannot grow beyond BufSize - 1 Size
```

### 13.15.2 Member Function Documentation

```
13.15.2.1 operator()()
```

Returns a formatted string.

Arg⇔	Variadic argument types
Ts	

#### **Parameters**

args	Variadic arguments
------	--------------------

### Returns

An std::string formatted according to fmt


The documentation for this class was generated from the following file:

src/utility.hpp

# 13.16 anonymous\_namespace{libloadplay.cpp}::Report::Frame Class Reference

Represents a frame of the report.

Collaboration diagram for anonymous\_namespace{libloadplay.cpp}::Report::Frame:



### **Public Member Functions**

• Frame (Report &report, uint64\_t const duration)

Construct a report frame.

CoreFrameReport & operator [] (coreid\_t const i)

Subscript operator for per core frame report data.

CoreFrameReport const & operator [] (coreid\_t const i) const

Subscript operator for per core frame report data.

• ∼Frame ()

Finalises the frame by outputting it.

### **Private Attributes**

• Report & report

The report this frame belongs to.

## 13.16.1 Detailed Description

Represents a frame of the report.

It provides access to each CoreFrameReport via the subscript operator [].

The frame data is output when the frame goes out of scope.

13.16.2 Constructor & Destructor Documentation

```
13.16.2.1 Frame()
anonymous_namespace{libloadplay.cpp}::Report::Frame::Frame (
```

Report & report,

uint64\_t const duration ) [inline]

Construct a report frame.

### Parameters

report	The report this frame belongs to
duration	The frame duration

## 13.16.3 Member Function Documentation

```
13.16.3.1 operator []() [1/2]
```

Subscript operator for per core frame report data.

# Parameters

```
i The core index
```

### Returns

A reference to the core frame data

```
13.16.3.2 operator []() [2/2]
```

```
 \begin{tabular}{ll} {\tt CoreFrameReport\ const\&\ anonymous\_namespace\{libloadplay.cpp\}::Report::Frame::operator\ []\ ($$ coreid_t\ const\ i$\ )$ const\ [inline]$ \\ \end{tabular}
```

Subscript operator for per core frame report data.

### **Parameters**

```
i The core index
```

### Returns

A const reference to the core frame data


The documentation for this class was generated from the following file:

• src/libloadplay.cpp

## 13.17 anonymous\_namespace{powerd++.cpp}::FreqGuard Class Reference

A core frequency guard.

Collaboration diagram for anonymous\_namespace{powerd++.cpp}::FreqGuard:



### **Public Member Functions**

• FreqGuard ()

Read and write all core frequencies, may throw.

∼FreqGuard ()

Restore all core frequencies.

## Private Attributes

std::unique\_ptr< mhz\_t[]> freqs
 The list of initial frequencies.

### 13.17.1 Detailed Description

A core frequency guard.

This uses the RAII pattern to achieve two things:

- Upon creation it reads and writes all controlling cores
- Upon destruction it sets all cores to the maximum frequencies

The documentation for this class was generated from the following file:

• src/powerd++.cpp

# 13.18 anonymous\_namespace{libloadplay.cpp}::Hold< T > Class Template Reference

Sets a referenced variable to a given value and restores it when going out of context.

**Public Member Functions** 

• Hold (T &ref, T const value)

The constructor sets the referenced varibale to the given value.

• ∼Hold ()

Restores the original value.

### **Private Attributes**

T const restore

The original value.

T & ref

Reference to the variable.

# 13.18.1 Detailed Description

```
template<typename T>
class anonymous_namespace{libloadplay.cpp}::Hold< T >
```

Sets a referenced variable to a given value and restores it when going out of context.

```
The type of the value to hold
```

13.18.2 Constructor & Destructor Documentation

The constructor sets the referenced varibale to the given value.

## Parameters

ref	The variable to hold and restore
value	The value to set the variable to

13.18.3 Member Data Documentation

```
13.18.3.1 ref

template<typename T >

T& anonymous_namespace{libloadplay.cpp}::Hold< T >::ref [private]
```

Reference to the variable.

```
13.18.3.2 restore

template<typename T >
T const anonymous_namespace{libloadplay.cpp}::Hold< T >::restore [private]
```

The original value.

The documentation for this class was generated from the following file:


src/libloadplay.cpp

13.19 sys::io::is\_superset\_of< LSetT, set< RSet ... >> Struct Template Reference


Specialise is\_superset\_of to unpack the right hand io::set.

```
#include <io.hpp>
```

 $Inheritance\ diagram\ for\ sys::io::is\_superset\_of < LSetT,\ set < RSet \dots >>:$ 



Collaboration diagram for sys::io::is\_superset\_of< LSetT, set< RSet ... >>:



Additional Inherited Members

13.19.1 Detailed Description

```
template<class LSetT, auto ... RSet> struct sys::io::is_superset_of< LSetT, set< RSet ... >>
```

Specialise is\_superset\_of to unpack the right hand io::set.

LSetT	The left hand io::set
RSet	The right hand io::set values


The documentation for this struct was generated from the following file:

• src/sys/io.hpp

# 13.20 anonymous\_namespace{libloadplay.cpp}::Main Class Reference

Singleton class representing the main execution environment.

Collaboration diagram for anonymous\_namespace{libloadplay.cpp}::Main:



## **Public Member Functions**

• Main ()

The constructor starts up the emulation.

~Main ()

Clean up the background emulation thread.

## Private Attributes

std::thread bgthread

 $The\ background\ emulation\ thread.$ 

ifile< io::own > fin {sys::env::vars["LOADPLAY\_IN"], "rb"}

The optional input file.

ofile< io::own > fout {sys::env::vars["LOADPLAY\_OUT"], "wb"}

The optional output file.

• bool die {false}

Used to request premature death from the emulation thread.

## 13.20.1 Detailed Description

Singleton class representing the main execution environment.

13.20.2 Constructor & Destructor Documentation

13.20.2.1 Main()

anonymous\_namespace{libloadplay.cpp}::Main::Main ( ) [inline]

The constructor starts up the emulation.

- Read the headers from input and populate sysctls
- · Ensure the existence of all required sysctls
- Spawn an Emulator instance in its own thread

The documentation for this class was generated from the following file:


• src/libloadplay.cpp

# 13.21 utility::Max< T > Class Template Reference

A simple value container that provides the maximum of assigned values.

#include <utility.hpp>

Collaboration diagram for utility::Max< T >:



**Public Member Functions** 

• constexpr Max (T const &value)

Construct from an initial value.

• constexpr operator T const & () const

Returns the current maximum.

constexpr Max & operator= (T const &value)

Assign a new value, if it is greater than the current value.

## Private Attributes

• T value

The maximum of the assigned values.

## 13.21.1 Detailed Description

```
template<typename T> class utility::Max< T>
```

A simple value container that provides the maximum of assigned values.

**Template Parameters** 

```
T The value type
```

### 13.21.2 Constructor & Destructor Documentation

```
13.21.2.1 Max()
```

Construct from an initial value.

**Parameters** 

```
value | The initial value
```

## 13.21.3 Member Function Documentation

```
13.21.3.1 operator T const &()

template<typename T>
constexpr utility::Max< T >::operator T const & ( ) const [inline]
```

Returns the current maximum.

Returns

The maximum by const reference

Assign a new value, if it is greater than the current value.

#### Parameters

value The value to assign	1
---------------------------	---

Returns

A self reference

The documentation for this class was generated from the following file:

• src/utility.hpp

## 13.22 anonymous\_namespace{libloadplay.cpp}::mib\_t Struct Reference

Represents MIB, but wraps it to provide the necessary operators to use it as an std::map key.

**Public Member Functions** 

```
    template<typename... Ints>
        constexpr mib_t (Ints const ... ints)
```

Construct a mib with the given number of arguments.

• mib\_t (int const \*const mibs, u\_int const len)

Initialise from a pointer to an int array.

• bool operator== (mib\_t const &op) const

Equality operator required by std::map.

bool operator< (mib\_t const &op) const</li>

Less than operator required by std::map.

operator int \* ()

Cast to int \* for value access.

operator int const \* () const

 ${\it Cast\ to\ int\ const\ * for\ value\ access.}$ 

Public Attributes

• int mibs [CTL\_MAXNAME]

The mib values.

### 13.22.1 Detailed Description

Represents MIB, but wraps it to provide the necessary operators to use it as an std::map key.

13.22.2 Constructor & Destructor Documentation

```
13.22.2.1 mib_t() [1/2]
template<typename... Ints>
constexpr anonymous_namespace{libloadplay.cpp}::mib_t::mib_t (
```

Ints const ... ints ) [inline]

Construct a mib with the given number of arguments.

**Template Parameters** 

```
Ints A list of integer types
```

### Parameters

ints A list of integers to create a mib from

```
13.22.2.2 mib_t() [2/2]
```

Initialise from a pointer to an int array.

**Parameters** 

mibs,len The array and its length

## 13.22.3 Member Function Documentation

```
13.22.3.1 operator int *()
anonymous_namespace{libloadplay.cpp}::mib_t::operator int * ( ) [inline]
Cast to int * for value access.
Returns
     A pointer to mibs
13.22.3.2 operator int const *()
anonymous_namespace{libloadplay.cpp}::mib_t::operator int const * ( ) const [inline]
Cast to int const * for value access.
Returns
     A pointer to mibs
13.22.3.3 operator<()
bool anonymous_namespace{libloadplay.cpp}::mib_t::operator< (</pre>
              mib_t const & op ) const [inline]
Less than operator required by std::map.
Parameters
      Another mib_t instance
Returns
     Whether this mib is less than the given one
13.22.3.4 operator==()
bool anonymous_namespace{libloadplay.cpp}::mib_t::operator== (
              mib_t const & op ) const [inline]
Equality operator required by std::map.
Parameters
      Another mib_t instance
```

Returns

Whether all values in this and the given mib are equal

The documentation for this struct was generated from the following file:


• src/libloadplay.cpp

## 13.23 utility::Min< T > Class Template Reference

A simple value container that provides the minimum of assigned values.

#include <utility.hpp>

Collaboration diagram for utility::Min< T >:



# Public Member Functions

• constexpr Min (T const &value)

Construct from an initial value.

• constexpr operator T const & () const

Returns the current minimum.

• constexpr Min & operator= (T const &value)

Assign a new value, if it is less than the current value.

# Private Attributes

• T value

The minimum of the assigned values.

## 13.23.1 Detailed Description

template<typename T> class utility::Min< T>

A simple value container that provides the minimum of assigned values.

```
The value type
```

13.23.2 Constructor & Destructor Documentation

```
13.23.2.1 Min()
```

Construct from an initial value.

**Parameters** 

```
value | The initial value
```

13.23.3 Member Function Documentation

```
13.23.3.1 operator T const &()
```

```
\label{template} $$ \ensuremath{\sf template}$< typename T>$$ constexpr utility::Min< T>::operator T const & ( ) const [inline]
```

Returns the current minimum.

Returns

The minimum by const reference

```
13.23.3.2 operator=()
```

Assign a new value, if it is less than the current value.

**Parameters** 

value The v	alue to assign
-------------	----------------

Returns

A self reference

The documentation for this class was generated from the following file:


• src/utility.hpp

13.24 sys::ctl::Once< T, SysctlT > Class Template Reference

A read once representation of a Sysctl.

#include <sysctl.hpp>

Collaboration diagram for sys::ctl::Once< T, SysctlT >:



**Public Member Functions** 

- Once (T const &value, SysctlT const &sysctl) noexcept
   The constructor tries to read and store the requested sysctl.
- operator T const & () const

Return a const reference to the value.

Private Attributes

• T value

The sysctl value read upon construction.

### 13.24.1 Detailed Description

```
template<typename T, class SysctlT> class sys::ctl::Once< T, SysctlT >
```

A read once representation of a Sysctl.

This reads a sysctl once upon construction and always returns that value. It does not support assignment.

This class is intended for sysctls that are not expected to change, such as hw.ncpu. A special property of this class is that the constructor does not throw and takes a default value in case reading the sysctl fails.

```
// Read number of CPU cores, assume 1 on failure:
Once<coreid_t, Sysctl<2>> ncpu{1, {CTL_HW, HW_NCPU}};
// Equivalent:
int hw_ncpu;
try {
    Sysctl<2>{CTL_HW, HW_NCPU}.get(hw_ncpu);
} catch (sys::sc_error<error>) {
    hw_ncpu = 1;
}
```

### **Template Parameters**

Т	The type to represent the sysctl as
SysctlT	The Sysctl type

#### 13.24.2 Constructor & Destructor Documentation

### 13.24.2.1 Once()

The constructor tries to read and store the requested sysctl.

If reading the requested sysctl fails for any reason, the given value is stored instead.

### **Parameters**

value	The fallback value
sysctl	The sysctl to represent

#### 13.24.3 Member Function Documentation

```
13.24.3.1 operator T const &()

template<typename T, class SysctlT>
sys::ctl::Once< T, SysctlT >::operator T const & ( ) const [inline]
```

Return a const reference to the value.

Returns

A const reference to the value

The documentation for this class was generated from the following file:

src/sys/sysctl.hpp

## 13.25 nih::Options < OptionT, DefCount > Class Template Reference

An instance of this class offers operators to retrieve command line options and arguments.

```
#include <Options.hpp>
```

**Public Member Functions** 

Options (int const argc, char const \*const \*const argv, char const \*const usage, Parameter < OptionT > const (&defs)[DefCount])

Construct an options functor.

Options & operator() ()

Updates the internal state by parsing the next option.

operator OptionT () const

Implicitly cast to the current option.

char const \* operator [] (int const i) const

Retrieve arguments to the current option.

• std::string usage () const

Returns a string for usage output, created from the option definitions.

std::string show (int const i, int const n=1) const

Provide a string containing the entire command line, with the indexed argument highlighted.

• int offset () const

Returns the argument offset of the current parameter/argument.

### Private Member Functions

Parameter < OptionT > const & get (char const ch)

Finds the short option matching the given character.

Parameter < OptionT > const & get (char const \*const str)

Finds the long option matching the given string.

Static Private Member Functions

static char const \* removePath (char const \*const file)

Returns a pointer to the file name portion of the given string.

static bool match (char const \*const lstr, char const \*const rstr)

Returns true if the given strings match.

static bool bmatch (char const \*const str, char const \*const prefix)

Returns true if the given string starts with the given prefix.

### Private Attributes

int const argc

The number of command line arguments.

char const \*const \*const argv

The command line arguments.

char const \*const usageStr

A string literal for the usage() output.

Parameter < OptionT > const (& defs)[DefCount]

A reference to the option definitions.

• Parameter < OptionT > const opt\_unknown

The option definition to use for unknown options.

• Parameter < OptionT > const opt\_noopt

The option definition to use for non-options.

Parameter < OptionT > const opt\_dash

The option definition to use for a single dash.

Parameter < OptionT > const opt\_ldash

The option definition to use for a single double-dash.

• int argi

The index of the command line argument containing the current option.

char const \* argp

Points to the current short option character.

• Parameter < OptionT > const \* current

Points to the current option definition.

### 13.25.1 Detailed Description

```
template < class OptionT, size_t DefCount >
class nih::Options < OptionT, DefCount >
```

An instance of this class offers operators to retrieve command line options and arguments.

Instantiate with make\_Options() to infer template parameters automatically.

Check the operator () and operator [] for use.

### **Template Parameters**

OptionT	An enum or enum class matching the requirements set by enum_has_members
DefCount	The number of option definitions

### 13.25.2 Constructor & Destructor Documentation

```
13.25.2.1 Options()
```

Construct an options functor.

#### **Parameters**

argc,argv	The command line arguments
usage	A usage string following "usage: progname "
defs	An array of parameter definitions

## 13.25.3 Member Function Documentation

```
13.25.3.1 bmatch()
```

```
template<class OptionT , size_t DefCount>  static \ bool \ nih::Options< OptionT, \ DefCount>::bmatch \ ( \\ char \ const \ *const \ str, \\ char \ const \ *const \ prefix \ ) \quad [inline], \ [static], \ [private]
```

Returns true if the given string starts with the given prefix.

### Parameters

str,prefix   Two 0 terminated strings	,
---------------------------------------	---

## Return values

true	The string starts with the prefix
false	The string does not start with the prefix

```
13.25.3.2 get() [1/2]
```

Finds the short option matching the given character.

**Parameters** 

```
ch The short option to find
```

Returns

An option definition by reference

Finds the long option matching the given string.

Parameters

```
str The long option to find
```

Returns

An option definition by reference

Returns true if the given strings match.

Parameters

lstr,rstr	Two 0 terminated strings
-----------	--------------------------

Return values

true	The given strings match
false	The strings do not match

```
13.25.3.5 offset()

template < class OptionT , size_t DefCount >
int nih::Options < OptionT, DefCount >::offset ( ) const [inline]
```

Returns the argument offset of the current parameter/argument.

Warning

This may return a value >= argc if the current state is OptionT::OPT\_DONE

Returns

The current argument index

Retrieve arguments to the current option.

The string containing the current option is returned with i = 0, the arguments following the option with greater values of i.

When no more arguments are left the empty string is returned.

**Parameters** 

```
i The index of the argument to retrieve
```

Returns

The option or one of its arguments

```
13.25.3.7 operator OptionT()

template < class OptionT , size_t DefCount >
nih::Options < OptionT, DefCount >::operator OptionT ( ) const [inline]
```

Implicitly cast to the current option.

Returns

An OptionT member representing the current option

## Return values

OPT_UNKNOWN	An option that was not in the list of option definitions was encountered
OPT_NOOPT	An argument that is not an option was encountered
OPT_DASH	A lone dash "-" was encountered
OPT_LDASH	A lone long dash "" was encountered
OPT_DONE	All arguments have been processed, or argument processing has not yet started

```
13.25.3.8 operator()()

template<class OptionT , size_t DefCount>
Options& nih::Options< OptionT, DefCount >::operator() ( ) [inline]
```

Updates the internal state by parsing the next option.

When reaching the end of the argument list, the internal state is reset, so a successive call will restart the argument parsing.

### Returns

A self-reference

```
13.25.3.9 removePath()

template<class OptionT , size_t DefCount>
static char const* nih::Options< OptionT, DefCount >::removePath (
```

Returns a pointer to the file name portion of the given string.

### Parameters

```
file The string containing the path to the file
```

## Returns

A pointer to the file name portion of the path

	taining the entire o				
ie current impiem	entation nigniights	arguments by	underlining the	em with " $\sim \sim \sim$ .	

#### **Parameters**

i	The argument index, like operator []
n	The number of arguments to highlight, highlights all remaining arguments if $n \le 0$

#### Returns

A string formatted to highlight the given argument

```
13.25.3.11 usage()

template<class OptionT , size_t DefCount>
std::string nih::Options< OptionT, DefCount >::usage ( ) const [inline]
```

Returns a string for usage output, created from the option definitions.

#### Returns

A usage string for printing on the CLI

13.25.4 Member Data Documentation

```
13.25.4.1 opt_dash

template < class OptionT , size_t DefCount >

Parameter < OptionT > const nih::Options < OptionT, DefCount >::opt_dash [private]

Initial value:
{
         OptionT::OPT_DASH, 0, nullptr, nullptr
}
```

The option definition to use for a single dash.

```
13.25.4.2 opt_ldash

template < class OptionT , size_t DefCount>
Parameter < OptionT > const nih::Options < OptionT, DefCount >::opt_ldash [private]

Initial value:
{
          OptionT::OPT_LDASH, 0, nullptr, nullptr
}
```

The option definition to use for a single double-dash.

```
13.25.4.3 opt_noopt

template<class OptionT , size_t DefCount>
Parameter<OptionT> const nih::Options< OptionT, DefCount >::opt_noopt [private]

Initial value:
{
         OptionT::OPT_NOOPT, 0, nullptr, nullptr, nullptr
}
```

The option definition to use for non-options.

```
13.25.4.4 opt_unknown

template<class OptionT , size_t DefCount>
Parameter<OptionT> const nih::Options< OptionT, DefCount >::opt_unknown [private]

Initial value:
{
    OptionT::OPT_UNKNOWN, 0, nullptr, nullptr, nullptr
```

The option definition to use for unknown options.

The documentation for this class was generated from the following file:

src/Options.hpp

# 13.26 sys::pid::Pidfile Class Reference

A wrapper around the pidfile\_\* family of commands implementing the RAII pattern.

```
#include <pidfile.hpp>
```

**Public Member Functions** 

- Pidfile (char const \*const pfname, mode\_t const mode)
  - Attempts to open the pidfile.
- ∼Pidfile ()

Removes the pidfile.

• pid\_t other ()

Returns the PID of the other process holding the lock.

• void write ()

Write PID to the file, should be called after daemon().

#### **Private Attributes**

• pid\_t otherpid

In case of failure to acquire the lock, the PID of the other process holding it is stored here.

pidfh \* pfh

Pointer to the pidfile state data structure.

# 13.26.1 Detailed Description

A wrapper around the pidfile\_\* family of commands implementing the RAII pattern.

13.26.2 Constructor & Destructor Documentation

Attempts to open the pidfile.

Parameters

pfname,mode	Arguments to pidfile_open()
-------------	-----------------------------

# Exceptions

pid_t	Throws the PID of the other process already holding the requested pidfile
sys::sc_error <error></error>	Throws with the errno of pidfile_open()

13.26.3 Member Function Documentation

```
13.26.3.1 write()
void sys::pid::Pidfile::write ( ) [inline]
```

Write PID to the file, should be called after daemon().

Exceptions

13.26.4 Member Data Documentation

13.26.4.1 pfh

pidfh\* sys::pid::Pidfile::pfh [private]

Pointer to the pidfile state data structure.

Thus is allocated by pidfile\_open() and assumedly freed by pidfile\_remove().

The documentation for this class was generated from the following file:

• src/sys/pidfile.hpp

# 13.27 anonymous\_namespace{libloadplay.cpp}::Report Class Reference

Provides a mechanism to provide frame wise per core load information.

Collaboration diagram for anonymous namespace{libloadplay.cpp}::Report:



#### Classes

• class Frame

Represents a frame of the report.

#### **Public Member Functions**

• Report (ofile < io::link > fout, coreid\_t const ncpu)

Construct a report.

• template<typename ... ArgTs>

Frame frame (ArgTs &&... args)

Constructs a frame for this report.

# Private Attributes

ofile< io::link > fout

The output stream to report to.

coreid\_t const ncpu

The number of cpu cores to provide reports for.

• Sum< uint64\_t > time

The time passed in [ms].

std::unique\_ptr< CoreFrameReport[]> cores

Per frame per core data.

# 13.27.1 Detailed Description

Provides a mechanism to provide frame wise per core load information.

13.27.2 Constructor & Destructor Documentation

```
13.27.2.1 Report()
```

```
\label{libbondplay.cpp} $$ ::Report::Report ( \\ ofile < io::link > fout, \\ coreid_t const ncpu ) [inline] $$
```

# Construct a report.

# Parameters

fout	The stream to output to
псри	The number of CPU cores to report

# 13.27.3 Member Function Documentation

```
13.27.3.1 frame()
```

Constructs a frame for this report.

**Template Parameters** 

Arg⇔	The constructor argument types
Ts	

# Parameters

args	The constructor arguments

The documentation for this class was generated from the following file:

• src/libloadplay.cpp

# 13.28 sys::sc\_error< Domain > Struct Template Reference

Can be thrown by syscall function wrappers if the function returned with an error.

```
#include <error.hpp>
```

**Public Member Functions** 

- operator int () const
  - Cast to integer.
- char const \* c\_str () const

Return c style string.

#### **Public Attributes**

· int error

The errno set by the native C function.

### 13.28.1 Detailed Description

```
template < class Domain >
struct sys::sc_error < Domain >
```

Can be thrown by syscall function wrappers if the function returned with an error.

This is its own type for easy catching, but implicitly casts to int for easy comparison.

**Template Parameters** 

Domain A type marking the domain the error comes from, e.g. sys::ctl::error

# 13.28.2 Member Function Documentation

```
13.28.2.1 c_str()

template < class Domain > 
char const* sys::sc_error < Domain >::c_str ( ) const [inline]
```

Return c style string.

#### Returns

A string representation of the error

```
13.28.2.2 operator int()
{\tt template}{<}{\tt class\ Domain}\ >
sys::sc_error< Domain >::operator int ( ) const [inline]
Cast to integer.
Returns
      The errno code
The documentation for this struct was generated from the following file:
    • src/sys/error.hpp
         sys::sig::Signal Class Reference
13.29
Sets up a given signal handler and restores the old handler when going out of scope.
#include <signal.hpp>
Public Member Functions

    Signal (int const sig, sig_t const handler)

          Sets up the given handler.
    • ~Signal ()
          Restore previous signal handler.
Private Attributes

    int const sig

          The signal this handler is handling.

    sig_t const handler

          The previous signal handler.
13.29.1 Detailed Description
Sets up a given signal handler and restores the old handler when going out of scope.
13.29.2 Constructor & Destructor Documentation
13.29.2.1 Signal()
```

Sets up the given handler.

sys::sig::Signal::Signal (

int const sig,

 ${\tt sig\_t}$  const  ${\it handler}$  ) [inline]

# **Parameters**

sig	The signal to set a handler for
handler	The signal handling function

# Exceptions

sys::sc_error <error> Throws with the errno of</error>	nal()
--	-------

The documentation for this class was generated from the following file:


• src/sys/signal.hpp

# 13.30 utility::Sum< T > Class Template Reference

A simple value container only allowing += and copy assignment.

#include <utility.hpp>

Collaboration diagram for utility::Sum< T >:



**Public Member Functions** 

• constexpr Sum (T const &value)

Construct from an initial value.

• constexpr Sum ()

Default construct.

• constexpr operator T const & () const

Returns the current sum of values.

• constexpr Sum & operator+= (T const &value)

Add a value to the sum.

# Private Attributes

• T value

The sum of values accumulated.

13.30.1 Detailed Description

```
template<typename T> class utility::Sum< T>
```

A simple value container only allowing += and copy assignment.

**Template Parameters** 

```
T | The value type
```

13.30.2 Constructor & Destructor Documentation

```
13.30.2.1 Sum()
```

Construct from an initial value.

**Parameters** 

```
value The initial value
```

13.30.3 Member Function Documentation

```
13.30.3.1 operator T const &()
```

```
\label{template} $$ \ensuremath{\sf template}$< typename T>$$ constexpr utility::Sum< T>::operator T const & ( ) const [inline]
```

Returns the current sum of values.

Returns

The sum of values by const reference

Add a value to the sum.

**Parameters** 

value The value to add to the current sum

Returns

A self reference

The documentation for this class was generated from the following file:

src/utility.hpp

# 13.31 sys::ctl::Sync< T, SysctlT > Class Template Reference

This is a wrapper around Sysctl that allows semantically transparent use of a sysctl.

```
#include <sysctl.hpp>
```

**Public Member Functions** 

• constexpr Sync ()

The default constructor.

• constexpr Sync (SysctlT const &sysctl) noexcept

The constructor copies the given Sysctl instance.

• Sync & operator= (T const &value)

Transparently assiges values of type T to the represented Sysctl instance.

• operator T () const

Implicitly cast to the represented type.

# Private Attributes

SysctlT sysctl

A sysctl to represent.

# 13.31.1 Detailed Description

```
template < typename\ T,\ class\ SysctlT > \\ class\ sys::ctl::Sync < T,\ SysctlT >
```

Note that both assignment and read access (implemented through type casting to T) may throw an exception.

# **Template Parameters**

Т	The type to represent the sysctl as
SysctlT	The Sysctl type

#### 13.31.2 Constructor & Destructor Documentation

```
13.31.2.1 Sync() [1/2]

template<typename T, class SysctlT>
constexpr sys::ctl::Sync< T, SysctlT >::Sync ( ) [inline]
```

The default constructor.

This is available to defer initialisation to a later moment. This might be useful when initialising global or static instances by a character string repesented name.

The constructor copies the given Sysctl instance.

#### **Parameters**

sysctl The Sysctl instance to represent

#### 13.31.3 Member Function Documentation

```
13.31.3.1 operator T()

template<typename T, class SysctlT>
sys::ctl::Sync< T, SysctlT >::operator T ( ) const [inline]
```

Implicitly cast to the represented type.

Returns

Returns the value from the sysctl

Transparently assiges values of type T to the represented Sysctl instance.

**Parameters** 

value The value to as:	sign
------------------------	------

Returns

A self reference

The documentation for this class was generated from the following file:

src/sys/sysctl.hpp

# 13.32 sys::ctl::Sysctl< MibDepth > Class Template Reference

Represents a sysctl MIB address.

```
#include <sysctl.hpp>
```

**Public Member Functions** 

- template<typename... Tail>
   constexpr Sysctl (mib\_t const head, Tail const ... tail) noexcept
   Initialise the MIB address directly.
- size\_t size () const

The size of the sysctl.

• void get (void \*const buf, size\_t const bufsize) const

Update the given buffer with a value retrieved from the sysctl.

template<typename T > void get (T &value) const

Update the given value with a value retreived from the sysctl.

• template<typename T > std::unique\_ptr<  $T[\ ] > get () const$ 

Retrieve an array from the sysctl address.

void set (void const \*const buf, size\_t const bufsize)

Update the the sysctl value with the given buffer.

template<typename T > void set (T const &value)

Update the the sysctl value with the given value.

#### **Private Attributes**

mib\_t mib [MibDepth]
 Stores the MIB address.

### 13.32.1 Detailed Description

```
template < size_t MibDepth = 0 > class sys::ctl::Sysctl < MibDepth >
```

Represents a sysctl MIB address.

It offers set() and get() methods to access these sysctls.

There are two ways of initialising a Sysctl instance, by symbolic name or by directly using the MIB address. The latter one only makes sense for sysctls with a fixed address, known at compile time, e.g. Sysctl<2>{CTL\_HW, HW\_NCPU} for "hw.ncpu". Check /usr/include/sys/sysctl.h for predefined MIBs.

For all other sysctls, symbolic names must be used. E.g. Sysctl <> {"dev.cpu.0.freq"}. Creating a Sysctl from a symbolic name may throw.

Fixed address sysctls may be created using the make\_Sysctl() function, e.g. make\_Sysctl(CTL\_HW, HW\_NCPU).

Instances created from symbolic names must use the Sysctl<0> specialisation, this can be done by omitting the template argument Sysctl<>.

**Template Parameters** 

```
MibDepth The MIB level, e.g. "hw.ncpu" is two levels deep
```

#### 13.32.2 Constructor & Destructor Documentation

Initialise the MIB address directly.

Some important sysctl values have a fixed address that can be initialised at compile time with a noexcept guarantee.

Spliting the MIB address into head and tail makes sure that Sysctl(char \*) does not match the template and is instead implicitly cast to invoke Sysctl(char const \*).

**Template Parameters** 

Tail The types of the trailing MIB address values (must be mib\_t)

#### **Parameters**

```
head,tail The mib
```

# 13.32.3 Member Function Documentation

Update the given buffer with a value retrieved from the sysctl.

#### Parameters

buf,bufsize	The target buffer and its size
-------------	--------------------------------

# Exceptions

sys::sc_error <error></error>	Throws if value retrieval fails or is incomplete, e.g. because the value does not fit
	into the target buffer

Update the given value with a value retreived from the sysctl.

**Template Parameters** 

The type store the sysctl value in

# **Parameters**

<i>value</i> A reference to the target value
--

# Exceptions

sys::sc_error <error></error>	Throws if value retrieval fails or is incomplete, e.g. because the value does not fit
	into the target type

```
13.32.3.3 get() [3/3]

template<size_t MibDepth = 0>
template<typename T >
std::unique_ptr<T[]> sys::ctl::Sysctl< MibDepth >::get ( ) const [inline]
```

Retrieve an array from the sysctl address.

This is useful to retrieve variable length sysctls, like characer strings.

**Template Parameters** 

```
The type stored in the array
```

#### Returns

And array of T with the right length to store the whole sysctl value

# Exceptions

sys::sc_error< error>	May throw if the size of the sysctl increases after the length was queried

Update the the sysctl value with the given buffer.

Parameters

buf,bufsize	The source buffer

# Exceptions

not be stored in the sysctl
-----------------------------

Update the the sysctl value with the given value.

**Template Parameters** 

```
T The value type
```

#### **Parameters**

value The value to set the sys	sctl to
--------------------------------	---------

```
13.32.3.6 size()
```

```
template<size_t MibDepth = 0>
size_t sys::ctl::Sysctl< MibDepth >::size ( ) const [inline]
```

The size of the sysctl.

Returns

The size in characters

The documentation for this class was generated from the following file:

• src/sys/sysctl.hpp

# 13.33 sys::ctl::Sysctl< 0 > Class Template Reference

This is a specialisation of Sysctl for sysctls using symbolic names.

```
#include <sysctl.hpp>
```

#### **Public Member Functions**

```
    constexpr Sysctl ()
```

The default constructor.

Sysctl (char const \*const name)

Initialise the MIB address from a character string.

• size\_t size () const

The size of the sysctl.

• void get (void \*const buf, size\_t const bufsize) const

Update the given buffer with a value retrieved from the sysctl.

template<typename T > void get (T &value) const

Update the given value with a value retreived from the sysctl.

• template<typename T >

```
std::unique_ptr< T[]> get () const
```

Retrieve an array from the sysctl address.

• void set (void const \*const buf, size\_t const bufsize)

Update the the sysctl value with the given buffer.

template<typename T >
 void set (T const &value)

Update the the sysctl value with the given value.

#### **Private Attributes**

• mib\_t mib [CTL\_MAXNAME]

Stores the MIB address.

size\_t depth

The MIB depth.

# 13.33.1 Detailed Description

```
template<> class sys::ctl::Sysctl< 0 >
```

This is a specialisation of Sysctl for sysctls using symbolic names.

A Sysctl instance created with the default constructor is unitialised, initialisation can be deferred to a later moment by using copy assignment. This can be used to create globals but construct them inline where exceptions can be handled.

# 13.33.2 Constructor & Destructor Documentation

```
13.33.2.1 Sysctl() [1/2]

constexpr sys::ctl::Sysctl< 0 >::Sysctl ( ) [inline]
```

The default constructor.

This is available to defer initialisation to a later moment.

Initialise the MIB address from a character string.

#### Parameters

name	The symbolic name of the sysctl
------	---------------------------------

# Exceptions

sys::sc_error <error></error>	May throw an exception if the addressed sysct does not exist or if the address is too	1
	long to store	

# 13.33.3 Member Function Documentation

Update the given buffer with a value retrieved from the sysctl.

#### Parameters

buf,bufsize	The target buffer and its size
-------------	--------------------------------

# Exceptions

sys::sc_error <error></error>	Throws if value retrieval fails or is incomplete, e.g. because the value does not fit
	into the target buffer

Update the given value with a value retreived from the sysctl.

**Template Parameters** 

The type store the sysctl value in

#### Parameters

value A reference to the target value
---------------------------------------

# Exceptions

sys::sc_error <error></error>	Throws if value retrieval fails or is incomplete, e.g. because the value does not fit	
	into the target type	

```
13.33.3.3 get() [3/3]

template<typename T >
std::unique_ptr<T[]> sys::ctl::Sysctl< 0 >::get ( ) const [inline]
```

Retrieve an array from the sysctl address.

This is useful to retrieve variable length sysctls, like characer strings.

**Template Parameters** 

```
The type stored in the array
```

# Returns

And array of T with the right length to store the whole sysctl value

# Exceptions

sys::sc\_error<error> May throw if the size of the sysctl increases after the length was queried

Update the the sysctl value with the given buffer.

### **Parameters**

buf,bufsize	The source buffer

# Exceptions

sys::sc_error <error></error>	If the source buffer cannot be stored in the sysctl
-------------------------------	---

Update the the sysctl value with the given value.

**Template Parameters** 

```
T The value type
```

#### **Parameters**

```
value The value to set the sysctl to
```

```
13.33.3.6 size()
size_t sys::ctl::Sysctl< 0 >::size ( ) const [inline]
```

The size of the sysctl.

Returns

The size in characters

The documentation for this class was generated from the following file:

• src/sys/sysctl.hpp

13.34 anonymous\_namespace{libloadplay.cpp}::Sysctls Class Reference

Singleton class representing the sysctl table for this library.

Collaboration diagram for anonymous\_namespace{libloadplay.cpp}::Sysctls:

#### **Public Member Functions**

void addValue (mib\_t const &mib, std::string const &value)

Add a value to the sysctls map.

• void addValue (std::string const &name, std::string const &value)

Add a value to the sysctls map.

• mib\_t const & getMib (char const \*const name) const

Returns a mib for a given symbolic name.

• SysctlValue & operator [] (char const \*const name)

Returns a reference to a sysctl value container.

SysctlValue & operator [] (mib\_t const &mib)

Returns a reference to a sysctl value container.

# **Private Types**

typedef std::lock\_guard< decltype(mtx)> lock\_guard
 The appropriate lock guard type for mtx.

#### **Private Attributes**

std::mutex mtx

A simple mutex.

• std::unordered\_map< std::string, mib\_t > mibs

Maps name  $\rightarrow$  mib.

• std::map< mib\_t, SysctlValue > sysctls

Maps  $mib \rightarrow (type, value)$ .

#### 13.34.1 Detailed Description

Singleton class representing the sysctl table for this library.

13.34.2 Member Function Documentation

```
13.34.2.1 addValue() [1/2]
```

```
void anonymous_namespace{libloadplay.cpp}::Sysctls::addValue (
    mib_t const & mib,
    std::string const & value ) [inline]
```

Add a value to the sysctls map.

#### **Parameters**

mib	The mib to add the value for
value	The value to store

```
13.34.2.2 addValue() [2/2]
```

Add a value to the sysctls map.

#### **Parameters**

name	The symbolic name of the mib to add the value for
value	The value to store

# 13.34.2.3 getMib()

Returns a mib for a given symbolic name.

#### **Parameters**

name	The MIB name
------	--------------

Returns

The MIB

```
13.34.2.4 operator []() [1/2]
```

Returns a reference to a sysctl value container.

### **Parameters**

name	The MIB name to return the reference for
------	--

Returns

A SysctlValue reference

```
13.34.2.5 operator []() [2/2]
SysctlValue& anonymous_namespace{libloadplay.cpp}::Sysctls::operator [] (
                  mib_t const & mib ) [inline]
Returns a reference to a sysctl value container.
Parameters
          The MIB to return the reference for
  mib
Returns
       A SysctlValue reference
13.34.3 Member Data Documentation
13.34.3.1 mibs
std::unordered_map<std::string, mib_t> anonymous_namespace{libloadplay.cpp}::Sysctls::mibs [private]
Initial value:
         {"hw.machine",
                             {CTL_HW, HW_MACHINE}},
                             {CTL_HW, HW_MODEL}}, {CTL_HW, HW_NCPU}},
         {"hw.model",
         {"hw.ncpu",
         {ACLINE,
                             {1000}},
         {FREQ,
                             {1001}},
         {FREQ_LEVELS,
                             {1002}},
         {CP_TIMES, {1003}}
{LOADREC_FEATURES, {1004}}
                             {1003}}.
Maps name \rightarrow mib.
13.34.3.2 sysctls
std::map<mib_t, SysctlValue> anonymous_namespace{libloadplay.cpp}::Sysctls::sysctls [private]
Initial value:
         {{CTL_HW, HW_MACHINE}, {CTLTYPE_STRING, "hw.machine"}}, {{CTL_HW, HW_MODEL}, {CTLTYPE_STRING, "hw.model"}}, {{CTL_HW, HW_NCPU}, {CTLTYPE_INT, "0"}},
         {{1000},
                                  {CTLTYPE_INT,
                                                    "2"}},
                                  {CTLTYPE_INT, "0"}},
{CTLTYPE_STRING, ""}},
         {{1001},
         {{1002},
                                                    ""}},
                                  {CTLTYPE_LONG,
         {{1003},
         {{1004},
                                  {CTLTYPE_U64,
Maps mib \rightarrow (type, value).
```

The documentation for this class was generated from the following file:

• src/libloadplay.cpp

# 13.35 anonymous\_namespace{libloadplay.cpp}::SysctlValue Class Reference

Instances of this class represents a specific sysctl value.

Collaboration diagram for anonymous\_namespace{libloadplay.cpp}::SysctlValue:



#### **Public Member Functions**

• SysctlValue ()

Default constructor.

SysctlValue (SysctlValue const &copy)

Copy constructor.

SysctlValue (SysctlValue &&move)

Move constructor.

• SysctlValue (unsigned int type, std::string const &value, callback\_function const callback=nullptr)

Construct from a type, value and optionally callback tuple.

SysctlValue & operator= (SysctlValue const &copy)

Copy assignment operator.

SysctlValue & operator= (SysctlValue &&move)

Move assignment operator.

size\_t size () const

Returns the required storage size according to the CTLTYPE.

• template<typename T >

```
int get (T *dst, size_t &size) const
```

Copy a list of values into the given buffer.

• int get (char \*dst, size\_t &size) const

Copy a C string into the given buffer.

• template<typename T>

T get () const

Returns a single value.

int get (void \*dst, size\_t &size) const

Copy a list of values into the given buffer.

• template<typename T >

void set (T const \*const newp, size\_t newlen)

Set this value to the values in the given buffer.

• int set (void const \*const newp, size\_t newlen)

Set this value to the values in the given buffer.

void set (std::string &&value)

Move a string to the value.

• void set (std::string const &value)

Copy a string to the value.

```
• template<typename T >
      void set (T const &value)
          Set the value.

    void registerOnSet (callback_function &&callback)

          Register a callback function.

    void registerOnSet (callback_function const &callback)

          Register a callback function.
Private Types

    typedef std::lock_guard< decltype(mtx)> lock_guard

          Lock guard type, fitting the mutex.
Private Member Functions
    • template<typename T >
      size_t size () const
          Provide the size of this value represented as a string of Ts.
Private Attributes

    decltype(onSet) typedef ::function_t callback_function

          Callback function type.
    • std::recursive mutex mtx
          A stackable mutex.
    • unsigned int type
          The sysctl type.
    • std::string value
          The value of the sysctl.

    Callback< SysctlValue & > onSet

          Callback function handle.
13.35.1 Detailed Description
Instances of this class represents a specific sysctl value.
There should only be one instance of this class per MIB.
```

Instances are thread safe.

# 13.35.2 Constructor & Destructor Documentation

```
13.35.2.1 SysctlValue() [1/3]
\verb"anonymous_namespace{libloadplay.cpp}::SysctlValue::SysctlValue (
               SysctlValue const & copy ) [inline]
```

Copy constructor.

#### **Parameters**

```
13.35.2.2 SysctlValue() [2/3]
```

Move constructor.

#### **Parameters**

move	The instance to move
------	----------------------

# 13.35.2.3 SysctlValue() [3/3]

```
anonymous_namespace{libloadplay.cpp}::SysctlValue::SysctlValue ( unsigned int type, std::string const & value, callback_function const callback = nullptr) [inline]
```

Construct from a type, value and optionally callback tuple.

#### Parameters

type	The CTLTYPE	
value	A string representation of the value	
callback	A callback function that is called for each set() call	

# 13.35.3 Member Function Documentation

Copy a list of values into the given buffer.

# **Template Parameters**

The type of the values to extract

#### Parameters

dst, size The destination buffer and size
---

#### Return values

	0	On success	
-	-1	On failure to fit all values into the taget buffer, also sets errno=ENOMEM	1

size\_t & size ) const [inline]

Copy a C string into the given buffer.

# Parameters

dst,size The destination buffer and siz
---

# Return values

```
    0 On success
    -1 On failure to fit all values into the taget buffer, also sets errno=ENOMEM
```

```
13.35.3.3 get() [3/4]
```

```
template<typename T >
T anonymous_namespace{libloadplay.cpp}::SysctlValue::get ( ) const [inline]
```

Returns a single value.

Template Parameters

```
T The type of the value
```

# Returns

The value

Copy a list of values into the given buffer.

Parameters

# Return values

0	On success	
-1	On failure to fit all values into the taget buffer, also sets errno=E	NOMEM

Copy assignment operator.

**Parameters** 

```
copy The instance to copy
```

Returns

A self reference

Move assignment operator.

Parameters

move The instance to move

Returns

A self reference

```
13.35.3.7 registerOnSet() [1/2]
```

```
\label{line:continuous_namespace} $$ void anonymous_namespace{libloadplay.cpp}::SysctlValue::registerOnSet ( $$ callback_function && callback $$ ) [inline]
```

Register a callback function.

**Parameters** 

```
callback The function to move to the callback handler
```

```
13.35.3.8 registerOnSet() [2/2]
```

```
\label{line:const} woid anonymous\_namespace \{ libloadplay.cpp \} :: SysctlValue :: register 0 n Set \ ( \\  callback\_function const \ \& \ callback \ ) \quad [inline]
```

Register a callback function.

Parameters

```
callback The function to copy to the callback handler
```

```
13.35.3.9 set() [1/5]
```

Set this value to the values in the given buffer.

Template Parameters

```
T The type of the values
```

Parameters

newp,newlen | The source buffer and size

Set this value to the values in the given buffer.

The buffer will be treated as an array of CTLTYPE values.

**Parameters** 

```
newp,newlen | The source buffer and size
```

Move a string to the value.

**Parameters** 

```
value The new value
```

```
13.35.3.12 set() [4/5]
```

Copy a string to the value.

Parameters

```
value The new value
```

Set the value.

**Template Parameters** 

```
T | The value type
```

#### **Parameters**

```
value The value to set
```

```
13.35.3.14 size() [1/2]
```

```
\label{template} $$ \text{template}$ < typename T > $$ \text{size_t anonymous_namespace}$ (libloadplay.cpp}::SysctlValue::size () const [inline], [private]
```

Provide the size of this value represented as a string of Ts.

**Template Parameters** 

```
T | The type this value is supposed to be a array of
```

#### Returns

The size of the whole string of Ts

```
13.35.3.15 size() [2/2]
```

```
size_t anonymous_namespace{libloadplay.cpp}::SysctlValue::size ( ) const [inline]
```

Returns the required storage size according to the CTLTYPE.

Returns

The required buffer size to hold the values.

# Exceptions

```
int Throws -1 if the current CTLTYPE is not implemented.
```

#### 13.35.4 Member Data Documentation

```
13.35.4.1 mtx

std::recursive_mutex anonymous_namespace{libloadplay.cpp}::SysctlValue::mtx [mutable], [private]

A stackable mutex.

nice for exposing methods publicly and still let them allow accessing each other.

13.35.4.2 value

std::string anonymous_namespace{libloadplay.cpp}::SysctlValue::value [private]

The value of the sysctl.
```

This is stored as a string and converted to the appropriate type by the set() and get() methods.

The documentation for this class was generated from the following file:

· src/libloadplay.cpp

# 13.36 sys::env::Var Class Reference

A reference type refering to an environment variable.

```
#include <env.hpp>
```

**Public Member Functions** 

template<size\_t Size>Var (char const (&name)[Size])

Construct an environment variable reference.

• Var (Var const &)=delete

Do not permit copy construction.

Var & operator= (Var const &)=delete

Do not permit copy assignment.

• operator char const \* () const

Retrieve the value of the environment variable.

• Var & operator= (char const \*const assign)

Assign a new value to the environment variable.

• Var & erase ()

Explicitly deletes the environment variable.

• char const \* c\_str () const

Explicitly retrieve the value as a character array.

std::string str () const

Explicitly retrieve the value as a std::string.

### Private Attributes

• char const \*const name

A pointer to the variable name.

# 13.36.1 Detailed Description

A reference type refering to an environment variable.

To avoid issues with the lifetime of the name string this is not copy constructible or assignable.

13.36.2 Constructor & Destructor Documentation

```
13.36.2.1 Var()

template<size_t Size>
sys::env::Var::Var (
```

char const (&) name[Size] ) [inline]

Construct an environment variable reference.

**Template Parameters** 

Size The size of the name buffer

#### **Parameters**

name The name of the environment variable

13.36.3 Member Function Documentation

```
13.36.3.1 c_str()

char const* sys::env::Var::c_str ( ) const [inline]
```

Explicitly retrieve the value as a character array.

Returns

A pointer to the character array with the variable value

#### Return values

nullptr | The variable does not exist

```
13.36.3.2 erase()
```

```
Var& sys::env::Var::erase ( ) [inline]
```

Explicitly deletes the environment variable.

Returns

A self-reference

# Exceptions

sc_error <error>{EINVAL}</error>	Invalid variable name
<pre>sc_error<error>{ENOMEM}</error></pre>	Failed to allocate memory when updating the environment

```
13.36.3.3 operator char const *()
```

```
sys::env::Var::operator char const * ( ) const [inline]
```

Retrieve the value of the environment variable.

Returns

A pointer to the character array with the variable value

### Return values

nullptr	The variable does not exist

```
13.36.3.4 operator=()
```

Assign a new value to the environment variable.

Deletes the variable if nullptr is assigned.

Parameters

assign	The new value

Returns

A self-reference

# Exceptions

sc_error <erro< th=""><th>or&gt;{EINVAL}</th><th>Invalid variable name</th></erro<>	or>{EINVAL}	Invalid variable name
sc_error <error></error>	>{ENOMEM}	Failed to allocate memory when updating the environment

```
13.36.3.5 str()
std::string sys::env::Var::str ( ) const [inline]
```

Explicitly retrieve the value as a std::string.

Returns an empty string if the variable does not exist. Use c\_str() to distinguish between an empty string and an inexistant variable.

Returns

A string containing the variable value

The documentation for this class was generated from the following file:

• src/sys/env.hpp

# 13.37 sys::env::Vars Struct Reference

A singleton class providing access to environment variables.

```
\verb"#include" < \verb"env.hpp">
```

**Public Member Functions** 

```
    template<typename T >
        Var const operator [] (T const &name) const
        Access environment variable by name.
```

• template<typename T >

```
Var operator [] (T const &name)
```

Access environment variable by name.

# 13.37.1 Detailed Description

A singleton class providing access to environment variables.

# 13.37.2 Member Function Documentation

Access environment variable by name.

14 File Documentation 173

## **Template Parameters**

```
The name argument type
```

### Parameters

```
name The name of the variable by reference
```

```
13.37.2.2 operator []() [2/2]
```

Access environment variable by name.

**Template Parameters** 

```
T The name argument type
```

## **Parameters**

```
name The name of the variable by reference
```

The documentation for this struct was generated from the following file:

• src/sys/env.hpp


# 14 File Documentation

# 14.1 src/clas.hpp File Reference


Implements functions to process command line arguments.

```
#include "types.hpp"
#include "errors.hpp"
#include "utility.hpp"
#include <string>
```

#include <utility>
Include dependency graph for clas.hpp:



This graph shows which files directly or indirectly include this file:



# Namespaces

• clas

A collection of functions to process command line arguments.

## Functions

- types::cptime\_t clas::load (char const \*const str)

  Convert string to load in the range [0, 1024].
- types::mhz\_t clas::freq (char const \*const str)

Convert string to frequency in MHz.

• types::ms clas::ival (char const \*const str)

Convert string to time interval in milliseconds.

size\_t clas::samples (char const \*const str)

A string encoded number of samples.

• types::decikelvin\_t clas::temperature (char const \*const str)

Convert string to temperature in dK.

• int clas::celsius (types::decikelvin\_t const val)

Converts dK into °C for display purposes.

template<typename T >
 std::pair< T, T > clas::range (T(&func)(char const \*const), char const \*const str)

Takes a string encoded range of values and returns them.


# 14.1.1 Detailed Description

Implements functions to process command line arguments.


# 14.2 src/constants.hpp File Reference

Defines a collection of constants.

#include "types.hpp"
Include dependency graph for constants.hpp:



This graph shows which files directly or indirectly include this file:



### Namespaces

constants

A collection of constants.

#### Variables

- char const \*const constants::CP\_TIMES = "kern.cp\_times"
  - The MIB name for per-CPU time statistics.
- char const \*const constants::ACLINE = "hw.acpi.acline"
  - The MIB name for the AC line state.
- char const \*const constants::FREQ = "dev.cpu.%d.freq"
  - The MIB name for CPU frequencies.
- char const \*const constants::FREQ\_LEVELS = "dev.cpu.%d.freq\_levels"
  - The MIB name for CPU frequency levels.
- char const \*const constants::TEMPERATURE = "dev.cpu.%d.temperature"
  - The MIB name for CPU temperatures.
- char const \*const constants::TJMAX\_SOURCES []
  - An array of maximum temperature sources.
- types::mhz\_t const constants::FREQ\_DEFAULT\_MAX {1000000}
  - Default maximum clock frequency value.
- types::mhz\_t const constants::FREQ\_DEFAULT\_MIN {0}
  - Default minimum clock frequency value.
- types::mhz\_t const constants::FREQ\_UNSET {1000001}
  - Clock frequency representing an uninitialised value.
- char const \*const constants::POWERD PIDFILE = "/var/run/powerd.pid"
  - The default pidfile name of powerd.
- types::cptime\_t const constants::ADP {512}
  - The load target for adaptive mode, equals 50% load.
- types::cptime\_t const constants::HADP {384}
  - The load target for hiadaptive mode, equals 37.5% load.
- types::decikelvin\_t const constants::HITEMP\_OFFSET {100}
  - The default temperautre offset between high and critical temperature.


# 14.2.1 Detailed Description

Defines a collection of constants.


# 14.3 src/Cycle.hpp File Reference

Implements timing::Cycle, a cyclic sleep functor.

```
#include <chrono>
#include <unistd.h>
Include dependency graph for Cycle.hpp:
```



This graph shows which files directly or indirectly include this file:



## Classes

• class timing::Cycle

Implements an interruptible cyclic sleeping functor.

# Namespaces

timing

Namespace for time management related functionality.


# 14.3.1 Detailed Description

Implements timing::Cycle, a cyclic sleep functor.


# 14.4 src/errors.hpp File Reference

Common error handling code.

#include "utility.hpp"
Include dependency graph for errors.hpp:



This graph shows which files directly or indirectly include this file:



## Classes

• struct errors::Exception

Exceptions bundle an exit code, errno value and message. More...

#### Namespaces

• errors

Common error handling types and functions.

#### **Enumerations**

enum errors::Exit:: int {
 errors::Exit::OK, errors::Exit::ECLARG, errors::Exit::EOUTOFRANGE, errors::Exit::ELOAD,
 errors::Exit::EFREQ, errors::Exit::EMODE, errors::Exit::EIVAL, errors::Exit::ESAMPLES,
 errors::Exit::ESYSCTL, errors::Exit::ENOFREQ, errors::Exit::ECONFLICT, errors::Exit::EPID,
 errors::Exit::EFORBIDDEN, errors::Exit::EDAEMON, errors::Exit::EWOPEN, errors::Exit::ESIGNAL,
 errors::Exit::ERANGEFMT, errors::Exit::ETEMPERATURE, errors::Exit::EEXCEPT, errors::Exit::EFILE,
 errors::Exit::EEXEC, errors::Exit::LENGTH }
 Exit codes.

#### **Functions**

void errors::fail (Exit const exitcode, int const err, std::string const &msg)
 Throws an Exception instance with the given message.

### Variables

• const char \*const errors::ExitStr []

Printable strings for exit codes.

### 14.4.1 Detailed Description


Common error handling code.

### 14.4.2 Class Documentation

## 14.4.2.1 struct errors::Exception

Exceptions bundle an exit code, errno value and message.

Collaboration diagram for errors::Exception:



#### Class Members

int err		The errno value at the time of creation.	
Exit	exitcode	The code to exit with.	
string	msg	An error message.	

## 14.5 src/libloadplay.cpp File Reference

Implements a library intended to be injected into a clock frequency deamon via LD\_PRELOAD.

```
#include "utility.hpp"
#include "constants.hpp"
#include "version.hpp"
#include "sys/env.hpp"
#include "sys/io.hpp"
#include <unordered_map>
#include <map>
#include <string>
#include <regex>
#include <sstream>
#include <memory>
#include <thread>
\verb"#include" < \verb"exception">
#include <mutex>
#include <chrono>
#include <vector>
#include <algorithm>
#include <cstring>
#include <cassert>
#include <csignal>
#include <sys/types.h>
#include <sys/sysctl.h>
#include <sys/resource.h>
#include <libutil.h>
#include <dlfcn.h>
#include <unistd.h>
Include dependency graph for libloadplay.cpp:
```



### Classes

- struct anonymous namespace{libloadplay.cpp}::mib\_t
  - Represents MIB, but wraps it to provide the necessary operators to use it as an std::map key.
- class anonymous\_namespace{libloadplay.cpp}::Callback< FunctionArgs >
  - Implements a recursion safe std::function wrapper.
- class anonymous\_namespace{libloadplay.cpp}::SysctlValue
  - Instances of this class represents a specific sysctl value.

class anonymous\_namespace{libloadplay.cpp}::Sysctls

Singleton class representing the sysctl table for this library.

struct anonymous\_namespace{libloadplay.cpp}::CoreReport

The reported state of a single CPU pipeline. More...

struct anonymous\_namespace{libloadplay.cpp}::CoreFrameReport

The report frame information for a single CPU pipeline. More...

class anonymous\_namespace{libloadplay.cpp}::Report

Provides a mechanism to provide frame wise per core load information.

class anonymous\_namespace{libloadplay.cpp}::Report::Frame

Represents a frame of the report.

class anonymous\_namespace{libloadplay.cpp}::Emulator

Instances of this class represent an emulator session.

• struct anonymous\_namespace{libloadplay.cpp}::Emulator::Core

Per core information. More...

class anonymous\_namespace{libloadplay.cpp}::Main

Singleton class representing the main execution environment.

class anonymous\_namespace{libloadplay.cpp}::Hold< T >

Sets a referenced variable to a given value and restores it when going out of context.

### Namespaces

anonymous\_namespace{libloadplay.cpp}

File local scope.

### **Typedefs**

template<auto Ownership>
 using anonymous\_namespace{libloadplay.cpp}::ofile = io::file< Ownership, io::write >

Output file type alias.

• template<auto Ownership>

using anonymous\_namespace{libloadplay.cpp}::ifile = io::file < Ownership, io::read > Input file type alias.

Functions

template<size\_t Size>

int anonymous\_namespace{libloadplay.cpp}::strcmp (char const \*const s1, char const (&s2)[Size])

Safe wrapper around strncmp, which automatically determines the buffer size of s2.

• std::regex anonymous\_namespace{libloadplay.cpp}::operator""\_r (char const \*const str, size\_t const len)

 $User\ defined\ literal\ for\ regular\ expressions.$ 

• template<typename ... ArgTs>

constexpr void anonymous\_namespace{libloadplay.cpp}::dprintf (ArgTs &&... args)

Calls io::ferr.printf(...) if built with -DEBUG.

template<>

std::string anonymous\_namespace{libloadplay.cpp}::SysctlValue::get < std::string > () const

Returns a copy of the value string.

• template<typename... MsgTs>

ofile < io::link > anonymous\_namespace{libloadplay.cpp}::debug (MsgTs &&... msg)

Print a debugging message if built with -DEBUG.

```
• template<typename... MsgTs>
  ofile < io::link > anonymous_namespace{libloadplay.cpp}::warn (MsgTs &&... msg)
     Print a warning.
• template<typename... MsgTs>
  ofile < io::link > anonymous_namespace{libloadplay.cpp}::fail (MsgTs &&... msg)
      This prints an error message and sets sys_results to make the hijacked process fail.

    ofile< io::link > anonymous_namespace{libloadplay.cpp}::operator<< (ofile< io::link > fout, Core←

  FrameReport const &frame)
     Print recorded and running clock frequency and load for a frame.
• int sysctl (const int *name, u int namelen, void *oldp, size t *oldlenp, const void *newp, size t newlen)
     Functions to intercept.

    int sysctlnametomib (const char *name, int *mibp, size_t *sizep)

     Intercept calls to sysctlnametomib().

    int sysctlbyname (const char *name, void *oldp, size_t *oldlenp, const void *newp, size_t newlen)

     Intercept calls to sysctlbyname().
• int daemon (int, int)
     Intercept calls to daemon().

    uid_t geteuid (void)

     Intercept calls to geteuid().

    pidfh * pidfile_open (const char *, mode_t, pid_t *)

     Intercept calls to pidfile open().

    int pidfile write (pidfh *)

     Intercept calls to pidfile_write().
int pidfile_close (pidfh *)
     Intercept calls to pidfile_close().
• int pidfile remove (pidfh *)
     Intercept calls to pidfile_remove().
int pidfile_fileno (pidfh const *)
     Intercept calls to pidfile_fileno().
```

### Variables

constexpr flag\_t const anonymous\_namespace{libloadplay.cpp}::FEATURES

The set of supported features.

int anonymous\_namespace{libloadplay.cpp}::sys\_results = 0

The success return value of intercepted functions.

- class anonymous\_namespace{libloadplay.cpp}::Sysctls anonymous\_namespace{libloadplay.cpp}::sysctls Sole instance of Sysctls.
- class anonymous\_namespace{libloadplay.cpp}::Main anonymous\_namespace{libloadplay.cpp}::main Sole instance of Main.
- bool anonymous\_namespace{libloadplay.cpp}::sysctl\_fallback = false

  Set to activate fallback to the original sysctl functions.

## 14.5.1 Detailed Description

Implements a library intended to be injected into a clock frequency deamon via LD\_PRELOAD.

This library reads instructions from io::fin (stdin) and outputs statistics about the hijacked process on io::fout (stdout).

The following environment variables affect the operation of loadplay:


Variable	Description
LOADPLAY_IN	Alternative input file
LOADPLAY_O↔	Alternative output file
UT	

### 14.5.2 Class Documentation

14.5.2.1 struct anonymous\_namespace{libloadplay.cpp}::CoreReport

The reported state of a single CPU pipeline.

Collaboration diagram for anonymous\_namespace{libloadplay.cpp}::CoreReport:




## Class Members

mhz_t	freq	The core clock frequency in [MHz].
double	load	The core load as a fraction.

14.5.2.2 struct anonymous\_namespace{libloadplay.cpp}::CoreFrameReport

The report frame information for a single CPU pipeline.

 $Collaboration\ diagram\ for\ an onymous\_namespace \{libloadplay.cpp\} :: CoreFrameReport:$ 



## Class Members

CoreReport	rec	The recorded core state.
CoreReport	run	The running core state.

# 14.5.2.3 struct anonymous\_namespace{libloadplay.cpp}::Emulator::Core

Per core information.

 $Collaboration\ diagram\ for\ anonymous\_namespace\{libloadplay.cpp\} :: Emulator :: Core:$ 



## Class Members

cptime_t	carryLoadCycles	The load cycles carried over to the next frame in [kcycles]. This is determined at the beginning of frame and used to calculated the simulation load at the beginning of the next frame.	
SysctlValue *	freqCtl	The sysctl handler. The constructor ensures this points to a valid handler.	

# Class Members

mhz_t	recFreq	The recorded clock frequency. If FREQ_TRACKING is enabled this is updated at during the preliminary stage and used at the beginning of frame stage.
mhz_t	runFreq	The clock frequency the simulation is running at. Updated at the end of frame and used in the next frame.
cptime_t	runLoadCycles	The load cycles simulated for this frame in [kcycles]. This is determined at the beginning of frame and used to calculate the reported load at the end of frame.

### 14.5.3 Function Documentation

Intercept calls to daemon().

Prevents process from separating from the controlling terminal.

Returns

The value of sys\_results

Intercept calls to geteuid().

Tells the asking process that it is running as root.

Returns

Always returns 0

```
14.5.3.3 pidfile_close()
int pidfile_close (
               pidfh * )
Intercept calls to pidfile_close().
Returns
     The value of sys_results
14.5.3.4 pidfile_fileno()
int pidfile_fileno (
               pidfh const * )
Intercept calls to pidfile_fileno().
Returns
     The value of sys_results
14.5.3.5 pidfile_open()
pidfh* pidfile_open (
               const char \ast ,
               mode_t ,
               pid_t * )
Intercept calls to pidfile_open().
Prevents pidfile locking and creation by the hijacked process.
Returns
     A dummy pointer
14.5.3.6 pidfile_remove()
int pidfile_remove (
               pidfh * )
Intercept calls to pidfile_remove().
Returns
```

The value of sys\_results

Intercept calls to pidfile\_write().

Returns

The value of sys\_results

Functions to intercept.

Intercept calls to sysctl().

Uses the local anonymous\_namespace{libloadplay::cpp}::sysctls store.

Falls back to the original under the following conditions:

- · sysctl\_fallback is set
- · kern.usrstack is requested
- vm.\* is requested

The call may fail for 3 reasons:

- 1. The fail() function was called and sys\_results was assigned -1
- 2. A target buffer was too small (errno == ENOMEM)
- 3. The given sysctl is not in the sysctls store (errno == ENOENT)

### Parameters

_		
	name,namelen,oldp,oldlenp,newp,newlen	Please refer to sysctl(3)

### Return values

0 The call succeeded

Return values

```
-1 The call failed
```

```
14.5.3.9 sysctlbyname()
```

Intercept calls to sysctlbyname().

Falls back on the original sysctlbyname() for the following names:

· kern.smp.cpus

May fail for the same reasons as sysctl().

## **Parameters**

name,oldp,oldlenp,newp,newlen | Please refer to sysct1(3)

Return values

0	The call succeeded
-1	The call failed

# 14.5.3.10 sysctlnametomib()

Intercept calls to sysctlnametomib().

Parameters

name,mibp,sizep Please refer to sysctl(3)

Return values

0 The call succeeded


#### Return values

-1 The call failed

# 14.6 src/loadplay.cpp File Reference

Implements the loadplay a bootstrapping tool for libloadplay.

```
#include "Options.hpp"
#include "errors.hpp"
#include "utility.hpp"
#include "sys/env.hpp"
#include "sys/io.hpp"
#include <unistd.h>
Include dependency graph for loadplay.cpp:
```



#### Namespaces

anonymous\_namespace{loadplay.cpp}

File local scope.

#### Enumerations

enum anonymous\_namespace{loadplay.cpp}::OE {
 anonymous\_namespace{loadplay.cpp}::OE::USAGE, anonymous\_namespace{loadplay.cpp}::OE::FILE\_IN,
 anonymous\_namespace{loadplay.cpp}::OE::FILE\_OUT, anonymous\_namespace{loadplay.cpp}::OE::CMD,
 anonymous\_namespace{loadplay.cpp}::OE::OPT\_NOOPT = CMD, anonymous\_namespace{loadplay.cpp}::OE::OPT\_UNKNO anonymous\_namespace{loadplay.cpp}::OE::OPT\_DASH, anonymous\_namespace{loadplay.cpp}::OE::OPT\_DASH,
 anonymous\_namespace{loadplay.cpp}::OE::OPT\_DONE }

An enum for command line parsing.

#### **Functions**

- char const \* anonymous\_namespace{loadplay.cpp}::filename (char const \*const path)
  - Performs very rudimentary file name argument checks.
- void anonymous\_namespace{loadplay.cpp}::execute (char const \*const file, char \*const argv[])

Executes the given command, substituting this process.

• int main (int argc, char \*argv[])

Parse command line arguments and execute the given command.

## Variables

- char const \*const anonymous\_namespace{loadplay.cpp}::USAGE = "[-h] [-i file] [-o file] command [...]"

  The short usage string.
- Parameter < OE > const anonymous\_namespace{loadplay.cpp}::PARAMETERS []
   Definitions of command line parameters.

## 14.6.1 Detailed Description

Implements the loadplay a bootstrapping tool for libloadplay.

### 14.6.2 Function Documentation

Parse command line arguments and execute the given command.

## Parameters

argc,argv	The command line arguments

## Returns

An exit code


See also

Exit

# 14.7 src/loadrec.cpp File Reference

Implements a load recorder, useful for simulating loads to test CPU clock daemons and settings.

```
#include "Options.hpp"
#include "types.hpp"
#include "constants.hpp"
#include "errors.hpp"
#include "utility.hpp"
#include "clas.hpp"
#include "version.hpp"
#include "sys/io.hpp"
#include "sys/sysctl.hpp"
#include <chrono>
#include <thread>
#include <memory>
#include <sys/resource.h>
Include dependency graph for loadrec.cpp:
```



#### Namespaces

anonymous\_namespace{loadrec.cpp}

File local scope.

### **Typedefs**

template<auto Ownership>
using anonymous\_namespace{loadrec.cpp}::ofile = io::file< Ownership, io::write >
Output file type alias.

### Enumerations

• enum anonymous\_namespace{loadrec.cpp}::OE { anonymous\_namespace{loadrec.cpp}::OE::USAGE, anonymous\_namespace{loadrec.cpp}::OE::IVAL\_DURATION, anonymous\_namespace{loadrec.cpp}::OE::IVAL\_POLL, anonymous\_namespace{loadrec.cpp}::OE::FILE\_OUTPUT, anonymous\_namespace{loadrec.cpp}::OE::FILE\_PID, anonymous\_namespace{loadrec.cpp}::OE::FLAG\_VERBOSE, anonymous\_namespace{loadrec.cpp}::OE::OPT\_UNKNOWN, anonymous\_namespace{loadrec.cpp}::OE::OPT\_NOOPT, anonymous\_namespace{loadrec.cpp}::OE::OPT\_DASH, anonymous\_namespace{loadrec.cpp}::OE::OPT\_LDASH, anonymous\_namespace{loadrec.cpp}::OE::OPT\_DONE }

An enum for command line parsing.

### **Functions**

14.7.2 Function Documentation

```
• template<typename... MsgTs>
      void anonymous_namespace{loadrec.cpp}::verbose (MsgTs &&... msg)
          Outputs the given printf style message on stderr if g.verbose is set.
    void anonymous_namespace{loadrec.cpp}::init ()
          Set up output to the given file.

    void anonymous_namespace{loadrec.cpp}::read_args (int const argc, char const *const argv[])

          Parse command line arguments.
    void anonymous_namespace{loadrec.cpp}::print_sysctls ()
          Print the sysctls.
    void anonymous_namespace{loadrec.cpp}::run ()
          Report the load frames.
    • int main (int argc, char *argv[])
         Main routine, setup and execute daemon, print errors.
Variables

    constexpr flag_t const anonymous_namespace{loadrec.cpp}::FEATURES

          The set of supported features.
      struct {
      bool verbose {false}
           Verbosity flag.
      ms duration {30000}
           Recording duration in ms.
      ms interval {25}
           Recording sample interval in ms.
       ofile < io::link > fout = io::fout
           The output stream either io::fout (stdout) or a file.
       char const * outfilename {nullptr}
           The user provided output file name.
       sys::ctl::SysctlOnce< coreid_t, 2 > const ncpu {1U, {CTL_HW, HW_NCPU}}
           The number of CPU cores/threads.
      } anonymous_namespace{loadrec.cpp}::g
          The global state.

    char const *const anonymous_namespace{loadrec.cpp}::USAGE = "[-hv] [-d ival] [-p ival] [-o file]"

          The short usage string.

    Parameter < OE > const anonymous_namespace{loadrec.cpp}::PARAMETERS []

          Definitions of command line parameters.
14.7.1 Detailed Description
Implements a load recorder, useful for simulating loads to test CPU clock daemons and settings.
```

Main routine, setup and execute daemon, print errors.

## **Parameters**

argc,argv	The command line arguments
argc,argv	The command line arguments

Returns

An exit code

See also


Exit

# 14.8 src/Options.hpp File Reference


This file provides nih::Options<>, a substitute for getopt(3).

```
#include "utility.hpp"
#include <cstddef>
#include <type_traits>
#include <cassert>
```

Include dependency graph for Options.hpp:



This graph shows which files directly or indirectly include this file:



#### Classes

struct nih::enum\_has\_members
 OptionT, class >

Tests whether the given enum provides all the required definitions.

struct nih::Parameter < OptionT >

Container for an option definition. More...

class nih::Options < OptionT, DefCount >

An instance of this class offers operators to retrieve command line options and arguments.

### Namespaces

• nih

Not invented here namespace, for code that substitutes already commonly available functionality.

#### **Functions**

template < class OptionT >
 size\_t nih::argCount (Parameter < OptionT > const &def)

Retrieves the count of arguments in an option definition.

template<class OptionT, size\_t DefCount>
 constexpr Options
 OptionT, DefCount > nih::make\_Options (int const argc, char const \*const \*const argv, char const \*const usage, Parameter
 OptionT > const (&defs)[DefCount])

Wrapper around the Options<> constructor, that uses function template matching to deduce template arguments.

# 14.8.1 Detailed Description

This file provides nih::Options<>, a substitute for getopt(3).

The getopt(3) interface takes the command line arguments as char \* const instead of char const \* l.e. it reserves the right to mutate the provided arguments, which it actually does.

The nih::Options<> functor is not a drop in substitute, but tries to be easily adoptable and does not change the data given to it.

```
To use the options an enum or enum class is required, e.g.:
enum class MyOptions {
    USAGE, FILE_IN, FILE_OUT, FLAG_VERBOSE,
    OPT_UNKNOWN, OPT_NOOPT, OPT_DASH, OPT_LDASH, OPT_DONE
};
```

The options prefixed with OPT\_ are obligatory. Their meaning is documented in nih::enum\_has\_members<>. Their presence is validated at compile time.

The enum values are returned when matching the next argument to a parameter. In order to do that a usage string and a list of parameter definitions are required:

Each entry in the array defines a parameter consisting of the following:

Field	Meaning
option	The option symbol (enum value)
sparam	An optional parameter character (short parameter)
lparam	An optional long parameter string
args	A comma separated list of parameter arguments
usage	A descriptive string

Multiple parameters may be mapped to a single option (e.g. --help and --usage). Parameters without arguments are called flags. It is possible to map parameters with different numbers of arguments to a single option, but this is arguably semantically confusing and should not be done.

Multiple flags' parameter characters can be concatenated in an argument. A parameter with arguments' character can appear at the end of a character chain. The first argument to the parameter may be concatenated as well. E.g. -v -i file, -vi file and -vifile are all equivalent. Parameters' string representations always stand alone, they can neither be combined with each other nor with parameter characters. E.g. --verbose --in file is the equivalent parameter string representation.

The usage string and the parameter usage strings are used to assemble the string provided by the nih::Options<>::usage() method.

The parameter definitions should be passed to nih::make\_Options() to create the functor:

```
int main(int argc, char * argv[]) {
    char const * infile = "-
    char const * outfile = "-";
    bool verbose = false;
    auto getopt = nih::make_Options(argc, argv, USAGE, PARAMETERS);
    while (true) switch (getopt()) { // get new option/argument
    case MyOptions::USAGE:
        std::cerr << getopt.usage(); // show usage</pre>
    case MyOptions::FILE_IN:
        infile = getopt[1]; // get first argument
    case MyOptions::FILE_OUT:
        outfile = getopt[1]; // get first argument
    case MyOptions::FLAG_VERBOSE:
        verbose = true;
       break:
    case MyOptions::OPT_UNKNOWN:
    case MyOptions::OPT_NOOPT:
    case MvOptions::OPT DASH:
    case MyOptions::OPT_LDASH:
        std::cerr << "Unexpected command line argument: "</pre>
                  << getopt[0] << '\n'; // output option/argument
       return 1;
    case MyOptions::OPT_DONE:
       return do_something(infile, outfile, verbose);
    return 0;
```

Every call of the functor moves on to the next parameter or argument. For non-option arguments it returns OPT\_NOOPT.

The getopt[1] calls return the first argument following the option. It is possible to retrieve more arguments than were defined in the options definition. The [] opterator always returns a valid, terminated string (provided the command line arguments are valid, terminated strings). So it is always safe to dereference the pointer, even when reading beyond the end of command line arguments.

The getopt[0] calls return the command line argument that contains the selected option. So in the FILE\_IN case it could be any of -i, --in, -vi, -ifile or -vifile. This is useful for the OPT\_UNKNOWN and OPT\_NOOPT cases. The getopt[1] call on the other hand would return file regardless of argument chaining.

### 14.8.2 Class Documentation

#### 14.8.2.1 struct nih::Parameter

```
template < class OptionT >
struct nih::Parameter < OptionT >
```

Container for an option definition.

Aliases can be defined by creating definitions with the same option member.

The lparam, args and usage members have to be 0 terminated, using string literals is safe.

# **Template Parameters**

(	OptionT	An enum or enum class representing the available options
---	---------	--

### Class Members


char const *	args	A comma separated list of arguments. Set to nullptr or "" if no argument is available.
char const *	lparam	The long version of this parameter. Set to nullptr or "" if no long parameter is available.
OptionT	option	The enum value to return for this option.
char	sparam	The short version of this parameter. Set to 0 if no short parameter is available.
char const *	usage	A usage string.

# 14.9 src/powerd++.cpp File Reference

Implements powerd++ a drop in replacement for FreeBSD's powerd.

```
#include "Options.hpp"
#include "Cycle.hpp"
#include "types.hpp"
#include "constants.hpp"
#include "errors.hpp"
#include "clas.hpp"
#include "utility.hpp"
#include "sys/sysctl.hpp"
#include "sys/pidfile.hpp"
#include "sys/signal.hpp"
#include "sys/io.hpp"
#include <locale>
#include <memory>
#include <algorithm>
#include <limits>
#include <cstdlib>
#include <cstdint>
```

#include <sys/resource.h>
Include dependency graph for powerd++.cpp:



#### Classes

- struct anonymous\_namespace{powerd++.cpp}::CoreGroup
  - Contains the management information for a group of cores with a common clock frequency. More...
- struct anonymous\_namespace{powerd++.cpp}::Core
  - Contains the management information for a single CPU core. More...
- struct anonymous\_namespace{powerd++.cpp}::Global
  - A collection of all the gloabl, mutable states. More...
- struct anonymous\_namespace{powerd++.cpp}::Global::ACSet
  - Per AC line state settings. More...
- class anonymous\_namespace{powerd++.cpp}::FreqGuard
  - A core frequency guard.

## Namespaces

anonymous\_namespace{powerd++.cpp}
 File local scope.

#### Enumerations

enum anonymous\_namespace{powerd++.cpp}::AcLineState: unsigned int { anonymous\_namespace{powerd++.cpp}::AcLineState::ONLINE, anonymous\_namespace{powerd++.cpp}::AcLineState::UNK anonymous\_namespace{powerd++.cpp}::AcLineState::LENGTH }

The available AC line states.

enum anonymous\_namespace{powerd++.cpp}::OE: {
 anonymous\_namespace{powerd++.cpp}::OE::USAGE, anonymous\_namespace{powerd++.cpp}::OE::MODE\_AC,
 anonymous\_namespace{powerd++.cpp}::OE::MODE\_BATT, anonymous\_namespace{powerd++.cpp}::OE::FREQ\_MIN,
 anonymous\_namespace{powerd++.cpp}::OE::FREQ\_MAX, anonymous\_namespace{powerd++.cpp}::OE::FREQ\_MIN\_AC,
 anonymous\_namespace{powerd++.cpp}::OE::FREQ\_MAX\_AC, anonymous\_namespace{powerd++.cpp}::OE::FREQ\_MIN\_BAGE,
 anonymous\_namespace{powerd++.cpp}::OE::FREQ\_MAX\_BATT, anonymous\_namespace{powerd++.cpp}::OE::FREQ\_RANGE,
 anonymous\_namespace{powerd++.cpp}::OE::FREQ\_RANGE,
 anonymous\_namespace{powerd++.cpp}::OE::HITEMP\_RANGE, anonymous\_namespace{powerd++.cpp}::OE::FREQ\_RANGE,
 anonymous\_namespace{powerd++.cpp}::OE::IVAL\_POLL, anonymous\_namespace{powerd++.cpp}::OE::FLAG\_FOREG,
 anonymous\_namespace{powerd++.cpp}::OE::CNT\_SAMPLES, anonymous\_namespace{powerd++.cpp}::OE::IGNORE,
 anonymous\_namespace{powerd++.cpp}::OE::OPT\_UNKNOWN, anonymous\_namespace{powerd++.cpp}::OE::OPT\_NOOPT,
 anonymous\_namespace{powerd++.cpp}::OE::OPT\_LONE}

An enum for command line parsing.

#### **Functions**

```
• template<typename... MsgTs>
  void anonymous_namespace{powerd++.cpp}::verbose (MsgTs &&... msg)
     Outputs the given printf style message on stderr if g.verbose is set.

    void anonymous_namespace{powerd++.cpp}::sysctl_fail (sys::sc_error < sys::ctl::error > const err)

     Treat sysctl errors.
void anonymous_namespace{powerd++.cpp}::init ()
     Perform initial tasks.
• template < bool Load = 1, bool Temperature = 0>
  void anonymous_namespace{powerd++.cpp}::update_loads ()
     Updates the cp_times ring buffer and computes the load average for each core.
  void anonymous_namespace{powerd++.cpp}::update_loads< 0, 0 > ()
     Do nada if neither load nor temperature are to be updated.
• template<bool Foreground, bool Temperature, bool Fixed>
  void anonymous_namespace{powerd++.cpp}::update_freq (Global::ACSet const &acstate)
     Update the CPU clocks depending on the AC line state and targets.

    void anonymous_namespace{powerd++.cpp}::update_freq ()

     Dispatch update_freq<>().
void anonymous_namespace{powerd++.cpp}::init_loads ()
     Fill the loads buffers with n samples.

    void anonymous namespace{powerd++.cpp}::set mode (AcLineState const line, char const *const str)

     Sets a load target or fixed frequency for the given AC line state.

    void anonymous_namespace{powerd++.cpp}::read_args (int const argc, char const *const argv[])

     Parse command line arguments.

    void anonymous_namespace{powerd++.cpp}::show_settings ()

     Prints the configuration on stderr in verbose mode.

    void anonymous_namespace{powerd++.cpp}::signal_recv (int signal)

     Sets g.signal, terminating the main loop.
void anonymous_namespace{powerd++.cpp}::run_daemon ()
     Daemonise and run the main loop.
int main (int argc, char *argv[])
     Main routine, setup and execute daemon, print errors.
```

## Variables

- struct anonymous\_namespace{powerd++.cpp}::Global anonymous\_namespace{powerd++.cpp}::g
   The gobal state.
- char const \*const anonymous\_namespace{powerd++.cpp}::USAGE = "[-hvf] [-abn mode] [-mM freq] [-FAB freq:freq] [-H temp:temp] [-p ival] [-s cnt] [-P file]"

The short usage string.

Parameter < OE > const anonymous\_namespace{powerd++.cpp}::PARAMETERS []
 Definitions of command line parameters.

### 14.9.1 Detailed Description


Implements powerd++ a drop in replacement for FreeBSD's powerd.

## 14.9.2 Class Documentation

# $14.9.2.1 \quad struct \ anonymous\_namespace \{powerd++.cpp\} :: CoreGroup$

Contains the management information for a group of cores with a common clock frequency.

 $Collaboration\ diagram\ for\ an onymous\_namespace \{powerd++.cpp\} :: CoreGroup:$ 




## Class Members

coreid_t	corei	The number of the core owning dev.cpu. d.freq.
SysctlSync< mhz_t >	freq	The sysctl dev.cpu. d.freq.
Max< mhz_t >	load	The maximum load reported by all cores in the group. This is updated by update_loads().
unique_ptr< mhz_t[]>	loads	A ring buffer of maximum load samples for this core group. Each maximum load sample is weighted with the core frequency at which it was taken.  This is updated by update_loads().
mhz_t	loadsum	The maximum load sum of all controlled cores. This is updated by update_loads().
Min< mhz_t >	max	The maximum group clock rate. The least of all core maxima in the group.
Max< mhz_t >	min	The minimum group clock rate. The greatest of all core minima in the group.
mhz_t	sample_freq	The dev.cpu. d.freq value for the current load sample. This is updated by update_loads().
Max < decikelvin_t >	temp	The maximum temperature measurement taken in the group.
Min< decikelvin_t >	temp_crit	Critical core temperature in dK.
Min< decikelvin_t >	temp_high	High core temperature in dK.

14.9.2.2 struct anonymous\_namespace{powerd++.cpp}::Core

Contains the management information for a single CPU core.

Collaboration diagram for anonymous\_namespace{powerd++.cpp}::Core:



# Class Members


cptime_t	all	Count of all ticks.
cptime_t const *	cp_time	A pointer to the kern.cp_times section for this core.
CoreGroup *	group	The core that controls the frequency for this core.
cptime_t	idle	The idle ticks count.
SysctlSync< decikelvin_t >	temp	The dev.cpu. d.temperature sysctl, if present.

# 14.9.2.3 struct anonymous\_namespace{powerd++.cpp}::Global

A collection of all the gloabl, mutable states.

This is mostly for semantic clarity.

Collaboration diagram for anonymous\_namespace{powerd++.cpp}::Global:




# Class Members

Sysctl	acline_ctl	The hw.acpi.acline ctl.
struct	ADP[3]	-
anonymous_namespace{powerd++		
struct	battery[3]	
anonymous_namespace{powerd++	an was	This buffer is to be allocated with
unique_ptr< Core[]>	cores	ncpu instances of the Core struct to store the management information of every core.
unique_ptr< cptime_t[][CPUSTATES]>	cp_times	The kern.cp_times buffer for all cores.
Sysctl	cp_times_ctl	The kern.cp_times sysctl.
bool	foreground	Foreground mode.
struct anonymous_namespace{powerd++	FREQ_DEFAULT_MAX[3]	
struct anonymous_namespace{powerd++	FREQ_DEFAULT_MIN[3]	
struct anonymous_namespace{powerd++	FREQ_UNSET[3]	
unique_ptr< CoreGroup[]>	groups	This buffer is to be allocated with the number of core groups. A core group is created by init() for each core that has a dev.cpu.d.freq handle.
struct anonymous_namespace{powerd++	HADP[3]	
ms	interval	The polling interval.
SysctlOnce< coreid_t, 2 > const	ncpu	The number of CPU cores or threads.
coreid_t	ngroups	The number of frequency controlling core groups.
struct anonymous_namespace{powerd++	online[3]	
char const *	pidfilename	Name of an alternative pidfile. If not given pidfile_open() uses a default name.
size_t	sample	The current sample.
size_t	samples	The number of load samples to take.
volatile sig_atomic_t	signal	The last signal received, used for terminating.
decikelvin_t	temp_crit	User set critical core temperature in dK.
decikelvin_t	temp_high	User set high core temperature in dK.
bool	temp_throttling	Temperature throttling mode.
struct	unknown[3]	The power states.
anonymous_namespace{powerd++		

 $14.9.2.4 \quad struct\ anonymous\_namespace\{powerd++.cpp\}::Global::ACSet$ 

Per AC line state settings.

 $Collaboration\ diagram\ for\ an onymous\_namespace \{powerd++.cpp\} :: Global :: ACSet:$ 



## Class Members

mhz_t	freq_max	Highest frequency to set in MHz.
mhz_t	freq_min	Lowest frequency to set in MHz.
char const *const	name	The string representation of this state.
mhz_t	target_freq	Fixed clock frequencies to use if the target load is set to 0.
cptime_t	target_load	Target load times [0, 1024]. The value 0 indicates the corresponding fixed frequency setting from target_freqs should be used.

# 14.9.3 Function Documentation

Main routine, setup and execute daemon, print errors.

#### **Parameters**

argc,argv	The command line arguments
-----------	----------------------------

## Returns

An exit code


See also

Exit


# 14.10 src/sys/env.hpp File Reference

Implements zero-cost abstractions for the getenv(3) facilities.

```
#include "error.hpp"
#include <cstdlib>
Include dependency graph for env.hpp:
```



This graph shows which files directly or indirectly include this file:



# Classes

• struct sys::env::error

The domain error type. More...

• class sys::env::Var

A reference type refering to an environment variable.

struct sys::env::Vars

A singleton class providing access to environment variables.

### Namespaces

• sys

Wrappers around native system interfaces.

sys::env

Provides wrappers around the getenv() family of functions.

### Variables

• struct sys::env::Vars sys::env::vars

Singleton providing access to environment variables.

# 14.10.1 Detailed Description

Implements zero-cost abstractions for the getenv(3) facilities.

14.10.2 Class Documentation


14.10.2.1 struct sys::env::error

The domain error type.


# 14.11 src/sys/error.hpp File Reference

Provides system call error handling.

#include <cerrno>
#include <cstring>
Include dependency graph for error.hpp:



This graph shows which files directly or indirectly include this file:



## Classes

• struct sys::sc\_error< Domain >

Can be thrown by syscall function wrappers if the function returned with an error.

# Namespaces

• sys

Wrappers around native system interfaces.


# 14.11.1 Detailed Description

Provides system call error handling.


# 14.12 src/sys/io.hpp File Reference

Implements c++ wrappers for <cstdio> I/O functionality.

#include <cstdio>
Include dependency graph for io.hpp:



This graph shows which files directly or indirectly include this file:



#### Classes

```
    class sys::io::file < Ownership, Features >

      Produces file access types around the C file handling facilities. More...

    struct sys::io::enable_if< bool, T >

      Similar to std::enable_if, but it also has the value of the expression.

    struct sys::io::enable_if< false, T >

      Specialise enable_if for a false expression.
struct sys::io::set < Set >
      Pack a set of integral values in a type. More...

    struct sys::io::contains < SetT, Value >

      Check whether a set type contains a value. More...

    struct sys::io::contains< set< Set ... >, Value >

      Specialise io::contains to unpack io::set.
struct sys::io::is_superset_of< LSetT, RSetT >
      Check whether the left hand set is a superest of the right hand set. More...

    struct sys::io::is_superset_of< LSetT, set< RSet ... >>

      Specialise is_superset_of to unpack the right hand io::set.
• struct sys::io::query
      Ask questions about the contents of a string. More...
· struct sys::io::query::contains_ftor
      Test a string whether it contains a set of characters.

    class sys::io::file_feature< FileT,... >

      Implements the base functionality of all file access types.

    class sys::io::file_feature< FileT, read, Tail ... >

      Implement read support for file types.
• class sys::io::file feature < FileT, write, Tail ... >
      Implement write support for file types.

    class sys::io::file_feature< FileT, seek, Tail ... >

      Implement seek support for file types.

    class sys::io::file< own, Features ... >

      Specialise for FILE object owning file instances.

    class sys::io::file< link, Features ... >

      Specialise for FILE object linking file instances.
```

#### Namespaces

• sys

Wrappers around native system interfaces.

• sys::io

This namespace contains c++ wrappers for < cstdio> functionality.

### **Typedefs**

```
    template < class SetT, auto Value > using sys::io::contains_t = typename contains < SetT, Value >::type
            Check whether a set type contains a value.
    template < class LSetT, class RSetT > using sys::io::is_superset_of_t = typename is_superset_of < LSetT, RSetT >::type
            Check whether the left hand set is a superest of the right hand set.
```

### Enumerations

- enum sys::io::feature { sys::io::feature::read, sys::io::feature::write, sys::io::feature::seek } Feature flags for file type composition.
- enum sys::io::ownership { sys::io::ownership::own, sys::io::ownership::link }

Ownership relation to the underlying FILE object.

#### Variables

- template<class SetT, auto Value> constexpr auto const sys::io::contains\_v = contains<SetT, Value>::value Check whether a set type contains a value.
- template<class LSetT, class RSetT > constexpr auto const sys::io::is\_superset\_of\_v = is\_superset\_of<LSetT, RSetT>::value Check whether the left hand set is a superest of the right hand set.
- file < link, write > sys::io::ferr {stderr}
   File access instances for stderr.
- file< link, write > sys::io::fout {stdout}

File access instances for stdout.

• file< link, read > sys::io::fin {stdin}

File access instances for stdin.

## 14.12.1 Detailed Description

Implements c++ wrappers for <cstdio> I/O functionality.

#### 14.12.2 Class Documentation

## 14.12.2.1 class sys::io::file

template<ownership Ownership, feature ... Features> class sys::io::file< Ownership, Features >

Produces file access types around the C file handling facilities.

# **Template Parameters**

Ownership	Determine the ownership relationship to the underlying FILE object
Features	A list of features the file type supports

## See also

```
ownership
feature
file<own, Features ...>
file<link, Features ...>
file_feature
```

14.12.2.2 struct sys::io::set

template<auto ... Set> struct sys::io::set< Set >

Pack a set of integral values in a type.

**Template Parameters** 

Set | A set of integral values

14.12.2.3 struct sys::io::contains

template < class SetT, auto Value > struct sys::io::contains < SetT, Value >

Check whether a set type contains a value.

**Template Parameters** 

SetT	A set of integral values packed in io::set
Value	The value to look up

14.12.2.4 struct sys::io::is\_superset\_of

template < class LSetT, class RSetT> struct sys::io::is\_superset\_of < LSetT, RSetT >

Check whether the left hand set is a superest of the right hand set.


**Template Parameters** 

LSetT,RSetT | Two io::set instances

14.12.2.5 struct sys::io::query

Ask questions about the contents of a string.

Collaboration diagram for sys::io::query:




### Class Members

	struct contains_ftor	contains	Query the string for characters.	
--	----------------------	----------	----------------------------------	--


# 14.13 src/sys/pidfile.hpp File Reference

Implements safer c++ wrappers for the pidfile\_\*() interface.

#include "error.hpp"
#include <libutil.h>
Include dependency graph for pidfile.hpp:



This graph shows which files directly or indirectly include this file:



### Classes

- struct sys::pid::error
  - The domain error type. More...
- · class sys::pid::Pidfile

A wrapper around the pidfile $\_*$  family of commands implementing the RAII pattern.

#### Namespaces

• sys

Wrappers around native system interfaces.

• sys::pid

This namespace contains safer c++ wrappers for the pidfile\_\*() interface.

### 14.13.1 Detailed Description

Implements safer c++ wrappers for the pidfile\_\*() interface.

Requires linking with -lutil.

14.13.2 Class Documentation


14.13.2.1 struct sys::pid::error

The domain error type.


# 14.14 src/sys/signal.hpp File Reference

Implements a c++ wrapper for the signal(3) call.

```
#include "error.hpp"
#include <csignal>
Include dependency graph for signal.hpp:
```



This graph shows which files directly or indirectly include this file:



### Classes

• struct sys::sig::error

The domain error type. More...

· class sys::sig::Signal

Sets up a given signal handler and restores the old handler when going out of scope.

### Namespaces

• sys

Wrappers around native system interfaces.

sys::sig

This namespace provides c++ wrappers for signal(3).

### **Typedefs**

using sys::sig::sig\_t = void(\*)(int)
 Convenience type for signal handlers.

### 14.14.1 Detailed Description

Implements a c++ wrapper for the signal(3) call.

14.14.2 Class Documentation


14.14.2.1 struct sys::sig::error

The domain error type.


### 14.15 src/sys/sysctl.hpp File Reference

Implements safer c++ wrappers for the sysctl() interface.

```
#include "error.hpp"
#include <memory>
#include <cassert>
#include <sys/types.h>
#include <sys/sysctl.h>
Include dependency graph for sysctl.hpp:
```



This graph shows which files directly or indirectly include this file:



#### Classes

```
struct sys::ctl::error
```

The domain error type. More...

class sys::ctl::Sysctl < MibDepth >

Represents a sysctl MIB address.

class sys::ctl::Sysctl< 0 >

This is a specialisation of Sysctl for sysctls using symbolic names.

class sys::ctl::Sync< T, SysctlT >

This is a wrapper around Sysctl that allows semantically transparent use of a sysctl.

class sys::ctl::Once< T, SysctlT >

A read once representation of a Sysctl.

#### Namespaces

• sys

Wrappers around native system interfaces.

sys::ctl

This namespace contains safer c++ wrappers for the sysctl() interface.

### Typedefs

typedef int sys::ctl::mib\_t

Management Information Base identifier type (see sysctl(3)).

```
    template<typename T, size_t MibDepth = 0>
    using sys::ctl::SysctlSync = Sync< T, Sysctl< MibDepth > >
```

A convenience alias around Sync.

template<typename T, size\_t MibDepth>
 using sys::ctl::SysctlOnce = Once< T, Sysctl< MibDepth >>

A convenience alias around Once.

### **Functions**

• void sys::ctl::sysctl\_raw (mib\_t const \*name, u\_int const namelen, void \*const oldp, size\_t \*const oldlenp, void const \*const newp, size\_t const newlen)

A wrapper around the sysctl() function.

```
    template<size t MibDepth>
```

```
void sys::ctl::sysctl_get (mib_t const (&mib)[MibDepth], void *const oldp, size_t &oldlen)
```

Returns a sysctl() value to a buffer.

• template<size\_t MibDepth>

```
void sys::ctl::sysctl_set (mib_t const (&mib)[MibDepth], void const *const newp, size_t const newlen)
```

Sets a sysctl() value.

• template<typename... Args>

```
constexpr Sysctl < sizeof...(Args) > sys::ctl::make_Sysctl (Args const ... args)
```

Create a Sysctl instances.

• template<typename T , class SysctlT >

```
constexpr Once< T, SysctlT > sys::ctl::make_Once (T const &value, SysctlT const &sysctl) noexcept
```

This creates a Once instance.

### 14.15.1 Detailed Description

Implements safer c++ wrappers for the sysctl() interface.

### 14.15.2 Class Documentation


### 14.15.2.1 struct sys::ctl::error

The domain error type.


# 14.16 src/types.hpp File Reference

A collection of type aliases.

#include <chrono>
Include dependency graph for types.hpp:



This graph shows which files directly or indirectly include this file:



# Namespaces

types

A collection of type aliases.

### Typedefs

- typedef std::chrono::milliseconds types::ms

  Millisecond type for polling intervals.
- typedef int types::coreid\_t

Type for CPU core indexing.

- typedef unsigned long types::cptime\_t
  - Type for load counting.
- typedef unsigned int types::mhz\_t

Type for CPU frequencies in MHz.

• typedef int types::decikelvin\_t

Type for temperatures in dK.


### 14.16.1 Detailed Description

A collection of type aliases.


# 14.17 src/utility.hpp File Reference

Implements generally useful functions.

```
#include <type_traits>
#include <string>
#include <cstdio>
Include dependency graph for utility.hpp:
```



This graph shows which files directly or indirectly include this file:



#### Classes

class utility::Formatter< BufSize >

A formatting wrapper around string literals.

• class utility::Sum< T >

A simple value container only allowing += and copy assignment.

class utility::Min< T >

A simple value container that provides the minimum of assigned values.

class utility::Max< T >

A simple value container that provides the maximum of assigned values.

### Namespaces

utility

A collection of generally useful functions.

· utility::literals

Contains literal operators.

### **Functions**

template<typename T, size\_t Count>
 constexpr size\_t utility::countof (T(&)[Count])

Like sizeof(), but it returns the number of elements an array consists of instead of the number of bytes.

 template<typename... Args> void utility::sprintf (Args...)

This is a safeguard against accidentally using sprintf().

template<size\_t Size, typename... Args>
 int utility::sprintf\_safe (char(&dst)[Size], char const \*const format, Args const ... args)

A wrapper around snprintf() that automatically pulls in the destination buffer size.

template<class ET, typename VT = typename std::underlying\_type<ET>::type>
constexpr VT utility::to\_value (ET const op)

Casts an enum to its underlying value.

• constexpr Formatter < 16384 > utility::literals::operator""\_fmt (char const \*const fmt, size\_t const)

Literal to convert a string literal to a Formatter instance.


### 14.17.1 Detailed Description

Implements generally useful functions.


# 14.18 src/version.hpp File Reference

Defines types and constants used for version management.

#include "utility.hpp"
#include <cstdint>
Include dependency graph for version.hpp:



This graph shows which files directly or indirectly include this file:



### Namespaces

version

Version information constants and types.

version::literals

Literals to set flag bits.

### **Typedefs**

• typedef uint64\_t version::flag\_t

The data type to use for feature flags.

#### Enumerations

enum version::LoadrecBits { version::LoadrecBits::FREQ\_TRACKING }
 Feature flags for load recordings.

#### **Functions**

• constexpr flag\_t version::literals::operator""\_FREQ\_TRACKING (unsigned long long int value) Set the FREQ\_TRACKING bit.

### Variables

• char const \*const version::LOADREC\_FEATURES = "usr.app.powerdxx.loadrec.features"

The pseudo MIB name for the load recording feature flags.

### 14.18.1 Detailed Description

Defines types and constants used for version management.

# Index

AcLineState	anonymous_namespace{libloadplay.cpp}::Report::Frame
anonymous_namespace{powerd++.cpp}, 43	115
addValue	Frame, 116
anonymous_namespace{libloadplay.cpp}::Sysctls,	operator [], 116
158, 159	anonymous_namespace{libloadplay.cpp}::Sysctls, 157
all	addValue, 158, 159
sys::io::query::contains_ftor, 80	getMib, 159
anonymous_namespace{clas.cpp}, 23	mibs, 160
Unit, 24	operator [], 159
unit, 25	sysctls, 160
UnitStr, 25	anonymous_namespace{libloadplay.cpp}::SysctlValue,
anonymous_namespace{libloadplay.cpp}, 25	161
debug, 29	get, 163–165
dprintf, 29	_
fail, 30	mtx, 168
FEATURES, 32	operator=, 165
ifile, 28	registerOnSet, 166
main, 32	set, 166, 167
ofile, 28	size, 168
operator<<, 31	SysctlValue, 162, 163
operator", 30	value, 169
•	anonymous_namespace{loadplay.cpp}, 33
strcmp, 31	execute, 34
sysctls, 32	filename, 34
SysctlValue::get < std::string >, 31	OE, 33
warn, 32	PARAMETERS, 35
anonymous_namespace{libloadplay.cpp}::Callback<	anonymous_namespace{loadrec.cpp}, 35
FunctionArgs >, 76	FEATURES, 38
Callback, 77	OE, 37
operator(), 78	ofile 36
anonymous_namespace{libloadplay.cpp}::CoreFrameRep	PARAMETERS, 38
27, 183	read_args, 37
anonymous_namespace{libloadplay.cpp}::CoreReport,	run, 37
28, 183	verbose, 38
anonymous_namespace{libloadplay.cpp}::Emulator, 83	anonymous_namespace{powerd++.cpp}, 39
Emulator, 85	AcLineState, 43
ncpu, 86	
operator(), 85	g, 47
$an on ymous\_names pace \{libload play.cpp\} :: Emulator :: Corollary :$	
84, 184	init_loads, 44
anonymous_namespace{libloadplay.cpp}::Hold $< T >$ ,	OE, 43
118	PARAMETERS, 47
Hold, 119	read_args, 45
ref, 119	set_mode, 45
restore, 119	signal_recv, 46
anonymous_namespace{libloadplay.cpp}::Main, 121	sysctl_fail, 46
Main, 122	update_freq, 46
anonymous_namespace{libloadplay.cpp}::mib_t, 124	update_loads, 47
mib_t, 125	verbose, 47
operator int *, 125	anonymous_namespace{powerd++.cpp}::Core, 40, 200
operator int const *, 126	anonymous_namespace{powerd++.cpp}::CoreGroup,
operator<, 126	41, 200
operator==, 126	anonymous_namespace{powerd++.cpp}::FreqGuard,
anonymous_namespace{libloadplay.cpp}::Report, 141	117
frame, 142	anonymous_namespace{powerd++.cpp}::Global, 42,
Report, 142	201

$an onymous\_name space \{powerd++.cpp\} :: Global :: ACSet,$	MODE_AC, 44
202	MODE_BATT, 44
anonymous_namespace{clas.cpp}	MODE_UNKNOWN, 44
CELSIUS, 24	ONLINE, 43
FAHRENHEIT, 24	OPT_DASH, 44
GHZ, 24	OPT_DONE, 44
HZ, 24	OPT_LDASH, 44
KELVIN, 24	OPT_NOOPT, 44
KHZ, 24	OPT_UNKNOWN, 44
MHZ, 24	UNKNOWN, 43
MILLISECOND, 24	USAGE, 44
PERCENT, 24	any
RANKINE, 24	sys::io::query::contains_ftor, 80
SCALAR, 24	argCount
SECOND, 24	nih, 57
THZ, 24	,
UNKNOWN, 24	BATTERY
anonymous_namespace{loadplay.cpp}	anonymous_namespace{powerd++.cpp}, 43
CMD, 34	bmatch
	nih::Options < OptionT, DefCount >, 133
FILE_IN, 34	>
FILE_OUT, 34	c_str
OPT_DASH, 34	sys::env::Var, 170
OPT_DONE, 34	sys::sc_error< Domain >, 143
OPT_LDASH, 34	Callback
OPT_NOOPT, 34	anonymous_namespace{libloadplay.cpp}::Callback<
OPT_UNKNOWN, 34	FunctionArgs >, 77
USAGE, 34	CELSIUS
anonymous_namespace{loadrec.cpp}	anonymous_namespace{clas.cpp}, 24
FILE_OUTPUT, 37	celsius
FILE_PID, 37	clas, 49
FLAG_VERBOSE, 37	clas, 49
IVAL_DURATION, 37	celsius, 49
IVAL_POLL, 37	
OPT_DASH, 37	freq, 49
OPT DONE, 37	ival, 49
OPT_LDASH, 37	load, 50
OPT_NOOPT, 37	range, 50
OPT_UNKNOWN, 37	samples, 51
USAGE, 37	temperature, 51
anonymous_namespace{powerd++.cpp}	close
BATTERY, 43	sys::io::file< own, Features >, 96
CNT_SAMPLES, 44	CMD
FILE PID, 44	anonymous_namespace{loadplay.cpp}, 34
FLAG FOREGROUND, 44	CNT_SAMPLES
FLAG_TOREGROUND, 44  FLAG_VERBOSE, 44	anonymous_namespace{powerd++.cpp}, 44
FREQ MAX, 44	constants, 52
<del>-</del> · · ·	TJMAX_SOURCES, 52
FREQ_MAX_AC, 44	contains_t
FREQ_MAX_BATT, 44	sys::io, 67
FREQ_MIN, 44	contains_v
FREQ_MIN_AC, 44	sys::io, 68
FREQ_MIN_BATT, 44	countof
FREQ_RANGE, 44	utility, 72
FREQ_RANGE_AC, 44	cptime_t
FREQ_RANGE_BATT, 44	types, 71
HITEMP_RANGE, 44	
IGNORE, 44	daemon
IVAL_POLL, 44	libloadplay.cpp, 185
LENGTH, 43	debug

anonymous_namespace{libloadplay.cpp}, 29	ESAMPLES, 55
dprintf	ESIGNAL, 55
anonymous_namespace{libloadplay.cpp}, 29	ESYSCTL, 55
FCLARC	ETEMPERATURE, 55
ECLARG	EWOPEN, 55
errors, 54	Exit, 54
ECONFLICT	ExitStr, 55
errors, 55	fail, 55
EDAEMON	LENGTH, 55
errors, 55	OK, 54
EEXCEPT	errors::Exception, 54, 179
errors, 55	ESAMPLES
EEXEC	errors, 55
errors, 55	ESIGNAL
EFILE	errors, 55
errors, 55	ESYSCTL
EFORBIDDEN	errors, 55
errors, 55	ETEMPERATURE
EFREQ	errors, 55
errors, 55	EWOPEN
EIVAL	errors, 55
errors, 55	execute
ELOAD	anonymous_namespace{loadplay.cpp}, 34
errors, 54	Exit
EMODE	errors, 54
errors, 55	ExitStr
Emulator	
anonymous_namespace{libloadplay.cpp}::Emulator,	errors, 55
85	FAHRENHEIT
ENOFREQ	anonymous_namespace{clas.cpp}, 24
errors, 55	fail
eof	anonymous_namespace{libloadplay.cpp}, 30
sys::io::file_feature< FileT, >, 99	errors, 55
EOUTOFRANGE	feature
errors, 54	sys::io, 67
EPID	FEATURES
errors, 55	anonymous_namespace{libloadplay.cpp}, 32
ERANGEFMT	anonymous_namespace{loadrec.cpp}, 38
errors, 55	file
erase	sys::io::file < link, Features >, 90, 91
sys::env::Var, 170	sys::io::file< own, Features >, 95, 96
error	file_feature
sys::io::file_feature< FileT, >, 99	sys::io::file_feature< FileT, >, 99
errors, 53	FILE_IN
ECLARG, 54	anonymous_namespace{loadplay.cpp}, 34
ECONFLICT, 55	FILE_OUT
EDAEMON, 55	anonymous_namespace{loadplay.cpp}, 34
EEXCEPT, 55	FILE_OUTPUT
EEXEC, 55	anonymous_namespace{loadrec.cpp}, 37
EFILE, 55	FILE_PID
EFORBIDDEN, 55	
	anonymous_namespace{loadrec.cpp}, 37
EFREQ, 55	anonymous_namespace{powerd++.cpp}, 44 filename
EIVAL, 55	
ELOAD, 54	anonymous_namespace{loadplay.cpp}, 34 FLAG_FOREGROUND
EMODE, 55	
ENOFREQ, 55	anonymous_namespace{powerd++.cpp}, 44
EOUTOFRANGE, 54	FLAG_VERBOSE
EPID, 55	anonymous_namespace{loadrec.cpp}, 37
ERANGEFMT, 55	anonymous_namespace{powerd++.cpp}, 44

flush	anonymous_namespace{clas.cpp}, 24
sys::io::file_feature< FileT, write, Tail >, 110	
Frame	ifile
anonymous_namespace{libloadplay.cpp}::Report::Fi 116	IGNORE
frame	anonymous_namespace{powerd++.cpp}, 44
anonymous_namespace{libloadplay.cpp}::Report, 142	<pre>init     anonymous_namespace{powerd++.cpp}, 44</pre>
freq	init_loads
clas, 49	anonymous_namespace{powerd++.cpp}, 44
FREQ_MAX	is_superset_of_t
anonymous_namespace{powerd++.cpp}, 44	sys::io, 67
FREQ_MAX_AC	is_superset_of_v
anonymous_namespace{powerd++.cpp}, 44	sys::io, 69
FREQ_MAX_BATT	ival
anonymous_namespace{powerd++.cpp}, 44	clas, 49
FREQ_MIN	IVAL_DURATION
anonymous_namespace{powerd++.cpp}, 44 FREQ_MIN_AC	anonymous_namespace{loadrec.cpp}, 37 IVAL_POLL
anonymous_namespace{powerd++.cpp}, 44	anonymous_namespace{loadrec.cpp}, 37
FREQ_MIN_BATT	anonymous_namespace{powerd++.cpp}, 44
anonymous_namespace{powerd++.cpp}, 44	KELVIN
FREQ_RANGE	anonymous_namespace{clas.cpp}, 24
anonymous_namespace{powerd++.cpp}, 44 FREQ_RANGE_AC	KHZ
anonymous_namespace{powerd++.cpp}, 44	anonymous_namespace{clas.cpp}, 24
FREQ_RANGE_BATT	LENGTH
anonymous_namespace{powerd++.cpp}, 44 FREQ_TRACKING	anonymous_namespace{powerd++.cpp}, 43
version, 75	errors, 55
version, 75	libloadplay.cpp
g	daemon, 185
anonymous_namespace{powerd++.cpp}, 47	geteuid, 185
get	pidfile_close, 185
anonymous_namespace{libloadplay.cpp}::SysctlValu	ue, pidfile_fileno, 186 pidfile_open, 186
nih::Options< OptionT, DefCount >, 133, 134	pidfile_remove, 186
sys::ctl::Sysctl< 0 >, 155, 156	pidfile_write, 186
sys::ctl::Sysctl< MibDepth >, 151, 152	sysctl, 187
sys::io::file< link, Features >, 92	sysctlbyname, 188
sys::io::file< own, Features >, 97	sysctlnametomib, 188
getc	link
sys::io::file_feature< FileT, read, Tail >, 102	sys::io, 68
geteuid	load
libloadplay.cpp, 185	clas, 50
getMib	loadplay.cpp
anonymous_namespace{libloadplay.cpp}::Sysctls,	main, 190
159	loadrec.cpp
gets	main, 192
sys::io::file_feature< FileT, read, Tail >, 102	LoadrecBits
GHZ	version, 75
anonymous_namespace{clas.cpp}, 24	Main
HITEMP_RANGE	anonymous_namespace{libloadplay.cpp}::Main
anonymous_namespace{powerd++.cpp}, 44	122
Hold	main
$an onymous\_names pace \{libload play.cpp\} :: Hold <$	anonymous_namespace{libloadplay.cpp}, 32 loadplay.cpp, 190
T >, 119 HZ	loadrec.cpp, 190
	ющиестерр, 172

powerd++.cpp, 203 make_Once	anonymous_namespace{loadplay.cpp}, 33 anonymous_namespace{loadrec.cpp}, 37
sys::ctl, 60	anonymous_namespace{powerd++.cpp}, 43
make_Options	offset
nih, 57	nih::Options< OptionT, DefCount >, 134
make_Sysctl	ofile
sys::ctl, 61	anonymous_namespace{libloadplay.cpp}, 28
match	anonymous_namespace{loadrec.cpp}, 36
nih::Options< OptionT, DefCount >, 134	OK
Max	errors, 54
utility::Max $<$ T $>$ , 123	Once
MHZ	sys::ctl::Once< T, SysctlT >, 130
anonymous_namespace{clas.cpp}, 24	ONLINE
mib_t	anonymous_namespace{powerd++.cpp}, 43
anonymous_namespace{libloadplay.cpp}::mib_t,	operator []
125	•
mibs	anonymous_namespace{libloadplay.cpp}::Report::Frame,
anonymous_namespace{libloadplay.cpp}::Sysctls,	
160	anonymous_namespace{libloadplay.cpp}::Sysctls,
MILLISECOND	159
	nih::Options < OptionT, DefCount >, 135
anonymous_namespace{clas.cpp}, 24	sys::env::Vars, 172, 173
Min	operator bool
utility::Min< T >, 128	sys::io::file_feature< FileT, >, 100
MODE_AC	operator char const *
anonymous_namespace{powerd++.cpp}, 44	sys::env::Var, 171
MODE_BATT	operator int
anonymous_namespace{powerd++.cpp}, 44	sys::sc_error< Domain >, 143
MODE_UNKNOWN	operator int *
anonymous_namespace{powerd++.cpp}, 44	anonymous_namespace{libloadplay.cpp}::mib_t,
mtx	105
anonymous_namespace{libloadplay.cpp}::SysctlValu	Je oberator int const *
168	
	anonymous_namespace{libloadplay.cpp}::mib_t, 126
ncpu	
anonymous_namespace{libloadplay.cpp}::Emulator,	operator Option 1
86	,
nih, 56	operator T
argCount, 57	sys::ctl::Sync< T, SysctlT >, 148
make_Options, 57	operator T const &
nih::enum_has_members< OptionT, class >, 87	sys::ctl::Once< T, SysctlT >, 130
nih::Options< OptionT, DefCount >, 131	utility::Max $<$ T $>$ , 123
bmatch, 133	utility::Min< T >, 128
get, 133, 134	utility::Sum< T >, 146
match, 134	operator<
offset, 134	anonymous_namespace{libloadplay.cpp}::mib_t,
	126
operator [], 135	operator<<
operator OptionT, 135	anonymous_namespace{libloadplay.cpp}, 31
operator(), 136	operator()
opt_dash, 138	•
opt_ldash, 138	anonymous_namespace{libloadplay.cpp}::Callback<
opt_noopt, 138	FunctionArgs >, 78
opt_unknown, 139	anonymous_namespace{libloadplay.cpp}::Emulator,
Options, 133	85
removePath, 136	nih::Options< OptionT, DefCount >, 136
show, 136	sys::io::query::contains_ftor, 81
usage, 138	timing::Cycle, 82, 83
nih::Parameter, 56, 197	utility::Formatter< BufSize >, 114
	operator+=
OE	utility::Sum< T >, 146

operator=	pfh
anonymous_namespace{libloadplay.cpp}::SysctlVal	ue, sys::pid::Pidfile, 140
165	Pidfile
sys::ctl::Sync< T, SysctlT >, 148	sys::pid::Pidfile, 140
sys::env::Var, 171	pidfile_close
sys::io::file< link, Features >, 92	libloadplay.cpp, 185
sys::io::file< own, Features >, 97	pidfile_fileno
utility::Max <t>, 124</t>	libloadplay.cpp, 186
utility::Min< T >, 128	pidfile_open
operator==	libloadplay.cpp, 186
anonymous_namespace{libloadplay.cpp}::mib_t,	pidfile_remove
126	libloadplay.cpp, 186
operator""_fmt	pidfile_write
utility::literals, 74	libloadplay.cpp, 186
operator""_FREQ_TRACKING	powerd++.cpp
version::literals, 76	main, 203
operator""_r	print
anonymous_namespace{libloadplay.cpp}, 30	sys::io::file_feature< FileT, write, Tail >, 110
OPT_DASH	printf
anonymous_namespace{loadplay.cpp}, 34	sys::io::file_feature< FileT, write, Tail >, 111
anonymous_namespace{loadrec.cpp}, 37	putc
anonymous_namespace{powerd++.cpp}, 44	sys::io::file_feature< FileT, write, Tail >, 112
opt_dash	, <u> </u>
nih::Options< OptionT, DefCount >, 138	range
OPT_DONE	clas, 50
anonymous_namespace{loadplay.cpp}, 34	RANKINE
anonymous_namespace{loadrec.cpp}, 37	anonymous_namespace{clas.cpp}, 24
anonymous_namespace{powerd++.cpp}, 44	read
OPT_LDASH	sys::io, 68
anonymous_namespace{loadplay.cpp}, 34	sys::io::file_feature< FileT, read, Tail >, 103
anonymous_namespace{loadrec.cpp}, 37	read_args
anonymous_namespace{powerd++.cpp}, 44	anonymous_namespace{loadrec.cpp}, 37
opt_ldash	anonymous_namespace{powerd++.cpp}, 45
nih::Options < OptionT, DefCount >, 138	ref
OPT_NOOPT	anonymous_namespace{libloadplay.cpp}::Hold<
anonymous_namespace{loadplay.cpp}, 34	T >, 119
anonymous_namespace{loadrec.cpp}, 37	registerOnSet
anonymous_namespace{powerd++.cpp}, 44	anonymous_namespace{libloadplay.cpp}::SysctlValue
opt_noopt	166
nih::Options< OptionT, DefCount >, 138	release
OPT UNKNOWN	sys::io::file< own, Features >, 97
anonymous_namespace{loadplay.cpp}, 34	removePath
anonymous_namespace{loadrec.cpp}, 37	nih::Options< OptionT, DefCount >, 136
	Report Sprioris, Bereduit >, 150
anonymous_namespace{powerd++.cpp}, 44	anonymous_namespace{libloadplay.cpp}::Report,
opt_unknown	142
nih::Options < OptionT, DefCount >, 139	restore
Options	
nih::Options < OptionT, DefCount >, 133	anonymous_namespace{libloadplay.cpp}::Hold<
own	T >, 119
sys::io, 68	rewind
ownership	sys::io::file_feature< FileT, seek, Tail >, 106
sys::io, 68	run
PARAMETERS	anonymous_namespace{loadrec.cpp}, 37
anonymous_namespace{loadplay.cpp}, 35	samples
anonymous_namespace{loadrec.cpp}, 38	clas, 51
	SCALAR
anonymous_namespace{powerd++.cpp}, 47	
PERCENT	anonymous_namespace{clas.cpp}, 24
anonymous_namespace{clas.cpp}, 24	scanf

```
sys::io::file_feature< FileT, read, Tail ... >, 104
                                                                make_Sysctl, 61
SECOND
                                                                sysctl_get, 61
     anonymous_namespace{clas.cpp}, 24
                                                                sysctl_raw, 62
seek
                                                                sysctl_set, 62
                                                                SysctlOnce, 60
     sys::io, 68
     sys::io::file\_feature < FileT, seek, Tail \dots >, 106
                                                                SysctlSync, 60
                                                           sys::ctl::error, 60, 215
set
     anonymous_namespace{libloadplay.cpp}::SysctlValueys::ctl::Once < T, SysctlT >, 129
          166, 167
                                                                Once, 130
     sys::ctl::Sysctl< 0 >, 156
                                                                operator T const &, 130
     sys::ctl::Sysctl< MibDepth >, 152, 153
                                                           sys::ctl::Sync< T, SysctlT >, 147
set\_mode
                                                                operator T, 148
     anonymous_namespace{powerd++.cpp}, 45
                                                                operator=, 148
show
                                                                Sync, 148
     nih::Options < OptionT, DefCount >, 136
                                                           sys::ctl::Sysctl< 0 >, 153
Signal
                                                                get, 155, 156
     sys::sig::Signal, 144
                                                                set, 156
signal_recv
                                                                size, 157
                                                                Sysctl, 154
     anonymous_namespace{powerd++.cpp}, 46
size
                                                           sys::ctl::Sysctl< MibDepth >, 149
     anonymous_namespace{libloadplay.cpp}::SysctlValue,
                                                                get, 151, 152
                                                                set, 152, 153
     sys::ctl::Sysctl< 0 >, 157
                                                                size, 153
     sys::ctl::Sysctl < MibDepth >, 153
                                                                Sysctl, 150
sprintf
                                                           sys::env, 63
     utility, 72
                                                                vars, 63
sprintf_safe
                                                           sys::env::error, 63, 205
     utility, 73
                                                           sys::env::Var, 169
src/clas.hpp, 173
                                                                c_str, 170
src/constants.hpp, 175
                                                                erase, 170
src/Cycle.hpp, 177
                                                                operator char const *, 171
src/errors.hpp, 178
                                                                operator=, 171
src/libloadplay.cpp, 180
                                                                str, 172
src/loadplay.cpp, 189
                                                                Var. 170
src/loadrec.cpp, 190
                                                           sys::env::Vars, 172
src/Options.hpp, 194
                                                                operator [], 172, 173
                                                           sys::io, 64
src/powerd++.cpp, 197
src/sys/env.hpp, 204
                                                                contains_t, 67
src/sys/error.hpp, 205
                                                                contains_v, 68
src/sys/io.hpp, 206
                                                                feature, 67
src/sys/pidfile.hpp, 210
                                                                is_superset_of_t, 67
src/sys/signal.hpp, 212
                                                                is_superset_of_v, 69
src/sys/sysctl.hpp, 213
                                                                link, 68
src/types.hpp, 215
                                                                own, 68
src/utility.hpp, 216
                                                                ownership, 68
src/version.hpp, 218
                                                                read, 68
Standard I/O File Access, 23
                                                                seek, 68
str
                                                                write, 68
     sys::env::Var, 172
                                                           sys::io::contains, 65, 209
strcmp
                                                           sys::io::contains< set< Set ... >, Value >, 78
     anonymous_namespace{libloadplay.cpp}, 31
                                                           sys::io::enable_if< bool, T >, 86
Sum
                                                           sys::io::enable_if< false, T>, 87
                                                           sys::io::file, 65, 208
     utility::Sum< T>, 146
                                                           sys::io::file < link, Features ... >, 89
Svnc
     sys::ctl::Sync< T, SysctlT >, 148
                                                                file, 90, 91
                                                                get, 92
sys, 58
sys::ctl, 58
                                                                operator=, 92
     make_Once, 60
                                                           sys::io::file < own, Features ... >, 93
```

close, 96	sys::ctl, 62
file, 95, 96	sysctlbyname
get, 97	libloadplay.cpp, 188
operator=, 97	sysctlnametomib
release, 97	libloadplay.cpp, 188
sys::io::file_feature< FileT, read, Tail >, 100	SysctlOnce
getc, 102	sys::ctl, 60
gets, 102	sysctls
read, 103	anonymous_namespace{libloadplay.cpp}, 32
scanf, 104	anonymous_namespace{libloadplay.cpp}::Sysctls,
sys::io::file_feature< FileT, seek, Tail >, 105	160
rewind, 106	SysctlSync
seek, 106	sys::ctl, 60
tell, 108	SysctlValue
sys::io::file_feature< FileT, write, Tail >, 108	anonymous_namespace{libloadplay.cpp}::SysctlValue
flush, 110	162, 163
print, 110	SysctlValue::get < std::string >
printf, 111	anonymous_namespace{libloadplay.cpp}, 31
putc, 112	7 - 1 ( 1 7 11)
•	tell
write, 112, 113	sys::io::file_feature< FileT, seek, Tail >, 108
sys::io::file_feature< FileT, >, 98	temperature
eof, 99	clas, 51
error, 99	THZ
file_feature, 99	anonymous_namespace{clas.cpp}, 24
operator bool, 100	timing, 70
sys::io::is_superset_of, 66, 209	timing::Cycle, 81
sys::io::is_superset_of< LSetT, set< RSet > >, 120	operator(), 82, 83
sys::io::query, 66, 209	TJMAX_SOURCES
sys::io::query::contains_ftor, 79	constants, 52
all, 80	to_value
any, 80	utility, 73
operator(), 81	types, 70
sys::io::set, 66, 208	cptime_t, 71
sys::pid, 69	eptime_t, 71
sys::pid::error, 69, 211	Unit
sys::pid::Pidfile, 139	anonymous_namespace{clas.cpp}, 24
pfh, 140	unit
Pidfile, 140	anonymous_namespace{clas.cpp}, 25
write, 140	UnitStr
sys::sc_error< Domain >, 143	anonymous_namespace{clas.cpp}, 25
c_str, 143	UNKNOWN
operator int, 143	anonymous_namespace{clas.cpp}, 24
sys::sig, 69	anonymous_namespace{powerd++.cpp}, 43
sys::sig::error, 70, 213	update_freq
sys::sig::Signal, 144	anonymous_namespace{powerd++.cpp}, 46
Signal, 144	update_loads
Sysctl	anonymous_namespace{powerd++.cpp}, 47
sys::ctl::Sysctl< 0 >, 154	USAGE
sys::ctl::Sysctl < MibDepth >, 150	
sysctl	anonymous_namespace{loadplay.cpp}, 34
•	anonymous_namespace{loadrec.cpp}, 37
libloadplay.cpp, 187	anonymous_namespace{powerd++.cpp}, 44
sysctl_fail	usage
anonymous_namespace{powerd++.cpp}, 46	nih::Options< OptionT, DefCount >, 138
sysctl_get	utility, 71
sys::ctl, 61	countof, 72
sysctl_raw	sprintf, 72
sys::ctl, 62	sprintf_safe, 73
sysctl_set	to_value, 73

```
utility::Formatter < BufSize >, 114
    operator(), 114
utility::literals, 74
    operator""_fmt, 74
utility::Max < T >, 122
     Max, 123
    operator T const &, 123
     operator=, 124
utility::Min< T>, 127
     Min, 128
    operator T const &, 128
    operator=, 128
utility::Sum< T>, 145
    operator T const &, 146
    operator+=, 146
     Sum, 146
value
     anonymous_namespace{libloadplay.cpp}::SysctlValue,
Var
     sys::env::Var, 170
vars
    sys::env, 63
verbose
     anonymous_namespace{loadrec.cpp}, 38
     anonymous_namespace{powerd++.cpp}, 47
version, 74
     FREQ_TRACKING, 75
    LoadrecBits, 75
version::literals, 75
    operator""_FREQ_TRACKING, 76
     anonymous_namespace{libloadplay.cpp}, 32
write
     sys::io, 68
    sys::io::file\_feature < FileT, \ write, \ Tail \ \dots \ >, \ 112,
          113
    sys::pid::Pidfile, 140
```