

Encryption

CONFIDENTIAL

RC4-128 · permission flags · open and owner passwords

How It Works

PDF encryption (RC4-128, algorithm V=2 R=3) is applied as a post-processing pass after document assembly. The engine derives a 128-bit file encryption key from the password and permission flags, then encrypts all string literals and stream bytes in-place. Object offsets stay valid because RC4 is length-preserving.

API

Call `setEncryption` before `renderPdf` — the PDF bytes are then returned already encrypted.

Permissions only (no open password)

```
engine.setEncryption("", "s3cr3t", { print: false, copy: false })
```

File opens without prompting; cooperative viewers enforce the flags.

With open password

```
engine.setEncryption("password", "owner", { copy: false })
```

Viewers prompt for the user password before displaying content.

Permission Flags

Flag	Effect when disabled
<code>print</code>	Printing disabled in viewer
<code>copy</code>	Text and graphic extraction blocked
<code>modify</code>	Content modification blocked
<code>annotate</code>	Adding or modifying annotations blocked
<code>fill_forms</code>	Form field filling disabled
<code>assemble</code>	Page insertion, deletion, rotation blocked
<code>print_hq</code>	High-quality printing degraded to low resolution

Note on strength

Permission flags are advisory — cooperative viewers honour them, but tools such as `qpdf` can strip them in seconds when the open password is empty. They are a deterrent, not a lock. For strong access control, pair with an open password.