



SuperMike-III User Environment

Feng Chen
HPC User Services
LSU HPC & LSU
sys-help@LSU.org

Louisiana State University
Baton Rouge
July 28, 2022






Outline

- > Things to be covered in this section
 - SuperMike-III job queues
 - Job submission on SuperMike-III
 - Interactive and batch jobs using Slurm
 - Serial and parallel jobs
 - Monitor your jobs







SuperMike-III HPC User Environment


Overview of SuperMike-III

07/28/2022






Inside A Cluster Rack














Conceptual Relationship







Summary of SuperMike-III

- SuperMike-III is a 1.3 PetaFlop peak performance cluster with the latest CPUs from Intel and GPUs from NVIDIA, comprised of 183 compute nodes connected by 200 Gbps Infiniband fabric:
 - 171 regular nodes: two 32-core Intel Ice Lake CPUs, 256 GB RAM
 - 8 GPU nodes: two 32-core Intel Ice Lake CPUs, 256 GB RAM, four NVIDIA Tesla A100 GPUs
 - 4 bigmem nodes: two 32-core Intel Ice Lake CPUs, 2 TB RAM
- log in SuperMike-III with your current LSU HPC credentials using
 - ssh mike.hpc.lsu.edu
- Before you submit jobs on SuperMike-III, please make sure that you review the user guide here:
 - http://www.hpc.lsu.edu/docs/guides.php?system=SuperMike3
- The biggest difference SuperMIC users would notice on SuperMike-III is that, instead of Torque/Moab (PBS), Slurm is employed as the workload and resource manager.





SuperMike-III HPC User Environment

SuperMike-III Job Queues


07/28/2022





Cluster Environment

- Multiple compute nodes
- Multiple users
- Each user may have multiple jobs running simultaneously
- Multiple users may share the same node







Job submission basics

- 1. Find appropriate queue
- 2. Understand the queuing system and your requirements and proceed to submit jobs
- 3. Monitor jobs during execution





Job Queues (Partitions)

- Nodes are organized into queues. Nodes can be shared.
- Each job queue (partition) differs in
 - Number of available nodes
 - Max run time
 - Max running jobs per user
 - Nodes may have special characteristics: GPU, Large memory, etc.
- > Jobs need to specify resource requirements
 - Nodes, time, queue
- It's called a queue for a reason, but jobs don't run on a "First Come First Served" policy,
 - This will be detailed in later slides



Queue Characteristics – LSU clusters

Machine	Queue	Max Runtime (h)	ppn	Max nodes per job
SuperMIC	workq	72		128
	checkpt	12	20	256
	single	168	1,2,4,6,8	1
	bigmem	72	48	1
Machine	Partition	Max Runtime (h)	cores per node	Max nodes per job
	workq	72	64	96
SuperMike-III	checkpt	72 64		96
	single	168	64	1
	gpu	72	64	4
	bigmem	72	64	1

[❖] By default, you job will be submitted to "single" queue (partition).





Queue Characteristics

"sinfo" will give you more info on the queues

[fchen14@mike2 slurmdoc]\$ sinfo **PARTITION AVAIL TIMELIMIT** NODES STATE NODELIST admin infinite 4 mix mike[001-003,192] up admin infinite **197** idle mike[004-190,193-202] up infinite down mike191 admin 1 up single* up 3-00:00:00 mix mike[001-003,192] 4 single* idle mike[004-190] up 3-00:00:00 187 single* down mike191 up 3-00:00:00 1 checkpt mix mike[001-003,192] up 3-00:00:00 4 checkpt idle mike[004-190] 3-00:00:00 187 checkpt up 3-00:00:00 1 down mike191 workq up 3-00:00:00 mix mike[001-003,192] 4 workq up 3-00:00:00 187 idle mike[004-190] workq up 3-00:00:00 down mike191 1 3-00:00:00 idle mike[193-200] gpu 8 bigmem up 3-00:00:00 2 idle mike[201-202]





Queue Querying – Linux Clusters

Displays information about active, eligible, blocked, and/or recently completed jobs: showq command

ACTIVE DOBID	JOBS JOBNAME	USERNAME	STATE	CORE	REMAINING	STARTTIME
					=======	
4896	cellranger	lyan1	Running	64	21:42:43	Tue Jul 26 14:55:23
4924	bash	fchen14	Running	64	11:05:50	Tue Jul 26 16:18:30
4946	xhpcg_skx	lyan1	Running	2048	11:33:16	Tue Jul 26 16:45:56
4956	supernova.	lyan1	Running	64	23:42:50	Tue Jul 26 16:55:30
4964	test	yexu	Running	64	3:52:34	Tue Jul 26 17:05:14
4968	gmx_mpi	lyan1	Running	128	11:59:19	Tue Jul 26 17:11:59
4969	bash	lyan1	Running	64	11:59:41	Tue Jul 26 17:12:21
•	7 active jobs					
Total 1	ohs• 7 Ac	tive lobs: 7	Tdle '	lohs: 0	Blocke	d Johs • 0





SuperMike-III HPC User Environment

Job Submission Through Slurm

07/28/2022





PBS to Slurm

Why Slurm?

- Slurm has a more open model
- Slurm also feels more modern in its design and implementation
- Slurm scales well, job starts faster, etc.

What will we cover in this session?

- Basic Slurm job submission
 - Interactive job
 - Batch job





Two Job Types

Interactive job

- User can interact with the terminal on the compute node.
- Interactive jobs can be used for testing and troubleshooting code.
- Requesting an interactive job will allocate resources and log you into a shell on a compute node.

> Batch job


- Executed without user intervention using a job script
- Batch jobs are used for production runs.
- Requesting an interactive job will allocate resources and execute the job commands in a non-interactive shell





Slurm Interactive Job Command

To start an interactive job, use the srun command like the example below:







Check Available Allocations

```
[fchen14.fchen14-t460] ➤ ssh fchen14@mike.hpc.lsu.edu
Send questions and comments to the email ticket system at sys-help@loni.org.
SuperMike-3 at LSU (Open in friendly user mode)
17-May-2022
SuperMike-3 is a 1.3 PetaFlop peak performance cluster with 11,712 CPU cores,
... Message Of The Day...
[fchen14@mike1 ~]$ showquota
User filesystem quotas for fchen14 (uid 32584):
                                        files
                                                 fquota
    Filesystem
                   MB used
                              quota
    /homem
                      433
                              10000
                                        21532
    /work /project
                    302299
                                       2325239
                                                4000000
Storage allocation
                   MB used
                                        files
                                              expiration
                              quota
    sa fchen14
                                              2000-01-01
CPU Allocation SUs:
                     remaining allocated
                                        expiration
   hpc_hpcadmin8:
                     393715.16
                              2000000.00
                                        2022-07-01
   hpc_train_2022:
                      49301.54
```





Start an Slurm Interactive Job

```
[fchen14@mike1 ~]$ srun --x11 -t 1:00:00 -n8 -N1 -p single -A hpc_train_2022 --pty /bin/bash srun: Job is in held state, pending scheduler release srun: job 4799 queued and waiting for resources

Interactive job 4799 running:
srun: job 4799 has been allocated resources

[fchen14@mike156 ~]$ hostname
mike156

[fchen14@mike156 ~]$ some job commands # your own job commands
```





Slurm Environmental Variables

```
[fchen14@mike2 slurmdoc]$ srun --x11 -t 1:00:00 -n8 -N1 -p single -A
LSU LSUadmin1 --pty /bin/bash
[fchen14@mike156 slurmdoc]$ echo $SLURM
$SLURM CLUSTER NAME
                              $SLURM JOB NAME
$SLURM NPROCS
                              $SLURM STEP NODELIST
$SLURM_CPU_BIND
                              $SLURM JOB NODELIST
$SLURM NTASKS
                              $SLURM STEP NUM NODES
$SLURM CPU BIND LIST
                              $SLURM JOB NUM NODES
$SLURM_PRIO_PROCESS
                              $SLURM_STEP_NUM_TASKS
$SLURM CPU BIND TYPE
                              $SLURM JOB PARTITION
$SLURM PROCID
                              $SLURM_STEP_TASKS_PER_NODE
$SLURM JOB GID
                              $SLURM NNODES
$SLURM STEPID
                              $SLURM TOPOLOGY ADDR PATTERN
$SLURM JOBID
                              $SLURM NODEID
$SLURM STEP ID
                              $SLURM UMASK
$SLURM JOB ID
                              $SLURM NODELIST
$SLURM STEP LAUNCHER PORT
                              $SLURM WORKING CLUSTER
```





Slurm Batch Job Script

- To create a batch Slurm script, use your favorite editor (e.g. vi or emacs, nano) to create a text file with both Slurm instructions and commands how to run your job.
- > All Slurm directives (special instructions) are prefaced by the #SBATCH.

```
#!/bin/bash
                                                                        Tells the job
#SBATCH -N 1 # request one node
#SBATCH -t 2:00:00 # request two hours
                                                                        scheduler how much
#SBATCH -p single # in single partition (queue)
                                                                        resource you need.
#SBATCH -A your allocation name
#SBATCH -o %x-%j.out-%N # optional, name of the stdout, using the job number (%j) and the
hostname of the node (%N)
#SBATCH -e %x-%j.err-%N # optional, name of the stderr, using job and hostname values
# below are job commands
date
cd /work/$USER/myjob
                                                                        How will you
./mydemo
# Mark the time it finishes.
                                                                        use the
date
                                                                         resources?
# exit the job
```

exit 0





Common Slurm Switches

- #SBATCH -A allocation_name:
 - short for --account, charge jobs to your allocation named allocation_name.
- #SBATCH -N <number_of_nodes>:
 - short for --nodes, number of nodes on which to run.
- #SBATCH -n <number_of_cores/processes>:
 - short for --ntasks, number of tasks (CPU cores) to run job on. The memory limit for jobs is 4 GB of MEM per CPU core requested.
- #SBATCH -c <cores_per_process>:
 - short for --ncpus-per-task, number of threads per process.
- #SBATCH -p partition:
 - short for --partition, submit job to the partition queue. Allowed values for partition:
 single, checkpt, workq, gpu, bigmem. Depending on cluster (use sinfo command)
- #SBATCH -t hh:mm:ss:
 - short for --time, request walltime.
- #SBATCH -o filename.out:
 - short for --output, write standard output.
- #SBATCH -e filename.err:
 - short for --error, write standard error.
 - Note that by default, Slurm will merge standard error and standard output.





Submit Slurm Batch Job

To submit the above job to the scheduler, save the above script as a text file, e.g., singlenode.sh, then use the sbatch command to submit, the output will be something like the below:

```
[fchen14@mike2 slurmdoc]$ sbatch singlenode.slm
Submitted batch job 37355 estimates 9 SUs from allocation LSU_train_2020.
Estimated remaining SUs: 37352
See running job information with: scontrol show job 37355
```

To check the status of your job use the squeue command:

```
[fchen14@mike2 slurmdoc]$ squeue -u $USER
                                  USER ACCOUNT
JOBID PARTITION
                  005
                         NAME
                                                                          TIME
                                                     STATE
                                                           PRIORITY
SUBMIT TIM TIME LIMI NODES CPUS MIN MEMORY NODELIST(REASON)
                    checkpt normal batch.sl fchen14 LSU tra
            37480
                                                              RUNNING
       0:06 2020-09-18
                        1:00:00
1
                                     2
                                           96 3958M mike[161-162]
```





Common Slurm Commands (1)

- squeue is used to show the partition (queue) status. Useful options:
 - u <username>: limit output to jobs by username --state=pending: limit output to pending (i.e. queued) jobs --state=running: limit output to running jobs
 - Below is an example to query all jobs submitted by current user (fchen14)

```
[fchen14@mike2 slurmdoc]$ squeue -u fchen14

JOBID PARTITION NAME USER ST TIME_LIMIT TIME CPUS NODES NODELIST(REASON)
37876 workq hybrid_job fchen14 CF 5:00 0:04 96 2 mike[005-006]
```





Common Slurm Commands (2)

sinfo is used to view information about Slurm nodes and partitions.

```
[fchen14@mike156 ~]$ sinfo
PARTITION AVAIL
                 TIMELIMIT
                            NODES
                                   STATE NODELIST
admin
                  infinite
                                   inval mike[147,175]
             up
                                2
admin
                 infinite
                                    comp mike183
                                1
             up
admin
                 infinite
                                     mix mike156
                                1
             up
admin
                 infinite
                              178
                                    idle mike[001-146,148-155,157-174,176-181]
             up
admin
                  infinite
                                1
                                    down mike182
             up
single*
            up 7-00:00:00
                                1 inval mike147
single*
                                1
                                     mix mike156
            up 7-00:00:00
single*
            up 7-00:00:00
                                    idle mike[001-146,148-155,157-171]
                              169
checkpt
                                   inval mike147
            up 3-00:00:00
checkpt
             up 3-00:00:00
                                1
                                     mix mike156
checkpt
             up 3-00:00:00
                              169
                                    idle mike[001-146,148-155,157-171]
workq
                                   inval mike147
             up 3-00:00:00
workq
             up 3-00:00:00
                                1
                                     mix mike156
workq
                                    idle mike[001-146,148-155,157-171]
             up 3-00:00:00
                              169
bigmem
                                   inval mike175
             up 3-00:00:00
                                1
bigmem
             up 3-00:00:00
                                    idle mike[172-174]
                                3
                                    comp mike183
             up 3-00:00:00
                                1
gpu
             up 3-00:00:00
                                6
                                    idle mike[176-181]
gpu
             up 3-00:00:00
                                    down mike182
                                1
gpu
```





Common Slurm Commands (3)

scancel is used to signal or cancel jobs. Typical usage with squeue.

```
[fchen14@mike1 ~]$ squeue -u fchen14
            JOBID PARTITION
                               NAME
                                        USER ST
                                                      TIME
                                                            NODES NODELIST(REASON)
              341
                    checkpt
                            bash fchen14 R
                                                      0:13
                                                                1 mike001
              340
                    checkpt
                            bash fchen14 R
                                                   1:50:57
                                                                1 mike002
# cancel (delete) job with JOBID 340
[fchen14@mike1 ~]$ scancel 340
# job status might display a temporary "CG" ("CompletinG") status immediately after
scancel
[fchen14@mike1 ~]$ squeue -u fchen14
            JOBID PARTITION
                               NAME
                                        USER ST
                                                      TIME
                                                            NODES NODELIST(REASON)
                            bash fchen14 CG
                                                                1 mike002
              340
                    checkpt
                                                   1:51:08
                    checkpt
                            bash fchen14 R
                                                                1 mike001
              341
                                                      0:41
[fchen14@mike1 ~]$ squeue -u fchen14
            JOBID PARTITION
                               NAME
                                        USER ST
                                                            NODES NODELIST(REASON)
                                                      TIME
                            bash fchen14 R
              341
                    checkpt
                                                      1:08
                                                                1 mike001
```





Common Slurm Commands (4)

scontrol is used to view or modify Slurm configuration and state. Typical usage for the user is to check job status:

```
[fchen14@mike1 ~]$ squeue -u fchen14 # show all jobs
             JOBID PARTITION
                                 NAME
                                                        TIME NODES NODELIST(REASON)
                                          USER ST
                                                                  1 mike001
               341
                     checkpt
                                 bash fchen14 R
                                                     1:29:20
[fchen14@mike1 ~]$ scontrol show job 341
JohTd=341 JohName=bash
  UserId=fchen14(32584) GroupId=Admins(10000) MCS label=N/A
  Priority=1 Nice=0 Account=hpc hpcadmin6 QOS=normal
   JobState=RUNNING Reason=None Dependency=(null)
   ... some details omitted...
  MinCPUsNode=1 MinMemoryNode=22332M MinTmpDiskNode=0
  Features=(null) DelayBoot=00:00:00
  OverSubscribe=NO Contiguous=0 Licenses=(null) Network=(null)
  Command=/bin/bash
  WorkDir=/home/fchen14/test
  Power=
```





- Serial Jobs
- Parallel Jobs
 - SMP (Shared Memory Parallelism)
 - OpenMP
 - Python's Multiprocessing
 - Pthread
 - R's mcapply
 - MPI
 - Hybrid





Serial Job Script Template

```
#!/bin/bash
#SBATCH --job-name=serial_job_test # Job name
#SBATCH --ntasks=1
                                     # Using a single core
#SBATCH --time=00:10:00 # Time limit hh:mm:ss
#SBATCH --output=%x_%j.log # Standard output and error log,
                            # %x: job name
                            # %j: job-id
module load python
echo "Running job on a single CPU core"
date
/home/user/single core job.py
date
```



Shared Memory Parallelism (SMP) Jobs

- Shared-Memory Parallelism (SMP) is when workload is shared among different CPU cores using multiple threads or processes running within a single compute node and these cores have access to common (shared) memory.
 - SMP jobs cannot make use of multiple nodes and all the cores must be physically located the same node.
 - When running SMP jobs, you must make the SMP application aware of how many cores to use.
 - How that is done depends on the specific type of application. Typical examples:
 - OpenMP (Open Multi-Processing)
 - First set --ntasks=1, and then set OMP_NUM_THREADS to a value less than or equal to the number of cpus-per-task
 - Pthreads
 - · Python's multiprocessing module
 - R's mcapply





SMP Job Script (OpenMP Based)

```
#!/bin/bash
#SBATCH --job-name=smp job
                                     # Job name
#SBATCH --nodes=1
                                     # Run all processes on a single node
#SBATCH --ntasks=1
                                     # Run a single task
                                     # Number of CPU cores per task
#SBATCH --cpus-per-task=8
                                     # Time limit hh:mm:ss
#SBATCH --time=00:10:00
#SBATCH --output=%x %j.log
                                     # Standard output and error log
date
# use this line if your job uses OpenMP
export OMP NUM THREADS=$Slurm CPUS PER TASK
/home/user/smp job.out
date
```



MPI (Message Passing Interface) Job

- According to Slurm documentation (https://slurm.schedmd.com/mpi_guide.html), "there are three fundamentally different modes of operation used by various MPI implementation with Slurm:
 - "Slurm directly launches the tasks and performs initialization of communications through the PMI2 or PMIx APIs. (Supported by most modern MPI implementations.)
 - Use mpirun launches tasks using Slurm's infrastructure (not using PMIx).
 - Slurm creates a resource allocation for the job and then mpirun launches tasks using some mechanism other than Slurm." (We do not recommend HPC/LSU users use this method to launch their MPI jobs.)"





MPI Job - (PMIx Versions)

➤ If you compiled your MPI application using our default mvapich2 libraries (which is compiled with PMIx enabled), you should start the application directly using the srun command.

```
#!/bin/bash
#SBATCH --job-name=mpi job test # Job name
#SBATCH --partition=workq
                                    # For jobs using more than 1 node, submit to workq
#SBATCH --nodes=2
                                    # Number of nodes to be allocated
#SBATCH --ntasks=96
                                    # Number of MPI tasks (i.e. processes/cores)
#SBATCH --time=00:05:00
                                    # Wall time limit (hh:mm:ss)
#SBATCH --output=%x %j.log # Standard output and error
echo
echo "Slurm Nodes Allocated
                                    = $Slurm JOB NODELIST"
                                    = $Slurm JOB NUM NODES"
echo "Number of Nodes Allocated
                                    = $Slurm NTASKS"
echo "Number of Tasks Allocated
module load mvapich2/2.3.3/intel-19.0.5
srun -n $SLURM NTASKS ./a.out
```





MPI Job - (Non-PMIx Versions)

If your MPI application did not use our default module key mvapich2/2.3.3/intel-19.0.5, you should start the application using the mpirun command.

```
#!/bin/bash
#SBATCH --job-name=mpi job test
                                    # Job name
#SBATCH --partition=workq
                                    # For jobs using more than 1 node, submit to workq
#SBATCH --nodes=2
                                    # Number of nodes to be allocated
#SBATCH --ntasks=96
                                    # Number of MPI tasks (i.e. processes/cores)
#SBATCH --time=00:05:00
                                    # Wall time limit (hh:mm:ss)
#SBATCH --output=mpi test %j.log
                                    # Standard output and error
echo ""
echo "Slurm Nodes Allocated
                                    = $Slurm JOB NODELIST"
                                    = $Slurm JOB NUM NODES"
echo "Number of Nodes Allocated
echo "Number of Tasks Allocated
                                    = $Slurm NTASKS"
module load mvapich2/2.3.3/intel-19.0.5-hydra
mpirun -n $Slurm NTASKS ./a.out
```





Hybrid (MPI + SMP) Job

Hybrid jobs are MPI applications where each MPI process is multithreaded and can use multiple cores across multiple nodes. If the MPI implementation is compiled with PMIx enabled, use the srun command to start the hybrid job, otherwise, use the mpirun command to start it.

```
#!/bin/bash
#SBATCH --partition=workq
                                    # Need to submit workq for multiple node jobs
                                    # Maximum number of nodes to be allocated
#SBATCH --nodes=2
#SBATCH --ntasks=4
                                    # Number of MPI tasks (i.e. processes)
#SBATCH --cpus-per-task=24
                                    # Number of cores per MPI task
                                    # Wall time limit (hh:mm:ss)
#SBATCH --time=00:05:00
#SBATCH --output=hybrid_test_%j.log # Standard output and error file
echo "Number of Nodes Allocated
                                    = $Slurm JOB NUM NODES"
                                    = $Slurm NTASKS"
echo "Number of Tasks Allocated
echo "Number of Cores/Task Allocated = $Slurm CPUS PER TASK"
module load mvapich2/2.3.3/intel-19.0.5
# PMIx version
srun -n $Slurm NTASKS -c $Slurm CPUS PER TASK ./a pmix.out
# Non-PMIx version
module swap mvapich2/2.3.3/intel-19.0.5 mvapich2/2.3.3/intel-19.0.5-hydra
export OMP NUM THREADS=$Slurm CPUS PER TASK
mpirun -n $Slurm NTASKS ./a hydra.out
```





Inspect Job Results

Check job standard output/standard error by inspecting the redirected files:

```
[fchen14@mike2 slurmdoc]$ cat hybrid test 37723.log
Date
                 = Tue Sep 22 15:37:44 CDT 2020
                 = mike001
Hostname
Working Directory = /home/fchen14/slurmdoc
Number of Nodes Allocated = 2
Slurm Nodes Allocated = mike[001-002]
Number of Tasks Allocated
                              = 4
Number of Cores/Task Allocated = 24
Loading mvapich2/2.3.3/intel-19.0.5
 Loading requirement: intel/19.0.5
Autoloading hdf5/1.10.6/intel-19.0.5-mvapich-2.3.3
Autoloading fftw/3.3.8/intel-19.0.5-mvapich-2.3.3
Autoloading netcdf-c/4.7.3/intel-19.0.5-mvapich-2.3.3
```





SuperMike-III HPC User Environment

Job Monitoring





Job Monitoring on SuperMike-III

Check details on your job using qstat

```
$ squeue -u $USER : For quick look at nodes assigned to you
$ scontrol show job <jobid> : For details on your job
$ scancel jobid : To delete job
```

Check memory usage of your job using qshow

```
$ qshow jobid
```

Please pay close attention to the load and the memory consumed by your job!





Using the "top" command

The top program provides a dynamic real-time view of a running system.

```
top - 23:30:16 up 51 days, 16:18, 4 users, load average: 0.16, 0.05, 0.06
Tasks: 692 total, 2 running, 690 sleeping, 0 stopped, 0 zombie
%Cpu(s): 1.1 us, 1.0 sy, 0.0 ni, 97.9 id, 0.0 wa, 0.0 hi, 0.0 si, 0.0 st
KiB Mem : 19647060+total, 18699553+free, 8677504 used, 797560 buff/cache
KiB Swap: 13421772+total, 13405440+free, 163328 used. 18702988+avail Mem
```

PTD USFR	PR	NT	VTRT	RES	SHR S	%СРП	%MFM	TTMF+	COMMAND
208754 fchen14	20	0	7731040	5.5g	20108 R	100.0	2.9	0:16.50	lmp
208999 fchen14	20	Ø	172868	2948	1624 R	0.7	0.0	0:00.07	top
1 root	20	0	191624	2832	1544 S	0.0	0.0	21:18.21	systemd
2 root	20	0	0	0	0 S	0.0	0.0	0:04.81	kthreadd
4 root	0	-20	0	0	0 S	0.0	0.0	0:00.00	kworker/0:0H
6 root	20	0	0	0	0 S	0.0	0.0	1:06.85	ksoftirqd/0



Check memory Usage for Multi-Node Job

Check health of your job using qshow \$ qshow <jobid>

```
[fchen14@mike2 slurmdoc]$ sbatch ex lmp hybrid.sh
Submitted batch job 37888 estimates 8 SUs from allocation LSU LSUadmin1.
Estimated remaining SUs: 521696
JOBID
          NAME
                              PARTITION
                                         TIME LIMIT
                                                     ST
                                                         CPUS
                                                               NODES
                                                                       REASON
          hybrid job test workq
                                                     PD
37888
                                          5:00
                                                          96
                                                                       None
[fchen14@mike2 slurmdoc]$ qshow 37888
PBS job: 37888, nodes: 2
Hostname Days Load CPU U# (User:Process:VirtualMemory:Memory:Hours)
mike005
              0 Autoloading 211 6 fchen14:lmp:5847M:3.2G fchen14:lmp:5846M:3.3G
fchen14:slurm scr+:113M:2M fchen14:srun:388M:5M fchen14:srun:50M:1M
mike006
              0 Autoloading 216  3 fchen14:lmp:5870M:5.1G fchen14:lmp:4447M:3.3G
PBS job=37888 user=fchen14 allocation=LSU LSUadmin1 queue=workq total load=0.00
cpu hours=0.00 wall hours=0.00 unused nodes=0 total nodes=2 ppn=48 avg load=0.00
avg cpu=213% avg mem=7640mb avg vmem=11746mb
top proc=fchen14:lmp:mike006:5870M:5.1G:0.0hr:105% node processes=3
```






Pay attention to single queue usage

- Single queue Used for jobs that will only execute on a single node, i.e. -N1 -n1-63.
- > Jobs in the single queue should not use:
 - More than 3GB memory per core for QB2 (64G/20).
 - More than 4GB memory per core for SuperMike-III (192G/48).
- ➢ If applications require more memory, scale the number of cores (--ntasks) to the amount of memory required: i.e. max memory available for jobs in single queue is 16GB for --ntasks 4 on SuperMike-III.





Core and Memory in Single queue



Question:

On SuperMIC, if my job needs 17GB memory, what -ppn value should I use?

On SuperMike-III, if my job needs 17GB memory, what --ntasks (-n) value should I use?





Short Summary

- How to check queue (partition) information in slurm?
- How to submit Slurm interactive job?
- How to submit Slurm batch job?
 - SMP (OpenMP)
 - MPI
 - Hybrid
- Monitor your job?
- Questions?





Next Sessions

- **>** 11:30 12:30
 - Performance benchmarks and tuning
- **>** 12:30 02:00
 - Lunch break
- **>** 02:00 04:00
 - Q&A + On-ramp sessions (breakout sessions)