Lab2实验报告

姓名: 谭栋泽

学号: 23336011

Lab2实验报告

实验结果实验过程

LVT向量操作 时钟中断 串口中断

实验结果

正确实现xapic, 并且实现时钟中断后, 第一次查看到信息

```
) jysos_kernel::memory: Free Usable Memory: 45.020 MiB
) jysos_kernel::memory: Frame Allocator initialized.
) jysos_kernel: Interrupts Enabled.
) jysos_kernel: YatSenOS initialized.
) jysos_kernel: Hello World from YatSenOS v2!
) jysos_kernel: Hello World from YatSenOS v2!
) jysos_kernel::interrupt::clock: clock interrupt #1
) jysos_kernel: Hello World from YatSenOS v2!
) jysos_kernel: Hello World from YatSenOS v2!
```

解决自旋锁错误占用导致info忽略的神秘问题(实验过程有),成功实现串口输入和中断显示

```
[INFO] ysos_kernel: YatSenOS initialized.
[INFO] ysos_kernel::interrupt::clock: Tick! @1
Received data from serial:[ 11111]
111]ived data from serial:[ ä½ å¥½
Received data from serial:[ 1111111113342443]
Received data from serial:[ helllo]
Received data from serial:[ h]
Received data from serial:[ ]
Received data from serial:[ ]
Received data from serial:[ ]
```

成功input用户输入,输入过程可以正确回显和退格

```
v0.2.0
[+] Serial Initialized.
[INFO ] ysos_kernel::utils::logger: Logger Initialized.
[INFO] ysos_kernel::memory::address: Physical Offset : 0xffff8000000000000
[INFO ] ysos_kernel::memory::gdt: Privilege Stack : 0xffffff0000014398-0xffffff0000015398
[INFO] ysos kernel::memory::gdt: interrupt Stack : 0xffffff0000015398-0xffffff0000016398
[INFO] ysos kernel::memory::gdt: Kernel IST Size : 12.000 KiB
[INFO ] ysos_kernel::memory::gdt: GDT Initialized.
[INFO ] ysos_kernel::memory::allocator: Kernel Heap Size : 8.000 MiB
[INFO ] ysos_kernel::memory::allocator: Kernel Heap Initialized.
[INFO ] ysos kernel::interrupt: Interrupts Initialized.
[INFO ] ysos kernel::memory: Physical Memory
                                             : 95.625 MiB
[INFO ] ysos kernel::memory: Free Usable Memory: 45.016 MiB
[INFO ] ysos kernel::memory: Frame Allocator initialized.
[INFO ] ysos kernel: Interrupts Enabled.
[INFO ] ysos kernel: YatSenOS initialized.
> 11111
You said: 11111
> hello yatos
You said: hello yatos
> exit
[INFO ] ysos_kernel: YatSenOS shutting down.
```

实验过程

一些实验中遇到的问题和思考

LVT向量操作

其实就是操作一大堆表示配置信息的二进制位,构造正确的配置,写入正确的位置。

那就要一大堆二进制运算, 本来我是打算这样实现的

```
1 | bitflags! {
2
       /// LVT (Local Vector Table) flags
3
       struct LvtFlags: u32 {
4
           const MASKED = 1 \ll 16;
                                   // 中断屏蔽位
           const LEVEL_TRIGGERED = 1 << 15; // 电平触发(vs边沿触发)
5
6
           const ACTIVE_LOW = 1 << 13; // 低电平有效(vs高电平)
7
           const DELIVERY_STATUS = 1 << 12; // 传送状态
8
           const VECTOR = 0xFF; // 中断向量号
9
       }
10 }
```

这部分参考代码是这样, 感觉比它好一点, 多一层封装

```
1  let mut lvt_timer = self.read(0x320);
2  // clear and set Vector
3  lvt_timer &= !(0xFF);
4  lvt_timer |= Interrupts::IrqBase as u32 + Irq::Timer as u32;
5  lvt_timer &= !(1 << 16); // clear Mask
6  lvt_timer |= 1 << 17; // set Timer Periodic Mode
7  self.write(0x320, lvt_timer);</pre>
```

但感觉用起来还是很奇怪,既然rust都零成本抽象了,我为什么一定要这样做呢,我开始尝试更面向对象一点。

我们直接定义一个编辑器

```
impl LVT_Editor {
1
        pub fn new() -> Self {
2
 3
            LVT_Editor { data: 0 }
 4
        }
 5
 6
        pub fn with_data(data: u32) -> Self {
 7
            LVT_Editor { data }
 8
        }
 9
10
        pub fn bits(&self) -> u32 {
11
            self.data
12
        }
13
14
        // 终端屏蔽
15
        pub fn write_masked(mut self, masked: bool) -> Self {
            if masked {
16
17
                self.data |= LvtFlags::MASKED.bits();
            } else {
18
19
                self.data &= !LvtFlags::MASKED.bits();
20
            }
21
            self
22
        }
23
24
        // 设置电平触发
25
        pub fn write_level_triggered(mut self, level_triggered: bool) -> Self {
            if level_triggered {
26
27
                self.data |= LvtFlags::LEVEL_TRIGGERED.bits();
28
29
                self.data &= !LvtFlags::LEVEL_TRIGGERED.bits();
            }
30
31
            self
32
        }
33
        // 设置低电平有效
34
35
        pub fn write_active_low(mut self, active_low: bool) -> Self {
36
            if active_low {
37
                self.data |= LvtFlags::ACTIVE_LOW.bits();
38
39
                self.data &= !LvtFlags::ACTIVE_LOW.bits();
            }
40
            self.
41
42
        }
43
        // 设置中断向量号
44
        pub fn write_vector(mut self, vector: u32) -> Self {
45
46
            self.data &= !LvtFlags::VECTOR.bits(); // 清除原有向量
            self.data |= vector & LvtFlags::VECTOR.bits(); // 设置新向量
47
            self
48
49
        }
50
```

```
51 }
52
```

那它用起来应该是这样的

```
self.write(APIC_LVT_TIMER, LVT_Editor::new()

.write_masked(false) // 禁用计时器中断

.write_level_triggered(false) // 边沿触发

.write_active_low(false) // 高电平有效

.write_vector(Interrupts::IrqBase as u32 + Irq::Timer as u32)// 设置处理 set Timer Periodic Mode

.write_bit(17, true)

.bits());
```

哦很好,可读性比一堆位运算好太多,至少看起来这样。

你可以直观看到这三个版本的代码比较

```
// 3. 禁用逻辑中断线 (LINT0, LINT1)
self.write(reg: APIC_LVT_LINT0, value: LVT_Editor::new().write_masked(true).bits());
self.write(reg: APIC_LVT_LINT1, value: LvtFlags::MASKED.bits());
self.write(reg: 0x350, value: 1 << 16); // set Mask
```

我觉得第一种更好,更进一步,甚至可以把几个子类型都实现了, 这里只抽取公共部分抽象,所以仍然 存在write_bit这种本身没有实际含义的操作。没有过分的抽象, 有需求可以友好重构,这是一种折中的 编程方法。

时钟中断

这个地方由于多线程安全,必须用原子操作,因为存在一个用于时钟计数的静态变量

```
extern "x86-interrupt" fn clock_interrupt_handler(_stack_frame:
    InterruptStackFrame) {
2
        // 使用原子操作
 3
        static COUNTER: AtomicUsize = AtomicUsize::new(0);
4
 5
        let count = COUNTER.fetch_add(1, Ordering::Relaxed);
6
7
        // 偶尔输出一次
8
        if count % 1 == 0 {
9
            info!("Clock interrupt #{}", count + 1);
10
        }
11
12
        // 确认中断
13
        crate::interrupt::ack();
14
   }
```

改成和教程差不多的结构

```
x86_64::instructions::interrupts::without_interrupts(|| {
 5
            if inc\_counter() \% 0x10 == 0 {
 6
                info!("Tick! @{}", read_counter());
 7
            }
 8
            super::ack();
 9
        });
10
    }
11
12
13
    // FIX-ME
    #[inline]
14
15
    pub fn read_counter() -> usize {
        COUNTER.load(Ordering::Relaxed)
16
17
    }
18
19
    #[inline]
    pub fn inc_counter() -> usize {
20
        COUNTER.fetch_add(1, Ordering::Relaxed)
21
22
    }
```

串口中断

出现double fault错误,初步认定是IDT设置错误,然后发现忘记注册串口中断处理了

```
1 | serial::register_idt(&mut idt);
```

当前的串口实现

```
pub unsafe fn register_idt(idt: &mut InterruptDescriptorTable) {
 2
        idt[Interrupts::IrqBase as u8 + interrupt::Irq::Serial0 as u8]
 3
            .set_handler_fn(serial_interrupt_handler);
 4
    }
 5
 6
 7
    extern "x86-interrupt" fn serial_interrupt_handler(_stack_frame:
    InterruptStackFrame) {
 8
        // 处理串口中断
9
10
        let mut serial = get_serial_for_sure();
11
        print!("Received data from serial:[ ");
        while let Some(byte) = serial.receive() {
12
            print!("{}", byte);
13
14
15
        println!("]");
16
17
        // 确认中断
18
        crate::interrupt::ack();
19
    }
```

哦! 我突然醒悟,这个地方应该是正确中断了,也正确print了, 但是print的锁被我占用了, 它获取不 到锁,自动忽略了输出,导致最后什么也没有发生。

找到原因就很容易解决了,利用rust的语法特性?把用到锁的位置包裹起来,等用完会被自动回收。

```
extern "x86-interrupt" fn serial_interrupt_handler(_stack_frame: InterruptStackFrame) {

// 处理串口中断

x86_64::instructions::interrupts::without_interrupts(|| {

print!("Received data from serial:[ ");
loop

{
 let result: Option<u8>;
 {
 let mut serial: MutexGuard<'_, SerialPort> = get_serial_for_sure();
 result = serial.receive();
 }
 if let Some(byte: u8) = result {
 print!("{}", byte as char);
 } else {
 break;
 }
 }
 println!("]");
 super::ack();
 });
}
```

那只后要写的东西就比较显然了, 缓冲区缓冲一下。

```
pub extern "x86-interrupt" fn serial_interrupt_handler(_st:
    InterruptStackFrame) {
 2
        receive();
 3
        super::ack();
 4
    }
 5
   /// Receive character from uart 16550
 6
 7
    /// Should be called on every interrupt
8
    fn receive() {
9
        // FIX-ME: receive character from uart 16550, put it into INPUT_BUFFER
        let result;
10
11
12
            let mut serial = get_serial_for_sure();
13
            result = serial.receive();
14
       }
        if let Some(key) = result {
15
16
            input::push_key(key);
            print!("{}", key as char);
17
18
        } else {
19
        }
20 }
```

这样还不能正确回显退格,改进一下

我们在这里处理, 又直接回到串口确实有点不太好了

```
1
      pub fn push_key(key: Key) {
  2
          if INPUT_BUF.push(key).is_err() {
  3
              warn!("Input buffer is full. Dropping key '{:?}'", key);
  4
          }else{
              match key {
  5
                  b'\n' => {
  6
  7
                      if let Some(mut serial) = get_serial() {
  8
                          serial.send(b'\n');
  9
                      }}
                  b'\r' => {
 10
 11
                      if let Some(mut serial) = get_serial() {
 12
                          serial.send(b'\n');
 13
                      }}
 14
                  // 退格键 (Backspace: 0x08, Delete: 0x7F)
 15
                  0x08 \mid 0x7F \Rightarrow \{
 16
                          if let Some(mut serial) = get_serial() {
 17
                              serial.backspace();
 18
                          }}
 19
                  key if key >= 32 && key <= 126 => {
                      if let Some(mut serial) = get_serial() {
 20
 21
                          serial.send(key);
 22
                      }
 23
                  }
 24
                  _ => {
 25
                  }
 26
 27
 28
              // println!("Key pushed: {}", key as char);
 29
          }
 30 }
```

非常好,可以正确回显,包括退格和换行, getline也应该可以正常接入接下来把用户交互的代码复制进去,就可以正常运行。