# **Propainter Development**

#### Yanglin ZHANG

2024-10-03

# Task 1: Deploy gradio

### **Development Environment**

Clone the repository by running the following command:

```
git clone git@github.com:lucky9-cyou/ProPainter.git
```

Download the <u>propainter</u> checkpoints and <u>SAM</u> checkpoints. For SAM, we use the sam\_vit\_h\_4b8939.pth checkpoint.

Install the development environment by running the following commands:

```
# create new anaconda env
conda create -n propainter python=3.8 -y
conda activate propainter
# install pytorch
conda install pytorch torchvision torchaudio pytorch-cuda=11.8 -c pytorch -c
nvidia
# intall tensortrt for cuda 11.8
wget https://developer.nvidia.com/downloads/compute/machine-learning/tensorrt/
10.5.0/local repo/nv-tensorrt-local-repo-ubuntu2204-10.5.0-cuda-11.8 1.0-1 amd
64.deb
dpkg -i nv-tensorrt-local-repo-ubuntu2204-10.5.0-cuda-11.8 1.0-1 amd64.deb
sudo cp /var/nv-tensorrt-local-repo-ubuntu2204-10.5.0-cuda-11.8/nv-tensorrt-
local-EE22FB8A-keyring.gpg /usr/share/keyrings/
sudo apt update
sudo apt install tensorrt
python3 -m pip install --upgrade tensorrt-cull
# install python dependencies
pip3 install -r requirements.txt
# install web dependences
pip install -r web-demos/hugging_face/requirements.txt
```

# **Run the Gradio Application**

Run the following command to start the Gradio application:

```
cd web-demos/hugging_face/
python3 app.py
```

The Gradio application will be available at 'http://127.0.0.1:7860/' by VSCode port forwarding or 'http://101.126.90.71:50183'.

# Task 2: Invoke the Gradio Application

You can use client.py to invoke the Gradio application. The following is an example of how to use the client to invoke the Gradio application:

```
python client.py --video inputs/sample/sample.mp4 --pose weights/vitpose.pt
```

The inpainted video will be saved to outputs/sample.mp4. If you want to change the output path, you can use the --output option.

# Task 3: Optimization inference speed

### **Time Analysis**

Current command:

```
/usr/src/tensorrt/bin/trtexec --onnx=raft.onnx --saveEngine=raft-fp8.engine --
fp8 --verbose --minShapes='gtlf_1:1x3x640x360','gtlf_2:1x3x640x360' --
optShapes='gtlf_1:12x3x640x360','gtlf_2:12x3x640x360' --
maxShapes='gtlf_1:12x3x640x360','gtlf_2:12x3x640x360' --
dumpOptimizationProfile --builderOptimizationLevel=5 --useSpinWait --
sparsity=enable > raft-fp8.log
```

All the time is based on the sample.mp4 video. The video resolution is 640x360 (360p), and the video length is 1032 frames.

	VOS tracking	Raft time	Complete flow time	Image propagation	Feature Propagation
Time	24090.20447	58275.726223	6067.899583	1963.095136	86457.671271
	ms	ms	ms	ms	ms

# **RAFT Optimization**

The RAFT model is composed of three parts: feature block, context block and update block. The following is the optimization strategy for each block:

- Use TensorRT Model Optimizer to convert the PyTorch model to ONNX format.
- Using tensorrt best mode to optimization.

#### Some commands:

```
/usr/src/tensorrt/bin/trtexec --onnx=raft_fnet_quan.onnx --
saveEngine=raft_fnet_quan_best.engine --best --verbose --
minShapes='x:2x3x640x360' --optShapes='x:24x3x640x360' --
maxShapes='x:24x3x640x360' --dumpOptimizationProfile --
builderOptimizationLevel=4 --useSpinWait --sparsity=enable >
raft_fnet_quan_best.log

/usr/src/tensorrt/bin/trtexec --onnx=raft_cnet_quan.onnx --
saveEngine=raft_cnet_quan_best.engine --best --verbose --
minShapes='x:1x3x640x360' --optShapes='x:12x3x640x360' --
maxShapes='x:12x3x640x360' --dumpOptimizationProfile --
builderOptimizationLevel=4 --useSpinWait --sparsity=enable >
```

```
raft_cnet_quan_best.log
```

```
/usr/src/tensorrt/bin/trtexec --onnx=raft_update_block_quan.onnx --
saveEngine=raft_update_block_quan_best.engine --best --verbose --
minShapes='net_in:1x128x80x45','inp:1x128x80x45','corr:1x324x80x45','flow:1x2x80x45'
--
optShapes='net_in:12x128x80x45','inp:12x128x80x45','corr:12x324x80x45','flow:12x2x80x45'
--
maxShapes='net_in:12x128x80x45','inp:12x128x80x45','corr:12x324x80x45','flow:12x2x80x45'
--dumpOptimizationProfile --builderOptimizationLevel=4 --useSpinWait --
sparsity=enable > raft_update_block_quan_best.log
```

#### Optimization results:

	Torch fp32	TensorRT best	Speedup
Time	58275.726223 ms	25342.446789 ms	2.2

### **Feature Propagation and Transformer Optimization**

#### **Model Inference Optimization**

The feature propagation and transformer are the most time-consuming parts of the model. It is composed of encoder, decoder, softsplit, softcomp, feat\_prop and transformer. The following is the optimization strategy for each part:

- Use TensorRT Model Optimizer to convert the PyTorch model to ONNX format.
- Using tensorrt best mode to optimization.
- Not consider transformer optimization.

#### Some commands:

```
/usr/src/tensorrt/bin/trtexec --onnx=inpainter encoder.onnx --
saveEngine=inpainter_encoder_best.engine --best --verbose --
minShapes='input:9x5x640x360' --optShapes='input:18x5x640x360' --
maxShapes='input:18x5x640x360' --dumpOptimizationProfile --
builderOptimizationLevel=4 --useSpinWait --sparsity=enable >
inpainter_encoder.log
/usr/src/tensorrt/bin/trtexec --onnx=inpainter decoder.onnx --
saveEngine=inpainter decoder best.engine --best --verbose --
minShapes='input:6x128x160x90' --optShapes='input:11x128x160x90' --
maxShapes='input:11x128x160x90' --dumpOptimizationProfile --
builderOptimizationLevel=4 --useSpinWait --sparsity=enable >
inpainter_decoder.log
/usr/src/tensorrt/bin/trtexec --onnx=inpainter_feat_back_deform_align.onnx --
saveEngine=inpainter_feat_back_deform_align_best.engine --best --verbose --
dumpOptimizationProfile --builderOptimizationLevel=4 --useSpinWait --
sparsity=enable > inpainter_feat_back_deform_align.log
/usr/src/tensorrt/bin/trtexec --onnx=inpainter feat forw deform align.onnx --
saveEngine=inpainter_feat_forw_deform_align_best.engine --best --verbose --
```

```
dumpOptimizationProfile --builderOptimizationLevel=4 --useSpinWait --
sparsity=enable > inpainter_feat_forw_deform_align.log
/usr/src/tensorrt/bin/trtexec --onnx=inpainter feat back backbone.onnx --
saveEngine=inpainter feat back backbone best.engine --best --verbose
dumpOptimizationProfile --builderOptimizationLevel=4 --useSpinWait --
sparsity=enable > inpainter_feat_back_backbone.log
/usr/src/tensorrt/bin/trtexec --onnx=inpainter feat forw backbone.onnx --
saveEngine=inpainter_feat_forw_backbone_best.engine --best --verbose
dumpOptimizationProfile --builderOptimizationLevel=4 --useSpinWait --
sparsity=enable > inpainter feat forw backbone.log
/usr/src/tensorrt/bin/trtexec --onnx=inpainter feat fuse.onnx --
saveEngine=inpainter_feat_fuse_best.engine --best --verbose --
minShapes='feat:6x258x160x90' --optShapes='feat:11x258x160x90' --
maxShapes='feat:11x258x160x90' --dumpOptimizationProfile --
builderOptimizationLevel=4 --useSpinWait --sparsity=enable >
inpainter_feat_fuse.log
```

Optimization results:

	Torch fp32 + fp16	TensorRT Encoder best	TensorRT Feature best	Speedup
Time	86457.671271 ms	79078.691251 ms	78972.896806	1.09

**NOTE:** <u>TensorRT Model Optimizer</u> will cause loss of accuracy for encoder and decoder. Most computation is in the transformer part, but the transformer part very complex and hard to optimize. It need more time to optimize.

#### **Multi-thread Optimization**

We can use multi-thread to optimize the inference feat propagation and transformer.

Optimization results:

	Torch fp32 + fp16	Multi Thread	Speedup
Time	86457.671271 ms	68060.301863 ms	1.27

# **Inpainting Optimization**

Optimization results:

	Torch fp32 + fp16	Final	Speedup
Time	185057.978153 ms	122179.337429 ms	1.51