Propainter Development

Yanglin ZHANG

2024-10-02

Task 1: Deploy gradio

Development Environment

Clone the repository by running the following command:

```
git clone git@github.com:lucky9-cyou/ProPainter.git
```

Download the <u>propainter</u> checkpoints and <u>SAM</u> checkpoints. For SAM, we use the sam_vit_h_4b8939.pth checkpoint.

Install the development environment by running the following commands:

```
# create new anaconda env
conda create -n propainter python=3.8 -y
conda activate propainter
# install pytorch
conda install pytorch torchvision torchaudio pytorch-cuda=11.8 -c pytorch -c
nvidia
# intall tensortrt for cuda 11.8
wget https://developer.nvidia.com/downloads/compute/machine-learning/tensorrt/
10.5.0/local repo/nv-tensorrt-local-repo-ubuntu2204-10.5.0-cuda-11.8 1.0-1 amd
64.deb
dpkg -i nv-tensorrt-local-repo-ubuntu2204-10.5.0-cuda-11.8 1.0-1 amd64.deb
sudo cp /var/nv-tensorrt-local-repo-ubuntu2204-10.5.0-cuda-11.8/nv-tensorrt-
local-EE22FB8A-keyring.gpg /usr/share/keyrings/
sudo apt update
sudo apt install tensorrt
python3 -m pip install --upgrade tensorrt-cull
# install python dependencies
pip3 install -r requirements.txt
# install web dependences
pip install -r web-demos/hugging_face/requirements.txt
```

Run the Gradio Application

Run the following command to start the Gradio application:

```
cd web-demos/hugging_face/
python3 app.py
```

The Gradio application will be available at 'http://127.0.0.1:7860/' by VSCode port forwarding or 'http://101.126.90.71:50183'.

Task 2: Invoke the Gradio Application

You can use client.py to invoke the Gradio application. The following is an example of how to use the client to invoke the Gradio application:

```
python client.py --video inputs/sample/sample.mp4 --pose weights/vitpose.pt
```

The inpainted video will be saved to outputs/sample.mp4. If you want to change the output path, you can use the --output option.

Task 3: Optimization inference speed

Time Analysis

Current command:

```
/usr/src/tensorrt/bin/trtexec --onnx=raft.onnx --saveEngine=raft-fp8.engine --fp8 --verbose --minShapes='gtlf_1:1x3x640x360','gtlf_2:1x3x640x360' -- optShapes='gtlf_1:12x3x640x360','gtlf_2:12x3x640x360' -- maxShapes='gtlf_1:12x3x640x360','gtlf_2:12x3x640x360' -- dumpOptimizationProfile --builderOptimizationLevel=5 --useSpinWait -- sparsity=enable > raft-fp8.log
```

All the time is based on the sample.mp4 video. The video resolution is 640x360 (360p), and the video length is 1032 frames.

	VOS tracking	Raft time	Complete flow time	Image propagation	Feature Propagation
Time	24090.20447	58275.726223	6067.899583	1963.095136	86457.671271
	ms	ms	ms	ms	ms

RAFT Optimization

The RAFT model is composed of three parts: feature block, context block and update block. The following is the optimization strategy for each block:

• Using tensorrt best mode to optimization.

Some commands: