Wireless MAC

1 Elements of a wireless network

Wireless hosts:

- Laptop, smartphone
- Run applications
- May be stationary or mobile

Base station:

- Typically connected to wired network
- Relay responsible for sending packets between wired network and wireless host(s) in its "area"

Wireless link:

- Typically used to connect mobile(s) to base station
- Also used as backbone link
- Multiple access protocol coordinates link access
- Various data rates, transmission distances

Infrastructure mode:

- Base station connects mobiles into wired network
- Handoff: mobile changes base station providing connection into wired network

Ad hoc mode:

- No base stations
- Nodes can only transmit to other nodes within link coverage
- Nodes organize themselves into a network: route among themselves

Standard	Frequency Range	Data Rate
802.11b	2.4 GHz	Up to 11 Mbps
802.11a	5 GHz	Up to 54 Mbps
802.11g	2.4 GHz	Up to 54 Mbps
802.11n	2.4 GHz and 5 GHz	Up to 450 Mbps
802.11ac	5GHz	Up to 1300 Mbps

2 Wireless Link Characteristics

Important differences from wired link


- Decreased signal strength: radio signal attenuates as it propagates through matter
- Interference from other sources: standardized wireless network frequencies shared by other devices interfere as well
- Multipath propagation: radio signal reflects off object ground, arriving at destination at slightly different times

Make communication across a wireless link much more difficult

Definition: Hidden terminals


Senders that cannot sense each other but nonetheless collide at intended receiver

Multiple wireless senders and receivers create additional problems (beyond multiple access)



Hidden terminal problem

- B,A hear each other
- B,C hear each other
- A,C can't hear each other, means A,C unaware of their interference at B



Signal attenuation:

- B,A hear each other
- B,C hear each other
- A,C can't hear each other interfering at B

Definition: Exposed terminals

Senders who can sense each other but still transmit safely (to different receivers)

3 802.11 LAN architecture

Wireless host communicates with base station:

Base station = access point (AP)

Basic Service Set (BSS) (aka "cell") in infrastructure mode contains:

- Wireless hosts
- Access point (AP): base station
- Ad hoc mode: hosts only

4 802.11: Channels, association


802.11b: 2.4 GHz - 2.485 GHz spectrum divided into 11 channels at different frequencies

- AP admin chooses frequency for AP
- Interference possible: channel can be same as that chosen by neighbouring AP

Host must associate with an AP


- Scans channels, listening for beacon frames containing AP's name (SSID) and MAC address
- Selects AP to associate with
- May perform authentication

5 802.11: passive/active scanning



Passive scanning

- 1. Beacon frames sent from APs
- 2. Association request frame sent: H1 to selected AP
- 3. Association response frame sent from selected AP to H1



Active scanning

- 1. Probe request frame broadcast from H1
- 2. Probe response frames sent from APs
- 3. Association request frame sent: H1 to selected AP
- 4. Association response frame sent from selected AP to H1

6 802.11: multiple access

- Avoid collisions: 2+ nodes transmitting at same time
- 802.11: CSMA sense before transmitting don't collide with ongoing transmission by another node
- 802.11: no collision detection
 - Difficult to receive (sense collisions) when transmitting due to weak received signals (fading)
 - Can't sense all collisions in any case: hidden terming, fading
 - Goal: avoid collisions: CSMA/CA

7 IEEE 802.11 MAC Protocol: CSMA/CA

802.11 sender

- 1. If sense channel idle for DIFS then transmit entire frame (no CD)
- 2. If sense channel busy then
 - Start random backoff time
 - Timer counts down while channel idle
 - Transmit when timer expires
 - If no ACK, increase random backoff interval, repeat 2

802.11 receiver

• If frame received OK return ACK after SIFS (ACK needed due to hidden terminal problem)


Idea: allow sender to "reserve" channel rather than random access of data frames: avoid collisions of long data frames

- Sender first transmits small request-to-send (RTS) packets to BS using CSMA
 - RTSs may still collide with each other (but they're short)
- BS broadcasts clear-to-send CTS in response to RTS
- CTS heard by all nodes
 - Sender transmits data frame
 - Other stations defer transmissions

Important: Collisions

Avoid data frame collisions completely using small reservations packets

8 802.11 frame: addressing



Address 2: MAC address of wireless host or AP transmitting this frame

