Linux任督二脉之内管理(三)

麦当劳喜欢您来,喜欢您再来



方端关注 Imux间码场



进程的内存消耗和泄漏


- *进程的VMA。
- *进程内存消耗的4个概念: vss、rss、pss和 ss
- *page fault的几种可能性,major和ming*
- *应用内存泄漏的界定方法
- *应用内存泄漏的检测方法: valgrind和addresssanitizer

练习题

- *看一下进程的/proc/
 /maps和smaps文件;
- *pmap一个进程;
- *把同一个程序运行2次,运行1次,观察pss;再运行,得到2个进程,观察代码段的pss变化;
- *valgrind检查内存错误

进程的虚拟地址空间VMA

进程的每一段虚拟地址空间就是一个VMA




pmap, /proc/<pid>/maps, /proc/<pid>/smaps

```
baohua@baohua-VirtualBox:~$ pmap 3474
        ./a.out
3474:
08048000
              4K r-x-- a.out
08049000
              4K r---- a.out
0804a000
              4K rw--- a.out
b75e0000
              4K rw---
                          anon
           1704K r-x-- libc-2.19 so
b75e1000
b778b000
              8K r---- libc-2.19.so
b778d000
              4K rw--- libc-2.19.so
b778e000
             12K rw---
                          [ anon ]
b77af000
             12K rw---
                          [ anon ]
b77b2000
              8K r----
                          [ anon ]
b77b4000
              8K r-x--
                         [ anon ]
b77b6000
            128K r-x-- ld-2.19.so
b77d6000
              4K r---- ld-2.19.so
b77d7000
              4K rw--- ld-2.19.so
bfcbf000
            132K rw---
                         [ stack ]
           2040K
total
```

```
baohua@baohua-VirtualBox:~$ cat /proc/3474/maps
08048000-08049000 r-xp 00000000 08:01 265913
                                                 /home/baohua/a.out
08049000-0804a000 r--p 00000000 08:01 265913
                                                 /home/baohua/a.out
0804a000-0804b000 rw-p 00001000 08:01 26593
                                                 /home/baohua/a.out
b75e0000-b75e1000 rw-p 00000000 00:00 👌
b75e1000-b778b000 r-xp 00000000 08:01 560893
                                                 /lib/i386-linux-gnu/libc-2.19.so
b778b000-b778d000 r--p 001aa000 08>01 560893
                                                 /lib/i386-linux-anu/libc-2.19.so
b778d000-b778e000 rw-p 001ac000 08:01 560893
                                                 /lib/i386-linux-gnu/libc-2.19.so
b778e000-b7791000 rw-p 00000000 00:00 0
b77af000-b77b2000 rw-p 00000000 00:00 0
b77b2000-b77b4000 r--p 0000000 00:00 0
                                                 [vvar]
b77b4000-b77b6000 r-xp(80000000 00:00 0
                                                 [vdso]
b77b6000-b77d6000 r xx 00000000 08:01 575684
                                                 /lib/i386-linux-gnu/ld-2.19.so
b77d6000-b77d7000 x--p 0001f000 08:01 575684
                                                 /lib/i386-linux-gnu/ld-2.19.so
b77d7000-b77d8000 ry-p 00020000 08:01 575684
                                                 /lib/i386-linux-gnu/ld-2.19.so
fcbf000-bfee0000 rw-p 00000000 00:00 0
                                                 [stack]
```

```
baohua@baohua-VirtualBox:~$ cat /proc/3474/smaps
                                                     more
                                                  /home/bachua/a.out
08048000-08049000 r-xp 00000000 08:01 265913
Size:
                       4 kB
                       4 kB
Rss:
                       4 kB
Pss:
                       0 kB
Shared Clean:
Shared Dirty:
                       0 kB
Private Clean:
                       4 kB
Private Dirty:
                       0 kB
Referenced:
                       4 kB
Anonymous:
                       0 kB
AnonHugePages:
                       0 kB
                       0 kB
Swap:
KernelPageSize:
                       4 kB
MMUPageSize:
                       4 kB
Locked:
                       0 kB
VmFlags: rd ex mr mw me dw
08049000-0804a000 r--p 00000000 08:01 265913
                                                  /home/bachua/a.out
Size:
                       4 kB
Rss:
                       4 kB
```


VMA与程序的各个段以及库



VSS vs. RSS

1. Program calls brk() to grow its heap

brk() enlarges heap VMA.
 New pages are not mapped onto physical memory.



Page fault的几种可能性

Heap区域 VMA R+W

页表权限 R 第一次写,发生page fault

申请一页内存

页表权限 R+W

空区域

内存访问落在非法区,

2

···· VMA

代码段 VMA R+X 在此区与,segv 了 在此区执行,申请页,


读出代码段

结论: 发生pagefault后,有可能segv


- ✓ 非法区域 (2)
- ✓ VMA权限不对 (3)

有可能,不segv,而是申请内存(1Minor,4Major)

内存被进程如何瓜分?




vss/rss/pss/uss



smem – process memory

baohua@baohua-VirtualBox:~\$ smem						
PID	User	Command	Swap	USS	PSS	RSS
3474	baohua	./a.out	0 0	68	76	1028
3352	baohua	/bin/cat	0	112	143	1896
2750	baohua	/usr/bin/VBoxClientseaml	200	84	217	1164
2743	baohua	/usr/bin/VBoxClientdispl	0	84	219	1172
2755	baohua	/usr/bin/VBoxClientdraga	0	92	219	1140
2733	baohua	/usr/bin/VBoxClientcliph	0	120	236	1160
2838	baohua	upstart-dbus-bridgedaemo	0	208	271	1696
2839	baohua	upstart-dbus-bridge - daemo	0	228	295	1784
2787	baohua	upstart-event-bridge	0	264	315	2928
3049	baohua	/sbin/initctl emit indicato	0	232	327	2988
2836	baohua	upstart-file-bridgedaemo	0	268	346	1772
2752	baohua	/usr/bin/VBoxClientseaml	0	244	467	3296
2746	baohua	/usr/bin/VBoxelientdispl	0	248	474	3384
2830	baohua	gpg-agent daemonsh	32	528	543	1704
2758	baohua	/usr/bin/VBoxClientdraga	32	332	563	3572
2887	baohua	/bin/dbus-daemonconfig-f	0	404	581	3320
3054	baohua	/usr/lib/i386-linux-gnu/ind	0	524	602	5484
3287	baohua	/usr/lib/gvfs/gvfsd-metadat	0	544	618	5580
2892	baohua	/usr/lib/at-spi2-core/at-sp	0	540	640	5844
2960	baohua	/usr/lib/ibus/ibus-engine-s	0	556	691	6364
1000	19		<u> 100</u>	-		1 - 1 - 1 - 1 - 1 - 1 - 1 - 1 - 1 - 1 -

smem - pie和bar



进程内存泄漏的界定

连续多点采样法,随着时间越久,进程耗费内存越多



观察一个有内存泄漏的进程

```
void main(void)
          unsigned int *p1, *p2;
          while(1)
                    p1=malloc(4096*3);
                    p1[0] = 0;
                    p1[1024] = 1;
                    p1[1024*2] = 2;
                    p2=malloc(1024);
                    p2[0] = 1;
                    free(p2);
                    sleep(1);
          }
}
                   baohua@baohua-VirtualBox: Shem -P a.out
                     PID User
                                  Command
                                                                            USS
                                                                                     PSS
                                                                                              RSS
                                                                  Swap
                                                                            116
                                                                                     125
                                                                                             1172
                    3836 baohua
                                   ./a.out
                                                                     0
                                  /usr/bin/python /usr/bin/sm
                    3837 baohua
                                                                           4776
                                                                                    4803
                                                                                             6912
                   baohua@baohua-VirtualBox:~$ smem -P a.out
                                  Command
                     PID User
                                                                            USS
                                                                                     PSS
                                                                                              RSS
                                                                  Swap
                    3836 baohua .../a.out
                                                                            128
                                                                                     137
                                                                                             1184
                    3838 baohua / /usr/bin/python /usr/bin/sm
                                                                                             6840
                                                                           4770
                                                                                    4801
                   baohua@baobua-VirtualBox:~$ smem -P a.out
                                                                            USS
                     PID User
                                  Command
                                                                  Swap
                                                                                     PSS
                                                                                              RSS
                    3836 baohua
                                   ./a.out
                                                                            140
                                                                                     149
                                                                                             1196
                                                                                    4811
                                                                                             6904
                    3839 baohua
                                  /usr/bin/python /usr/bin/sm
                                                                           4780
                   baohua@baohua-VirtualBox:~$ smem -P a.out
                     PID User
                                  Command
                                                                  Swap
                                                                            USS
                                                                                     PSS
                                                                                              RSS
                    3836 baohua
                                                                            152
                                                                                             1208
                                   ./a.out
                                                                                     161
                                  /usr/bin/python /usr/bin/sm
                                                                           4776
                                                                                    4803
                                                                                             6912
                    3840 baohua
                                                                     0
```

内存泄漏的检查-valgrind

valgrind --tool=memcheck --leak-check=yes ./a.out

```
==3978== Memcheck, a memory error detector
==3978== Copyright (C) 2002-2013, and GNU GPL'd, by Julian_Seward et al.
==3978== Using Valgrind-3.10.0.SVN and LibVEX; rerun with (h) for copyright info
==3978== Command: ./a.out
==3978==
^C==3978==
==3978== HEAP SUMMARY:
             in use at exit: 73,728 bytes in 6 kg cks
==3978==
          total heap usage: 12 allocs, 6 frees 179,872 bytes allocated
==3978==
==3978==
==3978== 61,440 bytes in 5 blocks are definitely lost in loss record 2 of 2
           at 0x402A17C: malloc (in-///x/xlib/valgrind/vgpreload memcheck-x86-linux.so)
==3978==
            by 0x8048491: main (leak-example.c:6)
==3978==
==3978==
==3978== LEAK SUMMARY:
           definitely lost: 61 440 bytes in 5 blocks
==3978==
            indirectly lost: 6 bytes in 0 blocks
==3978==
              possibly lost 0 bytes in 0 blocks
==3978==
            still reachable: 12,288 bytes in 1 blocks
==3978==
==3978==
                 suppressed: 0 bytes in 0 blocks
==3978== Reachable blocks (those to which a pointer was found) are not shown.
```

内存泄漏的检查-addresssanitizer

```
gcc-g-fsanitize=address./leak-example.c
```

13 17855, 1/19/2018

Thur the the second of the control o

https://github.com/21cnbao/geemory-courses

谢谢!

in Milly My one code.