# PyTorch ONNX + Raspberry Pi + NCS

최병찬

### PyTorch ONNX + Raspberry Pi + NCS Workflow

#### [ 관련 Reference ]


- Conversion of PyTorch Classification Models and Launch with OpenCV Python:
   <a href="https://docs.opencv.org/4.x/dc/d70/pytorch\_cls\_tutorial\_dnn\_conversion.html">https://docs.opencv.org/4.x/dc/d70/pytorch\_cls\_tutorial\_dnn\_conversion.html</a>
- Part 1: Deploying a PyTorch MobileNetV2 Classifier on the Intel Neural Compute Stick 2:
   <a href="https://pemami4911.github.io/blog/2021/07/09/part-1-neural-compute-stick-2.html">https://pemami4911.github.io/blog/2021/07/09/part-1-neural-compute-stick-2.html</a>
- OpenVINO 2021.4.2 설치 패키지 Repository : https://storage.openvinotoolkit.org/repositories/openvino/packages/2021.4.2/
- OpenVINO 2021.4.2 Toolkit 설치 가이드 :

  https://docs.openvino.ai/2021.4/openvino\_docs\_install\_guides\_installing\_openvino\_linux.html
- OpenVINO Model Optimizer ONNX IR 변환 :

  https://docs.openvino.ai/latest/openvino\_docs\_MO\_DG\_prepare\_model\_convert\_model\_Convert\_Model\_From\_ONNX.html
- OpenVINO PyTorch ONNX OpenVINO IR 변환 : <a href="https://docs.openvino.ai/2021.4/notebooks/102-pytorch-onnx-to-openvino-with-output.html">https://docs.openvino.ai/2021.4/notebooks/102-pytorch-onnx-to-openvino-with-output.html</a>
- OpenVINO, OpenCV, and Movidius NCS on the Raspberry Pi :
   <a href="https://pyimagesearch.com/2019/04/08/openvino-opencv-and-movidius-ncs-on-the-raspberry-pi/">https://pyimagesearch.com/2019/04/08/openvino-opencv-and-movidius-ncs-on-the-raspberry-pi/</a>
- EEMBC 임베디드 딥러닝 벤치마크: <a href="https://www.eembc.org/mlmark/scores.php">https://www.eembc.org/mlmark/scores.php</a>

# PyTorch ONNX + Raspberry Pi + NCS Workflow Setup


### PyTorch ONNX + Raspberry Pi + NCS Workflow



#### **Host PC – Anaconda (pytorch) : Anaconda Install**

- 설치 파일 전송 방법
  - > https://www.anaconda.com/products/distribution#Downloads 이동
  - 64-Bit (x86) Installer (581 MB) 다운로드
  - WinSCP 또는 MobaXterm을 통해 설치파일을 WSL 세션으로 전송함
  - ▶ bash 명령어를 사용하여 Anaconda 설치 Bash 파일 실행
- Wget을 이용한 Terminal에서 설치 방법
  - > https://www.anaconda.com/products/distribution#Downloads 이동
  - 64-Bit (x86) Installer (581 MB) 다운로드 우클릭 → 새로운 탭에서 실행
  - ▶ 새로운 탭에 나오는 경로를 WSL Terminal 세션에서 Wget <새로운 탭 주소> 명령어 실행 (ex : wget https://repo.anaconda.com/archive/Anaconda3-2021.11-Linux-x86 64.sh)
  - ➤ Wget을 통해 다운로드된 Anaconda 설치 Bash 파일을 실행

Host PC – Anaconda (pytorch) : Anaconda Install



https://www.anaconda.com/products/distribution#Downloads 으로 이동



Anaconda 공식 사이트에서 리눅스 아이콘 클릭

- (1) 64-Bit (x86) Installer (581 MB) 다운로드 → 설치파일 WSL 세션으로 전송 후 설치
- (2) 64-Bit (x86) Installer (581 MB) 우클릭 후 주소 복사 → WSL 세션에서 Wget으로 다운로드 후 설치

#### **Host PC – Anaconda (pytorch) : Anaconda Install**

- Ananconda 환경 만들기
  - Anaconda 설치 후 Terminal 종료 후 재실행
  - ▶ 실행 시 앞에 <base>가 붙는지 확인 (예: (base) luwis@DESKTOP-MDNHLT3:~\$ ▮ )
  - > Python 3 이상의 환경을 갖춘 Conda 가상환경 생성 명령어 사용하여 가상 환경 만들기
    - > conda create -n <가상환경 이름> python=3.xx
      - (※ OpenVINO는 Python 3.7 이상을 요구함)

(ex: 'Python 3.7'을 이용하는 'pytorch'라는 conda 가상환경 만들기: conda create -n pytorch python=3.7)

- ➤ Anaconda 환경이 만들어진 후 가상환경 접속하기
  - > conda activate <가상환경 이름>

(ex: 'pytorch'라는 conda 환경 접속하기: conda activate pytorch / (pytorch) luwis@DESKTOP-MDNHLT3:~\$ ▮ )


- ▶ 현존하는 모든 Anaconda 환경 리스트 확인하기 : conda env list
- ➤ 현재 접속한 Anaconda 환경 로그아웃 하기: conda deactivate

#### **Host PC – Anaconda (pytorch) : Anaconda Install**

- Ananconda 환경에 PyTorch 설치하기
  - ➤ Anaconda 환경에서 PyTorch 가상환경 접속하기
    - conda activate <가상환경 이름>

(ex: 'pytorch'라는 conda 환경 접속하기: conda activate pytorch / (pytorch) luwis@DESKTOP-MDNHLT3:~\$ ▮

▶ PyTorch 공식 사이트(https://pytorch.org/)에서 제공하는 Anaconda 설치 명령어 실행



➤ Anaconda 환경에서 PyTorch 설치 확인

```
(base) luwis@DESKTOP-T793Q6K:~$ conda activate pytorch (pytorch) luwis@DESKTOP-T793Q6K:~$ python3
Python 3.7.15 (default, Nov 24 2022, 21:12:53)
[GCC 11.2.0] :: Anaconda, Inc. on linux
Type "help", "copyright", "credits" or "license" for more information.
>>> import torch
>>> torch.__version__
'1.13.1'
```

# **Host PC OpenVINO Setup**


### **Host PC OpenVINO Setup**

### Host PC - OpenVINO 2021.4.2

- 1) Isb\_release -a: Host PC 리눅스 버전 확인
- 2) wget

https://storage.openvinotoolkit.org/repositories/openvino/packages/2021.4.2/l\_openvino\_toolkit\_data\_dev\_ub untu20\_p\_2021.4.752.tgz -O openvino\_2021.4.2\_dev.tgz

: Host PC OpenVINO 2021.4.2 다운로드



3) tar -xf openvino\_2021.4.2.tgz : 압축 해제

### **Host PC OpenVINO Setup**

#### Host PC - OpenVINO 2021.4.2

- 4) mv l\_openvino\_toolkit\_runtime\_raspbian\_p\_2021.4.752.tgz /home/<USER>/intel/openvino\_2021.4.2 : intel 디렉토리로 압축물 이동
- 5) cd /home/<USER>/intel/openvino\_2021.4.2 : openvino 디렉토리로 이동
- 6) sudo apt install cmake : cmake 다운로드

Optional: Dependency 문제로 실행 안될 경우 적용함

- 7) (base) sudo -E ./install\_dependencies/install\_openvino\_dependencies.sh : OpenVINO 종속성 프로그램 설치
- 8) (base) sudo -E ./development\_tools/model\_optimizer/install\_prerequisites/install\_prerequisites.sh

: Model Optimizer Dependency 설치 (※ Sytem-wide로 Dependency 설치 / ∵ apt 사용 설치)

(base) luwis@DESKTOP-T793Q6K:~/intel/openvino\_2021.4.2\_dev/deployment\_tools/model\_optimizer/install\_prerequisites\$ sudo -E ./install\_prerequisites.sh ■

- 9) (base) source ./bin/setupvars.h
  - : 환경변수 적용
    - → 시스템 및 터미널 실행 시 자동 적용하기 위해서는 .bashrc에 "source /home/<USER>/intel/bin/setupvars.sh" 추가
- 10) [setupvars.sh] OpenVINO environment initialized 확인

## **Model Conversion**

### Model Conversion (PyTorch → ONNX)

#### **Host PC – Anaconda (pytorch) : PyTorch – ONNX Conversion**

```
import torch
import torch.onnx
from torchvision import models
import os
onnx model_path = "models"
                                                                                Pretrained ResNet 50 로딩
onnx model name = "resnet50.onnx"
full model path = os.path.join(onnx model path, onnx model name)
batch size = 1
original model = models.resnet50(weights=models.ResNet50 Weights.IMAGENET1K V1)
original_model.eval()
                                                                                PyTorch Model을 ONNX로 변환하는
                                                                                과정에 사용할 Dummy Input/Ouput
dummy input = torch.randn(batch_size, 3, 224, 224)
dummy_output = original_model(dummy_input)
torch.onnx.export(
   original_model,
                                                                                 ONNX 변환
   dummy_input,
   full model path,
   verbose=True,
                                 변환할 ONNX
   input_names=["input"],
                                  버전 명시
   output names=["output"],
   opset version=13
```

#### Model Conversion (ONNX → OpenVINO IR)

#### **Host PC – Anaconda (base): Model Optimizer Conversion Success**

(base) luwis@DESKTOP-T793Q6K:~/intel/openvino\_2021.4.2\_dev/deployment\_tools/model\_optimizer\$ python3 mo.py --input\_model /home/luwis/tmp/torch\_onnx\_conversion/models/resnet50.onnx --output\_dir /home/luwis/tmp/torch\_onnx\_conversion/models

- deployment\_tools → model\_optimizer : OpenVINO Model Optimizer 디렉토리 이동
- mo.py --input\_model <ONNX Model 경로> --output\_dir <OpenVINO IR 결과물 출력 디렉토리>
  - : Model Optimizer 실행 Python Script 사용
  - (※ Anaconda base에서 실행 / ∵ Dependency가 System-wide로 설치 되었기 때문임)

모델 변환 성공 확인

```
Model Optimizer arguments:
Common parameters:
       - Path to the Input Model:
                                      /home/luwis/tmp/torch onnx conversion/models/resnet50.onnx
                                      /home/luwis/tmp/torch onnx conversion/models
       - Path for generated IR:
       - IR output name:
                              resnet50
       - Log level: ERROR
       - Batch:
                      Not specified, inherited from the model
       - Input layers:
                              Not specified, inherited from the model
       - Output layers:
                              Not specified, inherited from the model
       - Input shapes:
                              Not specified, inherited from the model
       - Mean values: Not specified
       - Scale values:
                              Not specified
       - Scale factor:
                              Not specified
                                                                     ONNX – IR
                              FP32
       - Precision of IR:
       - Enable fusing:
                              True
                                                                  변화 셋팅 확인
       - Enable grouped convolutions fusing: True
       - Move mean values to preprocess section:
                                                      None
       - Reverse input channels:
```

```
Detected not satisfied dependencies:
       numpy: installed: 1.21.5, required: < 1.20
Please install required versions of components or use install prerequisites script
/home/luwis/intel/openvino 2021.4.2 dev/deployment tools/model optimizer/install prerequisit
Note that install_prerequisites scripts may install additional components.
/home/luwis/intel/openvino_2021.4.2_dev/deployment_tools/model_optimizer/extensions/front/on
 ure_function}` instead.
  'data_type': TENSOR_TYPE_TO_NP_TYPE[t_type.elem_type]
/home/luwis/intel/openvino_2021.4.2_dev/deployment_tools/model_optimizer/extensions/analysis
fe. If you specifically wanted the numpy scalar type, use `np.bool_` here.
   recated in NumPy 1.20; for more details and guidance: https://numpy.org/devdocs/release/1
 nodes = graph.get_op_nodes(op='Parameter', data_type=np.bool)
/home/luwis/intel/openvino_2021.4.2_dev/deployment_tools/model_optimizer/extensions/ops/Redu
u specifically wanted the numpy scalar type, use `np.bool ` here.
  precated in NumPy 1.20; for more details and guidance: <u>https://numpy.org/devdocs/release/1</u>
 used dims = np.zeros(len(in_shape), dtype=np.bool)
/home/luwis/intel/openvino_2021.4.2_dev/deployment_tools/model_optimizer/mo/front/common/par
 safe. If you specifically wanted the numpy scalar type, use `np.bool ` here.
 <mark>eprecated</mark> in NumPy 1.20; for more details and guidance: <u>https://numpy.org/devdocs/release/</u>1
 SUCCESS ] Generated IR version 10 model.
  SUCCESS ] XML file: /home/luwis/tmp/torch onnx conversion/models/resnet50.xml
  SUCCESS ] BIN file: /home/luwis/tmp/torch_onnx_conversion/models/resnet50.bin
 SUCCESS | Total execution time: 6.62 seconds.
[ SUCCESS ] Memory consumed: 399 MB.
1τ's peen a wnile, check for a new version of intel(κ) Distribution of OpenViNO(IM) toolkit
he GitHub*
```

### Model Conversion (ONNX → OpenVINO IR)

Host PC - Anaconda (base): Model Optimizer Conversion Fail - Depedency Error

(base) luwis@DESKTOP-T793Q6K:~/intel/openvino\_2021.4.2\_dev/deployment\_tools/model\_optimizer\$ python3 mo.py --input\_model /home/luwis/tmp/torch\_onnx\_conversion/models/resnet50.onnx --output\_dir /home/luwis/tmp/torch\_onnx\_conversion/models

- deployment\_tools → model\_optimizer : OpenVINO Model Optimizer 디렉토리 이동
- mo.py --input\_model <ONNX Model 경로> --output\_dir <OpenVINO IR 결과물 출력 디렉토리>
  - : Model Optimizer 실행 Python Script 사용

(※ Anaconda base에서 실행 / ∵ Dependency가 System-wide로 설치 되었기 때문임)

```
WARNING ]
Detected not satisfied dependencies:
            onnx: not installed, required: >= 1.8.1
             numpy: installed: 1.21.5, required: < 1.20
lease install required versions of components or use install_prerequisites script
home/luwis/intel/openvino_2021.4.2_dev/deployment_tools/model_optimizer/install_prerequisites/install_prerequisites_onnx.sh/
  te that install prerequisites scripts may install additional components.
                   ----- INTERNAL ER
                  Unexpected exception happened.
                  Please contact Model Optimizer developers and forward the following information:
                  No module named 'onnx'
                  Traceback (most recent call last):
             home/luwis/intel/openvino_2021.4.2_dev/deployment_tools/model_optimizer/mo/main.py", line 394, in main'
  File "/home/luwis/intel/openvino_2021.4.2_dev/deployment_tools/model_optimizer/mo/main.py", line 356, in driver
  ret_res = emit_ir(prepare_ir(argv), argv)
File "/home/luwis/intel/openvino_2021.4.2_dev/deployment_tools/model_optimizer/mo/main.py", line 251, in prepare_ir
 import_extensions.load_dirs(argv.framework, extensions, get_front_classes)
File "/home/luwis/intel/openvino_2021.4.2_dev/deployment_tools/model_optimizer/mo/utils/import_extensions.py", line 91, in load_dirs
load_dir(framework, path, get_front_classes)
File "/home/luwis/intel/openvino_2021.4.2_dev/deployment_tools/model_optimizer/mo/utils/import_extensions.py", line 76, in load_dirs
load_dir(s/home/luwis/intel/openvino_2021.4.2_dev/deployment_tools/model_optimizer/mo/utils/import_extensions.py", line 76, in load_dir
 rite //olow/z/und-y-turet/open-troi_sy-to-bey-pag-y-lown-
import_by_path(os.path.)oin(path, *p), [ext, *p])

File "/home/luwis/intel/openvino_2021.4.2 dev/deployment_tools/model_optimizer/mo/utils/import_extensions.py", line 20, in import_by_path
importlib.import_module('{}.()'.format('.'.join(middle_names), name))

File "/home/luwis/anaconda3/lib/python3.9/importlib/__init__py", line 127, in import_module
 return bootstrap_god_import(name[level:], package, level)
File "sfrozen importlib. bootstrap=", line 1030, in _god_import File "sfrozen importlib. bootstrap=", line 1030, in _god_import
File "sfrozen importlib. bootstrap=", line 1007, in _find_and_load
File "sfrozen importlib. bootstrap=", line 980, in _find_and_load unlocked
File "sfrozen importlib. bootstrap=", line 980, in _load_unlocked
File "sfrozen importlib. bootstrap external=", line 350, in exe_module
File "sfrozen importlib. bootstrap external=", line 350, in exe_module
File "sfrozen importlib. bootstrap "line 379 in _god_internal=", line 550, in exe_module
File "sfrozen importlib. bootstrap "line 379 in _god_internal=", line 550, in exe_module
  File "<frozen importlib._bootstrap>", line 228, in _call_with_frames_removed
  File "/home/luwis/intel/openvino_2021.4.2_dev/deployment_tools/model_optimizer/mo/front/onnx/loader.py", line 11, in <module>
   duleNotFoundError: No module named 'onnx'
```

Prerequisites: onnx, networkx, numpy

- pip install onnx
- pip install networkx
- pip install numpy

# **OpenVINO – NCS Inference Run**

#### **OpenVINO – NCS Inference Run**

#### Raspberry Pi 4 + NCS 2 : OpenVINO Inference Run

```
import cv2 as cv
                                                           # Input Image Blob Preparation
                                                                                                           OpenVINO IR 모델에
                                                           input blob = next(iter(net.input info))
import numpy as np
                                                                                                          사용할 입출력 Layer 선언
                                                           out \overline{blob} = \text{next(iter(net.outputs))}
import sys
import os
                                                                                                              입출력 Numerical
                                                           net.input info[input blob].precision = 'U8'
import time
                                                                                                               Precision 설정
                                                           net.outputs[out blob].precision = 'FP32'
from openvino.inference engine import IECore
                                                           # Model Loading to Device
                                                           print("Loading network on {}".format(device))
                                         변환된 OpenVINO
# Model Setup
                                        IR 모델 경로 명시
model path = "./resnet50.xml"
                                                           exec net = ie.load network(network=net, device name=device)
                                                                                             OpenVINO IR모델을 NCS2에 로딩함
                                                           # Model Inference Forward Pass
                                       모델을 실행할 NCS2의
device = "MYRIAD"
                                                           print("Starting inference in synchronous mode")
                                          아키텍쳐 명시
                                                                                                                   Input Layer에
입력 데이터를
# OpenVINO Inference Engine Setup
                                                           start time = time.time()
                                        OpenVINO Inference
ie = IECore()
                                                                                                                   넣고 Inference
                                                           res = exec net.infer(inputs={input blob : input img})
                                         Engine 인스턴스 생성
                                                                                                                      수행
# Intermediate Representation Reading
                                                            end time = time.time()
print("Reading network : {}".format(model path))
                                                            print("Time Taken : {:.3f} sec".format(end time - start time))
                                                           print("Estimated FPS : {:.3f} fps".format(1 / (end time - start time)))
net = ie.read network(model=model path)
                                                            print((res[out blob]).shape)
                                          모델 Weight 로딩
# Input Image Loading
input img = cv.imread("./test input.jpg")
input img = cv.resize(input img, (224, 224))
                                                               oi@raspberrypi:~/intel/cv_vino_test/onnx_test    $ python3 cv vino test.py
input img = np.transpose(input img, (2, 0, 1))
                                                              Reading network : ./resnet50.xml
input img = np.expand dims(input img, axis=0)
                                                              Loading network on MYRIAD
input ima = input ima / 255.
                                                              Starting inference in synchronous mode
                                                              Time Taken: 0.060 sec
                                                              Estimated FPS : 16.566 fps
                                                              (1, 1000)
               입력 이미지 로딩
```