Sir Syed University Of Engineering & Technology - Department of Computer Science

# **LAB 08**

**Objective: To study about:** 

To Configuring RIP (Routing Information Protocol)

#### **Theory:**

### **Routing Information Protocol:**

RIP is a standardized Distance Vector protocol, designed for use on smaller networks. RIP was one of the first true Distance Vector routing protocols, and is supported on a wide variety of systems.

RIP adheres to the following Distance Vector characteristics:

- RIP sends out periodic routing updates (every 30 seconds)
- RIP sends out the full routing table every periodic update
- RIP uses a form of distance as its metric (in this case, hop count)
- RIP uses the Bellman-Ford Distance Vector algorithm to determine the best "path" to a particular destination
- RIP supports IP and IPX routing.
- RIP utilizes UDP port 520
- RIP routes have an administrative distance of 120.
- RIP has a maximum hop count of 15 hops.

Any network that is 16 hops away or more is considered unreachable to RIP, thus the maximum diameter of the network is 15 hops. A metric of 16 hops in RIP is considered a poison route or infinity metric.

RIP has two versions, Version 1 (RIPv1) and Version 2 (RIPv2).


RIPv1 (RFC 1058) is classful, and thus does not include the subnet mask with its routing table updates. Because of this, RIPv1 does not support Variable Length Subnet Masks (VLSMs). When using RIPv1, networks must be contiguous, and subnets of a major network must be configured with identical subnet masks. Otherwise, route table inconsistencies (or worse) will occur.

RIPv2 (RFC 2543) is classless, and thus does include the subnet mask with its routing table updates. RIPv2 fully supports VLSMs, allowing discontinuous networks and varying subnet masks to exist.

Other enhancements offered by RIPv2 include:

- Routing updates are sent via multicast, using address 224.0.0.9
- Encrypted authentication can be configured between RIPv2 routers
- Route tagging is supported (explained in a later section).their networks to match the functional and security requirements of their systems without having to run new cables or make major changes in their current network infrastructure.

#### Sir Syed University Of Engineering & Technology - Department of Computer Science



## **Procedure:**

## Step1:

The topology consists of 3 Cisco routers which are connected with each other and also with 3switches and switches are connected with 3PCs

## Step 2:

A WIC-1T card is placed in the slots in each router. Switch off the router and place the card in the slots and turn it on again. One end of the cable is DTE and the other is automatically DCE.

# Step 3:

We have total 5 networks, now assign ip to each network, assign first three ip in pc using default gateways: 192.168.1.1, 192.168.2.1, 192.168.3.1 and remaining two on the serial interface of router.

# **Step 4:**

Now configure fast Ethernet and serial interface of router by using CLI. Configuration of R0 are as follow:

```
Router#conf t
Router#conf terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config) #int fa 0/0
Router(config-if) #ip add
Router(config-if) #ip address 192.168.1.1 255.255.255.0
Router(config-if) #no shut
Router (config-if) #no shutdown
Router (config-if) #exit
Router(config) #int s 0/0/0
Kouter(contig-it) #ip add
Router(config-if) #ip address 10.0.0.1 255.0.0.0
Router(config-if) #clock r
Router(config-if) #clock rate 64000
Router(config-if) #no shut down
Router (config-if) #exit
Router (config) #
```

Sir Syed University Of Engineering & Technology – Department of Computer Science

# **Step 5:**

## Enabling RIP:

By using following commands:

- Router rip
- Network ip address

Enable a RIP routing process, which places you in router configuration mode. And associate the networks with a RIP routing process. Then enter the command **show ip route** on Ro, R1 and R2 to verify that the new route is now in the routing table.

```
Gateway of last resort is not set
     20.0.0.0/8 is directly connected, Serial0/0/0
     30.0.0.0/8 is directly connected, FastEthernet0/0
    40.0.0.0/8 is directly connected, Serial0/1/0
    50.0.0.0/8 [120/1] via 40.0.0.2, 00:00:20, Serial0/1/0
Router#conf ty
Router#conf ty
% Invalid input detected at '^' marker.
Router#conf t
Router#conf terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config) #router rip
Router(config-router) #network
% Incomplete command.
Router(config-router) #network 10.0.0.0
Router(config-router) #net
Router(config-router) #network 20.0.0.0
```

Router(config-router) #network 30.0.0.0 Router(config-router) #exit		
Exercises:		
<b>Q1.</b> What is RIP what is the use of RIP?		
<b>Q2.</b> How do we configure RIP?		

Data Communication & Networking	Lab-08
Sir Syed University Of Engineering & Technology – Department of Computer Science	
Q3 On which basis RIP decides the best path (routing metric)?	
Q.4 What is the maximum Hop count for RIP is?	
Q.5 In how many seconds RIP end the routing updates to adjacent routers.	
Q.6 In which routing protocol did RIP lie ?	
Q.7 What is the difference between DCE & DTE?	
Q.8 What is the purpose of show ip route?	
Q.9 Why we connect two routers with serial port?	
Q.10 What is difference between RIPV1& RIPV2?	

Sir Syed University Of Engineering & Technology – Department of Computer Science
Q.11 What do you understand by the term metrics?
Q.12 What is the basic purpose of clock rate and why we give it in between networks?
Q.13 What is administrative distance?
Q.13 What is administrative distance:
Q.14 What is the basic purpose of WIC1T & WIC2T slot port?