## **Basics**

- dot product:  $\underline{a} \cdot \underline{b} = a_1b_1 + a_2b_2 + \ldots = |\underline{a}||\underline{b}|\cos\theta, \ W = \underline{F} \cdot \underline{d}$  where F is force and d is distance
- $\bullet \ \, \text{Cross Product:} \,\, \underline{v} \times \underline{w} = \begin{vmatrix} i & -j & k \\ v_1 & v_2 & v_3 \\ w_1 & w_2 & W_3 \end{vmatrix}$
- The area of the quadrilateral which the vectors are enclosing is the determinant of the cross product
- Vector equation of line :  $(x,y,z)=(x_0,y_0,z_0)+t(a,b,c)$ ; where (a,b,c) is a vector parallel to the line and  $(x_0,y_0,z_0)$  is a point on the line
- Standard equation of line/plane:  $\underline{n}\cdot((x,y,z)-(x_0,y_0,z_0))=0$ , where  $\underline{n}$  is a vector normal to the line/plane
- $\bullet \ \ \text{projection $\underline{\bf a}$ onto $\underline{\bf b}$: $Proj_{\underline{b}}(\underline{a}) = \underline{a}_{\underline{b}} = (\underline{a} \cdot \frac{\underline{a}}{|\underline{b}|}) \, \frac{\underline{b}}{|\underline{b}|})$}$

### Parametrization and Tangents to planes ...

- Curve:  $R^2 : \underline{r} = (x(t), y(t)) ; R^3 : \underline{r} = (x(t), y(t), z(t))$
- Tangent line at  $t=t_0$ :  $L(s)=\underline{r}(t_0)+s\underline{r'}(t_0)$
- Tangent plane of graph at (a,b,f(a,b)):  $z=f(a,b)+f_x(a,b)(x-a)+f_x(a,b)(y-b)$

# Parametrized Surface $(\underline{r}(u,v))$ and Curve and regular parametrization

- $\bullet \quad \underline{r}(u,v) = (x(u,v),y(u,v),z(u,v))$
- $\frac{r_u(u_0,v_0)}{\underline{r}(u_0,v_0)}$  and  $\underline{r_v}(u_0,v_0)$  are two vectors parallel to the plane tangent to the surface at
- $\underline{n} = \underline{r_u}(u_0, v_0) \times \underline{r_v}(u_0, v_0)$  is a vector normal to the above tangent plane, if  $\underline{n} \neq \underline{0}$  then the parametrization is regular at  $\underline{r}(u_0, v_0)$
- Tangent plane can be written in two ways:
  - As a parametrization:  $(x,y,z)=\underline{r}(u_0,v_0)+a\underline{r_u}(u_0,v_0)+b\underline{r_v}(u_0,v_0)$
  - As a level set (Standard equation):  $\underline{n} \cdot ((x, y, z) \underline{r}(u_0, v_0)) = 0$
- Parametrization of special surfaces
  - cylinder:  $\underline{r}(\theta, z) = (R\cos(\theta), R\sin(\theta), z)$
  - sphere:  $\underline{r}(\theta, \phi) = (R \sin(\phi) \cos(\theta), R \sin(\phi) \sin(\theta), R \cos(\phi))$
  - graph y = f(x):  $\underline{r}(x) = (x, f(x))$
- Parametrization of curves
  - line segment:  $\underline{r}(t) = \underline{a} + t(\underline{b} \underline{b})$
  - circle in  $R^2$ :  $\underline{r}(t) = (R\cos(t), R\sin(t))$
  - graph z = f(x, y):  $\underline{r}(x, y) = (x, y, f(x, y))$

## Surfaces and Gradient vectors

- Common surfaces:
  - Bowl/cup:  $z = x^2 + y^2$
  - Saddle:  $z = x^2 y^2$
  - Sphere:  $x^2 + y^2 + z^2 = R^2$
  - Cone:  $z = \pm c \sqrt{x^2 + y^2}$
  - Cylinder:  $x^2 + y^2 = R^2$
  - Plane: ax + by + cz = d

#### Level sets

- ullet level set of f(x,y) is a curve in the xy-plane: f(x,y)=const
- $\bullet \;\;$  level set of f(x,y,z) is a graph in the xyz-plane: f(x,y,z)=const

## Gradient Vector $\nabla f = (f_{x_1}, f_{x_2}, ..., f_{x_n})$

- $\bullet$  Maximum increase: the direction: direction of  $\nabla f$  ; the rate:  $|\nabla f|$
- Minimum increase: opposite direction of  $\nabla f$ ; the rate:  $-|\nabla f|$
- $\bullet~$  No change: the normal to  $\nabla f$
- Rate of change in direction  $\hat{u}$ : directional derivative  $D_{\hat{u}}f(\underline{p}) = \nabla f(\underline{p}) \cdot \hat{u}$
- ullet  $\nabla f$  is normal to level sets
- Tangent set to level set at  $\underline{\mathbf{p}}$  :  $\nabla f(\underline{p}) \cdot (\underline{x} \underline{p}) = 0$

# Linear approximation, tangent plane, Local minimum and Maximum (optimization)

- $\bullet \ \ \mathbf{Linearization} \colon \ L(\underline{x}) = f(\underline{p}) + \nabla f(\underline{p}) \cdot (\underline{x} \underline{p})$
- Linear Approximation :  $f(\underline{x}) = L(\underline{x})$
- Critical Points:  $\nabla f(\underline{p}) = \underline{0}$
- Second derivative test:  $D = f_{xx}f_{yy} (f_{xy})^2$  at point  $\underline{p}$ 
  - $\ \ \mbox{If} \ D > 0 \mbox{ and } (f_{xx} > 0 \mbox{ or } f_{yy} > 0), \mbox{ then } \underline{p} \mbox{ is a local min}$
  - If D>0 and  $(f_{xx}<0 \text{ or } f_{yy}<0),$  then  $\underline{\textbf{p}}$  is a local max
  - $\ \ \mbox{If} \ D < 0 \ \mbox{then} \ \underline{\bf p} \ \mbox{is a saddle point}$
- chain rule:  $f = f(\underline{x}), x_i = x_i(\underline{t})$  then  $\frac{\partial f}{\partial t_i} = \nabla f(\underline{x}) \cdot \frac{\partial \underline{x}}{\partial t_i}$

## Coordinate systems

- $\bullet \ \ \mathbf{Rectangular} \ \mathbf{Coordinates} \ (x,y,z) \\$ 
  - to cylindrical :  $x = r \cos \theta$  ,  $y = r \sin \theta$  , z = z
  - from cylindrical:  $r = \sqrt{x^2 + y^2}$ ,  $\theta = \tan^{-1}(\frac{y}{x})$ , z = z
- Cylinder Coordinates  $(\theta, r, z)$ 
  - from spherical :  $r = \rho \cos \phi$  ,  $z = \rho \sin \phi$  ,  $\theta = \theta$
  - to spherical :  $\rho = \sqrt{r^2 + z^2}$  ,  $\phi \tan^{-1}(\frac{r}{z}$  ,  $\theta = \theta$
- Spherical Coordinates  $(\phi, \theta, \rho)$ 
  - $\ \ \mathbf{from \ rectangular} \ : \ \rho = \sqrt{x^2 + y^2 + z^2}, \ \phi = \tan^{-1}(\frac{\sqrt{x^2 + y^2}}{z}), \ \theta = \tan^{-1}(\frac{y}{x})$
  - to rectangular :  $x=\rho\sin\phi\cos\theta$   $y=\rho\sin\phi\sin\theta$   $z=\rho\cos\phi$

## Surface Area, Area, Volume, Mass, ...

- $R^2$  Area elements dA
  - Cartesian(x, y) dA = dxdy
  - $Polar(\theta, r) dA = rdrd\theta$
- R<sup>3</sup> Volume elements dV
  - Cartesian(x, y), z dV = dxdydz
  - Cylindrical $(\theta, r, z) dV = r dr d\theta dz$
  - Spherical( $\theta$ ,  $\rho$ ,  $\phi$ )  $dV = \rho^2 \sin \phi d\rho d\phi d\theta$
- Surface Area element (dS) / Surface Area
  - Surface Area element:  $dS = |\underline{ru} \times \underline{ru}| du dv$
  - Surface Area:  $\iint_D dS = \iint_D dS \iint_D |\underline{r_u} \times \underline{r_u}| du dv$
- . 26...