Basics

- dot product: $\underline{a} \cdot \underline{b} = a_1b_1 + a_2b_2 + \ldots = |\underline{a}||\underline{b}|\cos\theta, \ W = \underline{F} \cdot \underline{d}$ where F is force and d is distance
- $\bullet \ \, \text{Cross Product:} \, \, \underline{v} \times \underline{w} = \begin{vmatrix} i & -j & k \\ v_1 & v_2 & v_3 \\ w_1 & w_2 & W_3 \end{vmatrix}$
- The area of the quadrilateral which the vectors are enclosing is the determinant of the cross product
- Vector equation of line : $(x,y,z)=(x_0,y_0,z_0)+t(a,b,c)$; where (a,b,c) is a vector parallel to the line and (x_0,y_0,z_0) is a point on the line
- Standard equation of line/plane: $\underline{n}\cdot((x,y,z)-(x_0,y_0,z_0))=0$, where \underline{n} is a vector normal to the line/plane
- projection $\underline{\mathbf{a}}$ onto $\underline{\mathbf{b}}$: $Proj_{\underline{b}}(\underline{a}) = \underline{a}_{\underline{b}} = (\underline{a} \cdot \frac{\underline{a}}{|\overline{b}|}) \frac{\underline{b}}{|\overline{b}|})$

Parametrization and Tangents to planes ...

- Curve: R^2 : $\underline{r} = (x(t), y(t))$; R^3 : $\underline{r} = (x(t), y(t), z(t))$
- $\bullet \ \ {\bf Tangent \ line \ at} \ t=t_0 \colon \ L(s)=\underline{r}(t_0)+s\underline{r'}(t_0)$
- Tangent plane of graph at (a,b,f(a,b)): $z=f(a,b)+f_x(a,b)(x-a)+f_x(a,b)(y-b)$

Parametrized Surface $(\underline{r}(u,v))$ and Curve and regular parametrization

- $\underline{r}_{\underline{u}}(u_0, v_0)$ and $\underline{r}_{\underline{v}}(u_0, v_0)$ are two vectors parallel to the plane tangent to the surface at $\underline{r}(u_0, v_0)$
- $\underline{n} = \underline{r_u}(u_0, v_0) \times \underline{r_v}(u_0, v_0)$ is a vector normal to the above tangent plane, if $\underline{n} \neq \underline{0}$ then the parametrization is regular at $\underline{r}(u_0, v_0)$
- · Tangent plane can be written in two ways
 - As a parametrization: $(x,y,z)=\underline{r}(u_0,v_0)+a\underline{ru}(u_0,v_0)+b\underline{rv}(u_0,v_0)$
 - – As a level set (Standard equation): $\underline{n} \cdot ((x,y,z) - \underline{r}(u_0,v_0)) = 0$
- Parametrization of special surfaces
 - cylinder: $\underline{r}(\theta, z) = (R\cos(\theta), R\sin(\theta), z)$
 - sphere: $\underline{r}(\theta, \phi) = (R \sin(\phi) \cos(\theta), R \sin(\phi) \sin(\theta), R \cos(\phi))$
 - graph y = f(x): $\underline{r}(x) = (x, f(x))$
- Parametrization of curves
 - line segment: $\underline{r}(t) = \underline{a} + t(\underline{b} \underline{b})$
 - circle in R^2 : $\underline{r}(t) = (R\cos(t), R\sin(t))$
 - graph z = f(x, y): $\underline{r}(x, y) = (x, y, f(x, y))$

Surfaces and Gradient vectors

- Common surfaces:
 - Bowl/cup: $z = x^2 + y^2$
 - Saddle: $z = x^2 y^2$
 - Sphere: $x^2 + y^2 + z^2 = R^2$
 - Cone: $z = \pm c\sqrt{x^2 + y^2}$
 - Cylinder: $x^2 + y^2 = R^2$
 - Plane: ax + by + cz = d

Level sets

- ullet level set of f(x,y) is a curve in the xy-plane: f(x,y)=const
- level set of f(x, y, z) is a graph in the xyz-plane: f(x, y, z) = const

Gradient Vector $\nabla f = (f_{x_1}, f_{x_2}, ..., f_{x_n})$

- \bullet Maximum increase: the direction: direction of ∇f ; the rate: $|\nabla f|$
- \bullet Minimum increase: opposite direction of ∇f ; the rate: $-|\nabla f|$
- \bullet $\,$ No change: the normal to ∇f
- Rate of change in direction $\hat{u}\colon \mathbf{directional\ derivative\ } D_{\hat{u}}f(\underline{p}) = \nabla f(\underline{p})\cdot \hat{u}$
- ullet ∇f is normal to level sets
- Tangent set to level set at \underline{p} : $\nabla f(\underline{p}) \cdot (\underline{x} \underline{p}) = 0$

Linear approximation, tangent plane, Local minimum and Maximum (optimization)

- $\bullet \ \ \mathbf{Linearization} \colon \ L(\underline{x}) = f(\underline{p}) + \nabla f(\underline{p}) \cdot (\underline{x} \underline{p})$
- $\bullet \ \ \mathbf{Linear} \ \mathbf{Approximation} : \ f(\underline{x}) = L(\underline{x}) \\$
- Critical Points: $\nabla f(\underline{p}) = \underline{0}$
- Second derivative test: $D = f_{xx}f_{yy} (f_{xy})^2$ at point \underline{p}
 - If D>0 and $(f_{xx}>0$ or $f_{yy}>0)$, then \underline{p} is a local min
 - If D>0 and $(f_{xx}<0 \text{ or } f_{yy}<0)$, then \underline{p} is a local max
 - If D < 0 then \underline{p} is a saddle point
- $\bullet \ \ {\bf chain \ rule} : \ f=f(\underline{x}), x_i=x_i(\underline{t}) \ {\bf then} \ \frac{\partial f}{\partial t_i}=\nabla f(\underline{x}) \cdot \frac{\partial \underline{x}}{\partial t_i}$

Coordinate systems

- Rectangular Coordinates (x, y, z)
- Cylinder Coordinates (θ, r, z)
- Spherical Coordinates (ϕ, θ, ρ)