Encoder Decoder

April 26, 2023

1 Encoder Decoder

Transfering MIPS assembly code to machine code and reverse.

1.1 Assemble the code: XOR \$s7, \$a3, \$t5

XOR:

• Type: R format instruction

• opcode: 000000

• funct: 100110

\$s7:

• Type: Saved register from \$s0 (\$16) to \$s7 (\$23)

• Number: \$23

\$a3:

• Type: Procedure Argument register from \$a0 (\$4) to \$a3 (\$7)

• Number: \$7

\$t5:

• Type: Temperory register from \$t0 (\$8) to \$t7 (\$15)

• Number: \$13

Every instruction in MIPS assembly language is 32 bit, all of them are equal in length. R format instructions are devided into these segements:

| opcode | rs | rt | rd | shamt | funct | | 000000 | 5 bit | 5 bit | 5 bit | 5 bit | 6 bit |

1.1.1 Solution

In this command:

• opcode: 000000

• rs: \$a3

• rt: \$t5

• rd: \$s7

Human readable format of the machine code of the command is:

• $(000000)_{\text{two}} (7)_{\text{ten}} (13)_{\text{ten}} (23)_{\text{ten}} (00000)_{\text{two}} (100110)_{\text{two}}$

Full binary format:

• 000000 00111 01101 10111 00000 100110

Compact:

 $\bullet \quad 00000000111011011011100000100110$

Hex format

| 0000 | 0000 | 1110 | 1101 | 1011 | 1000 | 0010 | 0110 |
| 0 | x | e | d | b | 8 | 2 | 6 |

• 0xedb826

1.2 Disassemble the code: 0x288900F8

First we should transfer this hex value into a binary format

1.2.1 Bin format

$$(2)_{\text{hex}} \to (0010)_{\text{bin}}$$

$$(8)_{\text{hex}} \to (1000)_{\text{bin}}$$

$$(9)_{\text{hex}} \to (1001)_{\text{bin}}$$

$$(0)_{\rm hex} \to (0000)_{\rm bin}$$

$$(F)_{\text{hex}} \rightarrow (1111)_{\text{bin}}$$

 $(00101000100010010000000011111000)_{\text{bin}} \rightarrow 32 \text{ bit}$

All MIPS instructions have an opcode section which is 6 bit long, so the opcode of this instructions is: 001010 If we check the MIPS Reference card, this opcode belongs to: slti set less than immediate.

This is an I format instruction. So let's disassemble it into it's parts:

| opcode | rs | rt | immediate

| 6 bit | 5 bit | 5 bit |

16 bit

So according to the instruction format and instruction parts:

- Opcode: 001010
- rs: $(00100)_{\rm bin} = (4)_{\rm decimal} \rightarrow $a0$
- rt: $(01001)_{\text{bin}} = (9)_{\text{decimal}} \rightarrow \$t1$
- immediate: $(0000000011111000)_{\text{bin}} = (248)_{\text{decimal}}$