## Troubleshoot

XCP 1.6.2

NetApp October 30, 2020

This PDF was generated from https://docs.netapp.com/us-en/xcp/xcp-troubleshoot-xcp-nfs.html on October 30, 2020. Always check docs.netapp.com for the latest.



# **Table of Contents**

Troubleshoot	
Troubleshoot XCP NFS errors	
Troubleshoot XCP SMB Errors	
Troubleshoot XCP File Analytics errors	

# **Troubleshoot**

### **Troubleshoot XCP NFS errors**

XCP issue	Solution
xcp: ERROR: must run as root	Execute XCP commands as root user
<pre>xcp: ERROR: License file /opt/NetApp/xFiles/xcp/license not found.</pre>	Download the license from https://xcp.netapp.com and copy to /opt/NetApp/xFiles/xcp/
xcp: ERROR: This license has expired	Renew or obtain the new XCP license from http://xcp.netapp.com.
xcp: ERROR: License unreadable	License file might be corrupted. Obtain the new XCP license from http://xcp.netapp.com.
xcp: ERROR: XCP not activated, run 'activate' first	Run the xcp activate command
This copy is not licensed	Obtain the appropriate XCP license file. Copy the XCP license to the /opt/NetApp/xFiles/xcp/directory on the XCP server. Run the xcp activate command to activate the license.
xcp: ERROR: Failed to activate license: Server unreachable	You are trying to activate the online license and your host system is not connected to internet.  Make sure your system is connected internet.
xcp: ERROR: Failed to activate license: Server xcp.netapp.com unreachable xcp: HINT: Configure DNS on this host or return to the license page to request a private license Expected error: Failed to activate license: Server xcp.netapp.com unreachable	Make sure xcp.netapp.com is reachable from your host or request for the offline license
<pre>xcp: ERROR: Catalog inaccessible: Cannot mount nfs_server:/export[:subdirectory]</pre>	Open the editor on the XCP Linux client host and update the configuration file with the proper catalog location. The XCP configuration file is located at /opt/NetApp/xFiles/xcp/xcp.ini. Sample entries of configuration file:  [root@scspr1949387001 ~]# cat /opt/NetApp/xFiles/xcp/xcp.ini # Sample xcp

XCP issue	Solution
nfs3 error 2: no such file or directory	Operation did not find the source file(s) on the target NFS export. Run the xcp sync command to copy the incremental updates from source to destination
xcp: ERROR: Empty or invalid index	Previous copy operation was interrupted before indexing the files. Rerun xcp copy with the new index and make sure the system returns "indexed" before interrupting copy
<pre>xcp: ERROR: compare batches: child process failed (exit code -9): recv <type 'exceptions.eoferror'="">:</type></pre>	Follow the instructions in the following KB article: Cannot allocate memory when synching NFS data
xcp: ERROR: For xcp to process ACLs, please mount <path> using the OS nfs4 client</path>	Mount the source/target on the XCP host

# **Troubleshoot XCP SMB Errors**

Issue	Solution
xcp: ERROR: This license has expired	Renew or obtain the new XCP license from http://xcp.netapp.com.
This copy is not licensed	Obtain the appropriate XCP license file. Copy the XCP license to the c:\netapp\xcp folder on the XCP host. Run the xcp activate command to activate the license
xcp: ERROR: XCP not activated, run 'activate' first	Download the XCP license from <a href="http://xcp.netapp.com">http://xcp.netapp.com</a> . Copy the file on the XCP Linux client host at c:\netapp\xcp on the XCP host. Run the xcp activate command to activate the license.
xcp: ERROR: License file C:\NetApp\XCP\license not found	Register for the XCP license at <a href="http://xcp.netapp.com">http://xcp.netapp.com</a> . Download and copy the license file to C:\NetApp\XCP\ on the XCP Windows client host.
xcp scan Error: The network name cannot be found	Rerun the command with correct share name

Issue	Solution
xcp copy Error: ERROR failed to obtain fallback security principal  Error message logged in xcp.log file: pywintypes.error: (1722, 'LookupAccountName', 'The RPC server is unavailable.')	Add the destination box in the hosts file (C:\Windows\System32\drivers\etc\hosts). Netapp storage destination box entry must be in the below format: ' <data data="" interface="" ip="" vserver=""> 1 or more white spaces <cifs name="" server=""></cifs></data>
<pre>xcp copy: ERROR failed to obtain fallback security principal (Post adding destination box entry in the hosts files)  Error messaged logged in xcp.log file: 'No mapping between account names and security IDs was done'</pre>	The fallback user/group does not exist at the target system (destination box) or active directory.  Rerun the command with correct fallback user/group options
<pre>xcp copy: ERROR failed to obtain fallback security principal (Post adding destination box entry in the hosts files)  Error messaged logged in xcp.log file: pywintypes.error: (87, 'LookupAccountName', 'The parameter is incorrect.')</pre>	Incorrect parameter for fallback user/group option. Rerun the command with the correct syntax for fallback user/group options
<pre>xcp copy with acl migration Erorr message logged in xcp.log file: pywintypes.error: (1314, 'GetNamedSecurityInfo', 'A required privilege is not held by the client.')</pre>	A user is facing an ssue related to security descriptors because with the privileges that the migrations user owns, XCP can only get owner, group, and DACL, but, it cannot get SACL.  Add your migration user to "Manage Audit and Security Log" policy in your Active Directory.  Reference: https://docs.microsoft.com/en-us/previous-versions/windows/it-pro/windows-server-2012-r2-and-2012/dn221953(v%3Dws.11)

# **Troubleshoot XCP File Analytics errors**

Issue	Solution
PostgreSQL installation or service failed	Run configure again and select the installation option. If the previous installation was successful, you can select the repair option. If you are still getting the error, try manual steps as follows:
	1. Run PostgreSQL on the Linux system
	sudo yum -y install postgresql-serversudo systemctl start postgresq
	2. Create a data directory for the PostgreSQL database:
	sudo mkdir /var/lib/postgres/data
	3. Initialize the database:
	sudo -i -u postgres initdb -D '/var/lib/pgsql/data
	4. Open the following file using an appropriate Linux file editor:
	/var/lib/pgsql/data/pg_hba.conf
	5. Remove the following entry:
	`# host all all 127.0.0.1/32 trust
	6. Add the following entry: # host all all 0.0.0.0/0 password
	7. Open the file /var/lib/pgsql/data/postgresql.conf
	8. Add the following entry:
	# listen_addresses='*'
	9. Start the PostgreSQL service:
	sudo systemctl start postgresql.service

Issue	Solution
HTTPD installation or service failed	Run configure again and select the installation option. If the previous installation was successful, you can select the repair option. If you are still getting the error, try manual steps as follows:  1. Install HTTPD on the Linux system:  sudo yum -y install httpd  2. Open the following configuration file to rewrite the rules:  /etc/httpd/conf/httpd.conf  3. Add the following entries to the file:  RewriteEngine On RewriteOptions Inherit <directory "="" html="" var="" www="">     `AllowOverride None Require all granted RewriteCond %{REQUEST_FILENAME} -f [OR]     `RewriteCond %{REQUEST_FILENAME} -d     `RewriteRule ^ xcp/index.html [L]  </directory>
	4. Start the HTTPD services:  sudo systemctl start httpd

Issue	Solution
SSL installation failed	Run configure again and select the installation option. If the previous installation was successful, you can select the repair option. If you are still getting the error, try manual steps as follows:
	1. Install mod_ssl:
	yum install mod_ssl -y
	2. Generate the Secure Sockets Layer (SSL) certificate:
	yum openssl req -x509 -nodes -days 365 -newkey rsa:2048 -keyout /etc/ssl/private/apache-selfsigned.key -out /etc/ssl/certs/apache-selfsigned.crt
	3. Enable the HTTPS services:
	yum openssl dhparam -out /etc/ssl/certs/dhparam.pem 2048
	4. Restart the HTTPD services:
	sudo systemctl restart httpd
	5. Copy the SSL certificate to an appropriate location:
	<pre>sudo cp -pr /etc/pki/tls/certs/localhost.crt /opt/NetApp/xFiles/xcp/server.crt sudo</pre>
Not able to open login page after successful install	Make sure your system is able to ping the Linux machine where XCP File Analytics is installed and HTTPD is running. If the services are not running, run configure and choose the repair option.
	Make sure that you are using supported version of browser. See the IMT: https://mysupport.netapp.com/matrix/

Issue	Solution
User login failed	<ul> <li>Make sure that you are using a supported version of the browser. See the IMT: https://mysupport.netapp.com/matrix/</li> </ul>
	Check the user is "admin" and the password is correct
	• Make sure the XCP service is running by issuing "xcp service status"
	<ul> <li>Verify that port 5030 is open on Linux. Open the application at <a href="https://">https://</a> <a href="https://">linux</a> ip&gt; :5030/api/xcp, and confirm that the messagereads msg: Missing Authorization Header</li> </ul>
	<ul> <li>Check whether the xcp.ini file is present in the /opt/NetApp/xFiles/xcp/ location. To reset the xcp.ini file, run the configuration script and select the Repair option. Next, select the menu option to rebuild xcp.ini file</li> </ul>
XCP GUI is not showing updated pages.	Clear the cache and try again
XCP service is not starting	To run the xcp service, use the sudo systectl start xcp command. Alternatively, run the configuration script and select the <b>Repair</b> option to start the services that are stopped
Failed to scan file share	File share/volume might not be readable. Check manually whether the file share is accessible/readable by running the xcp show command

Issue	Solution
Could not load file servers	Try a page refresh. If the problem persists, manually run the xcp show command on the prompt and check whether you can scan the file server. If successful, raise a ticket with NetApp customer support. If unsuccessful, check manually to see if the file server is active  Check whether the xcp.ini file and license files are in the correct location. To reset the xcp.ini file, run the configuration script and select the Repair option. Next, select the menu option to rebuild xcp.ini file.  Check the xcpfalogs logs to see if the license needs renewal
XCP File Analytics page is not displayed after system reboot	XCP services might be down. Run the configuration script and select the option to <b>Repair</b> . This will restart all the services that are stopped
The total space for an exported file system on a given file server might show more space compared to the allocated physical storage.	This can happen when there are qtree level exports inside the volume.  For example, if the volume size is 10 GB that is exported as /vol1 and there is a qtree inside the volume /vol1/qtree1, then the xcp show command will show the vol1 size as 10 GB and the qtree1 size as 10 GB. XCP File Analytics sums the space of both exports and gives the total space, in this case, 20 GB. It does not understand that qtree1 is a logical space.

### **Copyright Information**

Copyright © 2020 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval systemwithout prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

#### **Trademark Information**

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.